

N2O

User Manual

Note: All references to the N2O version in this manual are indicated by <i>vrs</i> or <i>v.r.s.</i> The current release of N2O is version 5.3.1.

This document is applicable to N2O, and N2O/3GL Version 5.3.1. N2O/3GL is a separately priced, optional feature.

Comments pertaining to this document, N2O, and N2O/3GL are encouraged. Please direct all comments to:

Treehouse Software, Inc.

2605 Nicholson Road, Suite 1230

Sewickley, PA 15143

Phone: 724.759.7070

Fax: 724.759.7067

E-mail: support@treehouse.com

<http://www.treehouse.com>

Worldwide marketing of N2O and other Treehouse products is handled through the Sewickley office.

Reproduction of any portion of this document without the written consent of Treehouse Software, Inc. is prohibited.

Copyright February 2010 by Treehouse Software, Inc. of Sewickley, Pennsylvania.

Last Updated: 03/11/2019

This page intentionally left blank.

PREFACE

The N2O documentation consists of an Administrator Manual, a User Manual, and an Administrative Guide. The Administrator Manual is designed to be used by the N2O Administrator, the User Manual is geared toward the everyday user of N2O, and the Administrative Setup Guide will assist the N2O Administrator in defining N2O's Environment Subsystem.

The first section of the Administrator Manual is an introduction, which defines Change Management and provides an overview of N2O.

The second section describes the installation procedure for N2O. This section illustrates the procedure for OS, VSE, VM, and Siemens BS2000 environments. Sample JCL is included for each environment. This section also describes conversion from N2O 4.0 to N2O 5.0.

The third section describes the Environment Subsystem. This section illustrates the manner in which site-specific information is provided to N2O. The sub-sections describing the Environment Subsystem are arranged in the order in which installation is performed. This arrangement allows the Environment Subsystem section to be used as a tutorial in addition to serving as a reference.

Security for N2O is administered in the Environment Subsystem, but it is discussed in the fourth section of the Administrator Manual. This section explains the different profiles that determine security for N2O users.

The fifth section describes N2O and N2O/3GL operations. Some of the operations included in this section are: customization options, running batch migrations and remote migrations, and Static SQL support.

N2O and N2O/3GL are products of Treehouse Software, Inc. and are copyright protected. ADABAS, Com-plete, NATURAL, NATURAL DB2, NATURAL SECURITY (NSC), NET-WORK, and PREDICT are products of Software AG. CICS, DOS, MVS/XA/ESA, TSO, RACF, VM, and DB2 are products of IBM. CA-LIBRARIAN, CA-PANVALET, CA-ACF2, CA-TOP SECRET and CA-ENDEVOR are products of Computer Associates.*

* In this document, CA-LIBRARIAN is referred to as LIBRARIAN, CA-PANVALET is referred to as PANVALET, CA-ACF2 is referred to as ACF2, CA-TOP SECRET is referred to as TOP SECRET, and CA-ENDEVOR is referred to as ENDEVOR.

TABLE OF CONTENTS

I. INTRODUCTION	1
I.1 Change Management Using N2O	1
I.2 N2O Subsystems	4
I.3 N2O Features.....	5
I.4 The N2O User Interface	7
II. MIGRATION SUBSYSTEM.....	15
II.1 Introduction	15
II.2 Request Events.....	17
II.2.1 Add an Event	20
II.2.2 Object Selection Process.....	24
II.2.2.1 Selecting NATURAL Objects.....	25
II.2.2.2 Selecting SYSERR Messages	28
II.2.2.3 Selecting PREDICT Objects.....	30
II.2.2.4 Selecting 3GL/OTHER Objects	35
II.2.2.5 Extracting and Renaming NATURAL Objects	38
II.2.2.7 Selecting METADATA	42
II.2.3 Migration Process	44
II.2.4 Copy an Event	47
II.2.5 Delete an Event	48
II.2.6 Inquire on an Event.....	49
II.2.7 Modify an Event	51
II.2.8 Recovery from Archive	52
II.2.9 N2OPURGE Recovery	56
II.2.10 Select Events for Processing.....	59
II.2.11 Object Selection Screen Messages.....	61
II.3 Authorize Events.....	63
II.3.1 Authorize an Event	64
II.3.2 Delete an Event	69
II.3.3 Inquire on an Event.....	70
II.3.4 Reject an Event	73
II.3.5 Select Events for Processing.....	74
II.4 Service Events	75
II.4.1 Delete an Event	76
II.4.2 Inquire on an Event.....	77
II.4.3 Service an Event.....	80
II.4.4 Select Events for Processing.....	84
II.5 Migration Utilities.....	85
II.5.1 Libraries Pending Autocompile	86
II.5.2 Process Deferred Move Events	90
II.5.3 Cancel Deferred Move Events	91
II.5.4 3GL/OTHER PDS Object Type Update	92
II.5.5 Build Event by Change Control.....	94
II.6 Checkout/Checkin Utilities	95
II.6.1 Cancel Utility	97
II.6.1.1 Cancel Utility.....	98
II.6.1.2 Cancel with Delete Utility	102
II.6.1.3 Cancel with Extract Utility.....	104
II.6.2 Transfer Utility.....	107
II.6.3 Transfer by Event Utility.....	110
II.6.4 Checkout Utility.....	112
II.6.5 Reject Utility.....	118
II.6.6 Enrollment Facility	119

II.6.7	Reject by Event Utility	122
II.7	Batch JCL Submission	124
II.7.1	Submit an Event	126
II.7.2	Submit a Master Event	128
II.7.3	Submit Migration Profiles	129
II.7.4	Submit All Pending Events	131
II.7.5	View JCL for a Profile	132
II.7.6	3GL/OTHER Autocompile	134
II.7.7	DB2 DBRM Generation	135
II.7.8	DB2 Plan Bind	137
III.	PROJECT TRACKING SUBSYSTEM	139
III.1	Introduction	139
III.2	Project Definition	141
III.2.1	Add a Project Definition	142
III.2.2	Copy a Project Definition	147
III.2.3	Delete a Project Definition	148
III.2.4	Inquire on a Project Definition	149
III.2.5	Modify a Project Definition	149
III.2.6	Select a Project Definition	150
III.3	Task List	151
III.3.1	Add a Task	152
III.3.2	Copy a Task	154
III.3.3	Delete a Task	154
III.3.4	Inquire on a Task	155
III.3.5	Modify a Task	155
III.3.6	Select a Task	156
III.4	Suggestion Box	157
III.4.1	Add a Suggestion	158
III.4.2	Copy a Suggestion	160
III.4.3	Delete a Suggestion	160
III.4.4	Inquire on a Suggestion	161
III.4.5	Modify a Suggestion	161
III.4.6	Select a Suggestion	162
III.5	Task Utilities	163
III.5.1	Update Stage for a Task	164
III.5.2	Cancel a Task	166
III.5.3	Reject a Task	168
III.5.4	Link Objects to a Task	170
III.5.5	Link Suggestions to a Task	174
III.5.6	Link Tasks to a Task	177
III.6	Project Tracking Reports	180
III.6.1	History of a Task	181
III.6.2	Task Details	183
III.6.3	Project Status	185
III.6.4	User Status	187
III.6.5	Events Related to a Task	189
III.6.6	Suggestion Details	191
IV.	REPORTING SUBSYSTEM	193
IV.1	Introduction	193
IV.2	Environment Reporting	195
IV.2.1	Authorized Users to an Environment	196
IV.2.2	Node Definition Usage	198
IV.2.3	Archive Definition Usage	200
IV.2.4	Environment Definition Usage	202
IV.2.5	Users Related to a Group-ID	204

IV.2.6	Environment Reporting in Batch.....	206
IV.3	Event Reporting.....	207
IV.3.1	Events Requiring Further Authorization	208
IV.3.2	Chronology of Events	211
IV.3.3	Events Related by Change Control	213
IV.3.4	Event Details	216
IV.3.5	Events Processed by Date	229
IV.3.6	Events With Warning Messages	232
IV.3.7	Events Pending Move	236
IV.3.8	Events Pending Autocompile	238
IV.3.9	Autocompile Summary for Events	241
IV.3.10	Event Reporting in Batch.....	247
IV.4	Object Reporting.....	248
IV.4.1	History of an Environment.....	250
IV.4.2	History of an Object.....	254
IV.4.3	Directory List	258
IV.4.4	Directory Compare	264
IV.4.5	Cross-Reference	269
IV.4.6	Checked-out Objects.....	271
IV.4.7	Objects Archived by N2OPURGE	281
IV.4.8	Archive Version Summary.....	284
IV.4.9	Events Pending for an Object.....	287
IV.5	Statistical Reporting.....	293
IV.5.1	Events Pending Autocompile for a Library	294
IV.5.2	Events Pending for an Environment.....	296
IV.5.3	Objects Migrated	298
IV.5.4	Objects Migrated by a User.....	300
IV.5.5	Objects Migrated for an Event.....	302
IV.5.6	Objects Migrated by Change Control	304
IV.5.7	Statistical Reporting in Batch	306
IV.6	Security Reporting	307
IV.6.1	N2O User Security	308
IV.6.2	User Groups	311
IV.6.3	Event Authorization	313
IV.6.4	Approval Profiles	316
IV.6.5	Function Profiles.....	318
IV.6.6	Migration Profiles.....	320
IV.6.7	Predict Profiles	324
IV.6.8	3GL Profiles.....	326
IV.6.9	Security Reporting in Batch.....	328
V.	TOOLBOX SUBSYSTEM	331
V.1	Introduction.....	331
V.2	Documentation Tools.....	333
V.2.1	Natural Object Listing	335
V.2.2	Map Listing	339
V.2.3	Data Area Listing.....	345
V.2.4	File Layouts	347
V.2.5	Descriptor X-REF Information	349
V.2.6	Object Flow Analysis	351
V.2.7	Object X-REF	354
V.2.8	SYSERR Message Listing.....	356
V.2.9	Archived 3GL Object Listing.....	359
V.2.10	Batch Documentation Process	362
V.3	Maintenance Tools	364
V.3.1	N2OPURGE Utility	365
V.3.2	Recover from an Archive Backup (Batch Only).....	372

V.3.3	Archive Backup Report (Batch Only).....	377
V.3.4	Recover from an Event Backup (Batch Only).....	380
V.4	Programmer Tools.....	382
V.4.1	Object Compare	383
V.4.2	Source Compare	385
V.4.3	N2OSCAN Utility	395
V.4.3.1	Scan Parm Sets	396
V.4.3.2	N2OSCAN Utility.....	399
V.4.3.2.1	Environment Scan Utility.....	400
V.4.3.2.2	Library Scan Utility.....	401
V.4.3.2.2.1	Select Scan Parm Set Function	402
V.4.3.2.2.2	Check Scan Parm Set Function	404
V.4.3.2.2.3	Execute Scan Function	406
V.4.3.2.3	Select Scan Output Set Function.....	410
V.4.3.2.3.1	Summary of Scan Output (Inquire Function).....	412
	The Summary of Scan Output pop-up window displays summary statistics for a Scan Output Set.	412
V.4.3.2.3.2	Select Library Scan Output Set (List Libs Scanned)	414
V.4.3.2.3.2.1	Select Object Scan Output Set Function	416
V.4.3.2.3.2.1.1	Scan Output Detail Function (List Strings Found)	419
V.4.3.2.3.2.1.2	Object Source View	421
V.4.3.2.3.2.1.3	Batch Source Display	422
V.4.3.2.3.2.2	Output Standard Report.....	425
V.4.3.2.4	Delete Scan Output Set Function	428
V.4.3.2.4.1	Batch Delete of Scan Output Set	430
V.4.3.2.4.2	String Found Report.....	431
V.4.3.2.5	Administrative Delete Scan Output Set Function.....	434
V.5	Utility Tools	436
V.5.1	Delete Checkout Records	438
V.5.2	Check for Duplicate Checkout Records	439
V.4.5.17.2	N2OSCAN Output Standar Report.....	439
V.5.3	Change an Event Status	440
V.4.5.17.2	N2OSCAN Output Standar Report.....	440
V.5.4	Display Header Record for an Event.....	441
V.4.5.17.2	N2OSCAN Output Standar Report.....	441
V.5.5	Display Event Detail Records for an Object	442
V.4.5.17.2	N2OSCAN Output Standar Report.....	442
V.5.6	Display All Records Related to an Event.....	443
V.5.7	Display All 0XXXXXXX Libraries	444
V.5.8	Display All 0XXXXXXX Programs in a Library	444
V.5.9	Delete All 0XXXXXXX Libraries	444
V.5.10	Unlock a Master Event	445
V.4.5.17.2	N2OSCAN Output Standar Report.....	445
V.5.11	Delete a User Canceling all their Checkouts.....	446
V.5.12	Delete 3GL Master Records.....	447
APPENDIX A	N2O Direct Commands	A-1
APPENDIX B	N2O Event Status	B-1
APPENDIX C	Error Messages	C-1
D.1	– Base N2O batch functions.....	D-1
	Archive Purge	D-1
	Catalog Capture.....	D-7
	Object Compare.....	D-11
	Source Compare - remote environments.....	D-12
	Source Compare – local environments.....	D-16
	Deferred Moves	D-18

Emergency Recovery in Batch	D-22
Emergency Recovery Acknowledgement	D-23
Event Purge	D-26
Batch Migration.....	D-29
N2OPURGE.....	D-35
Recover from Archive backup (Natural objects)	D-39
Recover from archive backup (3GL PDS Objects)	D-42
Recover Purged Events.....	D-43
Reporting	D-45
N2OSCAN	D-47
N2OSCAN delete specific scan output set	D-48
N2OSCAN Batch Delete by Date and User ID	D-49
N2OSCAN Batch source display	D-51
N2OSCAN	D-53
N2OSCAN Standard report	D-55
N2OSCAN String found report.....	D-56
Batch Update of Environment FUSER/FDIC Information	D-57
Archive Backup Reporting	D-59
3GL compile.....	D-61
3GL batch submit.....	D-61
D.2 – 3GL PDS JCL	D-62
PDS archive	D-62
PDS Catalog Capture	D-63
PDS Compile	D-63
PDS Move.....	D-64
PDS Migration.....	D-64
PDS archive recovery	D-65
PDS Archive recovery.....	D-65
3GL member submit to PREDICT pre-processor	D-66
D.3 – Panvalet JCL	D-67
Panvalet Catalog Capture.....	D-67
Panvalet Compile.....	D-67
Panvalet Migration	D-68
D.4 - Endeavor JCL	D-69
Endeavor Catalog capture	D-69
Endeavor migration.....	D-70
D.5 - Librarian JCL	D-71
Librarian catalog capture	D-71
Librarian Compile.....	D-71
Librarian migration	D-72
D.6 - DB2 related JCL	D-74
D.7 - Network Data Mover sample JCL	D-80
APPENDIX E Frequently Asked Questions.....	E-1
APPENDIX F N2OSCAN Glossary.....	F-1

This page intentionally left blank.

SECTION I

INTRODUCTION

I.1 Change Management Using N2O

N2O is an exceptional change management tool for programmers and others involved in application development. It performs many tasks including the following:

- Controls, monitors, and coordinates program changes made to applications
- Quickly and efficiently incorporates program changes into production
- Protects the integrity of production code and program changes
- Ensures that changes are tested and approved before being implemented
- Secures migrations by defining migration paths for users
- Archives and recovers previous versions of programs for an application
- Coordinates programming-related activities of development staff
- Maintains complete audit trails to provide the history of all program changes
- Tracks the status of changes and assists in managing projects
- Compares the differences between two NATURAL source programs, two NATURAL object programs, or two environments
- Documents and prints NATURAL objects, File Layouts, Descriptor X-Ref (Cross-Reference) Information, Object Flow Analysis, and Object X-Ref in local N2O environments
- Scans for strings over the object/library range specified by the user and reports on (and records for future lookup) all matches

These tasks help to minimize paper trails, secure environments, improve programmer productivity, reduce management review time, and add to the integrity of applications.

N2O provides Change Management for DDMS, METADATA, NATURAL objects, PREDICT objects, and SYSERR messages.


DDM	Data Definition Modules (DDM)
METADATA	METADATA for User Defined Entities
NATURAL objects	Any of the following in source and/or object format: programs, subprograms, subroutines, copycode, help routines, maps, global data areas, local data areas, parameter data areas, classes, adapters, dialogs, command processors, and text.
PREDICT objects	Any of PREDICT's predefined object types. N2O requires PREDICT version 3.1 or later for migrating PREDICT objects.
SYSERR messages	User-supplied messages in short and/or extended form.

N2O/3GL, a separately-priced optional feature, provides Change Management for 3GL objects by interfacing with ENDEAVOR, The LIBRARIAN, and PANVALET. N2O/3GL also migrates 3GL objects between OS/390 (MVS) Partitioned Datasets (PDSs) using the IEBCOPY Utility.

3GL objects

Any of the following categories: Assembler, COBOL, FORTRAN, PL/I, RPG, JCL, DATA, MISC, or OTHER.

The Change Management process begins with a request to correct problems, enhance features, or add new applications. To perform these tasks, programmers may migrate or transfer objects from one environment to another. These migrations define an Application Life Cycle.



Sample Application Life Cycle

The diagram above shows a sample Application Life Cycle consisting of three environments: Production (PROD), Development (DEV), and Test (TEST). The diagram also shows an Archive file (ARCH) which contains previous versions of programs.

A programmer migrates objects from the Production environment to the Development environment to initiate a change request. The Production versions of the objects are modified and tested in Development.

After modifying objects in the Development environment, programmers may migrate them to the Test environment where they can be evaluated and tested before being migrated to Production. Typically, a testing or quality assurance group must approve an object for migration to Production. If problem areas are identified during testing, the modified objects may be rejected back to Development. Programmers may then correct these problems and migrate the objects back to Test again. This cycle may be repeated several times. When testing is complete, the objects may be approved to migrate to Production, completing the Change Management process.

Note: Individual site Application Life Cycles may vary greatly from the sample.

N2O Events

An Event is the process of migrating an object between environments using N2O. Examples of Event names are: GEN-LEDG, PAYROLL, and BENEFITS. All migrations in the N2O system have an Event name and an Event sequence number. Event sequence numbers are internally assigned during the migration process.

Once an Event is created, the objects may be migrated immediately, or they may require authorization for migration. If authorization is required, the specified objects will not be migrated until proper authorization is obtained.

I.2 N2O Subsystems

N2O is divided into five Subsystems, each having a separate responsibility within the Change Management process. These Subsystems are logically arranged so that many similar functions can be executed within the same Subsystem.

Environment Subsystem

After installing N2O, the N2O Administrator must define the site's environment and Change Management requirements using the Environment Subsystem. Information and instructions for this subsystem are located in the ***N2O Administrator Manual***.

Migration Subsystem

The Migration Subsystem initiates the Change Management process by creating and processing Events.

This Subsystem allows users to create Events by selecting objects to migrate. These objects include DDMS, METADATA and NATURAL objects, PREDICT objects, 3GL/OTHER objects, and SYSERR messages. N2O verifies authorization for users before processing an Event. If authorization is necessary, N2O holds the Event until the proper authorization is provided. Once authorization occurs, N2O migrates the objects to the specified environment and stores information about the Event.

N2O provides Checkout/Checkin, a feature that controls and monitors changes in an Application Life Cycle. Checkout/Checkin is designed to protect the integrity of objects throughout the Application Life Cycle and to provide an audit trail. N2O can limit multiple checkouts for an object and prevents objects from being overwritten.

Project Tracking Subsystem

The Project Tracking Subsystem maintains detailed information about projects and associated tasks.

Project Tracking can be used to collect requests for changes to a project from users at all levels. A request for a change then becomes a task for a specific project. A task is documented and its progress can be tracked as it advances from one stage to another.

The Project Tracking Subsystem can be used for NATURAL and non-NATURAL application development, as well as other non-programming projects.

Reporting Subsystem

The Reporting Subsystem provides vital information for users, such as administrators, programmers, and auditors. For example, the checked-out Objects Report assists programmers in identifying objects currently checked out.

Toolbox Subsystem

The Toolbox Subsystem supplies application development tools for administrators and programmers. These tools aid in the development, maintenance, and documentation of NATURAL applications.

User-Defined Subsystem

The User-Defined Subsystem allows site-specific, customized programs to be accessed from the N2O menu system

I.3 N2O Features

N2O automates the Change Management process by offering many features, including the following:

Archiving/Recovery

Archiving/Recovery retains previous versions of NATURAL objects, PDS members, and SYSERR messages for future recovery. Users may access the Archive file to view and to recover these versions.

Audit Trail

The Audit Trail maintains information about Events and migrated objects.

Autocompile

Autocompile automates the NATURAL object and 3GL member compile process.

Checkout/Checkin

Checkout/Checkin controls and monitors object changes and protects the integrity of objects throughout the Application Life Cycle.

Compare Utilities

Compare utilities provide reports that identify the differences between two NATURAL source programs, two NATURAL object programs, or two environments.

Cross Reference (XREF)

Cross Reference (XREF) uses PREDICT XREF information to identify all related programs affected or invoked by a object selected to be migrated. XREF is available only for NATURAL objects.

Documentation Toolbox

Documentation Toolbox function provides utilities to print NATURAL objects, File Layouts, Descriptor X-Ref (Cross-Reference) Information, Object Flow Analysis, Object X-Ref, NATURAL SYSERRs, and Archived 3GL Objects in local N2O environments.

N2OSCAN

The N2OSCAN utility processes the source of NATURAL objects, scanning for strings over the object/library range specified by the user, and reports on (and records for future lookup) all matches.

On-line Authorization

On-line authorization ensures integrity and secures applications by allowing only authorized users to migrate objects between environments. This feature provides up to ten levels of authorization, and allows the N2O Administrator to specify the order of authorization. Routine migrations may not require any authorization.

On-line/Batch Migration

On-line/Batch Migration provides the flexibility of migrating objects on-line or in batch. On-line migrations allow users to migrate objects immediately. Batch migrations allow users to schedule migrations for specific times.

On-line Request System

The On-line Request System allows a user to select objects to migrate.

Project Tracking

Project Tracking allows the progress of programming projects and non-programming projects to be assessed quickly through on-line and batch reports.

Reporting

Reporting provides reports about Events and objects by accessing information stored as an audit trail within N2O.

Security

Security controls the migration of objects and access to N2O menus and functions.

User-exits

User-exits provide the flexibility to tailor N2O for site-specific needs, such as additional security and the ability to interface with other software.

I.4 The N2O User Interface

The N2O interface makes the setup and operation of the product easy and trouble-free. N2O makes use of PF-keys, supports the use of direct commands, has an on-line help facility, and has an error trapping system.

There are several types of screens that are used throughout N2O:

Startup Screens

Startup screens display authorization and version information about N2O.

Menu Screens

Menu screens display sub-functions and allow the selection of a sub-function.

Data Entry Screens

Data entry screens display input fields for entering data necessary to perform N2O functions.

Selection Screens

Selection screens display a list of items available for possible processing.

Help Screens

Help screens display information about the current function or valid data for the field.

Error Message Screens

Error message screens display information about an error that has occurred during the use of N2O.

Startup Screens

Entering "N2O" at the NATURAL "Next" prompt or logging on to the library N2OLIB and typing "Menu" displays the N2O startup screen.

```

      NN      NN      0000
      NNN     NN      00  00
      NNNN    NN      00  00
      NN  NN  NN      00  00
      NN  NN  NN      00  00
      NN  NNNN  22    22  00  00
      NN  NNN   22    00  00
      NN      NN    22    0000
                22
                22
                22222222

Authorized for use      N-2-O Trademark Pending      VERSION : 5.3
by licensee only      (C) COPYRIGHT 1988-2015      SM  LVL : 1

Treehouse Software, Inc.
2605 Nicholson Road Suite 230
Sewickley, Pennsylvania
(724) 759-7070

tsi@treehouse.com      www.treehouse.com      support@treehouse.com

Press ENTER to continue

```

Menu Screens

N2O menu screens display only the sub-functions listed in a user's security definition and contain an Enter Code field, a Direct Command line, and PF-keys. Menu screens are labeled in the lower right corner, identifying the Direct Command that accesses the menu screen.

01-12-31 11:38:00	N-2-O MAIN MENU	TSI0373 TSI1														
	<table><thead><tr><th>Code</th><th>Function</th></tr></thead><tbody><tr><td>E</td><td>Environment Subsystem</td></tr><tr><td>M</td><td>Migration Subsystem</td></tr><tr><td>R</td><td>Reporting Subsystem</td></tr><tr><td>T</td><td>Toolbox Subsystem</td></tr><tr><td>U</td><td>User-Defined Subsystem</td></tr><tr><td>.</td><td>Terminate N-2-O Session</td></tr></tbody></table>	Code	Function	E	Environment Subsystem	M	Migration Subsystem	R	Reporting Subsystem	T	Toolbox Subsystem	U	User-Defined Subsystem	.	Terminate N-2-O Session	
Code	Function															
E	Environment Subsystem															
M	Migration Subsystem															
R	Reporting Subsystem															
T	Toolbox Subsystem															
U	User-Defined Subsystem															
.	Terminate N-2-O Session															
Enter Code : M																
Direct Command: _____ N2O MENU																
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---																
HELP ---- END ENV MIG REP TOL USR PRJ ---- ---- EXIT																

The Enter Code field allows users to select a menu sub-function. For example, on the screen above, entering "M" in the Enter Code field accesses the Migration Subsystem Menu.

The Direct Command line allows users to directly access menu screens. For example, entering MIG MENU on the Direct Command line accesses the Migration Subsystem Menu.

The Direct Command line may also be used to update changes made to a user's security during the user's N2O session by entering "REFRESH" on the Direct Command line. NATURAL System commands may be executed using the Direct Command line. Each NATURAL System command must be preceded by SYS. For example, entering SYS FIN exits N2O and NATURAL.

The PF-keys allow users to request help, end the function, access menu screens, or exit N2O. PF-keys 13-24 provide the same functions as PF-keys 1-12. For example, pressing PF1 or PF13 displays on-line help.

N2O screens, except for the startup screens, follow a standard template. The upper left corner of the screen displays the date and time. The upper right corner of the screen displays the User-ID and Terminal-ID. The top middle of the screen displays the name of the current N2O screen.

Data Entry Screens

Data entry screens allow users to enter data to perform N2O functions.

```

13-10-04          N-2-O OBJECT REPORTING          TSI0373
14:01:18          HISTORY OF AN OBJECT            SC0TCP06

Object           : _____
Library          : _____
Date Range       : _____ - _____
List Events      : A (All/Closed/Open)
Detailed Report  : N (Batch Only)
Mode             : O

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
HELP  ----  END   ----  ----  ----  ----  ----  ----  ----  ----  ----  ----

```

For example, the History of an Object report requires an object name and a mode specification to display the history of an object. The Library and Date Range are optional fields that limit the output of the report.

Selection Screens

Selection screens display a list of items available for possible processing.

```

Valid Values: C - Copy D - Delete I - Inquire M - Modify
01-12-31          N-2-O SELECT EVENTS FOR PROCESSING          TSI0373
11:38:00          STATUS:O                                    TSI1

S      Event  Seq  From To  Event  ----Added----  ----Task----
-      -----  -      -      -      -      -      -      -
-      EXTRACT 3311 EXTP EXTM N      TSI1    01-12-31  *****
-      PAYOUT 1245 PAYP PAYD N      TSI1    01-12-31  *****

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
HELP  ----  END   ----  CHNG  ----  ----  ----  ----  ----  ----  ----

```

For example, the Select Events for Processing screen displays a list of Events. Entering D, I, or M in the Select field next to an Event identifies the function (Delete, Inquire, or Modify) to be performed.

Help Screens

Help Screens are available on Menu and Data Entry screens. There are two types of help screens: field-level help and screen-level help.

Field-Level Help

Pressing PF1 or entering "?" on a field invokes field-level help (if it is available).

01-12-31 11:38:00	N-2-O MAIN MENU	TSI0373 TSI1
	Code Function	

	E Environment Subsystem	
	M Migration Subsystem	
	R Reporting Subsystem	
	T Toolbox Subsystem	
	U User-Defined Subsystem	
	. Terminate N-2-O Session	

	Enter Code : _	
Direct Command: ? _____		N2O MENU
Enter-PF1---	PF2---	PF3---
PF4---	PF5---	PF6---
PF7---	PF8---	PF9---
PF10---	PF11---	PF12---
HELP ----	END ENV	MIG REP
TOL USR	PRJ ----	EXIT

For example, entering "?" on the Direct Command line invokes field-level help for direct commands.

After entering "?" on the Direct Command line, the pop-up window below displays a list of Direct Commands.

```

01-12-31                      N-2-O MAIN MENU                      TSI0373
11:38:00                                                              TSI1

                                Code  Function
+-----+-----+-----+-----+
|Please select a screen name|
| X  Command              Description|
+-----+-----+-----+-----+
| -   N2O MENU  MAIN MENU|
| -   ENV MENU  ENVIRONMENT SUBSYSTEM MENU|
| -   ENV ARCH  ARCHIVE DEFINITION MENU|
| -   ENV NODE  NODE DEFINITION MENU|
| -   ENV EVNT  MASTER EVENT MENU|
| X   ENV PARM  INSTALL FARMS MENU|
| -   ENV MIG   MIGRATION PROFILE MENU|
| -   ENV DEF   ENVIRONMENT DEFINITION MENU|
+-----+-----+-----+-----+

Direct Command:  ?_____ N2O MENU
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      HELP  ----  END   ENV   MIG   REP   TOL   USR   PRJ   ----  ----  EXIT

```

Users may select a direct command by entering "X" in the Select field next to the command. For example, the screen above indicates "ENV PARM" has been selected. After pressing Enter, "ENV PARM" is then inserted on the Direct Command line.

Pressing Enter without selecting an item displays the next page of the selection list. Pressing Enter on the last page displays the top of the selection list. Pressing PF3 returns to the screen.

Throughout the manual, the availability of field-level help is identified with an infinity character (∞) beside the field in the field description table.

Screen-Level Help

Pressing PF1 or entering "?" in a field that does not have field-level help invokes screen-level help.

```

01-12-31          N-2-O HELP SCREEN FOR N2O0000P          11:38:00

N2O Main Menu

Field             Description                                *
-----
ENTER CODE       The function to be executed.  Valid values
(required)       are as follows:

                  E   Environment Subsystem
                  Defines site standards for Change Management
                  *
                  M   Migration Subsystem
                  Migrates programs in a controlled manner using
                  information defined in the Environment Subsystem
                  *
                  P   Project Tracking Subsystem
                  Maintains detailed information about Projects and
                  tracks the progress of changes within those Projects
                  *

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
----- END ----- TOP   UP   DOWN  BOT  -----

```

For example, the screen above displays screen-level help for the N2O Main Menu.

All screen-level help for N2O is stored in the library N2ODOCS and may be modified by editing the program name identified at the top of the Help screen. For example, N2O0000P is the program to be accessed for editing help information for the above screen. Screen-level help displays a maximum of 36 lines of text.

The following PF-keys are provided for screen-level help:

<u>Key</u>	<u>Function</u>	<u>Description</u>
PF3	END	ends screen-level help
PF6	TOP	pages to the top of the text
PF7	UP	pages up (back) through the text
PF8	DOWN	pages down (forward) through the text
PF9	BOT	pages to the bottom of the text

Error Message Screens

Error Message screens display information about an error and identifies the N2O program that was running when the error occurred.

```
01-12-31          N-2-O FATAL ERROR DETECTED          TSI0373
11:38:00                                     TSI1

      A FATAL ERROR HAS BEEN DETECTED BY N2O ROUTINE:  N2O1380N
      THE FOLLOWING ERROR MESSAGE WAS PROVIDED BY THE FAILING ROUTINE:

      PGM: N2O9200N CMD: L9 CID: L9SR RC: 9 TRACK: RSRC

      Please contact your N-2-O System Administrator or
      Treehouse Software, Inc.
      409 Broad Street, Suite 140
      Sewickley, PA 15143  USA
      (412) 741-1677
      tsi@treehouse.com          www.treehouse.com          support@treehouse.com

      THIS N-2-O SESSION WILL BE TERMINATED.

      PRESS ENTER TO PROCEED.
```

For example, the screen above shows that program N2O1380N called the subprogram N2O9200N and received a response code 9. The solution to response code 9 is restarting N2O.

Have the PGM, CMD, CID, RC, and TRACK information available when calling Treehouse Software.

This page intentionally left blank.

SECTION II

MIGRATION SUBSYSTEM

II.1 Introduction

The Migration Subsystem is the core of N2O where Events are created. An Event is the process of migrating NATURAL objects, PREDICT objects, 3GL/OTHER objects, and/or SYSERR messages between environments using N2O.

The Migration Subsystem is used by developers to create and maintain Events, as well as by managers and support personnel to authorize Events. The Migration Subsystem relieves the DBA and systems administration staff of the day-to-day tasks associated with change management.

The Migration Subsystem section presents topics in the following order:

- Request Events
- Authorize Events
- Service Events
- Migration Utilities
- Checkout/Checkin Utilities
- Batch JCL Submission

Note: Field description tables in this section display valid object types for fields. Object types include the following: DDMS (D), METADATA (M), NATURAL objects (N), PREDICT objects (P), 3GL/OTHER objects (O), and SYSERR messages (S).

To access the Migration Subsystem menu, enter "M" on the N2O Main menu, enter the direct command MIG MENU, or press PF5 on any menu.

01-12-31 11:38:00	N-2-O MAIN MENU	TSI0373 TSI1																
	<table><thead><tr><th>Code</th><th>Function</th></tr></thead><tbody><tr><td>E</td><td>Environment Subsystem</td></tr><tr><td>M</td><td>Migration Subsystem</td></tr><tr><td>P</td><td>Project Tracking Subsystem</td></tr><tr><td>R</td><td>Reporting Subsystem</td></tr><tr><td>T</td><td>Toolbox Subsystem</td></tr><tr><td>U</td><td>User-Defined Subsystem</td></tr><tr><td>.</td><td>Terminate N-2-O Session</td></tr></tbody></table>	Code	Function	E	Environment Subsystem	M	Migration Subsystem	P	Project Tracking Subsystem	R	Reporting Subsystem	T	Toolbox Subsystem	U	User-Defined Subsystem	.	Terminate N-2-O Session	
Code	Function																	
E	Environment Subsystem																	
M	Migration Subsystem																	
P	Project Tracking Subsystem																	
R	Reporting Subsystem																	
T	Toolbox Subsystem																	
U	User-Defined Subsystem																	
.	Terminate N-2-O Session																	
	Enter Code: _																	
Direct Command: _____		N2O MENU																
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---																		
HELP ---- END ENV MIG REP TOL USR PRJ ---- ---- EXIT																		

After following the instructions on the previous page, the Migration Subsystem menu is displayed.

```

01-12-31          N-2-O MIGRATION SUBSYSTEM MENU          TSI0373
11:38:00                                     TSI1

          Code  Function
          ----  -
          A    Authorize Events
          B    Batch JCL Submission
          C    Checkout/Checkin Utilities
          M    Migration Utilities
          R    Request Events
          S    Service Events
          .    Terminate Migration Subsystem
          ----  -

Enter Code:  _

Direct Command:  _____  MIG MENU
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      HELP  ----  END  ENV  ----  REP  TOL  USR  PRJ  ----  ----  EXIT

```

Field	Description
Enter Code	<p>The function to be executed. Valid values are as follows:</p> <p>A Authorize Events Authorizes open Events that require authorization.</p> <p>B Batch JCL Submission Submits batch JCL to the systems internal reader.</p> <p>C Checkout/Checkin Utilities Updates the Checkout/Checkin status of objects and provides the ability to enroll new objects.</p> <p>M Migration Utilities Performs Autocompile (if necessary) and completes the MOVE process for Events.</p> <p>R Request Events Creates and maintains Events.</p> <p>S Service Events Processes authorized Events that require servicing.</p>

II.2 Request Events

The Request Events function initiates the migration process. This function allows users to request Events to migrate DDMS, METADATA, NATURAL objects, PREDICT objects, 3GL/OTHER objects, and/or SYSERR messages. Events are created using a Master Event, which provides default values for the Event. Master Events may define a Single Target Event or Multiple Target Event.

Multiple Target Events allow a user to migrate DDMS, NATURAL objects, PREDICT objects, and/or SYSERR messages from one environment to several environments using one Event. 3GL/OTHER objects cannot be migrated to multiple targets. The targets for the Event are identified on the Master Event.

Checkout/Checkin

N2O provides Checkout/Checkin, an optional feature that controls and monitors changes in an application life cycle. It is designed to protect the integrity of objects throughout the application life cycle and to provide an audit trail. N2O limits multiple checkouts for an object and prevents objects from being overwritten.

To use Checkout/Checkin, at least one environment must be defined as a BASE environment. A BASE environment serves as a repository for source code. All non-BASE environments are referred to as "development" environments. The Checkout/Checkin feature does not permit migrations between BASE environments.

There are two methods for checking out objects:

- Existing objects are marked as checked-out when an object is selected to migrate from a BASE environment to a development environment.
- New objects in a development environment may be marked as checked-out using the Checkout Utility. For more information, refer to **Section II.6 Checkout/Checkin Utilities**.

The maintenance cycle of an existing object typically begins when it migrates from a BASE environment to a development environment. The object may continue to migrate to other development environments (e.g., system test, training, quality assurance). The cycle ends when the object migrates back to the original BASE environment. N2O then marks the object as checked-in.

When Checkout/Checkin is active, an Extract Event may be used to copy objects to a development environment without changing the Checkout status. These objects are not checked out and may be copied regardless of their current Checkout status. The following restrictions apply to Extract Events:

- The target cannot be a BASE environment.
- The migration cannot overwrite currently checked-out objects.
- The Migration method must be COPY.

When creating Multiple Target Events, the first migration path is verified against Checkout/Checkin rules. All other paths are verified against Extract rules.

Note: Once an object is checked out, only the Checkout user may request further migrations of the object. If the N2O Administrator has installed N2OEDIT, NATURAL objects checked out to a user may be edited by that user only.

When Checkout/Checkin is active, Checkout/Checkin rules are verified during the selection process. Unless a request violates the rules, the Checkout/Checkin process is transparent to the user. When an object is selected to migrate from a BASE environment, N2O marks the object as checked out. Once an object is checked out, subsequent migrations must be initiated from the current checkout location by the current checkout user. The object selection screen for migrations from development environments only displays objects the user has checked out.

The final step in the development cycle is to migrate an object back to the BASE environment for checkin. The same user responsible for the checkout must perform the checkin, and the migration must originate from the current checkout location.

The following apply when performing migrations with Checkout/Checkin active:

Migrating from BASE to Development (Checkout)

- An object is considered checked-out immediately after it is selected to migrate.

Migrating between Development Environments

- The object must be currently checked out to the requesting user.
- The Event must be initiated from the current checkout location of the object.

Migrating from Development to BASE (Checkin)

- The object must currently be checked out by the requesting user.
- The Event must be initiated from the current checkout location of the object.
- The object is considered checked-in when the object is migrated.

To access the Request Events menu, enter "R" on the Migration Subsystem menu or enter the direct command MIG REQ on any menu.

01-12-31 11:38:00	N-2-O REQUEST EVENTS MENU		TSI0373 TSI1
	Code	Function	
	----	-----	
	A	Add an Event	
	C	Copy an Event	
	D	Delete an Event	
	I	Inquire on an Event	
	M	Modify an Event	
	R	Recovery from Archive	
	S	Select Events for Processing	
	.	Terminate Request Event Menu	
	----	-----	
	Enter Code: _	Event : _____	Type : N____
		Sequence : _____	Status: _
Direct Command _____ MIG REQ			
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---			
HELP ---- END ENV MIG REP TOL USR PRJ ---- ---- EXIT			

Field	Description
ENTER CODE	<p>The function to be executed. Valid values are as follows:</p> <p>A Add an Event Creates an Event for migrating objects.</p> <p>C Copy an Event Creates an Event for migrating objects by copying an existing Event.</p> <p>D Delete an Event Removes an Event that no longer needs to be processed.</p> <p>I Inquire on an Event Displays information about an Event.</p> <p>M Modify an Event Updates an Event.</p> <p>R Recovery from Archive Creates an Event for recovering objects.</p> <p>S Select Events for Processing Provides a list of Events that may be deleted, inquired on, or modified.</p>
∞ EVENT (required)	<p>The Master Event associated with the Event to be added or maintained. This name is a logical label used to differentiate individual migration paths. For the Select function, the name is used as a starting value.</p>
∞ TYPE (required for Add and Copy)	<p>The type of objects to migrate. Valid values are one or a combination of the following:</p> <p>N Indicates NATURAL objects. S Indicates SYSERR messages. P Indicates PREDICT objects. O Indicates 3GL/OTHER objects. D Indicates DDMS. M Indicates METADATA</p> <p>(METADATA and PREDICT objects (P) can not be migrated together)</p> <p>All object types may be migrated using a single Event (Default: N).</p>
SEQUENCE (required for Copy, Delete, Inquire and Modify)	<p>The Sequence number of the request to be maintained. For the Add function, N2O automatically assigns this number.</p>
∞ STATUS (optional)	<p>The Status selected for display. For valid values refer to Appendix B N2O Event Status.</p>
∞ indicates field-level help is available.	

II.2.1 Add an Event

The Add an Event function creates new Events for migrating objects.

To add an Event, enter "A" in the Enter Code field, the Master Event of the Event to be added in the Event field, and "D" (DDMS), "M" (METADATA), "N" (NATURAL objects), "P" (PREDICT objects), "O" (3GL/OTHER objects), and/or "S" (SYSERR messages) in the Type field on the Request Events menu.

```

01-12-31          N-2-O ADD AN EVENT          TSI0373
11:38:00          Event: PAYOUT      Sequence: 1      TSI1

      From Env      : PROD      From Library      : PAYPROD
      To Env        : DEV        To Library        : PAYDEV
      Process Date   : 20011231   Process Time     : 11:38:00
      Starting Program: _____
      Task Group     : _____ Task Number      : _____
      Include Objects from UEX15: N

C _____
o _____
m _____
m _____
e _____
n _____
t _____
s _____

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
HELP  ---  END  ---  ---  ---  ---  ---  ---  ---  ---  ---  ---  ---

```

In the screen above, the Event is "PAYOUT", Sequence "1". Sequence "1" was the first/next available sequence number assigned by N2O.

The Master Event provides the other default values displayed in the Add an Event screen.

The following Field Descriptions apply to all Request Events functions (Add, Copy, Delete, Inquire, and Modify).

Field	Type	Description
EVENT (supplied)	N,S,P,O, D,M	The Master Event of the migration.
SEQUENCE (supplied)	N,S,P,O, D,M	The sequence number of the Event.
FROM ENV (required)	N,S,P,O, D,M	The source Environment Definition of the migration. When using Add or Copy an Event, this field may be modified if the master Event is not locked.
FROM LIBRARY (required)	N,S	The library containing the NATURAL objects and/or SYSERR messages for the migration. When using Add or Copy an Event, this field may be modified if the master Event is not locked.
TO ENV (required)	N,S,P,O, D,M	The target Environment Definition of the migration. When using Add or Copy an Event, this field may be modified if the master Event is not locked. An "*" indicates the Event is a Multiple Target Event.

(continued from previous page)

Field	Type	Description
TO LIBRARY (required)	N,S	The library to which NATURAL objects and/or SYSERR messages are to be migrated. When using Add or Copy an Event, this field may be modified. An "*" indicates the Event is a Multiple Target Event.
PROCESS DATE (required)	N,S,P,O, D,M	The earliest date on which the batch migration may take place. N2O automatically supplies the current date for Add an Event and Copy an Event, but it may be modified by the user if postdating of the migration is desired. When using Add, Copy, or Modify an Event, this field may be modified. For more information about submitting batch Events, refer to Section II.7 Batch JCL Submission .
PROCESS TIME (required)	N,S,P,O, D,M	The earliest time during the Process Date on which the batch migration may take place. When using Add, Copy, or Modify an Event, this field may be modified.
STARTING PROGRAM (optional)	N	<p>The first NATURAL object to appear in the NATURAL object selection list. An "*" may be used as a wildcard character to start the selection list with NATURAL objects prefixed by a string (e.g., "PAY51*" shows a list of all NATURAL objects with names in the range of Starting Program "PAY51AAA" and Ending Program "PAY51999").</p> <p>If the user enters "*" as the Starting Program in an Event, all NATURAL objects are marked for migration. When using Add, Copy, or Modify an Event for NATURAL migrations, this field may be modified.</p> <p>If Program Dependent Master Events (PDME) are used, the Starting Program specified must be within the range of default values defined on the Master Event.</p>
STARTING MESSAGE (optional)	S	<p>The first SYSERR message to appear in the SYSERR message selection list.</p> <p>If the user enters "*" as the Starting Message in an Event, the entire application is marked for migration. When using Add, Copy, or Modify an Event for SYSERR migrations, this field may be modified.</p>

(continued from previous page)

Field	Type	Description
SYSERR TYPE (required if migrating SYSERR)	S	<p>The type of SYSERR messages to migrate:</p> <p>U Indicates user-supplied short messages are to be migrated.</p> <p>U Indicates user-supplied long (extended) L messages are to be migrated.</p> <p>U Indicates both short and long messages are to be migrated.</p> <p>When using Add or Copy an Event for SYSERR migrations, this field may be modified.</p>
SYSERR LANGUAGE (required if migrating SYSERR)	S	<p>The language to be migrated. Valid values are single alphanumeric characters in the ranges 1 - 9, A - Z and a - y. These values are equivalent to the values available for the *LANGUAGE system variable.</p> <p>* Indicates all languages are to be migrated.</p> <p>When using Add or Copy an Event for SYSERR migrations, this field may be modified, unless Checkout/Checkin is active.</p>
CHANGE CONTROL (required if Master Event change control='Y')	N,S,P,O, D,M	A value that relates multiple Events to a specific change request. This field is only displayed if Change Control is required. When using Add, Copy, or Modify an Event, this field may be modified.
TASK GROUP (required if Project Tracking on Master Event = 'Y')	N,S,P,O, D,M	A value that relates multiple Events to a specific Task Group from the N2O Project Tracking Subsystem. This field is only displayed if Project Tracking is required. When using Add, Copy, or Modify an Event, this field may be modified.
TASK NUMBER (required if Project Tracking on Master Event = 'Y')	N,S,P,O, D,M	A number that relates multiple Events to a specific task from the N2O Project Tracking Subsystem. This field is only displayed if Project Tracking is required. When using Add, Copy, or Modify an Event, this field may be modified.
INCLUDE OBJECTS FROM UEX15 (required)	N,S,P,O, D,M	"Y" indicates User-Exit 15 will be called to include Objects in the Event. "N" indicates User-Exit 15 will not be called. This field defaults to 'N'.
COMMENTS (optional)	N,S,P,O, D,M	A 10-line comment area describing the Event. When using Add, Copy, or Modify an Event, this field may be modified. If the master Event has Comments = 'YES', this field defaults to the Master Event comments.

Selecting Multiple Target Environments

01-12-31 11:38:00	N-2-O ADD AN EVENT Event: PAYMULT Sequence: 4	TSI0373 TSI1
From Env : PROD	From Library : PAYPROD	
To Env : *	To Library : *	
Process Date : 20011231	Process Time : 10:28:24	
Starting Pro		
Target Environments:		
C	DEV PAYDEV	
O	QA PAYQA1	
M		
E		
N		
T		
S		
Enter-PF1---PF2---PF3--- -PF10--PF11--PF12---		
HELP ---- END ----		

When "*" is specified for the Environment and Library, the user must define the multiple targets in which to migrate.

Field	Description
From Environment (supplied)	Environment from which objects are migrated.
Target Environments	Environment/library to which objects are migrated.

II.2.2 **Object Selection Process**

The object selection process allows users to select objects to migrate. A screen is displayed allowing objects to be selected. When objects are selected, a message providing information about the selection is displayed. For more information about messages displayed when objects are selected, refer to **Section II.2.11 Object Selection Screen Messages**.

The following PF-keys are provided for scrolling throughout the selection process:

<u>Key</u>	<u>Function</u>	<u>Description</u>
PF7	Up	Pages up (back) through the text
PF8	Down	Pages down (forward) through the text

Note: The object selection screens for each object type to be migrated will appear. When all object selection screens have been displayed the migration process begins. (Refer to **Section II.2.3 Migration Process**.)

II.2.2.1 Selecting NATURAL Objects

When adding, copying, or modifying an Event that includes NATURAL objects, the NATURAL object selection screen is displayed. When User-Exit 15 is invoked or when copying or modifying an Event, ADD, REPLACE, or WARNING messages will be placed next to previously selected objects. NATURAL objects with no message in the Message field may be selected to migrate. When migrating from a development environment with Checkout/Checkin active, only NATURAL objects checked out to the user are displayed.

```

For the Event:  Type A to Add or D to Delete Objects
01-12-31      N-2-O ADD AN EVENT                      TSI0373
11:38:00      Event: PAYOUT      Sequence: 1          TSI1

From Env: PROD      From Library: PAYPROD      To Env: DEV      To Library: PAYDEV
Starting Object:  PAY5100M

S  Object      Object      Type      S/C      Message      S  Object      Object      Type      S/C      Message
-  PAY5100M    MAP      S
A  PAY5110M    MAP      S
-  PAY5120S    SUB-RTN  S
-  PAY5140S    SUB-RTN  S
-  PAY5160S    SUB-RTN  S
A  PAY5200P    PROGRAM  S
-  PAY5210S    SUB-RTN  S
-  PAY5230S    SUB-RTN  S
-  PAY5250S    SUB-RTN  S

S  Object      Object      Type      S/C      Message      S  Object      Object      Type      S/C      Message
A  PAY5100P    PROGRAM  S
-  PAY5110S    SUB-RTN  S
-  PAY5130S    SUB-RTN  S
-  PAY5150S    SUB-RTN  S
A  PAY5200M    MAP      S
-  PAY5210M    MAP      S
-  PAY5220S    SUB-RTN  S
A  PAY5240S    SUB-RTN  S
-  PAY5260S    SUB-RTN  S

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
HELP  ALL  END  INQ  ----  ----  UP  DOWN  ----  ----  ----  STOP
  
```

Entering a value in the Starting Object field defines the NATURAL object where the selection list begins.

NATURAL objects are selected to migrate by entering "A" (Add) in the Select field next to each NATURAL object. Pressing PF2 automatically places "A" in the Select field next to all NATURAL objects on the selection screen. Entering "D" (Delete) in the Select field next to any of these NATURAL objects removes them from the Event. Pressing PF4 displays a pop-up window of all previously-selected NATURAL objects.

Once selections have been made and Enter is pressed, the screen below is displayed.

```

Press PF1 for more information about Messages
01-12-31      N-2-O ADD AN EVENT                      TSI0373
11:38:00      Event: PAYOUT      Sequence: 1          TSI1

From Env: PROD      From Library: PAYPROD      To Env: DEV      To Library: PAYDEV
Starting Object:  PAY5100M

S  Object      Object      Type      S/C      Message      S  Object      Object      Type      S/C      Message
-  PAY5100M    MAP      S
-  PAY5110M    MAP      S      REPLACE
-  PAY5120S    SUB-RTN  S
-  PAY5140S    SUB-RTN  S
-  PAY5160S    SUB-RTN  S
-  PAY5200P    PROGRAM  S      REPLACE
-  PAY5210S    SUB-RTN  S
-  PAY5230S    SUB-RTN  S
-  PAY5250S    SUB-RTN  S

S  Object      Object      Type      S/C      Message      S  Object      Object      Type      S/C      Message
-  PAY5100P    PROGRAM  S
-  PAY5110S    SUB-RTN  S      ADD
-  PAY5130S    SUB-RTN  S
-  PAY5150S    SUB-RTN  S
-  PAY5200M    MAP      S      REPLACE
-  PAY5210M    MAP      S
-  PAY5220S    SUB-RTN  S
-  PAY5240S    SUB-RTN  S      FAILED
-  PAY5260S    SUB-RTN  S

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
HELP  ----  END  INQ  ----  ----  UP  DOWN  ----  ----  C/O  STOP
  
```

The screen on the previous page allows the user to verify selections. A message is displayed in the Message field for the selected NATURAL objects. Add or Replace is the usual message that will appear. For more information about messages, refer to **Section II.2.11 Object Selection Screen Messages**.

When the 'FAILED' or 'WARNING' message is displayed next to an Object, place the cursor over the Object and use PF11 to display any existing Checkout information.

After selecting and verifying NATURAL objects on the current screen, pressing Enter displays the next screen of NATURAL objects. Pressing Enter on the last page or PF12 ends the current selection process.

XREF Selection Process for NATURAL Objects

The XREF (Cross-Reference) selection process for NATURAL objects identifies NATURAL objects affected or invoked by the objects selected to migrate. This process uses Cross-Reference information stored in PREDICT and is invoked following the selection process for NATURAL objects. Objects identified by XREF may optionally be added to the Event.

There are two options available: "Include XREF objects in the Event" or "Do not include XREF objects in the Event". The N2O Administrator determines which options are available for the XREF selection process for NATURAL objects on a user-by-user basis.

If the N2O Administrator specifies one option for the user, no pop-up window is displayed and the option assigned to that user is performed. However, if the N2O Administrator specifies both options for a user, a pop-up window allows the user to select one of the options for the Event.

01-12-31		N-2-O ADD AN EVENT		TSI0373	
11:38:00		Event: PAYOUT Sequence: 1		TSI1	
From Env: PROD		From Library: PAYPROD		To Env: DEV	
		Starting Object: PAY5100M		To Library: PAYDEV	

S	Object	Type		S/C	Message
-	PAY5100M	MAP	Select An Option	S	REPLACE
-	PAY5110M	MAP		S	ADD
-	PAY5120S	SUB-RTN	Include XREF objects in	S	
-	PAY5140S	SUB-RTN	the Event.	S	
-	PAY5160S	SUB-RTN		S	REPLACE
-	PAY5200P	PROGRAM	- Do not include XREF objects in	S	ADD
-	PAY5210S	SUB-RTN	the Event.	S	
-	PAY5230S	SUB-RTN		S	
-	PAY5250S	SUB-RTN		S	

Enter-PF1---	PF2---	PF3---	PF4---	PF5---	PF6---	PF7---	PF8---	PF9---	PF10---	PF11---	PF12---
HELP	----	END	----	----	TOP	UP	DOWN	BOT	----	----	STOP

If the first option in the pop-up window, "Include XREF objects in the Event", is selected, the selection screen below is displayed.

```

Type A To Add NATURAL Programs To The Event
01-12-31      N-2-O XREF LISTING      TSI0373
11:38:00      Event: PAYOUT      Sequence: 1      TSI1

From Env: PROD      From Library: PAYPROD      To Env: DEV      To Library: PAYDEV

  S  Object      Explanation      Objects selected to migrate
---  -
-  MENU1      Invoked by      MENU
-  MENU1      Invoked by      MENU
-  PAY5100P    Affected by Changes to      PAY5100M  PAY5110M
              and is Invoked by      MENU
-  PAY5210S    Invoked by      PAY5200P
-  PAY5230S    Invoked by      PAY5200P
-  PAY5250S    Invoked by      PAY5200P

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      HELP  ALL  END  INQ  ---  ---  ---  ---  ---  ---  ---  STOP
  
```

NATURAL objects identified by XREF are selected to migrate by entering "A" (Add) in the Select field next to each NATURAL object.

If the second option, "Do not include XREF objects in the Event", is selected, XREF processing is ignored.

II.2.2.2 **Selecting SYSERR Messages**

When adding, copying, or modifying an Event that includes SYSERR messages, the SYSERR message selection screen is displayed. When User-Exit 15 is invoked or when copying or modifying an Event, ADD, REPLACE, or WARNING messages will be placed next to previously selected objects. SYSERR messages with no message in the Message field are available to be selected to migrate. When migrating from a development environment with Checkout/Checkin active, only SYSERR messages checked out to the user are displayed.

For the Event: Type A to Add or D to Delete Objects									
01-12-31		N-2-O ADD AN EVENT						TSI0373	
11:38:00		Event: PAYOUT Sequence: 1						TSI1	
From Env: PROD		From Library: PAYPROD		To Env: DEV		To Library: PAYDEV			
Starting Object: 1010									
		SYSERR				SYSERR		SYSERR	
S	Object	Language	S/L	Message	S	Object	Language	S/L	Message
A	1010	E	S		A	1015	E	S	
-	1015	E	S		-	1040	E	S	
-	1030	E	S		-	1060	E	S	
-	1040	E	S		-	1070	E	S	
-	1050	E	S		A	1090	E	S	
-	1055	E	S		-	1110	E	S	
-	1060	E	S		-	1125	E	S	
-	1070	E	S		-	1140	E	S	
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---									
HELP ALL END INQ ---- TOP UP DOWN BOT ---- ---- STOP									

Entering a value in the Starting Object field defines the SYSERR message where the selection list begins.

SYSERR messages are selected to migrate by entering "A" (Add) in the Select field next to each SYSERR message. Pressing PF2 automatically places "A" in the Select field next to all SYSERR messages on the selection screen. Entering "D" (Delete) in the Select field next to any of these SYSERR messages removes them from the Event. Pressing PF4 displays a pop-up window of all previously-selected SYSERR messages.

Once selections have been made and Enter is pressed, the screen below is displayed.

```

Press PF1 for more information about Messages
01-12-31      N-2-O ADD AN EVENT      TSI0373
11:38:00      Event: PAYOUT   Sequence: 1      TSI1

From Env: PROD      From Library: PAYPROD      To Env: DEV      To Library: PAYDEV
Starting Message: 1010

      SYSERR
S  Object      Language  S/L  Message      S  Object      Language  S/L  Message
-  1010      E          S      ADD      -  1015      E          S      ADD
-  1015      E          S          -  1040      E          S
-  1030      E          S          -  1060      E          S
-  1040      E          S          -  1070      E          S
-  1050      E          S          -  1090      E          S      FAILED
-  1055      E          S          -  1110      E          S
-  1060      E          S          -  1125      E          S
-  1070      E          S          -  1140      E          S

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      HELP  ----  END  INQ  ----  TOP  UP    DOWN  BOT  ----  C/O  STOP
  
```

This screen allows the user to verify selections. A message is displayed in the Message field for selected SYSERR messages. Add or Replace is the usual message that will appear. For more information about messages, refer to **Section II.2.11 Object Selection Screen Messages**.

When the 'FAILED' or 'WARNING' message is displayed next to an Object, place the cursor over the Object and use PF11 to display any existing Checkout information.

After selecting and verifying SYSERR messages on the current screen, pressing Enter displays the next screen of SYSERR messages. Pressing Enter on the last page or PF12 ends the current selection process.

II.2.2.3 Selecting PREDICT Objects

When migrating PREDICT objects, the user must select PREDICT object types to migrate.

After pressing Enter on the Add an Event screen, a pop-up window is displayed to allow users to select PREDICT object types to be displayed for selection.

```

01-12-31          N-2-O ADD AN EVENT          TSI0373
11:38:00          Event: PAYOUT              Sequence: 1      TSI1

From Env      : +-----+ : PAYPROD_
To Env        : |       | : PAYDEV_
Process Date   : | - - - - - | : 11:38:00
Starting Program: | - DA - PR | age : 0001
SYSEERR Type   : | - DC - RL | ge  : E
Change Control : | - ET - RP |
              Includ | - FI - RT | : N
C              | - KY - SC |
o              | - LS - SV |
m              | - MO - SY |
m              | - NO - US |
e              | - NW - VE |
n              | - PG - VM |
t              | - UDE -   |
s              +-----+

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
HELP  ----  END  ----  ----  ----  ----  ----  ----  ----  ----  ----

```

A separate object selection process is used for each PREDICT object type marked with "X" on the above pop-up window.

Field	Type	Description
X (optional)	P	"X" selects the PREDICT object types to be displayed for selection.
OBJECTS (supplied)	P	PREDICT objects may be selected from the following PREDICT object types:
	Type	Indicates Predict Version
	DA	Database
	DC	Dataspace
	ET	Extract
	FI	File
	IE	Interface V4.1.2 and above
	KY	Keyword
	LS	Library Structure
	MD	Method V4.1.2 and above
	MO	Module V3.4.2 and below
	NO	Node
	NW	Network
	PG	Package List
	PR	Program
	PY	Property V4.1.2 and above
	RL	Relationship
	RP	Report V3.4.2 and below
	RT	Report Listing
	SC	Storage Space
	SV	Server
	SY	System
	US	User
	VE	Verification
	VM	Virtual Machine
	UDE	User Defined Entities

When adding, copying, or modifying an Event that includes PREDICT objects, the PREDICT object selection screen is displayed. When User-Exit 15 is invoked or when copying or modifying an Event, ADD, REPLACE, or WARNING messages will be placed next to previously selected objects. PREDICT objects with no message in the Message field are available to be selected to migrate. When migrating from a development environment with Checkout/Checkin active, only PREDICT objects checked out to the user are displayed.

```

Type: A to Add File only; B to Add File and DDM; D - Delete
01-12-31      N-2-O ADD AN EVENT      TSI0373
11:38:00      Event: PAYOUT           Sequence: 1      TSI1

From Env: PROD      To Env: DEV      Object Type: FI
Starting Object: PAY-ADMINISTRATION

      S   Object                File
      _   PAY-ADMINISTRATION    Type   DDM   Message
      B   PAY-ARCHIVE           A       *
      A   PAY-MIGRATION         A       *
      A   PAY-TEST-FILE         U

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      HELP  ALL  END  INQ  ----  TOP  UP   DOWN  BOT  ----  ----  STOP

```

Entering a value in the Starting Object field defines the PREDICT object where the selection list begins.

PREDICT objects are selected to migrate by entering "A" (Add) in the Select field next to each PREDICT object. Pressing PF2 automatically places "A" in the Select field next to all PREDICT objects on the selection screen. For File definitions, an additional selection option is available. Entering "B" (Both) in the Select field next to the file name selects both the file and the generated DDM. Entering "D" (Delete) in the Select field next to any of these PREDICT objects removes them from the Event. Pressing PF4 displays a pop-up window of all previously-selected PREDICT objects.

Once selections have been made and Enter is pressed, the screen below is displayed.

```

Press PF1 for more information about Messages
01-12-31      N-2-O ADD AN EVENT      TSI0373
11:38:00      Event: PAYOUT           Sequence: 1      TSI1

From Env: PROD      To Env: DEV      Object Type: FI
Starting Object: BENEFITS

      S   Object                File
      _   PAY-ADMINISTRATION    Type   DDM   Message
      _   PAY-ARCHIVE           A       *   ADD
      _   PAY-MIGRATION         A       *   ADD
      _   PAY-TEST-FILE         U       *   FAILED

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      HELP  ALL  END  INQ  ----  TOP  UP   DOWN  BOT  ----  C/O-  STOP

```

The screen on the previous page allows the user to verify selections. A message is displayed in the Message field for selected PREDICT objects. Add or Replace is the usual message that will appear. For more information about messages, refer to **Section II.2.11 Object Selection Screen Messages**.

When the 'FAILED' or 'WARNING' message is displayed next to an Object, place the cursor over the Object and use PF11 to display any existing Checkout information.

After selecting and verifying PREDICT objects on the current screen, pressing Enter displays the next screen of PREDICT objects. Pressing Enter on the last page or PF12 ends the current selection process.

Related Userview Selection Process for PREDICT Files

The related userview selection process identifies userviews related to ADABAS Master Files selected to migrate. This process is invoked following the selection process for PREDICT files. The userviews identified by this process may optionally be added to the Event. When an ADABAS Master File is migrated, all ADABAS userviews of this file must also be migrated, or the userviews are locked and deleted at the target of the migration.

There are two options available: "Include related userviews in the Event" or "Do not include related userviews in the Event". The N2O Administrator determines which options are available for the related userview selection process for PREDICT files on a user-by-user basis.

If the N2O Administrator specifies one option for the user, no pop-up window is displayed and the option assigned to that user is performed. However, if the N2O Administrator specifies both options for a user, a pop-up window allows the user to select one of the options for the Event.

```

Press PF1 for more information about messages
01-12-31      N-2-O ADD AN EVENT      TSI0373
11:38:00      Event: PAYOUT           TSI1
Sequence: 1

From Env: PROD      To Env: DEV      Object Type: FI
Starting Object: PAYROLL

+-----+
S  Objec|      Select an Option      |
-  PAY-A|      |                      |
-  PAY-A| -  Include related userviews in  |
-  PAY-M| the Event.                    |
-  PAY-T|      |                      |
      |      |                      |
      | -  Do not include related userviews |
      | in the Event.                    |
      |      |                      |
      |      |                      |
+-----+

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      HELP  ALL  END  INQ  ----  TOP  UP  DOWN  BOT  ----  ----  STOP

```

If the first option in the pop-up window, "Include related userviews in the Event", is selected, the selection screen below is displayed.

```

Type A to ADD Userview to the Event.
01-12-31      N-2-O USERVIEW XREF LISTING      TSI0373
11:38:00      Event: PAYOUT Sequence: 1         TSI1

From Env: PROD      To Env: DEV      Object Type: FI

  S   Userview      Master File
  -   -----
  -   BENEFITS      PAYROLL

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      HELP  ALL  END  INQ  ----  ----  ----  ----  ----  ----  ----  STOP

```

Userviews are selected to migrate by entering "A" (Add) in the Select field next to each userview.

If the second option in the pop-up window, "Do not include related userviews in the Event", is selected, the related userview selection process is ignored and the selection process continues.

UDE Selection Process

If UDE – User Defined Entities is selected from the PREDICT object types the selection screen below is displayed.

```

01-12-31          N-2-O ADD AN EVENT          TS11
09:54:48          Event: PAYOUT      Sequence: 1      TERM

                From Env:  PROD                      To Env:  DEV

    UDE
    S Ty Description
    - CM COMPANIES
    - M2 METADATA2
    - M4 METADATA4
    - PD PRODUCTS

    UDE
    S Ty Description
    - M1 METADATA1
    - M3 METADATA3
    - M5 METADATA5

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      HELP  ---  END   ---  ---  ---  ---  ---  ---  ---  ---  ---  ---
  
```

A separate object selection process is used for each UDE marked with "X" on the above screen.

Field	Description
X (optional)	"X" selects the UDE – User Defined Entities to be displayed for selection.
Type (supplied)	Object type of the UDE – User Defined Entities
Description (supplied)	Description of the UDE – User Defined Entities

II.2.2.4 Selecting 3GL/OTHER Objects

When migrating 3GL/OTHER objects, the user must select 3GL/OTHER Categories to migrate.

After pressing Enter on the Add an Event screen, a pop-up window allows users to select 3GL/OTHER Categories to be displayed for selection. When requesting ENDEVOR Events, a pop-up window requires the ENDEVOR System and Subsystem to be entered before the pop-up window is displayed.

```

01-12-31          N-2-O ADD AN EVENT          TSI0373
11:38:00          Event: PAYOUT      Sequence: 1      TSI1

      From Env      : +-----+ry      : PAYPROD_
      To Env        : | X   Categories   |      : PAYDEV_
      Process Date  : | -   -----   |me   : 11:38:00
      Starting Program: | -   ASMB       |ssage : 0001
      SYSERR Type   : | -   COBOL      |uage  : E
      Change Control : | -   FORT       |
      Includ        : | -   PL/I        |: N
C      _____| -   RPG            |_____
o      _____| -   DATA          |_____
m      _____| -   JCL            |_____
e      _____| -   OTHER          |_____
n      _____+-----+_____
t      _____
s      _____

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      HELP  ---  END  ---  ---  ---  ---  ---  ---  ---  ---  ---  ---

```

A separate object selection process is used for each 3GL/OTHER Category marked with "X" on the above pop-up window.

Field	Description
X (optional)	"X" selects the 3GL/OTHER Categories to be displayed for selection.
CATEGORIES (supplied)	3GL/OTHER members may be selected from the following categories:
	ASMB Indicates all types of Assembler.
	COBOL Indicates all types of COBOL.
	FORT Indicates all types of FORTRAN.
	PL/I Indicates all types of PL/I.
	RPG Indicates RPG.
	DATA Indicates DATA FILES.
	JCL Indicates JCL, CLIST, CNTL.
	OTHER Indicates all other types.

When adding, copying, or modifying an Event that includes 3GL/OTHER objects, the 3GL/OTHER selection screen is displayed. When User-Exit 15 is invoked or when copying or modifying an Event, ADD, REPLACE, or WARNING messages will be placed next to previously selected objects. 3GL/OTHER objects with no message in the Message field are available to be selected to migrate. When migrating from a development environment with Checkout/Checkin active, only 3GL/OTHER objects checked out to the user display.

Type A to Add 3GL/OTHER Members to the Event, D to Delete					
01-12-31		N-2-O ADD AN EVENT		TSI0373	
11:38:00		Event: PAYOUT		Sequence: 1	
				TSI1	
DSN Name: COBOL.DATASET					
From Env: PROD		To Env: DEV		Category: COBOL	
Starting Object: PAYROLL1					
S	Object	Type	Message	S	Object
A	PAYROLL1	COBOL		A	PAYROLL2
-	PAYROLL3	COBOL		-	TAXSUM1
-	TAXSUM2	COB72			ANSCB
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12--- HELP ALL END INQ ---- TOP UP DOWN BOT ---- ---- STOP					

Entering a value in the Starting Object field defines the 3GL/OTHER object where the selection list begins.

3GL/OTHER objects are selected to migrate by entering "A" (Add) in the Select field next to each 3GL/OTHER object. Pressing PF2 automatically places "A" in the Select field next to all members on the selection screen. Entering "D" (Delete) in the Select field next to any of these 3GL/OTHER objects removes them from the Event. Pressing PF4 displays a pop-up window of all previously selected 3GL/OTHER objects.

Once selections have been made and Enter is pressed, the screen below is displayed.

```

Press PF1 for more information about Messages
01-12-31          N-2-O ADD AN EVENT          TSI0373
11:38:00          Event: PAYOUT      Sequence: 1      TSI1
          DSN Name: COBOL.DATASET
From Env: PROD          To Env: DEV          Category: COBOL
          Starting Object: PAYROLL1

          Object
          Type      Message
S Object      Type      Message
- PAYROLL1    COBOL     FAILED
- PAYROLL3    COBOL
- TAXSUM2     COB72

          Object      Type      Message
S Object      Type      Message
- PAYROLL2    COBOL     ADD
- TAXSUM1     ANSCB

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      HELP  ----  END   INQ   ----  TOP   UP    DOWN  BOT   ----  C/O   STOP

```

This screen allows the user to verify selections. A message is displayed in the Message field for the selected 3GL/OTHER objects. 'ADD' or 'REPLACE' are the usual messages that appear. For more information about messages, refer to **Section II.2.11 Object Selection Screen Messages**.

When the 'FAILED' or 'WARNING' message is displayed next to an Object, place the cursor over the Object and use PF11 to display any existing Checkout information.

After selecting and verifying 3GL/OTHER objects on the current screen, pressing Enter displays the next screen of 3GL/OTHER objects. Pressing Enter on the last page or PF12 ends the current selection process.

II.2.2.5 Extracting and Renaming NATURAL Objects

When using an Extract Event (migrate a copy of an object without creating a checkout), the user has the option of renaming the Object in the target environment. The new Object will be created in the target environment and an N2O catalog master record will be created for the new Object in the From Environment. The Object will not be checked-out. If the new Object is to be migrated back to the Base Environment, check the Object out using the Checkout Utility.

The following rules are in effect during an Extract Event in which Objects are renamed:

- The "new" Object cannot exist in N2O.
- The "new" Object cannot exist in the FUSER.
- The Extract Event must be a single-target Event to utilize the rename option.
- The XREF selection process will occur for the original Object if XREF selection is turned on.
- No Autocompile will take place for an Object being renamed.

When adding, copying, or modifying an Extract Event that includes NATURAL objects, the 'NATURAL object selection and rename' screen is displayed. When User-Exit 15 is invoked or when copying or modifying an Event, ADD messages will be placed next to previously selected objects. NATURAL objects with no message in the Message field may be selected to migrate.

```

For the Event:Type A to Add or D to Delete Objects
01-12-31          N-2-O ADD AN EVENT          TSI0373
11:38:00          Event: PAYOUT Sequence: 264  TSI1

From Env:  PROD  From Library:  PAYPROD  To Env:  DEV  To Library: PAYDEV
Starting Object:  PROGL___
Object
S Object      Type      S/C  Rename To  Message
A PAY5100P    PROGRAM  S      _____
A PAY5110P    PROGRAM  S      _____
- PAY5130P    PROGRAM  S      _____
- PAY5150P    PROGRAM  S      _____
- PAY5160S    SUB-RTN  S      _____
- PAY6000P    PROGRAM  S      _____
A PAY6010P    PROGRAM  S      PAY601A__
A PAY6020P    PROGRAM  S      PAYEX6___
- PAY6030P    PROGRAM  S      _____
- PAY6040P    PROGRAM  S      _____
- PAY6050P    PROGRAM  S      _____
- PAY6060P    PROGRAM  S      _____
A PAY7000P    PROGRAM  S      PAYEX7___
- PAY7010P    PROGRAM  S      _____

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      HELP  ALL   END   ----   ----   ----   UP    DOWN   ----   ----   STOP
  
```

Entering a value in the Starting Object field defines the NATURAL object where the selection list begins.

NATURAL objects are selected to migrate by entering "A" (Add) in the Select field next to each NATURAL object. Pressing PF2 automatically places "A" in the Select field next to all NATURAL objects on the selection screen. Entering "D" (Delete) in the Select field next to any of these NATURAL objects removes them from the Event. Pressing PF4 displays a pop-up window of all previously-selected NATURAL objects.

Once selections have been made and Enter is pressed, the screen below is displayed.

```

Press PF1 for specific information regarding messages
01-12-31          N-2-O ADD AN EVENT          TSI0373
11:38:00          Event: PRODTST Sequence: 264  TSI1

From Env: KALT From Library: PRODLIB To Env: KALT To Library: TESTLIB
Starting Object: PROG1__
Object
S Object      Type      S/C  Rename To  Message
- PAY5100P    PROGRAM  S    _____  ADD
- PAY5110P    PROGRAM  S    _____  REPLACE
- PAY5130P    PROGRAM  S    _____
- PAY5150P    PROGRAM  S    _____
- PAY5160S    SUB-RTN  S    _____
- PAY6000P    PROGRAM  S    _____
- PAY6010P    PROGRAM  S    PAY601A_  ADD
- PAY6020P    PROGRAM  S    PAYEX6_   ADD
- PAY6030P    PROGRAM  S    _____
- PAY6040P    PROGRAM  S    _____
- PAY6050P    PROGRAM  S    _____
- PAY6060P    PROGRAM  S    _____
- PAY7000P    PROGRAM  S    PAYEX7_   EXISTS
- PAY7010P    PROGRAM  S    _____

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12-
      HELP  ----  END   ----  ----  ----  UP   DOWN  ----  ----  C/O  STOP

```

The screen above allows the user to verify selections. A message is displayed in the Message field for the selected NATURAL objects. ADD is the usual message that will appear. For more information about messages, refer to **Section II.2.11 Object Selection Screen Messages**.

After selecting and verifying NATURAL objects on the current screen, pressing Enter displays the next screen of NATURAL objects. Pressing Enter on the last page or PF12 ends the current selection process.

II.2.2.6 Selecting DDMS

When adding, copying, or modifying an Event that includes DDMS, the DDM selection screen is displayed. When User-Exit 15 is invoked or when copying or modifying an Event, ADD, REPLACE, or WARNING messages will be placed next to previously selected objects. DDMS with no message in the Message field are available to be selected to migrate. When migrating from a development environment with Checkout/Checkin active, only DDMS checked out to the user are displayed.

```

For the Event:Type A to Add or D to Delete Objects
01-12-31          N-2-O MODIFY AN EVENT          TS11
10:18:20          Event: PAYOUT      Sequence: 1    TERM

      From Env:  PROD                      To Env:  DEV
Starting DDM:  AC-PAYGO-SCHED

      S  DDM                                DDM      ADA
      -  AC-PAYGO-SCHED                     Dbid   Fnr   6  Message
      -  ADAREORG-EMPL                     ___ 55   ___ 99  X
      -  ADV-PRIORITY-ZIP                   ___ 71   ___ 64
      -  AR-REFUND                          ___ 71   ___ 131
      A  AR-TRANS                          ___ 71   ___ 133  X
      -  BEACON-FILE                       ___ 0    ___ 38  X
      -  BUDGET-STU                        ___ 71   ___ 65
      -  COMMAND                           ___ 1    ___ 1  X
      -  COMMODITIES-ADAB                   ___ 0    ___ 98  X
      A  EMPL-USERSVIEW                     ___ 0    ___ 1  X
      -  EMPLOYEES                         ___ 0    ___ 1  X
      -  EMPLOYEES-FILE                     ___ 0    ___ 1  X
      A  EMPLOYEES-PWD                      ___ 0    ___ 77  X
      -  FMP-ICM-CASE-V2                    ___ 0    ___ 118  X
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---F12-
      HELP  ----  END  INQ  ----  ----  UP    DOWN  ----  ----  ----  STOP
  
```

Entering a value in the Starting DDM field defines the DDM message where the selection list begins.

DDMS are selected to migrate by entering "A" (Add) in the Select field next to each DDM. Pressing PF2 automatically places "A" in the Select field next to all DDMS on the selection screen. Entering "D" (Delete) in the Select field next to any of these DDMS removes them from the Event. Pressing PF4 displays a pop-up window of all previously-selected DDMS.

Field	Description
DDM Dbid (optional)	Database number that the DDM will point to in the target environment.
DDM Fnr (optional)	File number that the DDM will point to in the target environment.
ADA 6 (supplied)	Marked with an X if the DDM was created in NATURAL 2.3 or above and will allow a Dbid and/or Fnr greater than 255.

Once selections have been made and Enter is pressed, the screen below is displayed.

```

Objects selected for migration, Press ENTER to proceed
01-12-31          N-2-O MODIFY AN EVENT          TS11
10:19:45          Event: PAYOUT      Sequence: 1    TERM

          From Env:  PROD                      To Env:  DEV

          S  DDM                                DDM      ADA
          -  AC-PAYGO-SCHED                    Dbid  Fnr   6  Message
          -  ADAREORG-EMPL                      ___ 71  ___ 241
          -  ADV-PRIORITY-ZIP                    ___ 55  ___ 99  X
          -  AR-REFUND                          ___ 71  ___ 64
          -  AR-TRANS                          ___ 71  ___ 131
          -  BEACON-FILE                        ___ 71  ___ 133  X  ADD
          -  BUDGET-STU                         ___ 0   ___ 38  X
          -  COMMAND                          ___ 71  ___ 65
          -  COMMODITIES-ADAB                    ___ 1   ___ 1  X
          -  EMPL-USERSVIEW                      ___ 0   ___ 98  X
          -  EMPLOYEES                          ___ 0   ___ 1  X  ADD
          -  EMPLOYEES-FILE                      ___ 0   ___ 1  X
          -  EMPLOYEES-PWD                      ___ 0   ___ 77  X  FAILED
          -  FMP-ICM-CASE-V2                    ___ 0   ___ 118 X

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---F12-
      HELP  ----  END  INQ  ----  ----  UP    DOWN  ----  ----  ----  STOP

```

This screen allows the user to verify selections. A message is displayed in the Message field for selected DDMS. Add or Replace is the usual message that will appear. For more information about messages, refer to **Section II.2.11 Object Selection Screen Messages**.

When the 'FAILED' or 'WARNING' message is displayed next to an Object, place the cursor over the Object and use PF11 to display any existing Checkout information.

After selecting and verifying DDMS on the current screen, pressing Enter displays the next screen of DDMS. Pressing Enter on the last page or PF12 ends the current selection process.

II.2.2.7 **Selecting METADATA**

When adding, copying, or modifying an Event that includes METADATA, the METADATA selection screen is displayed. When User-Exit 15 is invoked or when copying or modifying an Event, ADD, REPLACE, or WARNING messages will be placed next to previously selected objects. METADATA with no message in the Message field are available to be selected to migrate. When migrating from a development environment with Checkout/Checkin active, only METADATA checked out to the user are displayed.

```

For the Event:Type A to Add or D to Delete Objects
01-12-31          N-2-O ADD AN EVENT          TSI1
12:36:39          Event: PAYOUT      Sequence: 1      TERM

                From Env:  PROD              To Env:  DEV
                Starting METADATA:  CM

      S  OT  METADATA                      Message
      -  CM  COMPANIES
      A  M1  METADATA1
      -  M2  METADATA2
      -  M3  METADATA3
      -  M4  METADATA4
      -  M5  METADATA5
      A  PD  PRODUCTS

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      HELP  ALL   END   ----   ----   ----   UP    DOWN   ----   ----   ----   STOP
  
```

Entering a value in the Starting DDM field defines the DDM message where the selection list begins.

METADATA are selected to migrate by entering "A" (Add) in the Select field next to each DDM. Pressing PF2 automatically places "A" in the Select field next to all METADATA on the selection screen. Entering "D" (Delete) in the Select field next to any of these METADATA removes them from the Event. Pressing PF4 displays a pop-up window of all previously-selected METADATA.

Once selections have been made and Enter is pressed, the screen below is displayed.

```

For the Event:Type A to Add or D to Delete Objects
01-12-31          N-2-O ADD AN EVENT          TS11
12:38:14          Event: PAYOUT      Sequence: 1      TERM

          From Env:  PROD          To Env:  DEV
          Starting METADATA:  CM

          S  OT  METADATA          Message
          -  CM  COMPANIES
          -  M1  METADATA1          FAILED
          -  M2  METADATA2
          -  M3  METADATA3
          -  M4  METADATA4
          -  M5  METADATA5
          -  PD  PRODUCTS          ADD

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
HELP  ----  END  INQ  ----  ----  UP  DOWN  ----  ----  C/O  STOP
  
```

This screen allows the user to verify selections. A message is displayed in the Message field for selected METADATA. Add or Replace is the usual message that will appear. For more information about messages, refer to **Section II.2.11 Object Selection Screen Messages**.

When the 'FAILED' or 'WARNING' message is displayed next to an Object, place the cursor over the Object and use PF11 to display any existing Checkout information.

After selecting and verifying METADATA on the current screen, pressing Enter displays the next screen of METADATA. Pressing Enter on the last page or PF12 ends the current selection process.

II.2.3 **Migration Process**

When the Migration process begins, one of the following occurs:

- An authorization screen is displayed indicating the required levels of authorization (shown below).
- A screen is displayed to begin the migration process.

The authorization screen is displayed if authorization is required for an Event. This screen indicates how many levels of authorization are required. For more information, refer to **Section II.3 Authorize Events**.

```

01-12-31          N-2-O EVENT REQUEST          TSI0373
11:38:00          Event: PAYOUT      Sequence: 1      TSI1

                Event Awaiting Authorization
                (Requires 3 level(s) of authorization)

                Press ENTER to continue

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
-----

```

One of the following on-line or batch processing screens is displayed if authorization is not required for an Event.

When a batch Event is ready to begin the migration process, the screen below is displayed, giving the option to submit the batch job to the system internal reader or delay the submission.

```

01-12-31          N-2-O SUBMIT AN EVENT          TSI0373
11:38:00                                     TSI1

                Event   :    PAYOUT
                Sequence:    1

                is a batch Event

                Press ENTER To Submit JCL for this Event
                or
                PF3 to Delay the Submission of the JCL

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
HELP  ----  END   ----  ----  ----  ----  ----  ----  ----  ----  ----  ----

```

Pressing Enter submits the batch JCL (or EXECs) to the system internal reader by reading the batch JCL as defined on the Migration Profile for the Event and replacing any character strings prefixed with "&".

Pressing PF3 delays the submission of the JCL (or EXECs) for a Batch Event. The Event may then be submitted at the appropriate time using the Batch JCL Submission Facilities or using manual procedures.

Note: Depending on the value of the Batch Event Submission set by the N2O Administrator, the Event may be forced into delayed or immediate submission. In either case, this screen will not appear.

When an on-line Event is ready to begin the migration process, the screen below is displayed, giving the option to migrate the NATURAL objects and/or SYSERR messages.

```

Press Enter To Proceed Or PF3 To Stop Migration
01-12-31      N-2-O EVENT PROCESSING SCREEN      TSI0373
11:38:00      Event: PAYOUT   Sequence: 1        TSI1

From Env: PROD   From Library: PAYPROD   To Env: DEV   To Library: PAYDEV

Object                      Migrated                      Archived
----- Source ----- Object ----- Source ----- Object -----
*****
***   The number of selections   ***
***   in this Event is:         ***
***   NATURAL: 8                 ***
***   SYSERR : 0                 ***
***   DDM   : 0                 ***
*****

```

Pressing Enter proceeds with the migration. As NATURAL objects and/or SYSERR messages are migrated, each object scrolls upward by target. The target currently being processed is displayed at the top of the processing screen. A count is displayed for objects in each path.

PF3 stops the migration. To start the Event at a later time, use the Select Events for Processing option from the Request Event menu. Refer to **Section II.2.10 Select Events for Processing**.

When archiving is specified for an Event, NATURAL objects are automatically archived before being replaced. If Autocompile and Autorecovery are specified on the Migration Profile and the Event migrates only source code, the object code for Natural objects is also automatically archived. When using autorecovery, if the Autocompile process encounters errors, the original source and object code may be restored.

If Autocompile is specified and N2O User-Exit 4 (N2OUE04N) has been activated, the Libraries Pending Autocompile screen will be displayed. If User-Exit 4 has not been activated and Autocompile is specified, the user must execute the Autocompile. Refer to **Section II.5.1 Libraries Pending Autocompile**.

MOVE

If MOVE is specified for the Migration Method and the Deferred Time on the Migration Profile is 0, the deletion process is started immediately following the migration process.

After the completion of the migration process, the screen below is displayed.

```

Press Enter To Proceed
01-12-31          N-2-O EVENT PROCESSING SCREEN          TSI0373
11:38:00          Event: PAYQA      Sequence: 1          TSI1

From Env: DEV      From Library: PAYDEV      To Env: TEST      To Library: PAYTEST

Object              Migrated              Archived
-----              -
Object              Source              Object              Source              Object

*****
*** 6 Modules will be deleted from: ***
***      Env Def: DEV                ***
***      Library: PAYDEV             ***
*****

```

Pressing Enter proceeds with the deletion process for the Event. As NATURAL objects are deleted, each object scrolls upward until processing is complete.

A pop-up window is displayed at the end of the on-line migration process indicating the migration process for the Event has successfully completed.

```

+-----+
| Migration Complete for | ENT PROCESSING SCREEN          TSI0373
|                        | PAYOUT      Sequence: 1          TSI1
|                        | PAYDEV      To Env: TEST      To Library: PAYTEST
| Event      : PAYIN    |
| Event Sequence : 1    |
|                        |
+-----+ Source      Object      Source      Object
-----
PAY5100P      REPLACED      ****      ****      ****
PAY5110M      REPLACED      ****      ****      ****
PAY5110S      ADDED        ****      ****      ****
PAY5200M      REPLACED      ****      ****      ****
PAY5200P      REPLACED      ****      ****      ****
PAY5210M      ADDED        ****      ****      ****
6 out of 6

```

If the Event is an Extract Event for NATURAL objects, the message "Extract Complete" instead of "Migration Complete" is displayed and the 'Rename To' object will be shown in parenthesis to the right of the object name if the object is renamed during the extract.

If a Deferred MOVE is requested, the pop-up window also displays the earliest date and time at which the deletion process may begin.

II.2.4 Copy an Event

The Copy an Event function creates an Event for migrating objects by copying an existing Event. The Copy function copies the Change Control Number, Task Group, and Task Number, comments, and objects from the existing Event to the new Event.

To copy an Event, enter "C" in the Enter Code field, the Event to be copied in the Event field, and the Sequence number of the Event to be copied in the Sequence field, or leave the Event and Sequence fields blank. A pop-up window is displayed for the user to enter the new Event.

```

01-12-31      N-2-O REQUEST EVENTS MENU      TSI0373
11:38:00                                           TSI1

Code  Function
----  -
A     Add an Event
C     Copy an Event
D     Delete an Event
I     Inquire on an Event
M     Modify an Event
R     Recovery from Archive
S     Select Events for Processing
.     Termina +-----+
-     -         |
Enter Code: c   | Copy Event   :   PAYOUT2   |
                  | Event:      | Sequence:   1____ |
                  | Sequenc | To   Event   :   PAYOUT2_ |
                  +-----+

Direct Command: _____ MIG REQ

```

In the screen above, the new Event is "PAYOUT2", Sequence "2". Sequence "2" was the next available sequence number assigned by N2O. If the Change Control field or the Task Group and Task Number fields are required for the Event, they are defaulted from the original Event. The Comments fields are also defaulted from the original Event.

The setting of the LOCK EVENT field on the Master Event determines if a popup window is displayed. This window prompts for confirmation of copying the original Event's From/To Environment and Library Information and the Processing Date and Time. To confirm the copy request, enter "Y" in the pop-up window for the appropriate information. To cancel the copy request for the appropriate information, enter "N" in the pop-up window or press PF3.

```

01-12-31      N-2-O REQUEST EVENTS MENU      TSI0373
11:38:00                                           TSI1

Code  Function
----  -
A     Add an Event
C     Copy an Event
D     Delete an Event
I     Inquire on an Event
M     Modify an Event

+-----+
| Original Event: PAYOUT2          1 | +-----+
| Copy From/To LIB Info   : N      | |
| Copy Process Date and Time: N      | | PAYOUT2
+-----+ | 1____
          | Sequenc | To   Event   :   _PAYOUT2
          +-----+

Enter C |

Direct Command: _____ MIG REQ
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
HELP ---- END  ENV  MIG  REP  TOL  ---- PRJ  ----  ---- EXIT

```

All other information is defaulted from the Master Event.

The remainder of the copy Event process is identical to the Object Selection process (refer to **Section II.2.2 Object Selection Process**).

II.2.5 Delete an Event

The Delete an Event function removes an Event that no longer needs to be processed.

To delete an Event, enter "D" in the Enter Code field, the Event to be deleted in the Event field, and the Sequence number of the Event to be deleted in the Sequence field on the Request Events menu.

01-12-31 11:38:00	N-2-O DELETE AN EVENT Event: PAYOUT Sequence: 2	TSI0373 TSI1
From Env : PROD	From Library : PAYPROD_	
To Env : DEV	To Library : PAYDEV_	
Process Date : 19991231	Process Time : 11:38:00	
Added User-ID : TSI1__		
C	_____	
o	_____	
m	_____	
m	_____	
e	_____	+-----+ Do you want to Delete? N (Y/N) +-----+
n	_____	
t	_____	
s	_____	
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---		
-----END-----		

An Event can only be deleted by the user who creates the Event from the Request Events menu.

Closed Events (Status "C"), In-progress Events (Status "I"), and Held Events (Status "H") that have migrated objects cannot be deleted. Other In-progress Events may only be deleted from the Authorize Events menu. For more information about deleting In-progress Events, refer to **Section II.3.1 Authorize an Event**.

To delete the Event, enter "Y" in the pop-up window. To cancel the delete request, enter "N" in the pop-up window or press PF3.

II.2.6 Inquire on an Event

The Inquire on an Event function displays information about an Event.

To inquire on an Event, enter "I" in the Enter Code field, the Event to be displayed in the Event field, and the Sequence number of the Event to be displayed in the Sequence field on the Request Events menu.

```

Press ENTER to display the selection list
01-12-31      N-2-O INQUIRE ON AN EVENT      TSI0373
11:38:00      Event: PAYOUT      Sequence: 1      TSI1

      From Env      : PROD      From Library      : PAYPROD__
      To Env      : DEV      To Library      : PAYDEV__
      Process Date  : 20011231      Process Time   : 11:38:00
      Migrate Method : COPY      Change Control  : EXAMPLE__
      Added User-ID : TSI0373
      SYSERR Type   : US      SYSERR Language  : E
      THIS IS A SAMPLE EVENT _____
C _____
o _____
m _____
m _____
e _____
n _____
t _____
s _____

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
----- END -----

```

Pressing Enter displays a screen listing the objects for the Event.

When inquiring on an Event that migrates more than one type of object, the list for each type is displayed in the following order: NATURAL objects, PREDICT objects, 3GL/OTHER objects, and SYSERR messages.

```

Type X to view source programs
01-12-31      N-2-O INQUIRE ON AN EVENT      TSI0373
11:38:00      Event: PAYOUT      Sequence: 1      TSI1

From Env: PROD      From Library: PAYPROD      To Env: DEV      To Library: PAYDEV
Starting Object: PAY5100P

S Object      Object      S/C      Message      S Object      Object      S/C      Message
- PAY5100P      PROGRAM      S      REPLACE      - PAY5100M      MAP      S      REPLACE
- PAY5110S      SUB-RTN      S      ADD      - PAY5200M      MAP      S      REPLACE
- PAY5200P      PROGRAM      S      REPLACE      - PAY5210M      MAP      S      ADD

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
HELP ---- END ---- TOP UP DOWN BOT ---- EXIT

```

If the list of objects does not fit entirely on one screen, pressing Enter displays the next screen until the end of the list is displayed.

When reviewing the NATURAL object and SYSERR message lists, pressing PF12 displays the next type of Object. When reviewing the PREDICT object and 3GL/OTHER object lists, pressing PF12 displays the next PREDICT object type or the next 3GL/OTHER Category in the list.

Entering "X" beside a NATURAL object on the previous screen displays the source code of the NATURAL object.

```
Press PF4 For Update Information > + PROGRAM : PAY5100P Lib: PAYPROD
....+....1....+....2....+....3....+....4....+....5....+....Mode: STRUCT
0010 *
0020 * * * * *
0030 *   PAY (PROGRAM MANAGEMENT SYSTEM)   *
0040 *   TREEHOUSE SOFTWARE, INC.  (C) 1999.  *
0050 * * * * *
0060 *
0070 * PROGRAM   : PAY5100P
0080 *
0090 * AUTHOR(S) : TSI
0100 *
0110 * FUNCTION  : GET HELP DATA
0120 *
0130 * * * * *
0140 *
0150 DEFINE DATA
0160     GLOBAL
0170     USING PAYGDA
0180 END-DEFINE
0190 **
0200 INPUT WITH TEXT CS-MESSAGE USING MAP 'PAYM5100'

Press PF3 to Exit...Press PF12 to STOP viewing....6....+....7.
```

Pressing Enter displays the next page of source code. Pressing Enter on the last page displays the next selected NATURAL object in the list. If no other NATURAL objects are selected, pressing Enter returns to the display list.

Pressing PF4 displays update information for the NATURAL object, such as date and time saved, date and time cataloged, User-ID, and NATURAL version. Pressing PF12 cancels display of the current NATURAL object and begins display of the next NATURAL object. If no other NATURAL objects are selected, pressing PF12 returns to the display list.

II.2.7 Modify an Event

The Modify an Event function updates an Event. Only the user who creates the Event may modify the Event.

To modify an Event, enter "M" in the Enter Code field, the Event to be modified in the Event field, and the Sequence number of the Event to be modified in the Sequence field on the Request Events menu.

When modifying an Event, the Change Control or Task Group and Task Number, and Comments fields may be updated. Process Date and Process Time may also be updated to delay the migration of a batch Event.

The next step of the Modify an Event function is the object selection process. The object selection process allows users to select objects to migrate. A screen is displayed allowing objects to be selected. Entering "A" next to an object adds the object to the Event. Entering "D" next to a previously-selected object removes the object from the Event. For more information, refer to **Section II.2.2 Object Selection Process**.

01-12-31 11:38:00	N-2-O MODIFY AN EVENT Event: PAYOUT Sequence: 1	TSI0373 TSI1
From Env : PROD	From Library : PAYPROD	
To Env : DEV	To Library : PAYDEV	
Process Date : 20011231	Process Time : 11:38:00	
Starting Program: _____		
C _____		
O _____		
m _____		
e _____		
n _____		
t _____		
s _____		
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---		
HELP ---- END ----		

If modifying an In-progress Event (Status=I) a pop-up window will allow the Event to be continued. Press enter to continue the Event or PF3 to cancel the Modify. The user cannot change any values in an In-progress Event.

II.2.8 Recovery from Archive

The Recovery from Archive function creates an Event for recovering NATURAL objects, SYSERR messages, and/or PDS objects that have been archived. PREDICT, LIBRARIAN, PANVALET, and ENDEVOR objects are not currently archived. There are two methods of recovery:

- Event Recovery Recovers NATURAL objects, SYSERR messages, and/or PDS objects archived by an Event.
- N2OPURGE Recovery Recovers NATURAL objects archived by the N2OPURGE Utility. For more information refer to **Section II.2.9 N2O Purge Recovery**.

To create a Recovery from Archive Event, enter "R" in the Enter Code field, the Event to be added in the Event field, and "N", "S", or "O" in the Type field on the Request Events menu.

The Recovery from Archive function retrieves NATURAL objects, PDS objects, and/or SYSERR messages that have been archived by an Event. When archiving is active, NATURAL objects, PDS objects, and SYSERR messages being replaced by a migration are automatically archived. Recovery from Archive may recover to Multiple Targets using a Multiple Target Master Event. When performing Recovery from Archive, the Archive Event and Archive Sequence fields on the Recovery from Archive screen must contain the Event and Sequence that performed the archiving of the NATURAL objects, PDS objects, and/or SYSERR messages being recovered. To identify the Event and Sequence that archived the version of a NATURAL object, PDS object, and/or SYSERR message to be recovered, refer to **Section IV.4.8 Archive Version Summary**.

01-12-31 11:38:00	N-2-O RECOVERY FROM ARCHIVE Event: PAYREC Sequence: 1	TSI0373 TSI1
<div style="display: flex; justify-content: space-between;"> Archive Event : _____ Archive Sequence: _____ </div>		
<div style="display: flex; justify-content: space-between;"> To Env : DEV To Library : PAYDEV__ </div>		
<div style="display: flex; justify-content: space-between;"> Process Date : 20011231 Process Time : 11:38:00 </div>		
Starting Program: _____		
<div style="display: flex;"> <div style="flex: 1; text-align: center; padding-right: 10px;"> C o m m e n t s </div> <div style="flex: 4; border-bottom: 1px solid black; margin-bottom: 5px;"></div> </div> <div style="display: flex;"> <div style="flex: 1; text-align: center; padding-right: 10px;"></div> <div style="flex: 4; border-bottom: 1px solid black; margin-bottom: 5px;"></div> </div> <div style="display: flex;"> <div style="flex: 1; text-align: center; padding-right: 10px;"></div> <div style="flex: 4; border-bottom: 1px solid black; margin-bottom: 5px;"></div> </div> <div style="display: flex;"> <div style="flex: 1; text-align: center; padding-right: 10px;"></div> <div style="flex: 4; border-bottom: 1px solid black; margin-bottom: 5px;"></div> </div> <div style="display: flex;"> <div style="flex: 1; text-align: center; padding-right: 10px;"></div> <div style="flex: 4; border-bottom: 1px solid black; margin-bottom: 5px;"></div> </div> <div style="display: flex;"> <div style="flex: 1; text-align: center; padding-right: 10px;"></div> <div style="flex: 4; border-bottom: 1px solid black; margin-bottom: 5px;"></div> </div> <div style="display: flex;"> <div style="flex: 1; text-align: center; padding-right: 10px;"></div> <div style="flex: 4; border-bottom: 1px solid black; margin-bottom: 5px;"></div> </div>		
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12--- HELP ---- END ----		

Field	Type	Description
EVENT (supplied)	N,S,O	The Master Event of the recovery.
SEQUENCE (supplied)	N,S,O	The sequence number of the Event.
ARCHIVE EVENT (required)	N,S,O	The Event that archived the NATURAL objects, PDS objects, and/or SYSERR messages to be recovered. "N2OPURGE" must be specified to recover NATURAL objects deleted by the N2OPURGE Utility.
ARCHIVE SEQUENCE (required)	N,S,O	The sequence number of the Event that archived the NATURAL objects, PDS objects, and/or SYSERR messages to be recovered. When N2OPURGE is entered in the Archive Event field, the archive sequence is defaulted to "1" (this is the only valid value for N2OPURGE recoveries)
TO ENV (required)	N,S,O	The Environment Definition serving as the target of the recovery.
TO LIBRARY (required)	N,S	The library to which NATURAL objects or SYSERR messages are to be recovered. This field is not displayed for PDS object recoveries.
PROCESS DATE (required)	N,S,O	The earliest date on which the batch migration may take place. The current date is automatically supplied by N2O, but may be modified by the user if postdating of the migration is desired. For more information about submitting batch Events, refer to Section II.7 Batch Submission JCL .
PROCESS TIME (required)	N,S,O	The earliest time on the Process Date during which the batch migration may take place.
CHANGE CONTROL (required if specified in the Master Event)	N,S,O	A value that relates multiple Events to a specific change request. This field is only displayed if Change Control is required.
TASK GROUP (required if specified in the Master Event)	N,S,O	A value that relates multiple Events to a specific Task Group from the N2O Project Tracking Subsystem. This field is only displayed if Project Tracking is required. When using Add, Copy, or Modify an Event, this field may be modified.
TASK NUMBER (required if specified in the Master Event)	N,S,O	A number that relates multiple Events to a specific task from the N2O Project Tracking Subsystem. This field is only displayed if Project Tracking is required. When using Add, Copy, or Modify an Event, this field may be modified.

(continued from previous page)

Field	Type	Description
STARTING PROGRAM (optional)	N	<p>The first NATURAL object to appear in the NATURAL object selection list. An "*" may be used as a wildcard character to start the selection list with NATURAL objects prefixed by a string (e.g., "N2O*").</p> <p>If the user enters an "*" as the Starting Program for the Event, all NATURAL objects are marked for migration.</p>
STARTING MESSAGE (optional if SYSERR)	S	<p>The first SYSERR message to appear in the SYSERR message selection list.</p> <p>If the user enters an "*" as the Starting Message in an Event, all SYSERR messages are marked for migration.</p>
SYSERR TYPE (required for SYSERR)	S	<p>The type of SYSERR message to migrate. Valid values are as follows:</p> <ul style="list-style-type: none"> US Indicates user-supplied short messages are to be selected. UL Indicates user-supplied long (extended) messages are to be selected. U Indicates both short and long messages are to be selected.
SYSERR LANGUAGE (required for SYSERR)	S	<p>The language to be migrated. Valid values are single alphanumeric characters in the ranges 1 - 9, A - Z and a - y. These values are equivalent to the values available for the *LANGUAGE system variable.</p>
		<p>* Indicates all languages are to be migrated.</p>
COMMENTS (optional)	N,S,O	<p>A 10-line comment area describing the Event.</p>

If a Multiple Target Event is entered for the Archive Event, a pop-up window is displayed listing all paths of the Event that performed archiving. Events perform archiving on a target-by-target basis. To recover NATURAL objects or SYSERR messages from one of these paths, enter "X" next to the path that performed the archiving.

```

01-12-31          N-2-O RECOVERY FROM ARCHIVE          TSI0373
11:38:00          Event: PAYREC      Sequence: 1        TSI1

Archive Event   : PAYIN___ Archive Sequence: 1___

To Env         : DEV      To Library       : PAYDEV___
Process Date   : 20011231 Process Time    : 14:06:48
Starting Pro   +-----+
                  Please choose one
                  S   Recover from:
                  -   -----
C   _____ -   TEST   PAYTEST
o   _____ -   STG1   PAYSTG1
m   _____ -   STG2   PAYSTG2
e   _____
n   _____
t   _____
s   _____

Enter-PF1---PF2---PF3---+-----+PF10---PF11---PF12---
HELP  ---  END  ---  ---  ---  ---  ---  ---  ---  ---

```

The next step of the Recovery from Archive function is the object selection process. This process allows users to select objects to migrate. A screen is displayed allowing objects to be selected. Entering "A" next to an object adds the object to the Event. Entering "D" next to a previously-selected object removes the object from the Event. For more information, refer to **Section II.2.2 Object Selection Process**.

After the object selection process is complete, the migration process begins. For more information about the migration process, refer to **Section II.2.3 Migration Process**.

II.2.9 N2OPURGE Recovery

The N2OPURGE Recovery function retrieves NATURAL objects that have been archived and deleted using the N2OPURGE Utility. NATURAL objects archived using the N2OPURGE Utility are recovered from an Archive file using the Recovery from Archive function. When performing an N2OPURGE Recovery, "N2OPURGE" must be entered in the Archive Event field, and "1" is defaulted automatically in the Archive Sequence field on the Recovery from Archive screen. The To Env and To Library fields must contain the destination Environment Definition and Library where the NATURAL objects are to be recovered to. A pop-up window will be displayed after pressing ENTER. Enter the N2OPURGE recovery parameters.

```

01-12-31          N-2-O RECOVERY FROM ARCHIVE          TSI0373
11:38:00          Event: PAYREC      Sequence: 1        TSI1

Archive Event   : N2OPURGE  Archive Sequence: 1

|-----|
| N2OPURGE Archive Recovery Parameters |
| N2OPURGE From Env.....: prdt      |
| N2OPURGE From Library: payprod      |
|-----|
t
s
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
HELP  ---  END  ---  ---  ---  ---  ---  ---  ---  ---  ---  ---  ---

```

The N2OPURGE From Env and From Library fields must contain the Environment Definition and Library where the NATURAL objects resided before being deleted. This will limit the object selection list to only those NATURAL objects that were deleted from the specified From Environment and Library.

When recovering NATURAL objects that were archived by the N2OPURGE Utility, the following screen is displayed. For more information about the N2OPURGE Utility, refer to **Section V.3.1 N2OPURGE Utility**.

NATURAL objects with an ADD or REPLACE message in the Message field have been previously selected to migrate. NATURAL objects with no message in the Message field are available to be selected to migrate.

```

For the Event:  Type A to Add or D to Delete Objects
01-12-31          N-2-O Recovery from Archive          TSI0373
11:38:00          Event: PAYREC      Sequence: 1        TSI1

From Env: ARC1    From Library: PAYPROD    To Env: PROD    To Library: PAYPROD
Starting Object: PAY5100P

S Object      Purge      S/C Message      S Object      Purge      S/C Message
A PAY5100P    01-12-01  S                _ PAY5110M    01-02-17  S
A PAY5210M    01-04-06  S                A PAY5200M    01-05-06  S
_ PAY5200P    01-05-01  S

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
HELP  ALL  END  INQ  ---  TOP  UP  DOWN  BOT  ---  ---  STOP

```

Entering a value in the Starting Object field defines the NATURAL objects where the selection list begins.

NATURAL objects are selected to migrate by entering "A" (Add) in the Select field next to each NATURAL object. Pressing PF2 automatically places "A" in the Select field next to all NATURAL objects on the selection screen. Pressing PF4 displays a pop-up window of all previously-selected NATURAL objects. Entering "D" (Delete) in the Select field next to any of these NATURAL objects removes them from the list.

Field	Type	Description
EVENT (supplied)	N	The Master Event of the migration.
SEQUENCE (supplied)	N	The sequence number of the Event.
FROM ENV (supplied)	N	The source Environment Definition of the migration.
FROM LIBRARY (supplied)	N	The library from which the NATURAL objects were archived.
TO ENV (supplied)	N	The target Environment Definition of the migration.
TO LIBRARY (supplied)	N	The library to which the NATURAL objects are to be migrated.
STARTING OBJECT (optional)	N	The NATURAL object where the selection list begins. Defaults to the first NATURAL object on the screen.
S (optional)	N	<p>The selection code indicates the action to be taken on the NATURAL object. Valid values are as follows:</p> <p>A Adds the NATURAL object to the Event.</p> <p> Deletes the NATURAL object from the</p> <p>D Event.</p>
OBJECT (supplied)	N	The name of the NATURAL object.
PURGE DATE (supplied)	N	The date the NATURAL object was deleted using the N2OPURGE Utility.
S/C (supplied)	N	<p>The form of the NATURAL object. Valid values are as follows:</p> <p>S Indicates only the source form of the program may be selected.</p> <p>C Indicates only the cataloged form of the program may be selected.</p> <p>S/C Indicates both forms of the program may be selected.</p>
MESSAGE (supplied)	N	Provides information about the selection of an object. For more information about messages, refer to Section II.2.11 Object Selection Screen Messages .

Once selections have been made and Enter is pressed, the screen below is displayed.

```

Press PF1 for more information about Messages
01-12-31      N-2-O Recovery From Archive      TSI0373
11:38:00      Event: PAYREC   Sequence: 1      TSI1

From Env: ARC1      From Library: PAYPROD      To Env: PROD      To Library: PAYPROD
Starting Object: PAY5100P

S  Object      Purge      S/C  Message      S  Object      Purge      S/C  Message
-  PAY5100P    01-12-01  S      ADD      -  PAY5110M    01-02-17  S      ADD
-  PAY5210M    01-04-06  S      ADD      -  PAY5200M    01-05-06  S      ADD
-  PAY5200P    01-05-01  S

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      HELP  ----  END   INQ   ----  TOP   UP    DOWN  BOT   ----  ----  STOP
  
```

This screen allows the user to verify selections. A message is displayed in the Message field for the selected NATURAL objects. For more information about messages, refer to **Section II.2.11 Object Selection Screen Messages**.

After selecting and verifying NATURAL objects on the current screen, pressing Enter displays the next screen of objects. Pressing Enter on the last page or PF12 ends the current selection process and proceeds with the next selection process.

II.2.10 Select Events for Processing

The Select Events for Processing function provides a list of Events that may be copied, deleted, inquired on, or modified. The user's Function Profile security defines the user's valid functions.

To select Events for processing, enter "S" in the Enter Code field on the Request Events menu. A starting value may be entered in the Event and Sequence fields. Entering a value in the Status field limits the output to Events with the specified status. If no status is entered, a value of "O" is assumed. The Select Events for Processing function from the Request Events menu only displays Events created by the user.

```

Valid Values: C - Copy D - Delete I - Inquire M - Modify
01-12-31      N-2-O SELECT EVENTS FOR PROCESSING      TSI0373
11:38:00      Status: O      TSI1

S  Event      Seq      From To      Event      ---- Added ----      ---- Task ----
-  -----      -----      Env  Env      Type      User-ID  Date      Group      Number
-  EXTRACT    3311    PROD PAYM  N      TSI1      01-12-31      *****      *****

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
HELP  ----  END   ----  CHNG  ----  ----  ----  ----  ----  ----  ----

```

PF5 is available to toggle between the Project Tracking Task and Change Control for each Event listed on the select screen.

PF7 is available to toggle between sorting the events by Change Control and sorting by event/event sequence.

Field	Description
S (optional)	The function to be executed. Valid functions are C, D, I, or M (Copy, Delete, Inquire, or Modify). The user's Function Profile security defines the user's valid functions. The Event/Sequence selected is processed according to the function code entered.

Pressing Enter pages forward on all screens until the last screen is displayed. Pressing Enter on the last screen wraps around to display the first screen again.

Entering a “C” in the ‘S’ field on the Select Events for Processing screen invokes the copy option. A pop-up window will be displayed to allow users to enter a new Event name when one Event is copied to another Event with a different name.

```

Valid Values: C - Copy D - Delete I - Inquire M - Modify
01-12-31      N-2-O SELECT EVENTS FOR PROCESSING      TSI0373
11:38:00      Status:  O                               TSI1

S  Event      Seq      From To      Event ---- Added ---- Change
-  -----+-----+-----+-----+-----+-----+-----+-----+-----+
C  EXTRAC | Copy Event: EXTRACT Seq: 3311 | -12-31  *****
      | To Event: EXTRACT                |
      |                                     |
      +-----+

```

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---

HELP ---- END ---- TASK ----

II.2.11 Object Selection Screen Messages

Object Selection Screen Messages are messages received during the selection process. Typically, "ADD" or "REPLACE" messages are displayed when objects are selected. ADD indicates the selected object will be added to the target; REPLACE indicates the selected object will replace an object at the target. The following are additional messages that may be displayed:

FAILED

"FAILED" is displayed when Checkout/Checkin is active and one of the following rules is violated:

- When selecting objects to migrate, source code must be available for each NATURAL object to be migrated, and short text must be available for each SYSERR message to be migrated.
- When selecting objects to migrate to a development environment, the selected object cannot overwrite an object with the same name that is checked out in the development environment.
- When selecting objects to migrate from a BASE environment, the number of checkouts for the selected object may not exceed the Checkout/Checkin level. The N2O Administrator determines the Checkout/Checkin level.
- When selecting objects to migrate from a development environment, the checked-out objects may be in only one open Event. To identify Events containing the checked-out objects, refer to **Section IV.4.9 Events Pending for an Object**.
- When selecting objects to migrate to a BASE environment, the selected object must be migrated back to the original BASE environment.

When the "FAILED" message is displayed, place the cursor on the object in question and use PF11 to display any existing checkout information for that object.

The "FAILED" message indicates the selected object is not included in the Event.

WARNING

When the "WARNING" message is displayed, place the cursor on the object in questions and use PF11 to display any existing checkout information for that object.

"WARNING" is displayed when Checkout/Checkin is active and the selected object is checked out more than one time. "WARNING" indicates the object is added to the Event.

NO XREF

"NO XREF" is displayed when a NATURAL object is selected to migrate and PREDICT Cross-Reference data does not exist. The "NO XREF" message indicates the NATURAL object is not included in the Event.

NO DOC

"NO DOC" is displayed when a NATURAL object is selected to migrate and the PREDICT program documentation does not exist. The "NO DOC" message indicates the NATURAL object is not included in the Event.

OBJ FAIL

"OBJ FAIL" is displayed when a NATURAL object is selected to migrate and the object code does not exist or does not match the source code. The "OBJ FAIL" message indicates the NATURAL object is not included in the Event.

DENIED

"DENIED" is displayed when an object is selected to migrate and the object does not pass User-Exit 2 rules. The "DENIED" message indicates the object is not included in the Event.

NO SHORT

"NO SHORT" is displayed when only the long text of a SYSERR message is selected to migrate to a target and no short text exists at the target.

NO SRC

"NO SRC" is displayed when a NATURAL object is selected to migrate to multiple targets and source code does not exist. The "NO SRC" message indicates the NATURAL object is not included in the Event.

NO OBJ

"NO OBJ" is displayed when a NATURAL object is selected to migrate to multiple targets and object code does not exist. The "NO OBJ" message indicates the NATURAL object is not included in the Event.

MULTIPLE

"MULTIPLE" is displayed when a NATURAL object, PREDICT object, or SYSERR message is selected to migrate to multiple targets. "MULTIPLE" indicates the object is added to the Event.

NOSPACES

"NOSPACES" is displayed when a PREDICT object whose name contains one or more spaces is selected to migrate to a target. "NOSPACES" indicates the PREDICT object is not included in the Event.

MISC DUP

"MISC DUP" is displayed when a 3GL object is selected to migrate to a 3GL PDS environment with a category of MISC and an identically named 3GL object of a different category has already been selected for migration to that environment. The "MISC DUP" message indicates the 3GL object is not included in the Event.

II.3 Authorize Events

The Authorize Events section describes the functions used to authorize Events. The authorization process allows the user to view the Event selection list, as well as the source code of NATURAL objects. In-progress Events may only be deleted from the Authorize Event menu.

To access the Authorize Events menu, enter "A" on the Migration Subsystem menu. Entering the direct command MIG AUTH on any menu also accesses the Authorize Events menu.

```

01-12-31      N-2-O AUTHORIZE EVENTS MENU      TSI0373
11:38:00

Code  Function
----  -
A     Authorize an Event
D     Delete an Event
I     Inquire on an Event
R     Reject an Event
S     Select Events for Processing
.     Terminate Authorize Event
----  -

Enter Code:  _   Event   : _____

                Sequence : _____

                Status   :  _

Direct Command _____ MIG AUTH
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      HELP  ----  END  ENV  MIG  REP  TOL  USR  PRJ  ----  ----  EXIT

```

Field	Description
ENTER CODE	<p>The function to be executed. Valid values are as follows:</p> <p>A Authorize an Event Provides one level of authorization for an Event.</p> <p>D Delete an Event Removes an Event that no longer needs to be processed.</p> <p>I Inquire on an Event Displays information about an Event.</p> <p>R Reject an Event Allows an authorizer to reset all authorizations to send the event back to the developers.</p> <p>S Select Events for Processing Provides a list of Events that may be deleted, inquired on, or authorized.</p>
EVENT (Required for Authorize, Delete, and Inquire)	The Master Event of the request to be authorized or maintained. For the Select function, the name is used as a starting value.
SEQUENCE (Required for Authorize, Delete, and Inquire)	The Sequence number of the Event to be authorized or maintained.
STATUS (optional)	Limits Events displayed by the Select function. For valid values refer to Appendix B N2O Event Status .

II.3.1 Authorize an Event

The Authorize an Event function allows an approved user to provide a level of authorization for an Event. It also permits the authorizer to view the object selection list for an Event. The ability to view source code for any selected NATURAL object is also available under this option.

To authorize an Event, enter "A" in the Enter Code field, the Event to be authorized in the Event field, and the Sequence number of the Event to be authorized in the Sequence field on the Authorize Events menu.

```

Press ENTER to view the selection list
01-12-31      N-2-O AUTHORIZE AN EVENT      TSI0373
11:38:00      Event: PAYIN      Sequence: 1      TSI1

      From Env      : TEST      From Library      : PAYTEST_
      To Env      : PROD      To Library      : PAYPROD_
      Process Date  : 20011231  Process Time      : 11:34:00
      Added User-ID : TREE08__

      Task Group    : PAY330E_  Task Number      : 14__

      VERIFICATION PROGRAMS_____
      C _____
      o _____
      m _____
      m _____
      e _____
      n _____
      t _____
      s _____

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
----- END -----

```

The Process Date, Process Time, Change Control, and Comments fields are modifiable when authorizing an Event.

If PF5 is labeled AUTH, pressing PF5 will display the list of authorizers for Events that require multiple levels of authorization.

Field	Type	Description
EVENT (supplied)	N,S,P,O, M,D	The Master Event of the migration.
SEQUENCE (supplied)	N,S,P,O, M,D	The sequence number of the Event.
FROM ENV (supplied)	N,S,P,O, M,D	The source Environment Definition of the migration.
FROM LIBRARY (supplied)	N,S	The library containing the NATURAL objects and/or SYSERR messages to be migrated.
TO ENV (supplied)	N,S,P,O, M,D	The target Environment Definition of the migration.
TO LIBRARY (supplied)	N,S	The library to which NATURAL objects and/or SYSERR messages are to be migrated.

(continued from previous page)

Field	Type	Description
PROCESS DATE (required)	N,S,P,O, M,D	The earliest date on which the batch migration takes place. The current date is automatically supplied by N2O, but it may be modified by the user if postdating of the migration is desired. For more information about submitting batch Events, refer to Section II.7 Batch JCL Submission .
PROCESS TIME (required)	N,S,P,O, M,D	The earliest time on the Process Date during which the batch migration may take place.
ADDED USER-ID (supplied)	N,S,P,O, M,D	The user who created the Event.
TASK GROUP (required if Master Event Project Tracking = 'Y')	N,S,P,O, M,D	A value that relates multiple Events to a specific Task Group from the N2O Project Tracking Subsystem. This field is only displayed if Project Tracking is required. When using Add, Copy, or Modify an Event, this field may be modified.
TASK NUMBER (required if Master Event Project Tracking = 'Y')	N,S,P,O, M,D	A number that relates multiple Events to a specific task from the N2O Project Tracking Subsystem. This field is only displayed if Project Tracking is required. When using Add, Copy, or Modify an Event, this field may be modified.
COMMENTS (optional)	N,S,P,O, M,D	A 10-line comment area describing the Event.
AUTH USER-ID (supplied)	N,S,P,O, M,D	The last user who authorized the Event.
CHANGE CONTROL (required if Master Event Charge Control='Y')	N,S,P,O, M,D	A value that relates multiple Events to a specific change request. This field is only displayed if Change Control is required.

Pressing Enter displays a screen listing the objects selected for the Event. For example, the screen below displays NATURAL objects selected for Event "PAYIN", Sequence "1".

When authorizing an Event that migrates more than one object type, the selection list for each type is displayed in the following order: NATURAL objects, PREDICT objects, 3GL/OTHER objects, and SYSERR messages.

```

01-12-31          N-2-O AUTHORIZE AN EVENT          TSI0373
11:38:00          Event: PAYIN      Sequence: 1      TSI1

From Env: TEST      From Library: PAYTEST      To Env: PROD      To Library: PAYPROD
Starting Object: PAY5100P

S  Object      Object      S/C  Message      S  Object      Object      S/C  Message
-  PAY5100P    PROGRAM  S      REPLACE      -  PAY5100M    MAP      S      REPLACE
-  PAY5110S    SUB-RTN  S      ADD          -  PAY5200M    MAP      S      REPLACE
-  PAY5200P    PROGRAM  S      REPLACE      -  PAY5210M    MAP      S      ADD

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
HELP  ----  END   ----  ----  TOP  UP    DOWN  BOT  ----  ----  EXIT

```

If the selection list does not fit entirely on one screen, pressing Enter displays the next screen. This process is repeated until the end of the list.

When reviewing the NATURAL objects and SYSERR message lists, pressing PF12 displays the next object type list. When reviewing the PREDICT and 3GL/OTHER object lists, pressing PF12 displays the next PREDICT object type or the next 3GL/OTHER category in the selection list.

Source code for NATURAL objects may be viewed by entering "X" in the Select field beside the program name and pressing Enter. For more information, refer to **Section II.2.6 Inquire on an Event**.

Field	Type	Description
EVENT (supplied)	N,S,P,O, M,D	The Master Event of the migration.
SEQUENCE (supplied)	N,S,P,O, M,D	The sequence number of the Event.
FROM ENV (supplied)	N,S,P,O, M,D	The source Environment Definition of the migration.
FROM LIBRARY (supplied)	N,S	The library containing the NATURAL objects and/or SYSERR messages to be migrated.
TO ENV (supplied)	N,S,P,O, M,D	The target Environment Definition of the migration.
TO LIBRARY (supplied)	N,S	The library to which the NATURAL objects and/or SYSERR messages are to be migrated.

(continued from previous page)

Field	Type	Description
STARTING OBJECT (optional)	N,S,P,O, M,D	The object where the selection list begins.
S (optional)	N,S,P,O, M,D	"X" in the Select field allows source code of a NATURAL object to be viewed when inquiring on an Event.
OBJECT (supplied)	N,S,P,O, M,D	The name of the object.
OBJECT TYPE (supplied)	N,P,O	The NATURAL object type (e.g., program, map, subprogram, etc.).
S/C (supplied)	N	The form of the NATURAL object: S Indicates only the source form of the object may be selected. C Indicates only the cataloged form of the object may be selected. S/C Indicates both forms of the object may be selected.
DDM Dbid (optional)	D	Database number that the DDM will point to in the target environment.
DDM Fnr (optional)	D	File number that the DDM will point to in the target environment.
ADA 6 (supplied)	D	Marked with an X if the DDM was created in NATURAL 2.3 or above and will allow a Dbid and/or Fnr greater than 255.
METADATA (supplied)	M	Description of the UDE – User Defined Entities
MESSAGE (supplied)	N,S,P,O, M,D	Provides information about the selection of an object. For more information about messages, refer to Section II.2.11 Object Selection Screen Messages .

If additional levels of authorization are required, the screen below is displayed indicating how many more levels of authorization are required.

```

01-12-31      N-2-O EVENT REQUEST      TSI0373
11:38:00      Event: PAYIN      Sequence: 1      TSI1

Event Awaiting Authorization
(Requires 1 more level(s) of authorization)

Press ENTER to continue

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
-----

```

If servicing is required for the Event, the screen below is displayed.

01-12-31	N-2-O EVENT REQUEST	TSI0373
11:38:00	Event: PAYIN Sequence: 1	TSI1
Event Awaiting Servicing		
Press ENTER to continue		
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---		

If no additional levels of authorization or servicing are required, the migration process begins. For more information about the migration process, refer to **Section II.2.3 Migration Process**.

II.3.2 Delete an Event

The Delete an Event function removes an Event that no longer needs to be processed.

To delete an Event, enter "D" in the Enter Code field, the Event to be deleted in the Event field and the Sequence number of the Event to be deleted in the Sequence field on the Authorize Events menu.

Closed Events (Status "C") and In-progress Events (status "I") that have migrated Objects cannot be deleted. Other In-progress Events may only be deleted from the Authorize Event menu.

01-12-31 11:38:00	N-2-O DELETE AN EVENT Event: PAYOUT Sequence: 3		TSI0373 TSI1																
<table> <tr> <td>From Env</td> <td>: PROD</td> <td>From Library</td> <td>: PAYPROD_</td> </tr> <tr> <td>To Env</td> <td>: DEV</td> <td>To Library</td> <td>: PAYDEV_</td> </tr> <tr> <td>Process Date</td> <td>: 20011231</td> <td>Process Time</td> <td>: 11:38:00</td> </tr> <tr> <td>Added User-ID</td> <td>: TSI1__</td> <td></td> <td></td> </tr> </table>				From Env	: PROD	From Library	: PAYPROD_	To Env	: DEV	To Library	: PAYDEV_	Process Date	: 20011231	Process Time	: 11:38:00	Added User-ID	: TSI1__		
From Env	: PROD	From Library	: PAYPROD_																
To Env	: DEV	To Library	: PAYDEV_																
Process Date	: 20011231	Process Time	: 11:38:00																
Added User-ID	: TSI1__																		
C	_____																		
O	_____																		
M	_____																		
M	_____																		
E	+-----+																		
N	Do you want to Delete? N (Y/N)																		
T																			
S	+-----+																		
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---																			
----- END -----																			

To delete the Event, enter "Y" in the pop-up window. To cancel the delete request, press PF3 or enter "N" in the pop-up window.

Refer to **Section II.2.1 Add an Event** for a description of each field.

II.3.3 **Inquire on an Event**

The Inquire on an Event function displays Event information.

To inquire on an Event, enter "I" in the Enter Code field, the Event to be viewed in the Event field, and the Sequence number of the Event to be viewed in the Sequence field on the Authorize Events menu.

```

Press Enter to display the selection list
01-12-31      N-2-O INQUIRE ON AN EVENT      TSI0373
11:38:00      Event: EXTRACT  Sequence: 1      TSI1
                  Extract Event

      From Env      : PROD      From Library      : PAYPROD_
      To Env        : MAIN      To Library        : PAYMAIN_
      Process Date   : 20011231  Process Time     : 12:10:42
      Added User-ID  : TSI1_

      C
      o
      m
      m
      e
      n
      t
      s

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
----- END -----

```

Refer to **Section II.2.1 Add an Event** for a description of each field.

Pressing Enter displays a screen listing the objects selected for the Event. For example, the screen below displays NATURAL objects selected for Event "EXTRACT", Sequence "1".

When inquiring on an Event that migrates more than one object type, the selection list for each type is displayed in the following order: NATURAL objects, PREDICT objects, 3GL/OTHER objects, SYSERR messages DDMS and METADATA .

```

01-12-31      N-2-O INQUIRE ON AN EVENT      TSI0373
11:38:00      Event: EXTRACT  Sequence: 1      TSI1

From Env: PROD      From Library: PAYPROD  To Env: MAIN      To Library: PAYMAIN
                  Starting Object: PAY5100P

      Object      Object      S/C      Message      S      Object      Object      S/C      Message
      S      Object      Type      S/C      Message      S      Object      Type      S/C      Message
      -      PAY5100P  PROGRAM  S      REPLACE      -      PAY5100M  MAP      S      REPLACE
      -      PAY5110S  SUB-RTN  S      ADD          -      PAY5200M  MAP      S      REPLACE
      -      PAY5200P  PROGRAM  S      REPLACE      -      PAY5210M  MAP      S      ADD

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
HELP ----- END ----- TOP UP DOWN BOT ----- EXIT

```

If the list does not fit entirely on one screen, pressing Enter displays the next screen. This process is repeated until the end of the list.

When reviewing the DDMS, NATURAL objects and SYSERR message lists, pressing PF12 displays the next object type. When reviewing the METADATA, PREDICT and 3GL/OTHER object lists, pressing PF12 displays the next PREDICT object type or the next 3GL/OTHER category in the selection list.

Source code for NATURAL objects may be viewed by entering "X" in the Select field beside the object name and pressing Enter. For more information, refer to **Section II.2.6 Inquire on an Event**.

Field	Type	Description
EVENT (supplied)	N,S,P,O, M,D	The Master Event of the migration.
SEQUENCE (supplied)	N,S,P,O, M,D	The sequence number of the Event.
FROM ENV (supplied)	N,S,P,O, M,D	The source Environment Definition of the migration.
FROM LIBRARY (supplied)	N,S	The library containing the NATURAL objects and/or SYSERR messages to be migrated.
TO ENV (supplied)	N,S,P,O, M,D	The target Environment Definition of the migration.
TO LIBRARY (supplied)	N,S	The library to which the NATURAL objects and/or SYSERR messages are to be migrated.
STARTING OBJECT (optional)	N,S,P,O, M,D	The object where the selection list begins.
S (optional)	N,S,P,O, M,D	"X" in the Select field allows source code of a NATURAL object to be viewed when inquiring on an Event.
OBJECT (supplied)	N,S,P,O, M,D	The name of the object.
OBJECT TYPE (supplied)	N,P,O	The object type (e.g., program, map, subprogram, etc.)
S/C (supplied)	N	The form of the object: <ul style="list-style-type: none"> S Indicates only the source form of the object may be selected. C Indicates only the cataloged form of the object may be selected. S/C Indicates both forms of the object may be selected.

(continued from previous page)

Field	Type	Description
DDM Dbid (optional)	D	Database number that the DDM will point to in the target environment.
DDM Fnr (optional)	D	File number that the DDM will point to in the target environment.
ADA 6 (supplied)	D	Marked with an X if the DDM was created in NATURAL 2.3 or above and will allow a Dbid and/or Fnr greater than 255.
METADATA (supplied)	M	Description of the UDE – User Defined Entities
MESSAGE (supplied)	N,S,P,O	Provides information about the selection of an object. For more information about messages, refer to Section II.2.11 Object Selection Screen Messages .

II.3.4 Reject an Event

The Reject an Event function allows an authorizer to reject all authorizations applied to an Event.

To Reject an Event, enter "R" in the Enter Code field, the Event to be viewed in the Event field, and the Sequence number of the Event with authorizations to be rejected in the Sequence field on the Authorize Events menu.

Pressing Enter displays a screen listing the userids that have authorized the Event. For example, the screen below displays NATURAL objects selected for Event "PAYOUT", Sequence "3".

```

Reject Event: PAYOUT   Seq:      3
----- Authorization -----
#  USERID      DATE      TIME
-  -
1  AUTH1       20130729   15:29:21
2
3
4
5
6
7
8
9
10
Press ENTER to Reject the authorizations, or
PF3 to Stop the Reject Process

```

Pressing Enter will reject all Authorizations for the Event. Pressing PF3 will abort rejecting all Authorizations and leave the Authorizations in place.

Field	Type	Description
EVENT (supplied)	N,S,P,O, M,D	The Master Event of the migration.
SEQUENCE (supplied)	N,S,P,O, M,D	The sequence number of the Event.
USERID (supplied)	N,S,P,O, M,D	Userid that authorized the authorization level.
DATE (supplied)	N,S,P,O, M,D	Date of the authorization for the authorization level.
TIME (supplied)	N,S,P,O, M,D	Time of the authorization for the authorization level.

II.3.5 Select Events for Processing

The Select Events for Processing function provides a list of Events that may be deleted, inquired on, or authorized. This function only displays Events that need to be authorized.

To select Events for processing, enter "S" in the Enter Code field on the Authorize Events menu. A starting value may be entered in the Event and Sequence fields. Entering a value in the Status field limits the output to Events with the specified status. If no status is entered, a value of "O" is assumed.

```

Valid Values: D - Delete I - Inquire
01-12-31          N-2-O SELECT EVENTS FOR PROCESSING          TSI0373
11:38:00          Status: O          TSI1

S  Event      Seq      From To  Event  ---- Added ----  ---- Task ----
-  -----  -  -  -  -  -  -  -  -  -  -  -  -  -  -  -  -  -  -  -  -
-  EXTRACT    1      PROD MAIN  N      TSI0373  01-12-31  *****  *****

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      HELP  ----  END   ----  CHNG  ----  ----  ----  ----  ----  ----  ----
  
```

PF5 is available to toggle between the Project Tracking Task and Change Control for each Event listed on the select screen.

PF7 is available to toggle the sorting of displayed Events by Change Control or Event and Sequence.

Field	Description
S (optional)	The function to be executed. Possible functions are A, D, or I (Authorize, Delete, or Inquire). The user's Function Profile security defines the user's valid functions. The Event/Sequence selected is processed according to the function code entered.

Pressing Enter pages forward on all screens until the last screen is displayed. Pressing Enter on the last screen displays the first screen again.

II.4 Service Events

The Service Events section describes the functions used to service Events. The Service Events process allows the user to view the Event selection list, as well as the source code of NATURAL objects.

To access the Service Events menu, enter "S" on the Migration Subsystem menu. Entering the direct command MIG SERV on any menu also accesses the Service Events menu.

```

01-12-31          N-2-O SERVICE EVENTS MENU          TSI0373
11:38:00                                     TSI1

Code  Function
----  -
D    Delete an Event
I    Inquire on an Event
P    Service an Event
S    Select Events for Processing
.    Terminate Service Event
----  -

Enter Code: _   Event   : _____

                Sequence : _____

                Status   : _

Direct Command: _____ MIG SERV
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      HELP  ----  END  ENV  MIG  REP  TOL  USR  PRJ  ----  ----  EXIT

```

Field	Description
ENTER CODE	The function to be executed. Valid values are as follows: <ul style="list-style-type: none"> D Delete an Event Removes an Event that no longer needs to be Serviced. I Inquire on an Event Displays information about an Event. P Service an Event Provides a level of authorization above Authorize an Event. S Select Events for Processing Provides a list of Events that may be deleted, inquired on, or modified.
EVENT (Required for Inquire and Service)	The Master Event of the request to service or inquire on. For the Select function, the Event name is used as a starting search key.
SEQUENCE (Required for Inquire and Service)	The sequence number of the Event on which to service or inquire.
STATUS (optional)	The Status limits Events displayed by the Select function. For valid values refer to Appendix B N2O Event Status .

II.4.1 Delete an Event

The Delete an Event function removes an Event that no longer needs to be processed.

To delete an Event, enter "D" in the Enter Code field, the Event to be deleted in the Event field, and the Sequence number of the Event to be deleted in the Sequence field on the Service Events menu.

Closed Events (Status "C") and In-progress Events (status "I") that have migrated Objects cannot be deleted.

01-12-31 11:38:00	N-2-O DELETE AN EVENT Event: PAYOUT Sequence: 2	TSI0373 TSI1
From Env : PROD	From Library : PAYPROD_	
To Env : DEV	To Library : PAYDEV_	
Process Date : 20011231	Process Time : 11:38:00	
Added User-ID : TSI1__		
C		
o		
m		
m		
e		
n		
t		
s		
<div style="border: 1px solid black; padding: 5px; text-align: center;"> Do you want to Delete? N (Y/N) </div>		
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12--- --- END ---		

To delete the Event, enter "Y" in the pop-up window. To cancel the delete request, press PF3 or enter "N" in the pop-up window.

Refer to **Section II.2.1 Add an Event** for a description of each field.

II.4.2 Inquire on an Event

The Inquire on an Event function displays information about an Event.

To inquire on an Event, enter "I" in the Enter Code field, the Event to be displayed in the Event field, and the Sequence number of the Event to be displayed in the Sequence field on the Service Events menu.

```

Press Enter to display the selection list
01-12-31      N-2-O INQUIRE ON AN EVENT      TSI0373
11:38:00      Event: PAYIN   Sequence: 1      TSI1

      From Env      : TEST      From Library      : PAYTEST_
      To Env        : PROD      To Library        : PAYPROD_
      Process Date   : 20011231  Process Time      : 12:10:42
      Create User-ID : TSI1_

C _____
o _____
m _____
e _____
n _____
t _____
s _____

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      END
  
```

Pressing Enter displays a screen listing objects selected to migrate. For example, the screen below displays NATURAL objects selected for Event "PAYIN", Sequence "1".

When inquiring on an Event that migrates more than one object type, the selection list for each type is displayed in the following order: NATURAL objects, PREDICT objects, 3GL/OTHER objects, and SYSERR messages.

```

01-12-31      N-2-O INQUIRE ON AN EVENT      TSI0373
11:38:00      Event: PAYIN   Sequence: 1      TSI1

From Env: TEST      From Library: PAYTEST      To Env: PROD      To Library: PAYPROD
Starting Object: PAY5100P

S   Object      Object
  Object      Type      S/C   Message      S   Object      Object
  Object      Type      S/C   Message      S   Object      Object
-   PAY5100P    PROGRAM  S   REPLACE      -   PAY5100M    MAP      S   REPLACE
-   PAY5110S    SUB-RTN  S   ADD          -   PAY5200M    MAP      S   REPLACE
-   PAY5200P    PROGRAM  S   REPLACE      -   PAY5210M    MAP      S   ADD

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
HELP  END  TOP  UP  DOWN  BOT  EXIT
  
```

If the selection list does not fit entirely on one screen, pressing Enter displays the next screen. This process is repeated until the end of the list.

When reviewing the NATURAL objects and SYSERR message lists, pressing PF12 displays the next object type. When reviewing the PREDICT and 3GL/OTHER object lists, pressing PF12 displays the next PREDICT object type or the next 3GL/OTHER category in the selection list.

Source code for NATURAL objects may be viewed by entering "X" in the Select field beside the object name and pressing Enter. For more information, refer to **Section II.2.6 Inquire on an Event**.

Field	Type	Description
EVENT (supplied)	N,S,P,O, M,D	The Master Event of the migration.
SEQUENCE (supplied)	N,S,P,O, M,D	The sequence number of the Event.
FROM ENV (supplied)	N,S,P,O, M,D	The source Environment Definition of the migration.
FROM LIBRARY (supplied)	N,S	The library containing the NATURAL objects and/or SYSERR messages to be migrated.
TO ENV (supplied)	N,S,P,O, M,D	The target Environment Definition of the migration.
TO LIBRARY (supplied)	N,S	The library to which the NATURAL objects and/or SYSERR messages are to be migrated.
STARTING OBJECT (optional)	N,S,P,O, M,D	The object where the selection list begins.
S (optional)	N,S,P,O, M,D	"X" in the Select field allows source code of a NATURAL object to be viewed when inquiring on an Event.
OBJECT (supplied)	N,S,P,O, M,D	The name of the object.
OBJECT TYPE (supplied)	N,P,O	The NATURAL object type (e.g., program, map, subprogram, etc.).
S/C (supplied)	N	The form of the NATURAL object: <ul style="list-style-type: none"> S Indicates only the source form of the object may be selected. C Indicates only the cataloged form of the object may be selected. S/C Indicates both forms of the object may be selected.

(continued from previous page)

Field	Type	Description
DDM Dbid (optional)	D	Database number that the DDM will point to in the target environment.
DDM Fnr (optional)	D	File number that the DDM will point to in the target environment.
ADA 6 (supplied)	D	Marked with an X if the DDM was created in NATURAL 2.3 or above and will allow a Dbid and/or Fnr greater than 255.
METADATA (supplied)	M	Description of the UDE – User Defined Entities
MESSAGE (supplied)	N,S,P,O, M,D	Provides information about the selection of an object. For more information about messages, refer to Section II.2.11 Object Selection Screen Messages .

II.4.3 Service an Event

The Service an Event function allows a user to view the Event selection list. This function also provides the ability to view the source code of NATURAL objects and provides an additional level of authorization.

To service an Event, enter "P" in the Enter Code field, the Event to be serviced in the Event field, and the Sequence number of the Event to be serviced in the Sequence field on the Service Events menu.

```

Press ENTER to view the selection list
01-12-31      N-2-O SERVICE AN EVENT      TSI0373
11:38:00      Event: PAYIN      Sequence: 66      TSI1

      From Env      : TEST      From Library      : PAYTEST_
      To Env      : PROD      To Library      : PAYPROD_
      Process Date : 20011231      Process Time      : 11:34:00
      Added User-ID : TSI1      Authorize User-ID: TSI2

      Task Group      : PAYE      Task Number      : 7

      C
      o
      m
      m
      e
      n
      t
      s

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      END
  
```

The Process Date, Process Time, Change Control, and Comments fields are modifiable when servicing an Event.

If PF5 is labeled AUTH, pressing PF5 will display the list of authorizations for Events that require multiple levels of authorization.

Field	Type	Description
EVENT (supplied)	N,S,P,O, M,D	The Master Event of the migration.
SEQUENCE (supplied)	N,S,P,O, M,D	The sequence number of the Event.
FROM ENV (supplied)	N,S,P,O, M,D	The source Environment Definition of the migration.
FROM LIBRARY (supplied)	N,S	The library containing the NATURAL objects and/or SYSERR messages to be migrated.
TO ENV (supplied)	N,S,P,O, M,D	The target Environment Definition of the migration.
TO LIBRARY (supplied)	N,S	The library to which NATURAL objects and/or SYSERR messages are to be migrated.

(continued from previous page)

Field	Type	Description
PROCESS DATE (required)	N,S,P,O, M,D	The earliest date on which the batch migration takes place. The current date is automatically supplied by N2O, but it may be modified by the user if postdating of the migration is desired. For more information about submitting batch Events, refer to Section II.7 Batch JCL Submission .
PROCESS TIME (required)	N,S,P,O, M,D	The earliest time on the Process Date during which the batch migration may take place.
ADDED USER-ID (supplied)	N,S,P,O, M,D	The user who created the Event.
TASK GROUP (required)	N,S,P,O, M,D	A value that relates multiple Events to a specific Task Group from the N2O Project Tracking Subsystem. This field is only displayed if Project Tracking is required. When using Add, Copy, or Modify an Event, this field may be modified.
TASK NUMBER (required)	N,S,P,O, M,D	A number that relates multiple Events to a specific task from the N2O Project Tracking Subsystem. This field is only displayed if Project Tracking is required. When using Add, Copy, or Modify an Event, this field may be modified.
AUTH USER-ID (supplied)	N,S,P,O, M,D	The last user who authorized the Event.
CHANGE CONTROL (required)	N,S,P,O, M,D	A value that relates multiple Events to a specific change request. This field is only displayed if Change Control is required.
COMMENTS (optional)	N,S,P,O, M,D	A 10-line comment area describing the Event.

Pressing Enter displays a screen listing objects selected to migrate. For example, the screen below displays NATURAL objects selected for Event "PAYIN", Sequence "1".

When servicing an Event that migrates more than one object type, the selection list for each type is displayed in the following order: NATURAL objects , PREDICT objects, 3GL/OTHER objects, and SYSERR messages.

01-12-31	N-2-O SERVICE AN EVENT				TSI0373			
11:38:00	Event: PAYIN				Sequence: 1			
				TSI1				
From Env: TEST		From Library: PAYTEST		To Env: PROD		To Library: PAYPROD		
Starting Object: PAY5100P								
Object				Object				
S	Object	Type	S/C	Message	S	Object	Type	
—	PAY5100P	PROGRAM	S	REPLACE	—	PAY5100M	MAP	
—	PAY5110S	SUB-RTN	S	ADD	—	PAY5200M	MAP	
—	PAY5200P	PROGRAM	S	REPLACE	—	PAY5210M	MAP	
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---								
HELP		----	END	----	TOP	UP	DOWN	

If the selection list does not fit entirely on one screen, pressing Enter displays the next screen. This process is repeated until the end of the list.

When reviewing the NATURAL objects and SYSERR message lists, pressing PF12 displays the next object type. When reviewing the PREDICT and 3GL/OTHER object lists, pressing PF12 displays the next PREDICT object type or the next 3GL/OTHER category in the selection list.

Source code for NATURAL objects may be viewed by entering "X" in the Select field beside the object name and pressing Enter. For more information, refer to **Section II.2.6 Inquire on an Event**.

Field	Type	Description
EVENT (supplied)	N,S,P,O, M,D	The Master Event of the migration.
SEQUENCE (supplied)	N,S,P,O, M,D	The sequence number of the Event.
FROM ENV (supplied)	N,S,P,O, M,D	The source Environment Definition of the migration.
FROM LIBRARY (supplied)	N,S	The library containing the NATURAL objects and/or SYSERR messages to be migrated.
TO ENV (supplied)	N,S,P,O, M,D	The target Environment Definition of the migration.
TO LIBRARY (supplied)	N,S	The library to which the NATURAL objects and/or SYSERR messages are to be migrated.
STARTING OBJECT (optional)	N,S,P,O, M,D	The object where the selection list begins.
S (optional)	N,S,P,O, M,D	"X" in the Select field allows source code of a NATURAL object to be viewed when inquiring on an Event.
OBJECT (supplied)	N,S,P,O, M,D	The name of the object.
OBJECT TYPE (supplied)	N,P,O	The NATURAL object type (e.g., program, map, subprogram, etc.).
S/C (supplied)	N	The form of the NATURAL object: S Indicates only the source form of the object may be selected. C Indicates only the cataloged form of the object may be selected. S/C Indicates both forms of the object may be selected.
DDM Dbid (optional)	D	Database number that the DDM will point to in the target environment.
DDM Fnr (optional)	D	File number that the DDM will point to in the target environment.
ADA 6 (supplied)	D	Marked with an X if the DDM was created in NATURAL 2.3 or above and will allow a Dbid and/or Fnr greater than 255.
METADATA (supplied)	M	Description of the UDE – User Defined Entities
MESSAGE (supplied)	N,S,P,O, M,D	Provides information about the selection of an object. For more information about messages, refer to Section II.2.11 Object Selection Screen Messages .

II.4.4 Select Events for Processing

The Select Events for Processing function provides a list of Events that may be inquired on or serviced.

To select Events for processing, enter "S" in the Enter Code field on the Service Events menu. A starting value may be entered in the Event and Sequence fields. Entering a value in the Status field limits the output to Events with the specified status. Refer to **Appendix B N2O Event Status** for valid Status field values. If no status is entered, a value of "A" is assumed.

```

Valid Values: D - Delete I - Inquire P - Service
01-12-31      N-2-O SELECT EVENTS FOR PROCESSING      TSI0373
11:38:00      Status: O                                TSI1

S  Event      Seq      From To  Event  ---- Added ---- ---- Task ----
  -----
  _ PAYIN      1      TEST PROD  N      TSI1    01-12-31  *****

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      HELP  ----  END   ----  CHNG  ----  ----  ----  ----  ----  ----  ----
  
```

PF5 is available to toggle between the Project Tracking Task and Change Control for each Event listed on the select screen.

PF7 is available to toggle between sorting the events by Change Control and sorting by event/event sequence.

Field	Description
S (optional)	The function to be executed. Valid functions are D, I, and P (Delete, Inquire and Service). The user's Function Profile security defines the user's valid functions.

Only Events that a user may process are displayed. The Event/Sequence selected is processed according to the function code entered.

Pressing Enter pages forward on all screens until the last screen is displayed. Pressing Enter on the last screen wraps around to display the first screen again.

II.5 Migration Utilities

The Migration Utilities assist users in performing Autocompile and completing the MOVE process for Events.

To access the Migration Utilities menu, enter "M" on the Migration Subsystem menu. Entering the direct command MIG UTIL on any menu also accesses the Migration Utilities menu.

```

01-12-31          N-2-O MIGRATION UTILITIES MENU          TSI0373
11:38:00                                     TSI1

Code  Function
----  -
A     Libraries Pending Autocompile
B     Process Deferred Move Events
C     Cancel Deferred Move Events
D     3GL/Other PDS Member Type Update
E     Build Event by Change Control
.     Terminate Migration Utilities
----  -

Enter Code:  _

Direct Command _____ MIG UTIL
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      HELP  ----  END  ENV  MIG  REP  TOL  USR  PRJ  ----  ----  EXIT

```

Field	Description
ENTER CODE	<p>The function to be executed. Valid values are as follows:</p> <ul style="list-style-type: none"> A Libraries Pending Autocompile Displays a list of libraries that contain Events marked for Autocompile. B Process Deferred Move Events Processes deferred move Events. C Cancel Deferred Move Events Cancels deferred move Events. D 3GL/OTHER PDS Member Type Update 3GL/OTHER objects for 3GL/OTHER Autocompile. E Build Event by Change Control Build an Event by Change Control.

II.5.1 Libraries Pending Autocompile

Libraries Pending Autocompile displays a list of all libraries in the current FUSER that contain Events marked for Autocompile.

N2O provides Autocompile to automate the compile process for NATURAL source objects after they have been migrated. Autocompile automatically updates the NATURAL buffer pool for the target environment. If Autocompile is not used and object code is migrated, the NATURAL buffer pool is not updated. The Libraries Pending Autocompile function initiates the on-line Autocompile process.

XREF at the Target is available with Autocompile and uses Cross-Reference information stored in PREDICT. If the object type being migrated is specified in the XREF TARGET field on the Migration Profile, PREDICT Cross-Reference information will be used to determine all NATURAL objects affected by the migrated object(s). These affected objects and the objects being migrated will be autocompiled in the target Environment.

During the Autocompile process, N2O provides an optional Automatic Recovery feature. If an error occurred during the Event compilation process, then Automatic Recovery restores the previous versions of all the migrated objects within that Event.

After entering "A" in the Enter Code field and pressing Enter on the Migration Utilities menu, the Libraries Pending Autocompile screen is displayed. Entering "N2OCATI" on the NATURAL Command line also accesses the Libraries Pending Autocompile screen.

A pop-up window indicates that a scan of all libraries is being performed, which searches for libraries pending Autocompile. The screen below displays all libraries pending Autocompile. The number next to the library name identifies the number of Events that are pending Autocompile.

```

Type X to select a library to perform AUTOCOMPILE on (DOES NOT RETURN TO N2O)
01-12-31          N-2-O LIBRARIES PENDING AUTOCOMPILE          TSI0373
11:38:00                                     TSI1

                                DBID: 1      FNR: 231

                                X Library  Nbr    X Library  Nbr
                                - - - - - - - - - - - - - - -
                                _ PAYPROD  1

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
HELP  ----  END   ----  ----  ----  ----  ----  ----  ----  ----  ----  ----

```

To list the Events awaiting Autocompile for a library, enter "X" beside the library name and press Enter. Only one library may be selected.

N2O logs on to the selected library and lists all Events marked for Autocompile as shown on the Events Pending Autocompile screen. Entering "N2OCAT" on the NATURAL Command line in the target environment also accesses the Events Pending Autocompile screen. This provides the ability to perform Autocompile on remote environments.

```

Type X to perform Autocompile or D to Delete
01-12-31          N2O MIGRATION UTILITIES          TSI0373
11:38:00          EVENTS PENDING AUTOCOMPILE        TSI1

      S  Event   Seq   Date    Time    User-ID  Function
      -  - - - - - - - - - - - - - - - - - - - - -
      -  PAYIN   1     01-12-31  13:58:12  TSI1     CAT

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
HELP  ----  END   ----  ----  ----  ----  ----  ----  ----  ----  ----

```

The screen above displays a list of Events for the selected target library that are pending Autocompile. To compile NATURAL objects for an Event, enter "X" beside the Events. To delete the Autocompile process for an Event, enter "D" beside the Event. A pop-up window displays the number of Events to be deleted, and requests confirmation before deleting. It is possible to select more than one Event at a time.

After selecting Events for Autocompile and pressing Enter, the Automatic Compile Subsystem screen displays the Event selected for Autocompile.

```

01-12-31          N-2-O AUTOCOMPILE                TSI0373
11:38:00          TSI1

Autocompile has been requested for
Event : PAYIN      Sequence : 1

Press ENTER to proceed

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
HELP  ----  END   ----  ----  ----  ----  ----  ----  ----  ----

```

After pressing Enter on the Automatic Compile Subsystem screen, the Cataloging Phase screen displays each NATURAL object as it is cataloged. If an error occurs during the cataloging process, the error and the line number on which the error occurred are displayed next to the object.

```

11:38:00          ***** Recatalog Application *****          01-12-31
USER: TSI0373      Cataloging Phase                          LIBRARY: PAYPROD

                                     Object   Error Line
                                     -----   -
                                     -----

                                     Please wait
                                     -----

Objects   current   correct   failed   Curr. Object   BPAY      82    1050
          4         4         2         1         DELOPAY    CATSCAN
                                     COPIER

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
```

After the cataloging phase is complete, the Error Report screen is displayed if any of the NATURAL objects received syntax errors. This screen identifies NATURAL objects with errors, the errors they received, and the lines that caused the errors.

```

11:38:00          ***** Recatalog Application *****          TSI0373
User: TSI1         Error Report                               TSI1

Object   Error Line
-----   -
BPAY     82    1050
```

When Autocompile is completed for an Event, the Autocompile screen confirms that Autocompile is completed. After pressing Enter, User-Exit 7 is invoked. This User-Exit may be used to return the user to the N2O main menu or exit NATURAL (Refer to the **N2O Administration Manual** for details on User-Exit 7).

```

01-12-31          N-2-O AUTOCOMPILE          TSI0373
11:38:00          TSI1

Autocompile has completed for
Event : PAYIN      Sequence : 1

Press ENTER to proceed

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
-----

```

To restart a compile that was terminated abnormally, enter "N2OCAT" on the NATURAL Command line and press Enter. An Autocompile Re-Start screen is displayed. If Enter is pressed on the Re-Start screen, the compile process continues compiling NATURAL objects at the point where it had previously terminated. If PF3 is pressed, the request for Autocompile is deleted for that Event and the Autocompile process continues for the remaining Events.

II.5.2 Process Deferred Move Events

The Process Deferred Move Events function starts the deletion process for Deferred Move Events. This utility only processes on-line Events. Batch Events are handled by the deletion process for a Batch Deferred Move. Events having a deferred date and time greater than the current date and time are bypassed. User-Exit 12 may be called to secure the use of the Process Deferred Move Events function. (Refer to the **N2O Administration Manual** for details on User-Exit 12.)

After entering "B" in the Enter Code field on the Migration Utilities menu, the Process Deferred Move Events screen is displayed.

Type X To Process a Deferred Move Event							
01-12-31		N-2-O PROCESS DEFERRED MOVE EVENTS					TSI0373
11:38:00							TSI1
			From	From	--- Migration ---		Added
X	Event	Seq	Env	Library	Date	Time	User-ID
-	PAYTEST	2	DEV	PAYDEV	01-12-01	13:30:00	TSI0373
-	PAYTES	3	DEV	PAYDEV	01-12-01	15:30:00	TSI0373
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12--							
HELP ---- END ----							

The deletion process is initiated by entering "X" beside an Event. It is possible to select more than one Event at a time. As the Event is processed, the NATURAL objects scroll upward until processing is complete. A "CANCEL" message indicates that a previous migration has eliminated the need for the delete to occur. A verification screen is displayed after each selection is processed.

II.5.3 Cancel Deferred Move Events

The Cancel Deferred Move Events function cancels the deletion process for deferred moves. User-Exit 12 may be called to secure the use of the Cancel Deferred Move Events function. (Refer to the **N2O Administration Manual** for details on User-Exit 12.)

After entering "C" in the Enter Code field on the Migration Utilities menu, the Cancel Deferred Move Events screen is displayed.

```

Type X to cancel a Deferred Move Event
01-12-31          N-2-O CANCEL DEFERRED MOVE EVENTS          TSI0373
11:38:00                                     TSI1

      X   Event      Seq      From   From   --- Migration ---   Added
      -   - - - - -   - - -   Env    Library   Date      Time      User-ID
      -   - - - - -   - - -   - - -   - - - - -   - - - - -   - - - - -
      -   PAYTEST    2       DEV    PAYDEV    01-12-01  13:30:00  TSI0373
      -   PAYTEST    3       DEV    PAYDEV    01-12-01  15:30:00  TSI0373
      -   - - - - -   - - -   - - -   - - - - -   - - - - -   - - - - -

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      - - - - -   END   - - - - -   - - - - -   - - - - -   - - - - -
  
```

The deletions for an Event may be canceled by placing "X" beside the Event. It is possible to select more than one Event at a time.

II.5.4 3GL/OTHER PDS Object Type Update

The 3GL/OTHER PDS Object Type Update function updates the N2O Migration file with information about 3GL/OTHER PDS objects. This information is used during the migration selection process and the 3GL/OTHER Autocompile process.

After entering "D" in the Enter Code field on the Migration Utilities menu and pressing Enter, the 3GL/OTHER PDS Object Type Update screen is displayed.

01-12-31 11:38:00	N-2-O 3GL/OTHER PDS MEMBER TYPE UPDATE	TSI0373 TSI1
<div> <div>Env Def</div> <div>:</div> <div>PDSP</div> </div> <div> <div>Category</div> <div>:</div> <div>COBOL_</div> </div> <div> <div>Starting Value:</div> <div>_____</div> </div>		
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12--- HELP ---- END ----		

Field	Description
∞ ENV DEF (required)	The Environment Definition of the PDS to be updated.
∞ CATEGORY (required)	The 3GL/OTHER category to be selected for updating.
STARTING VALUE (optional)	The starting object.

∞ indicates field-level help is available.

After entering the appropriate information on the 3GL/OTHER PDS Object Type Update screen and pressing Enter, the PDS Object Type Update screen is displayed.

01-12-31 11:38:00	N2O 3GL/OTHER PDS MEMBER TYPE UPDATE		TSI0373 TSII
Env Def:	PDSP	Category:	COBOL
Member	Member Type	Message	
-----	-----	-----	
C-BOL-3	COBOL	_____	
CAKENAT6	COBOL	_____	
CARRPRTC	COBOL	_____	
CATALLC	COBOL	_____	
CATOS6	COBOL	_____	
CCATALL	COBOL	_____	
CDACMP	COBOL	_____	
CDADBS	COBOL	_____	
CDAFRM	COBOL	_____	
CDALOD	COBOL	_____	
CDAREORG	COBOL	_____	
CDAREP	COBOL	_____	
CDAULD	COBOL	_____	
CDAWAN	COBOL	_____	
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---			
HELP ---- END ----			

A list of objects and member types is displayed. The member types may be updated by entering a new value.

II.5.5 Build Event by Change Control

The Build Event by Change Control function allows the entry of an Event and change control number. This information will be used to build an Event containing all modules checked out using the associated change control number and currently residing in the Environment/Library of the Master Event entered. The existing checkouts will be transferred to the current user (if necessary) before being selected for the event.

After entering "E" in the Enter Code field on the Migration Utilities menu and pressing Enter, Build Event by Change Control Update screen is displayed.

```

14-01-14                      N-2-O MIGRATION UTILITIES MENU                      VLM1
14:52 +-----+-----+-----+-----+-----+-----+ CP11
!
!          *****
!          Build Event by Change Control
!          *****
!          Utility to consolidate all checkouts currently in the
!          from environment of the requested event that were
!          migrated with a specific Change Control, transfer the
!          checkout to the current user (if necessary), and build
!          an event that contains all the objects.
!          *****
!          Type          : N (N,S,P,O,D,M)
!          Event         :
!          Change Control:          (BLANK TO READ FROM EVENT)
!
!          ** PF1=Help  ENTER '.' OR PF3 TO CANCEL
!          *****
!
+-----+-----+-----+-----+-----+-----+
Direct Command: _____ MIG UTIL

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      HELP  ----  END   ENV   MIG   REP   TOL   ----  PRJ   ----  ----  EXIT

```

Field	Description
∞TYPE (required)	The type of objects affected. Valid values are as follows: D Indicates DDM. M Indicates METADATA. N Indicates NATURAL. P Indicates PREDICT. S Indicates SYSERR. O Indicates 3GL/OTHER
∞ EVENT (required)	The Master Event of the migration.
∞ CHANGE CONTROL (required)	A value that relates multiple Events to a specific change request.

∞ indicates field-level help is available.

II.6 Checkout/Checkin Utilities

When the Checkout/Checkin feature is active, it automatically updates the Checkout/Checkin status as objects migrate through the application life cycle. The Checkout/Checkin Utilities are also available to manually update the Checkout/Checkin status of an object.

Each of the Checkout/Checkin Utilities maintains an audit trail, which lists the User-ID of users of the utility, and the date and time the utility was executed. Other relevant information is stored according to the type of utility that was executed. The complete life cycle for an object may be viewed in **Section IV.4.2 History of an Object**.

User-Exit 5 may be called to secure the use of the Checkout/Checkin Utilities. This user-exit may be used to prevent users from canceling or transferring objects checked out to other users, to verify naming standards, or to prevent existing objects from being checked out (Refer to the **N2O Administration Manual** for details on User-Exit 5).

To access the Checkout/Checkin utilities menu, enter "C" in the Enter Code field on the Migration Subsystem menu. Entering the direct command MIG COCI on any menu also accesses the Checkout/Checkin Utilities menu.

01-12-31 11:38:00	N-2-O CHECKOUT/CHECKIN UTILITIES MENU	TSI0373 TSI1
	Code Function	

	A Cancel Utility	
	B Transfer Utility	
	C Transfer by Event Utility	
	D Checkout Utility	
	E Reject Utility	
	F Enrollment Facility	
	G Reject by Event Utility	
	. Terminate Checkout Utilities	
	- -----	
Enter Code: _	Type : N	
Direct Command: _____		MIG COCI
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---		
HELP ---- END ENV MIG REP TOL USR PRJ ---- ---- EXIT		

Note: The following sections display only NATURAL object screens. However, field description tables include fields found on screens for the following objects: DDMS (D), METADATA (M), NATURAL objects (N), PREDICT objects (P), 3GL/OTHER objects (O), and SYSERR messages (S).

Field	Description
ENTER CODE	<p>The function to be executed. Valid values are as follows:</p> <ul style="list-style-type: none"> A Cancel Utility Utilities that remove the Checkout status of an object. B Transfer Utility Transfers responsibility for a checked-out object to another user. C Transfer by Event Utility Transfers responsibility for all checked-out objects in an Event to another user. D Checkout Utility Checks out newly-created objects in a development environment. E Reject Utility Updates the checkout location to the previous development environment. F Enrollment Facility Updates the Migration file with information about objects on a remote node or objects in a 3GL Environment. G Reject by Event Utility Updates the checkout location to the previous environment for all objects in an Event.
TYPE	<p>The type of objects affected. Valid values are as follows:</p> <ul style="list-style-type: none"> D Indicates DDM. M Indicates METADATA. N Indicates NATURAL. P Indicates PREDICT. S Indicates SYSERR. O Indicates 3GL/OTHER. <p>This field is not required for the Transfer by Event Utility.</p>

II.6.1 Cancel Utility

To access the Cancel utility menu, enter "A" in the Enter Code field on the Checkout/Checkin Utilities menu. Entering the direct command MIG CANC on any menu also accesses the Cancel Utility menu.

If only one function is allowed by N2O Security, the Cancel Utility menu will be skipped and the allowed function screen will appear.

```

01-12-31      N-2-O CANCEL Utility MENU      TSI0373
11:38:00                                     TSI1

Code  Function
-----
A     Cancel
B     Cancel with Delete
C     Cancel with Extract
.     Terminate Cancel Utilities
-     -----

Enter Code:  _   Type :  N

Direct Command:                               MIG CANC
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
HELP  ----  END  ENV  MIG  REP  TOL  USR  PRJ  ----  ----  EXIT

```

NOTE – In order to access the 2 new cancel utility functions (added in N2O v5.2.1), Cancel with Delete and Cancel with Extract, a site must include the MIG CANC functions in a Function Profile assigned to the user.

Field	Description
ENTER CODE	<p>The function to be executed. Valid values are as follows:</p> <p>A Cancel Utility Removes the Checkout status of an object.</p> <p>B Cancel with Delete Utility Removes the Checkout status of an object and will delete the object from the current library.</p> <p>C Cancel with Extract Utility Removes the Checkout status of an object and create a Extract event to migrate a new copy of the object from the Base Environment/Library.</p>
TYPE	<p>The type of objects affected. Valid values are as follows:</p> <p>D Indicates DDM. M Indicates METADATA. N Indicates NATURAL. P Indicates PREDICT. S Indicates SYSERR. O Indicates 3GL/OTHER.</p> <p>This field is not required for the Cancel with Delete and Cancel with Extract Utilities.</p>

II.6.1.1 Cancel Utility

The Cancel Utility removes the checkout status of an object. A checked-out object may be canceled for any user, unless restricted by User-Exit 5.

After entering "A" in the Enter Code field and "N" (NATURAL) in the Type field on the Checkout/Checkin Utilities menu and pressing Enter, the Cancel Utility for NATURAL Objects screen is displayed.

01-12-31 11:38:00	N-2-O CANCEL UTILITY NATURAL OBJECTS	TSI0373 TSI010
<p> BASE Env : _____ BASE Library : _____ Object : _____ User-ID : TSI0373_ Checkout Date : _____ EQ (EQ,GT,LT) Current Env : _____ Current Library : _____ </p>		
<p> Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12--- HELP ---- END ---- </p>		

Field	Type	Description
BASE ENV (required)	N,S,P,O,M,D	The Environment Definition representing the repository for the checked-out object.
BASE LIBRARY (required)	N,S	The library within the environment that contains the checked-out NATURAL object or SYSERR message.
OBJECT (required)	N,S,P,O,M,D	The checked-out object to be canceled. "" Generates a selection list of all objects checked out to the user. The "" may also be used as a wildcard character to select objects prefixed by a string (e.g., N2O*).
USER-ID (required)	N,S,P,O,M, D	The User-ID responsible for the checked-out object (defaults to the user executing the utility). If User-Exit 5 does not restrict the utility, any User-ID may be entered. Partial names and wildcards (e.g., AAP*) may be entered.
ENDEVOR SYSTEM	O	The classification of an application for an ENDEVOR object.
ENDEVOR SUBSYSTEM	O	The specific application within a system for an ENDEVOR object.
CHECKOUT DATE	N,S,P,O,M, D	The date used to evaluate which checkouts are displayed based on when the Object was checked out.
CHECKOUT DATE CRITERIA (Ignored if CHECKOUT DATE is blank)	N,S,P,O,M, D	Criteria used to evaluate which checkouts are displayed based on when the Object was checked out. EQ=Equal,GT=Greater-Than,LT=Less-Than
CURRENT ENV	N,S,P,O,M, D	The Environment Definition serving as the current development location of the object.
CURRENT LIBRARY	N,S	The library within the development environment where the NATURAL objects and SYSERR messages currently are located.

When wildcarding is specified (** in the Object field) and Enter is pressed on the initial Cancel Utility screen, the screen below is displayed.

```

Type X to select
01-12-31          N-2-O CANCEL UTILITY          TSI0373
11:38:00          NATURAL PROGRAMS              TSI1
                Library:  PAYPROD              User-ID:  TSI0373
                Object
X   Object      Type      Message      X   OBJECT      Type      Message
-   - - - - -   - - - - -   - - - - -   -   - - - - -   - - - - -   - - - - -
-   PAY5900P    PROGRAM
-   PAY59101    MAP
-   PAY5950P    PROGRAM
-   PAY5953S    SUBROUTINE
-
                Object
X   OBJECT      Type      Message      X   OBJECT      Type      Message
-   - - - - -   - - - - -   - - - - -   -   - - - - -   - - - - -   - - - - -
-   PAY5910S    SUBROUTINE
-   PAY5920S    SUBROUTINE
-   PAY5952S    SUBROUTINE
-
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      - - - - -   END      - - - - -   - - - - -   - - - - -   - - - - -   - - - - -   STOP

```

Field	Type	Description
LIBRARY (supplied)	N,S	The library containing the NATURAL objects and/or SYSERR messages.
USER-ID (supplied)	N,S,P,O, M,D	The User-ID of the user responsible for the checked-out objects.
X (optional)	N,S,P,O, M,D	"X" in the Select field cancels the object.
OBJECT (supplied)	N,S,P,O, M,D.	The object to be canceled. Partial names and wildcards (e.g., AAP*, *s would list everything ending in s)
OBJECT TYPE (supplied)	N,P,O	Identifies the type of NATURAL objects, PREDICT objects, 3GL/OTHER objects, and/or SYSERR messages.
MESSAGE (supplied)	N,S,P,O, M,D	Indicates the success or failure of the requested cancel: <div> <div>CANCEL</div> <div>Indicates a successful cancel.</div> </div> <div> <div>FAILED</div> <div>Indicates a failed cancel.</div> </div> <div> <div>DENIED</div> <div>Indicates the cancel was prevented by user-exits.</div> </div>

When wildcarding is specified ('*' in the Object and Userid field) and Enter is pressed on the initial Cancel Utility screen, the screen below is displayed.

```

Type X to select
01-12-31          N-2-O CANCEL UTILITY          TSI1
13:01:09          NATURAL PROGRAMS              TERM

          Library: PAYPROD          User-ID: *
                Object
X Object  Type  Userid  Message  X Object  Type  Userid  Message
-----
- CITYTAXP PROGRAM  TSI1      - FEDTAXL  LOCAL  TSI1
- LIFEINSC COPYCODE TSI1      - LIFEINSL LOCAL  TSI1

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12--
----- END ----- STOP

```

Field	Type	Description
LIBRARY (supplied)	N,S	The library containing the NATURAL objects and/or SYSERR messages.
USER-ID (supplied)	N,S,P,O, M,D	The User-ID entered into the previous screen.
USERID (supplied)	N,S,P,O, M,D	The User-ID of the user responsible for the checked-out objects.
X (optional)	N,S,P,O, M,D	"X" in the Select field cancels the object.
OBJECT (supplied)	N,S,P,O, M,D.	The object to be canceled.
OBJECT TYPE (supplied)	N,P,O	Identifies the type of NATURAL objects, PREDICT objects, 3GL/OTHER objects, and/or SYSERR messages.
MESSAGE (supplied)	N,S,P,O, M,D	Indicates the success or failure of the requested cancel: <div> CANCEL Indicates a successful cancel. FAILED Indicates a failed cancel. DENIED Indicates the cancel was prevented by user-exits. </div>

II.6.1.2 Cancel with Delete Utility

The Cancel with Delete Utility removes the checkout status of an object and deletes the object from the Natural FUSER in the environment the object is currently checked out to. A checked-out object may be canceled for any user, unless restricted by User-Exit 5.

After entering "B" in the Enter Code field and "N" (NATURAL) in the Type field on the Checkout/Checkin Utilities menu and pressing Enter, the Cancel with Delete Utility for NATURAL Objects screen is displayed.

```

08-07-01          N-2-O CANCEL W/ DELETE          TSI1
16:44:35          NATURAL PROGRAMS                TERM

      BASE Env      : _____
      BASE Library   : _____
      Object         : _____
      User-ID        : _____
      Checkout Date   : _____ EQ (EQ,GT,LT)
      Current Env     : _____
      Current Library : _____

      This Cancel option will cancel the checkout of the
      Object(s) selected AND Delete the Objects(s) from
      the current Environment/Library

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      HELP  ----  END   ----  ----  ----  ----  ----  ----  ----  ----  ----  ----
  
```

Field	Type	Description
BASE ENV (required)	N	The Environment Definition representing the repository for the checked-out object.
BASE LIBRARY (required)	N	The library within the environment that contains the checked-out NATURAL object or SYSERR message.
OBJECT (required)	N	The checked-out object to be canceled.
USER-ID (required)	N	<p>"" Generates a selection list of all objects checked out to the user. The "" may also be used as a wildcard character to select objects prefixed by a string (e.g., N2O*).</p> <p>The User-ID responsible for the checked-out object (defaults to the user executing the utility). If User-Exit 5 does not restrict the utility, any User-ID may be entered. Partial names and wildcards (e.g., AAP*) may be entered.</p>
CHECKOUT DATE	N	The date used to evaluate which checkouts are displayed based on when the Object was checked out.
CHECKOUT DATE CRITERIA (Ignored if CHECKOUT DATE is blank)	N	<p>Criteria used to evaluate which checkouts are displayed based on when the Object was checked out.</p> <p>EQ=Equal,GT=Greater-Than,LT=Less-Than</p>
CURRENT ENV	N	The Environment Definition serving as the current development location of the object.
CURRENT LIBRARY	N	The library within the development environment where the NATURAL objects and SYSERR messages currently are located.

When wildcarding is specified ('*' in the Object field) and Enter is pressed on the initial Cancel Utility screen, the screen below is displayed.

```

Type X to select
01-12-31      N-2-O CANCEL W/ DETETE      TSI0373
11:38:00      NATURAL PROGRAMS          TSI1

      Library: PAYPROD      User-ID: TSI0373

      Object      Object      Object
      X      Object      Type      Message      X      OBJECT      Type      Message
      -      -      -      -      -      -      -      -
      -      PAY5900P      PROGRAM      -      PAY5910S      SUBROUTINE
      -      PAY59101      MAP      -      PAY5920S      SUBROUTINE
      -      PAY5950P      PROGRAM      -      PAY5952S      SUBROUTINE
      -      PAY5953S      SUBROUTINE

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      END
  
```

Field	Type	Description
LIBRARY (supplied)	N	The library containing the NATURAL objects and/or SYSERR messages.
USER-ID (supplied)	N	The User-ID of the user responsible for the checked-out objects.
X (optional)	N	"X" in the Select field cancels the object.
OBJECT (supplied)	N	The object to be canceled. Partial names and wildcards (e.g., AAP*, *s would list everything ending in s)
OBJECT TYPE (supplied)	N	Identifies the type of NATURAL objects, PREDICT objects, 3GL/OTHER objects, and/or SYSERR messages.
MESSAGE (supplied)	N	Indicates the success or failure of the requested cancel: <div><div>CANCEL</div><div>Indicates a successful cancel.</div><div>FAILED</div><div>Indicates a failed cancel.</div><div>DENIED</div><div>Indicates the cancel was prevented by user-exits.</div><div>DELETE</div><div>Indicates a successful cancel and the object was deleted from the Current Environment.</div></div>

II.6.1.3 Cancel with Extract Utility

The Cancel with Extract Utility removes the checkout status of an object and creates an EXTRACT event to migrate the current object from the base environment into the current checkout environment. A checked-out object may be canceled for any user, unless restricted by User-Exit 5.

After entering "C" in the Enter Code field and "N" (NATURAL) in the Type field on the Checkout/Checkin Utilities menu and pressing Enter, the Cancel with Extract Utility for NATURAL Objects screen is displayed.

```

08-07-01          N-2-O CANCEL W/ EXTRACT          TSI1
16:49:04          NATURAL PROGRAMS                TERM

      BASE Env      : _____
      BASE Library   : _____
      Object         : _____
      User-ID        : 1_____

      Extract Event   : _____

      Leave Blank or Press PF5 to retrieve information from the Event
      Current Env     : _____
      Current Library : _____

      This cancel option will cancel the checkout of the object(s)
      selected and creates an Extract Event to migrate the original
      object(s) (in the Base) to current environment/library

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
HELP  ----  END  ----  ----  ----  ----  ----  ----  ----  ----  ----  ----

```

Field	Type	Description
BASE ENV (required)	N	The Environment Definition representing the repository for the checked-out object.
BASE LIBRARY (required)	N	The library within the environment that contains the checked-out NATURAL object or SYSERR message.
OBJECT (required)	N	The checked-out object to be canceled.
USER-ID (required)	N	"" Generates a selection list of all objects checked out to the user. The "" may also be used as a wildcard character to select objects prefixed by a string (e.g., N2O*). The User-ID responsible for the checked-out object (defaults to the user executing the utility). If User-Exit 5 does not restrict the utility, any User-ID may be entered. Partial names and wildcards (e.g., AAP*) may be entered.
EXTRACT EVENT (required)	N	Extract Event which will migrate the cancelled objects.
CURRENT ENV (required)	N	The Environment Definition serving as the current development location of the object.
CURRENT LIBRARY (required)	N	The library within the development environment where the NATURAL objects and SYSERR messages currently are located.

When wildcarding is specified ('*' in the Object field) and Enter is pressed on the initial Cancel Utility screen, the screen below is displayed.

```

Type X to select
01-12-31      N-2-O CANCEL W/ EXTRACT      TSI0373
11:38:00      NATURAL PROGRAMS            TSI1

      Library: PAYPROD      User-ID: TSI0373

      Object      Object      Object
      X      Type      Message      X      OBJECT      Type      Message
      -      -      -      -      -      -      -      -
      -      PAY5900P  PROGRAM      -      PAY5910S  SUBROUTINE
      -      PAY59101  MAP      -      PAY5920S  SUBROUTINE
      -      PAY5950P  PROGRAM      -      PAY5952S  SUBROUTINE
      -      PAY5953S  SUBROUTINE

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      END
  
```

Field	Type	Description
LIBRARY (supplied)	N,S	The library containing the NATURAL objects and/or SYSERR messages.
USER-ID (supplied)	N,S,P,O, M,D	The User-ID of the user responsible for the checked-out objects.
X (optional)	N,S,P,O, M,D	"X" in the Select field cancels the object.
OBJECT (supplied)	N,S,P,O, M,D.	The object to be canceled. Partial names and wildcards (e.g., AAP*, *s would list everything ending in s)
OBJECT TYPE (supplied)	N,P,O	Identifies the type of NATURAL objects, PREDICT objects, 3GL/OTHER objects, and/or SYSERR messages.
MESSAGE (supplied)	N,S,P,O, M,D	Indicates the success or failure of the requested cancel: CANCEL Indicates a successful cancel. FAILED Indicates a failed cancel. DENIED Indicates the cancel was prevented by user-exits. EXTRACT Indicates a successful cancel and the object was added to the Extract Event.

After the user finishes canceling the checkouts, the option to process or modify the extract event that contains the objects cancelled will be displayed .

```

Type X to select
01-12-31          N-2-O CANCEL W/ EXTRACT          TSI1
13:01:09          NATURAL PROGRAMS                TERM

      Library:  PAYPROD          User-ID:  *
      Object
X Object  Typ +-----+-----+-----+-----+-----+-----+
- - - - -|-----|-----|-----|-----|-----|-----|
- CITYTAXP PROGR| Event: EEVENT  Seq:   31 Created | TSI1
- LIFEINSC COPYC| with      1 Objects | TSI1
-          |-----|-----|-----|-----|-----|-----|
          | Process Event:  Y |
          | Modify Event :  N |
          | Delete Event :  N |
          |-----|-----|-----|-----|-----|-----|

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12--
-----  END  -----

```

Field	Type	Description
Event	N,S,P,O, D,M	The Master Event of the Extract Event.
Sequence	N,S,P,O, D,M	The sequence number of the Event
Process Event		'Y' Continue to process the Extract Event 'N' do not process the Extract Event
Modify Event		'Y' Modify the generated Extract Event 'N' Do not modify the generated Extract Event
Delete Event		'Y' Delete the generated Extract Event 'N' Do not delete the generated Extract Event

II.6.2 Transfer Utility

The Transfer Utility transfers responsibility for a checked-out object to another user. Checkout responsibility may be transferred for any user, unless restricted by User-Exit 5 (Refer to the **N2O Administration Manual** for details on User-Exit 5).

After entering "B" in the Enter Code field and "N" (NATURAL) in the Type field on the Checkout/Checkin Utilities menu and pressing Enter, the Transfer Utility screen is displayed.

```

01-12-31          N-2-O TRANSFER UTILITY          TSI0373
11:38:00          NATURAL PROGRAMS                TSI1

                                     BASE Env      : ____
                                     BASE Library:  ____
                                     Object         : ____
                                     User-ID        : TSI0373_
                                     New User-ID   : ____

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      HELP  ---  END  ---  ---  ---  ---  ---  ---  ---  ---  ---  ---  ---

```

Field	Type	Description
BASE ENV (required)	N,S,P,O, M,D	The Environment Definition representing the repository for the checked out object.
BASE LIBRARY (required)	N,S	The library within the environment that contains the checked-out NATURAL object or SYSERR message.
OBJECT (required)	N,S,P,O, M,D	The checked-out object to be transferred. "*" Generates a selection list of all objects checked out to the user. The "*" may also be used as a wildcard character to select objects prefixed by a string (e.g., N2O*).
USER-ID (required)	N,S,P,O, M,D	The User-ID currently responsible for the object (defaults to the User-ID executing the utility). If User-Exit 5 does not restrict the utility, any User-ID may be substituted. Partial names and wildcards (e.g., AAP*, *s would list everything ending in s)
NEW USER-ID (required)	N,S,P,O, M,D	The User-ID being assigned the checked-out object.
ENDEVOR SYSTEM	O	The classification of an application for an ENDEVOR object.
ENDEVOR SUBSYSTEM	O	The specific application within a system for an ENDEVOR object.

When wildcarding is specified ('*' in the Object field) and Enter is pressed on the initial

Transfer Utility screen, the screen below is displayed.

```

Type X to select program(s)
01-12-31          N-2-O TRANSFER UTILITY          TSI0373
11:38:00          NATURAL PROGRAMS              TS11

      Library: PAYPROD          User-ID: TREE06

S  Object      Object      Message      S  Object      Object      Message
-  - - - - -    - - - - -    - - - - -    -  - - - - -    - - - - -    - - - - -
-  CMIGUTIL    COPYCODE
-  PAYENVA     PROGRAM
-  PAYENVC     PROGRAM
-  PAYENVE     PROGRAM
-  PAYEVNTB    PROGRAM
-  PAYEVNTD    PROGRAM
-  PAYEVNTF    PROGRAM
-  PAYEVNTI    PROGRAM
-  PAYOBJB     PROGRAM
-  PAYOBJG     PROGRAM
-  PAYOBJI     PROGRAM
-  PAYSTATB    PROGRAM
-  PAYSTATD    PROGRAM
-  PAYUE15N    SUB-RTN

-  PAYDCOCI    PROGRAM
-  PAYENVB     PROGRAM
-  PAYENVND    PROGRAM
-  PAYEVNTA    PROGRAM
-  PAYEVNTC    PROGRAM
-  PAYEVNTE    PROGRAM
-  PAYEVNTG    PROGRAM
-  PAYOBJA     PROGRAM
-  PAYOBJD     PROGRAM
-  PAYOBJH     PROGRAM
-  PAYSTATA    PROGRAM
-  PAYSTATC    PROGRAM
-  PAYSTATE    PROGRAM
-  PAYVCOCI    PROGRAM

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      HELP      END
  
```

Field	Type	Description
LIBRARY (supplied)	N,S	The library containing the NATURAL objects and/or SYSERR messages.
USER-ID(supplied)	N,S,P,O,M ,D	The User-ID of the user who is responsible for the objects.
S (optional)	N,S,P,O,M .D	"X" in the Select field transfers an object.
OBJECT (supplied)	N,S,P,O,M ,D	The object to be transferred.
OBJECT TYPE (supplied)	N,P,O	Identifies the type of NATURAL objects, PREDICT objects, 3GL/OTHER objects, and/or SYSERR messages.
MESSAGE (supplied)	N,S,P,O,M, D	Indicates the success or failure of the requested transfer: <div> <div>TRANSFER</div> <div>Indicates a successful transfer.</div> </div> <div> <div>FAILED</div> <div>Indicates a failed transfer.</div> </div> <div> <div>DENIED</div> <div>Indicates the transfer was prevented by User-Exit-5.</div> </div>

When wildcarding is specified ('*' in the Object and User-id field) and Enter is pressed on the initial Transfer Utility screen, the screen below is displayed.

```

Type X to select
01-12-31          N-2-O TRANSFER UTILITY          TSI1
13:20:27          NATURAL PROGRAMS                TERM

          Library: PAYPROD          User-ID: *
          Object
X Object  Type  Userid  Message  X Object  Type  Userid  Message
-----
- CITYTAXP PROGRAM  TSI1      - FEDTAXL  LOCAL  TSI1
- LIFEINSC COPYCODE TSI1      - LIFEINSL LOCAL  TSI1

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
-----
          END

```

Field	Type	Description
LIBRARY (supplied)	N,S	The library containing the NATURAL objects and/or SYSERR messages.
USER-ID (supplied)	N,S,P,O,M ,D	The User-ID entered into the previous screen.
USERID (supplied)	N,S,P,O,M ,D	The User-ID of the user who is responsible for the objects.
S (optional)	N,S,P,O,M ,D	"X" in the Select field transfers an object.
OBJECT (supplied)	N,S,P,O,M ,D	The object to be transferred.
OBJECT TYPE (supplied)	N,P,O	Identifies the type of NATURAL objects, PREDICT objects, 3GL/OTHER objects, and/or SYSERR messages.
MESSAGE (supplied)	N,S,P,O,M, D	Indicates the success or failure of the requested transfer: <div> <div>TRANSFER</div> <div>Indicates a successful transfer.</div> </div> <div> <div>FAILED</div> <div>Indicates a failed transfer.</div> </div> <div> <div>DENIED</div> <div>Indicates the transfer was prevented by User-Exit-5.</div> </div>

II.6.3 Transfer by Event Utility

The Transfer by Event Utility transfers responsibility for all checked-out objects in an Event to another user.

After entering "C" in the Enter Code field on the Checkout/Checkin Utilities menu and pressing Enter, the Transfer by Event Utility screen is displayed.

01-12-31 11:38:00	N-2-O TRANSFER BY EVENT UTILITY	TSI0373 TSI1
<div> <div>Event</div> <div>:</div> <div>_____</div> </div> <div> <div>Sequence</div> <div>:</div> <div>_____</div> </div> <div> <div>New User-ID</div> <div>:</div> <div>_____</div> </div> <div> <div>Change Control</div> <div>:</div> <div>_____</div> </div>		
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12--- HELP ---- END ----		

Field	Description
EVENT (required)	The Event that last migrated the checked-out objects that are to be transferred. The destination of the Event must match the current checkout location of the objects.
SEQUENCE (optional)	A starting Sequence number for the Event specified.
NEW USER-ID (required)	The User-ID that will be responsible for the checked-out object after the transfer.
CHANGE CONTROL (optional)	A limiting value for the Event specified. Only Events with this Change Control are shown.

After entering the information on the previous screen and pressing Enter, a list of Events is shown.

```

Type an X to select an Event for Transfer
01-12-31      N-2-O TRANSFER BY EVENT UTILITY      TSI0373
11:38:00                                TSI1

   X   Event      Seq      Change      --- From ---   --- To ---   Added
   -   - - - - -   - - -   - - - - -   Env  Library  Env  Library  User-ID
   -   PAYOUT      1      E141      PROD  PAYPROD  TEST  PAYTEST  TSI0373

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      END

```

Field	Description
X (optional)	"X" selects the Event.
EVENT (supplied)	The Master Event of the migration.
SEQ (supplied)	The sequence number of the Event.
CHANGE CONTROL (supplied)	A value that relates multiple Events to a specific change request.
FROM ENV (supplied)	The source Environment Definition of the Event.
FROM LIBRARY (supplied)	The source library for the Event.
TO ENV (supplied)	The target Environment Definition of the Event.
TO LIBRARY (supplied)	The target library of the Event.
ADDED USER-ID (supplied)	The User-ID of the user that created the Event.

The utility attempts to transfer checkout responsibility of all objects in an Event. If the utility successfully transfers objects, the Event is marked with "*" in the Select field. If the utility does not transfer any objects, the Event is marked with "F" in the Select field. If objects are not transferred, they are displayed on a separate screen with a reason for their failure.

II.6.4 Checkout Utility

The Checkout Utility checks out objects created in a development environment. Objects must be marked as checked out before they may be migrated to other environments. When Checkout/Checkin is active, existing objects are automatically checked out when they migrate from a BASE environment to a development environment.

The Checkout Utility updates the checkout status and identifies the current checkout location for an object. This utility does not migrate objects.

After entering "D" in the Enter Code field and "N" (NATURAL) in the Type field on the Checkout/Checkin Utilities menu and pressing Enter, the Checkout Utility screen is displayed. An object's Checkout/Checkin status can only be updated by the user who currently has the object checked out.

01-12-31 11:38:00	N-2-O CHECKOUT UTILITY NATURAL PROGRAMS	TSI0373 TSI1
<p>BASE Env : _____</p> <p>BASE Library : _____</p> <p>Current Env : _____</p> <p>Current Library : _____</p> <p>Object : _____</p> <p>Object Type : _____</p> <p>User-ID : TSI1_____</p>		
<p>Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---</p> <p>HELP ---- END ----</p>		

Field	Type	Description
BASE ENV (required)	N,S,P,O, M,D	The Environment Definition representing the repository for the checked-out object.
BASE LIBRARY (required)	N,S	The library within the environment containing the checked-out NATURAL objects and SYSERR messages.
CURRENT ENV (required)	N,S,P,O, M,D	The Environment Definition serving as the current development location of the object.
CURRENT LIBRARY (required)	N,S	The library within the development environment where the NATURAL objects and SYSERR messages currently are located.

(continued from previous page)

Field	Type	Description
OBJECT (required)	N,S,P,O, M,D	<p>The object to be checked out.</p> <p>"" Generates a selection list of all NATURAL objects, SYSERR messages, and PREDICT objects in the current environment and library. The "" may also be used as a wildcard character to select NATURAL objects, SYSERR messages, and PREDICT objects prefixed by a string (e.g., N2O*, *s would list everything ending in s)). If this field is left blank, a second data entry screen is displayed, allowing up to 28 objects to be entered.</p>
OBJECT TYPE (required)	N	<p>The object type to be checked out.</p> <p>Valid object types for NATURAL are as follows:</p> <ul style="list-style-type: none"> A Indicates Parameter data. C Indicates Copycode. G Indicates Global data. H Indicates Helproutine. L Indicates Local data. M Indicates Map. N Indicates Subprogram. P Indicates Program. S Indicates Subroutine. T Indicates Text. O Indicates Macro. R Indicates Report. Y Indicates ExpertModel. Z Indicates Recording. 3 Indicates Dialog. 4 Indicates Class. 5 Indicates Processor. K Indicates Server. 7 Indicates Function. 8 Indicates Adapter. O Indicates Macro.

(continued from previous page)

Field	Type	Description																																																																								
	P	Valid object types for PREDICT are as follows: <table><tr><th>Type</th><th>Indicates</th><th>Predict Version</th></tr><tr><td>DA</td><td>Database</td><td></td></tr><tr><td>DC</td><td>Dataspace</td><td></td></tr><tr><td>ET</td><td>Extract</td><td></td></tr><tr><td>FI</td><td>File</td><td></td></tr><tr><td>IE</td><td>Interface</td><td>V4.1.2 and above</td></tr><tr><td>KY</td><td>Keyword</td><td></td></tr><tr><td>LS</td><td>Library Structure</td><td></td></tr><tr><td>MD</td><td>Method</td><td>V4.1.2 and above</td></tr><tr><td>MO</td><td>Module</td><td>V3.4.2 and below</td></tr><tr><td>NO</td><td>Node</td><td></td></tr><tr><td>NW</td><td>Network</td><td></td></tr><tr><td>PG</td><td>PackageList</td><td></td></tr><tr><td>PR</td><td>Program</td><td></td></tr><tr><td>PY</td><td>Property</td><td>V4.1.2 and above</td></tr><tr><td>RL</td><td>Relationship</td><td></td></tr><tr><td>RP</td><td>Report</td><td>V3.4.2 and below</td></tr><tr><td>RT</td><td>Report Listing</td><td></td></tr><tr><td>SC</td><td>Storagespace</td><td></td></tr><tr><td>SV</td><td>Server</td><td></td></tr><tr><td>SY</td><td>System</td><td></td></tr><tr><td>US</td><td>User</td><td></td></tr><tr><td>VE</td><td>Verification</td><td></td></tr><tr><td>VM</td><td>Virtual Machine</td><td></td></tr></table>	Type	Indicates	Predict Version	DA	Database		DC	Dataspace		ET	Extract		FI	File		IE	Interface	V4.1.2 and above	KY	Keyword		LS	Library Structure		MD	Method	V4.1.2 and above	MO	Module	V3.4.2 and below	NO	Node		NW	Network		PG	PackageList		PR	Program		PY	Property	V4.1.2 and above	RL	Relationship		RP	Report	V3.4.2 and below	RT	Report Listing		SC	Storagespace		SV	Server		SY	System		US	User		VE	Verification		VM	Virtual Machine	
Type	Indicates	Predict Version																																																																								
DA	Database																																																																									
DC	Dataspace																																																																									
ET	Extract																																																																									
FI	File																																																																									
IE	Interface	V4.1.2 and above																																																																								
KY	Keyword																																																																									
LS	Library Structure																																																																									
MD	Method	V4.1.2 and above																																																																								
MO	Module	V3.4.2 and below																																																																								
NO	Node																																																																									
NW	Network																																																																									
PG	PackageList																																																																									
PR	Program																																																																									
PY	Property	V4.1.2 and above																																																																								
RL	Relationship																																																																									
RP	Report	V3.4.2 and below																																																																								
RT	Report Listing																																																																									
SC	Storagespace																																																																									
SV	Server																																																																									
SY	System																																																																									
US	User																																																																									
VE	Verification																																																																									
VM	Virtual Machine																																																																									
	O	The 3GL/OTHER type for a category: <table><tr><td>ASMB</td><td>Indicates all types of Assembler.</td></tr><tr><td>COBOL</td><td>Indicates all types of COBOL.</td></tr><tr><td>FORT</td><td>Indicates all types of FORTRAN.</td></tr><tr><td>PL/I</td><td>Indicates all types of PL/I.</td></tr><tr><td>RPG</td><td>Indicates RPG.</td></tr><tr><td>DATA</td><td>Indicates DATA FILES.</td></tr><tr><td>JCL</td><td>Indicates JCL, CLIST, CNTL.</td></tr><tr><td>OTHER</td><td>Indicates all other object types.</td></tr></table>	ASMB	Indicates all types of Assembler.	COBOL	Indicates all types of COBOL.	FORT	Indicates all types of FORTRAN.	PL/I	Indicates all types of PL/I.	RPG	Indicates RPG.	DATA	Indicates DATA FILES.	JCL	Indicates JCL, CLIST, CNTL.	OTHER	Indicates all other object types.																																																								
ASMB	Indicates all types of Assembler.																																																																									
COBOL	Indicates all types of COBOL.																																																																									
FORT	Indicates all types of FORTRAN.																																																																									
PL/I	Indicates all types of PL/I.																																																																									
RPG	Indicates RPG.																																																																									
DATA	Indicates DATA FILES.																																																																									
JCL	Indicates JCL, CLIST, CNTL.																																																																									
OTHER	Indicates all other object types.																																																																									
USER-ID (required)	N,S,P,O, M,D	The User-ID responsible for the checked-out Object (defaults to the user executing the utility). If User-Exit 5 does not restrict the utility, any User-ID may be substituted.																																																																								
CATEGORY (required)	O	<p>The category associated with the member being checked out. Valid 3GL/OTHER categories are as follows:</p> <table><tr><td>ASMB</td><td>Indicates all types of Assembler.</td></tr><tr><td>COBOL</td><td>Indicates all types of COBOL.</td></tr><tr><td>FORT</td><td>Indicates all types of FORTRAN.</td></tr><tr><td>PL/I</td><td>Indicates all types of PL/I.</td></tr><tr><td>RPG</td><td>Indicates RPG.</td></tr><tr><td>DATA</td><td>Indicates DATA FILES.</td></tr><tr><td>JCL</td><td>Indicates JCL, CLIST, CNTL.</td></tr><tr><td>OTHER</td><td>Indicates all other object types.</td></tr></table> <p>This field is valid for 3GL/OTHER checkouts only.</p>	ASMB	Indicates all types of Assembler.	COBOL	Indicates all types of COBOL.	FORT	Indicates all types of FORTRAN.	PL/I	Indicates all types of PL/I.	RPG	Indicates RPG.	DATA	Indicates DATA FILES.	JCL	Indicates JCL, CLIST, CNTL.	OTHER	Indicates all other object types.																																																								
ASMB	Indicates all types of Assembler.																																																																									
COBOL	Indicates all types of COBOL.																																																																									
FORT	Indicates all types of FORTRAN.																																																																									
PL/I	Indicates all types of PL/I.																																																																									
RPG	Indicates RPG.																																																																									
DATA	Indicates DATA FILES.																																																																									
JCL	Indicates JCL, CLIST, CNTL.																																																																									
OTHER	Indicates all other object types.																																																																									

(continued from previous page)

Field	Type	Description
FILE TYPE (required)	P	<p>The type of file being checked out. Valid values are:</p> <p>A Indicates ADABAS. C Indicates Conceptual. D Indicates DB2 table. E Indicates DB2 view. I Indicates IMS segment. J Indicates IMS seg. layout. K Indicates IMS userview. L Indicates Logical VSAM. M Indicates ISAM. O Indicates OTHER. P Indicates NATURAL PROCESS. Q Indicates PROCESS userviews. R Indicates Logical VSAM view. S Indicates Sequential. U Indicates ADABAS userview. V Indicates VSAM. W Indicates VSAM userview. Z Indicates Standard.</p>
DDM GENERATED (required)	P	<p>An identification of the existence or non-existence of a generated DDM.</p> <p>Y indicates a generated DDM exists for a file.</p> <p>N indicates a generated DDM does not exist for a file.</p>
ENDEVOR SYSTEM	O	The classification of an application for an ENDEVOR object.
ENDEVOR SUBSYSTEM	O	The specific application within a system for an ENDEVOR object.
DDM Dbid (required)	D	Database number that the DDM will point to.
DDM Fnr (required)	D	File number that the DDM will point to.
DDM ADA 6 (required)	D	Marked with an X if the DDM was created in NATURAL 2.3 or above and will allow a Dbid and/or Fnr greater than 255.
METADATA (required)	M	Description of the UDE – User Defined Entities

When wildcarding is specified ('*' in the Object field) on the initial Checkout Utility screen and Enter is pressed, the screen below is displayed.

```

Type X to select
01-12-31      N-2-O CHECKOUT UTILITY      TSI0373
11:38:00      NATURAL PROGRAMS           TSI1

      Library: PAYPROD      User-ID: TSI0373

      Object
X   Object  Type  Message      X   Object  Type  Message
-   -
-   PAY5900P  P
-   PAY59101  M
-   PAY5951S  S
-   PAY5952S  S
-   PAY5953S  S
-   -
-   PAY5910S  S
-   PAY5950P  P
-   PAY59511  M
-   PAY59521  M
-   PAY59531  M
-   -

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      HELP  ---  END  ---  ---  ---  ---  ---  ---  ---  ---  ---  ---

```

Field	Type	Description
LIBRARY (supplied)	N,S	The library containing the objects.
USER-ID (supplied)	N,S,P,M, D	The User-ID of the user responsible for the objects.
X (optional)	N,S,P,M, D	"X" in the Select field checks out an object.
OBJECT (supplied)	N,S,P,M, D	The object to be checked out.
OBJECT TYPE (supplied)	N,P	Identifies the object type to be checked out: <ul style="list-style-type: none"> A Indicates Parameter data. C Indicates Copycode. G Indicates Global data. H Indicates Helproutine. L Indicates Local data. M Indicates Map. N Indicates Subprogram. P Indicates Program. S Indicates Subroutine. O Indicates Macro. R Indicates Report. Y Indicates ExpertModel. Z Indicates Recording. 3 Indicates Dialog. 4 Indicates Class. 5 Indicates Processor. K Indicates Server. 7 Indicates Function. 8 Indicates Adapter. O Indicates Macro.

(continued from previous page)

Field	Type	Description
		Valid object types for PREDICT are as follows:
	Type	Indicates Predict Version
	DA	Database
	DC	Dataspace
	ET	Extract
	FI	File
	IE	Interface
	KY	Keyword
	LS	Library Structure
	MD	Method
	MO	Module
	NO	Node
	NW	Network
	PG	PackageList
	PR	Program
	PY	Property
	RL	Relationship
	RP	Report
	RT	Report Listing
	SC	Storagespace
	SV	Server
	SY	System
	US	User
	VE	Verification
	VM	Virtual Machine
DDM Dbid (supplied)	D	Database number that the DDM will point to.
DDM Fnr (supplied)	D	File number that the DDM will point to.
DDM ADA 6 (supplied)	D	Marked with an X if the DDM was created in NATURAL 2.3 or above and will allow a Dbid and/or Fnr greater than 255.
METADATA (supplied)	M	Description of the UDE – User Defined Entities
MESSAGE (supplied)	N,S,P,M, D	Indicates the success or failure of the requested checkout:
	CHKD OUT	Indicates a successful checkout.
	WARNING	Indicates multiple checkouts of the same objects.
	FAILED	Indicates a failed checkout.
	DENIED	Indicates User-Exit 5 prevented the checkout.
	REJECTED	Indicates N2O Security prevented the checkout.

When the 'FAILED' or 'WARNING' message is displayed next to an Object, place the cursor over the Object and use PF11 to display any existing Checkout information.

II.6.5 **Reject Utility**

The Reject Utility returns the checkout location to the previous development environment. This utility does not migrate objects.

Many sites have a review process as objects move from one development environment to another. For example, objects may be copied from Development to Quality Assurance. A user may determine that the objects have deficiencies and may wish to return the objects to development. Rather than create an Event to copy the objects back to the development environment, a user may use the Reject Utility.

After entering "E" in the Enter Code field and "N" (NATURAL) in the Type field on the Checkout/Checkin Utilities menu, the Reject Utility screen is displayed.

01-12-31 11:38:00	N-2-O REJECT UTILITY NATURAL PROGRAMS	TSI0373 TSI1
<p>BASE Env : _____</p> <p>BASE Library : _____</p> <p>Object : _____</p>		
<p>Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---</p> <p>HELP ---- END ----</p>		

Field	Type	Description
BASE ENV (required)	N,S,P,O, M,D	The Environment Definition representing the repository for the checked-out object.
BASE LIBRARY (required)	N,S	The library within the environment containing the checked-out NATURAL objects and SYSERR messages objects.
OBJECT (required)	N,S,P,O, M,D	The checked-out object to be rejected.
ENDEVOR SYSTEM	O	The classification of an application for an ENDEVOR object.
ENDEVOR SUBSYSTEM	O	The specific application within a system for an ENDEVOR object.

II.6.6 Enrollment Facility

The Enrollment Facility updates the N2O Migration file with information about objects on a remote node or 3GL/OTHER objects. This information is used during the migration selection process. The Enrollment Facility is used to enroll new objects in an environment, as well as to update information about existing objects.

After entering "F" in the Enter Code field and "N" (NATURAL) in the Type field on the Checkout/Checkin Utilities menu, the Enrollment Facility screen is displayed.

```

01-12-31          N-2-O ENROLLMENT FACILITY          TSI0373
11:38:00          NATURAL PROGRAMS                  TSI1

      Env Def      :      _____
      Library      :      _____
      Object       :      _____
      Src/Obj      :      _____
      Object Type  :      -

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      HELP  ---  END  ---  ---  ---  ---  ---  ---  ---  ---  ---  ---  ---

```

Field	Type	Description
ENV DEF (required)	N,S,P,O, M,D	The Environment Definition for the remote node or 3GL Environment containing the object to be enrolled.
LIBRARY (required)	N,S	The library within the remote Environment. This field is only available when enrolling NATURAL objects and SYSERR messages objects.
OBJECT (required)	N,S,P,O, M,D	The object to be enrolled.
SRC/OBJ (required)	N	The form of the NATURAL object.
	S	Indicates the source form of the object is being enrolled.
	C	Indicates the cataloged form of the object is being enrolled.
	SC	Indicates both forms of the object are being enrolled.
SHORT/LONG (required)	S	The length of the message to be enrolled.
	S	Indicates user-supplied short messages are to be enrolled.
	SL	Indicates both short and long message are to be enrolled.

(continued from previous page)

Field	Type	Description
OBJECT TYPE (required)	N,P	<p>The object type to be enrolled. Valid object types for NATURAL objects are as follows:</p> <ul style="list-style-type: none"> A Indicates Parameter data. C Indicates Copycode. G Indicates Global data. H Indicates Helproutine. L Indicates Local data. M Indicates Map. N Indicates Subprogram. P Indicates Program. S Indicates Subroutine. O Indicates Macro. R Indicates Report. Y Indicates ExpertModel. Z Indicates Recording. 3 Indicates Dialog. 4 Indicates Class. 5 Indicates Processor. K Indicates Server. 7 Indicates Function. 8 Indicates Adapter. O Indicates Macro.

Valid object types for PREDICT objects are as follows:

Type	Indicates	Predict Version
DA	Database	
DC	Dataspace	
ET	Extract	
FI	File	
IE	Interface	V4.1.2 and above
KY	Keyword	
LS	Library Structure	
MD	Method	V4.1.2 and above
MO	Module	V3.4.2 and below
NO	Node	
NW	Network	
PG	PackageList	
PR	Program	
PY	Property	V4.1.2 and above
RL	Relationship	
RP	Report	V3.4.2 and below
RT	Report Listing	
SC	Storagespace	
SV	Server	
SY	System	
US	User	
VE	Verification	
VM	Virtual Machine	

(continued from previous page)

Field	Type	Description
FILE TYPE (required)	P	<p>The type of file being checked out. Valid values are:</p> <p>A Indicates ADABAS. C Indicates Conceptual. D Indicates DB2 table. E Indicates DB2 view. I Indicates IMS segment. J Indicates IMS seg. layout. K Indicates IMS userview. L Indicates Logical VSAM. M Indicates ISAM. O Indicates OTHER. P Indicates NATURAL PROCESS. Q Indicates PROCESS userviews. R Indicates Logical VSAM view. S Indicates Sequential. U Indicates ADABAS userview. V Indicates VSAM. W Indicates VSAM userview. Z Indicates Standard.</p>
DDM GENERATED (required)	P	<p>Indicates whether a generated DDM exists or not.</p> <p>Y indicates a generated DDM exists for a file. N indicates a generated DDM does not exist for a file.</p>
CATEGORY (required)	O	<p>The category associated with the member. This field is only available when enrolling 3GL/OTHER objects. Valid 3GL/OTHER categories are as follows:</p> <p>ASMB Indicates all types of Assembler. COBOL Indicates all types of COBOL. FORT Indicates all types of FORTRAN. PL/I Indicates all types of PL/I. RPG Indicates RPG. DATA Indicates DATA FILES. JCL Indicates JCL, CLIST, CNTL. OTHER Indicates all other object types.</p>
ENDEVOR SYSTEM	O	<p>The classification of an application for an ENDEVOR object.</p>
ENDEVOR SUBSYSTEM	O	<p>The specific application within a system for an ENDEVOR object.</p>
DDM Dbid (supplied)	D	<p>Database number that the DDM will point to.</p>
DDM Fnr (supplied)	D	<p>File number that the DDM will point to.</p>

(continued from previous page)

Field	Type	Description
DDM ADA 6 (supplied)	D	Marked with an X if the DDM was created in NATURAL 2.3 or above and will allow a Dbid and/or Fnr greater than 255.
METADATA (supplied)	M	Description of the UDE – User Defined Entities

II.6.7 Reject by Event Utility

The Reject by Event Utility returns the checkout location to the previous development environment for all objects in an Event. This utility does not migrate objects.

Many sites have a review process as objects move from one development environment to another. For example, objects may be copied from a development environment to a quality assurance environment. A user may determine that the objects have deficiencies and wants to return the objects to development. Rather than create an Event to copy the objects back to the development environment, a user may use the Reject by Event Utility.

After entering "G" in the Enter Code field and "N" (NATURAL) in the Type field on the Checkout/Checkin Utilities menu, the Reject by Event Utility screen is displayed.

01-12-31
11:38:00
N-2-O REJECT BY EVENT UTILITY
TSI0373
TSI1

Event
Sequence

: _____
 : _____

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
 HELP ---- END ----

Field	Description
EVENT (required)	The Event that migrated the objects to be rejected.
SEQUENCE (optional)	The Event sequence that migrated the objects to be rejected.

After entering the information on the previous screen and pressing Enter, a list of Events is shown.

Type an X to select an Event for Reject								
01-12-31			N-2-O REJECT BY EVENT UTILITY					TSI0373
11:38:00								TSI1
X	Event	Seq	Change Control	Env	Library	Env	Library	Added User-ID
-	DEV2QUAL	1	*****	DEV	PAYDEV	QUAL	PAYQA	TSI0373
-	DEV2QUAL	2	*****	DEV	PAYDEV	QUAL	PAYQA	TSI0373
-	DEV2QUAL	3	*****	DEV	PAYDEV	QUAL	PAYQA	TSI0373
-	DEV2QUAL	4	*****	DEV	PAYDEV	QUAL	PAYQA	TSI0373
-	DEV2QUAL	5	*****	DEV	PAYDEV	QUAL	PAYQA	TSI0373
-	DEV2QUAL	6	*****	DEV	PAYDEV	QUAL	PAYQA	TSI0373
-	DEV2QUAL	7	*****	DEV	PAYDEV	QUAL	PAYQA	TSI0373
-	DEV2QUAL	8	*****	DEV	PAYDEV	QUAL	PAYQA	TSI0373
-	DEV2QUAL	9	*****	DEV	PAYDEV	QUAL	PAYQA	TSI0373
-	DEV2QUAL	10	*****	DEV	PAYDEV	QUAL	PAYQA	TSI0373
-	DEV2QUAL	11	*****	DEV	PAYDEV	QUAL	PAYQA	TSI0373
-	DEV2QUAL	12	*****	DEV	PAYDEV	QUAL	PAYQA	TSI0373
-	DEV2QUAL	13	*****	DEV	PAYDEV	QUAL	PAYQA	TSI0373
-	DEV2QUAL	14	*****	DEV	PAYDEV	QUAL	PAYQA	TSI0373
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---								
----- END -----								

Field	Description
X (optional)	"X" selects the Event.
EVENT (supplied)	The Master Event of the migration.
SEQ (supplied)	The sequence number of the Event.
CHANGE CONTROL (supplied)	A value that relates multiple Events to a specific change request.
FROM ENV (supplied)	The source Environment Definition of the Event.
FROM LIBRARY (supplied)	The source library for the Event.
TO ENV (supplied)	The target Environment Definition of the Event.
TO LIBRARY (supplied)	The target library of the Event.
ADDED USER-ID (supplied)	The User-ID of the user that created the Event.

The utility attempts to return each object in the Event to the previous development environment. If the utility successfully rejects all objects, the Event is marked with "*" in the Select field. If the utility fails to reject any objects, the Event is marked with "F" in the Select field. All objects are displayed on a separate screen with a status message.

II.7 **Batch JCL Submission**

N2O provides the ability to submit batch JCL (or EXECs) to a system internal reader. N2O reads batch JCL from the JCL Library specified on the Install Parms screen or on the Migration Profile for an Event. If the JCL contains substitution variables, N2O supplies and replaces the necessary values before submitting the JCL to the system internal reader. The N2O Job Submission Exit, "N2OUEJJE", must be modified for site RJE requirements before submitting batch JCL. If a system internal reader is not available, the batch JCL must be submitted manually. Refer to the **N2O Administration Manual** for details on N2OUEJJE.

To access the Batch JCL Submission menu, enter "B" in the Enter Code field on the Migration Subsystem menu. Entering the direct command MIG SUB on any menu also accesses the Batch JCL Submission menu.

01-12-31 11:38:00	N-2-O BATCH JCL SUBMISSION	TSI0373 TSI1
	Code Function	

	A Submit an Event	
	B Submit a Master Event	
	C Submit Migration Profiles	
	D Submit All Pending Events	
	E View JCL for a Profile	
	F 3GL/Other Autocompile	
	G DB2 DBRM Generation	
	H DB2 Plan Bind	
	. Terminate Batch JCL Submission	
	- -----	
	Enter Code: _	
Direct Command: _____		MIG SUB
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---		
HELP ---- END ENV MIG REP TOL USR PRJ ---- ---- EXIT		

Field	Description
ENTER CODE	<p>The function to be executed. Valid values are as follows:</p> <p>A Submit an Event Displays all Events pending batch migration and submits JCL for selected Events.</p> <p>B Submit a Master Event Displays a count of all Events pending batch migration for a master Event and submits JCL to process the group of Events.</p> <p>C Submit Migration Profiles Displays a count of all Events pending batch migration for a Migration Profile and submits JCL to process the group of Events.</p> <p>D Submit All Pending Events Displays a list of all Events pending batch migration and submits the JCL to migrate all Events.</p> <p>E View JCL for a Profile Displays the JCL associated with a Migration Profile.</p> <p>F 3GL/OTHER Autocompile Displays all closed 3GL/OTHER Events that are pending Autocompile, and submits the JCL to compile selected Events.</p> <p>G DB2 DBRM Generation Displays all Events pending DBRM generation, and submits JCL to generate DBRM(s) for selected Events.</p> <p>H DB2 Plan Bind Displays all Events for which a DBRM has been generated, and submits JCL to bind a DB2 Plan.</p>

II.7.1 Submit an Event

The Submit an Event function submits batch migration JCL (or EXECs) to a system internal reader for an Event. Batch Events that have been delayed are available for submission from this screen. Refer to **Section II.2.3 Migration Process**.

To access the Submit an Event Screen, enter "A" in the Enter Code field on the Batch JCL Submission menu.

```

Type an X - submit D - delete Event I - Inquire V - View JCL
01-12-31          N-2-O SUBMIT AN EVENT          TSI0373
11:38:00          TCP00004

Ret      Event  ----- System JCL ----- 3GL JCL -----
Code X Event   Seq  Library  Program  Pred Pgm  Library  Program  Arch Pgm
-----
-   PRODTEST 3      N2OJCL  PRODTEST  *****  *****  *****  *****
-   PRODTEST 2      N2OJCL  PRODTEST  *****  *****  *****  *****
-   PRODTEST 140     N2OJCL  PRODTEST  *****  *****  *****  *****
-   PRODTEST 141     N2OJCL  PRODTEST  *****  *****  *****  *****
-   PRODTEST 142     N2OJCL  PRODTEST  *****  *****  *****  *****
-   PRODTEST 143     N2OJCL  PRODTEST  *****  *****  *****  *****
-   PRODTEST 146     N2OJCL  PRODTEST  *****  *****  *****  *****
-   PRODTEST 147     N2OJCL  PRODTEST  *****  *****  *****  *****
-   PRODTEST 148     N2OJCL  PRODTEST  *****  *****  *****  *****
-   PRODTEST 176     N2OJCL  PRODTEST  *****  *****  *****  *****
-   PRODTEST 178     N2OJCL  PRODTEST  *****  *****  *****  *****
-   PRODTEST 234     N2OJCL  PRODTEST  *****  *****  *****  *****

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      END      USER      -----

```

Field	Type	Description
RET CODE (supplied)	N,S,P,O, M,D	A value appears in this column next to an Event if the job submission receives a return code greater than zero.
X (optional)	N,S,P,O, M,D	<p>"X" submits JCL for an Event. "D" deletes the Event.</p> <p>"I" displays information about an Event.</p> <p>"V" displays the JCL that will be submitted for the Event.</p> <p>After pressing enter,</p> <p>"*" Indicates a successful submission.</p> <p>"F" indicates a failed submission.</p> <p>"#" Indicates the JCL was deleted.</p> <p>"N" indicates the JCL was not found</p>
EVENT (supplied)	N,S,P,O, M,D	The Master Event of the migration.
EVENT SEQ (supplied)	N,S,P,O, M,D	The sequence number of the Event.
SYSTEM JCL LIBRARY (supplied)	N,S,P,O, M,D	The NATURAL library that contains the JCL for migrating DDMS, METADATA, NATURAL objects, PREDICT objects, and SYSERR messages.

(continued from previous page)

Field	Type	Description
SYSTEM JCL PROGRAM (supplied)	N,S,D	The NATURAL object that contains the JCL for migrating DDM, NATURAL objects and SYSERR messages.
SYSTEM JCL PRED PGM (supplied)	P,M	The NATURAL object that contains the JCL for migrating METADATA and PREDICT objects. Contains "DISABLED" if the BUILD-EXTRACT variable in User-Exit 14 is set to FALSE.
3GL JCL LIBRARY (supplied)	O	The NATURAL library that contains the JCL for migrating 3GL/OTHER objects.
3GL JCL PROGRAM (supplied)	O	The NATURAL object that contains the JCL for migrating 3GL/OTHER objects.
3GL JCL ARCH PGM (supplied)	O	The NATURAL object that contains the JCL for archiving PDS members.

If the Event contains a combination of NATURAL and 3GL/OTHER objects, two jobs are submitted for the Event.

The following PF-keys are provided for the Submit an Event function:

<u>Key</u>	<u>Function</u>	<u>Description</u>
PF5	USER	Toggle between displaying all events / displaying only the current user's event.

II.7.2 Submit a Master Event

The Submit a Master Event function submits batch migration JCL (or EXECs) to a system internal reader. All batch-ready Events for a Master Event are submitted as a single job.

To access the Submit a Master Event screen, enter "B" in the Enter Code field on the Batch JCL Submission menu.

```

Type X to submit or D to delete Event for a Master Event
01-12-31          N-2-O SUBMIT A MASTER EVENT          TSI0373
11:28:00                                     TCP00004

Ret      X      Master Event      Event
Code     -      -----      Count
-----
      _      PRODTST          12

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      END
  
```

Field	Type	Description
RET CODE (supplied)	N,S,P,O,M ,D	A value appears in this column next to an Event if the job submission receives a return code greater than zero.
X (optional)	N,S,P,O,M ,D	"X" in the Select field submits JCL for a Master Event. "D" in the Select field deletes the Event. "*" Indicates a successful submission. "F" indicates a failed submission. "#" Indicates the JCL was deleted.
MASTER EVENT (supplied)	N,S,P,O,M ,D	The Master Event of the migration.
EVENT COUNT (supplied)	N,S,P,O,M ,D	The number of batch-ready Events to be processed.

A list of all Master Events with pending batch jobs is displayed. The Event Count indicates how many Events are pending for the Master Event.

II.7.3 Submit Migration Profiles

The Submit Migration Profiles function submits batch migration JCL (or EXECs) to a system internal reader. All batch-ready Events for a Migration Profile are submitted as a single job.

To access the Submit Migration Profiles menu, enter "C" in the Enter Code field on the Batch JCL Submission menu.

```

Type X to submit, C for Change Control or D to delete Events
01-12-31          N-2-O SUBMIT MIGRATION PROFILES          TSI0373
11:38:00                                     TCP00004

Ret   Migration  Event ----- System JCL -----      3GL JCL-----
Code X Profile   Count Library  Program  Pred Pgm  Library  Program  Arch Pgm
-----
_  PROD  TEST    12  N2OJCL  PRODTST  *****  *****  *****  *****

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      ALL  END  -----

```

Field	Type	Description
RET CODE (supplied)	N,S,P,O,M ,D	A value appears in this column next to an Event if the job submission receives a return code greater than zero.
X (optional)	N,S,P,O,M ,D	<p>"X" in the Select field submits JCL for a Migration Profile.</p> <p>"C" in the Select field submits JCL for a Migration Profile to process all Events that are related to a specified Change Control.</p> <p>"D" in the Select field deletes all pending Events (status "B") for a Migration Profile.</p> <p>After pressing enter,</p> <p>"*" indicates successful submission</p> <p>"F" indicates failed submission</p> <p>"#" indicates the JCL was deleted.</p>
MIGRATION PROFILE (supplied)	N,S,P,O,M ,D	The Migration Profile to be submitted.
EVENT COUNT (supplied)	N,S,P,O,M ,D	The number of batch-ready Events to be processed.
SYSTEM JCL LIBRARY (supplied)	N,S,P,M,D	The NATURAL library that contains the JCL for migrating DDMS, METADATA, NATURAL objects, PREDICT objects, and SYSERR messages.
SYSTEM JCL PROGRAM (supplied)	N,S,D	The NATURAL object that contains the JCL for migrating DDMS, NATURAL objects, and SYSERR messages.

(continued from previous page)

Field	Type	Description
SYSTEM JCL PRED PGM (supplied)	P	The NATURAL object that contains the JCL for migrating METADATA and PREDICT objects. Contains "DISABLED" if the BUILD-EXTRACT variable in user exit 14 is set to FALSE.
3GL JCL LIBRARY (supplied)	O	The NATURAL library that contains the JCL for migrating 3GL/OTHER objects.
3GL JCL PROGRAM (supplied)	O	The NATURAL object that contains the JCL for migrating 3GL/OTHER objects.
3GL JCL ARCH PGM (supplied)	O	The NATURAL object that contains the JCL for archiving PDS objects.

A list of all Migration Profiles with pending batch jobs is displayed. The Event Count indicates how many Events are pending for the Migration Profile.

When "C" is used in the Select field to submit JCL for a Migration Profile, based on change control number, the following popup window allows the Change Control to be input or selected.

```

Type X to submit, C for Change Control or D to delete JCL
01-12-31          N-2-O SUBMIT MIGRATION PROFILES          TSI0373
11:38:00          +-----+                               TCP00004
                  | Select or Enter a Change Control:      |
Ret   Migration  | X CC   #   X CC   #   X CC   #   | L-----|
Code X Profile   | -----|                               Arch Pgm
-----|         |         |         |         | - - - - -|
C PROD TEST     | _ CHGCNTL1 3 _ CHGCNRL2 2 | * * * * *|
                  |         |         |         |         |
                  |         |         |         |         |
                  +-----+                               +-----+
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      ALL   END

```

Field	Type	Description
Select or Enter a Change Control (optional)	N,S,P,O,M ,D	Input of Change Control.
X (optional)	N,S,P,O,M ,D	"X" in the Select field selects the Change Control.
CC (supplied)	N,S,P,O,M ,D	Change Control.
# (supplied)	N,S,P,O,M ,D	Number of events associated with the Change Control.

II.7.4 Submit All Pending Events

The Submit All Pending Events function submits batch migration JCL (or EXECs) to a system internal reader. All batch-ready Events are submitted as a single job.

To access the Submit All Pending Events screen, enter "D" in the Enter Code field on the Batch JCL Submission menu.

```

Press ENTER to submit JCL for all Events
01-12-31          N-2-O SUBMIT ALL PENDING EVENTS          TSI0373
11:38:00                                     TSI1

      Event      Seq      From      To      Event      Seq      From      To
      -----      ----      ---      ---      -----      ----      ---      ---
      PAYIN       2          DEV      PROD      PAYIN       3          DEV      PROD

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12
      -----      END      -----

```

Field	Type	Description
EVENT (supplied)	N,S,P,O, M,D	The Master Event of the migration.
SEQ (supplied)	N,S,P,O, M,D	The sequence number of the Event.
FROM ENV (supplied)	N,S,P,O, M,D	The source Environment Definition of the migration.
TO ENV (supplied)	N,S,P,O, M,D	The target Environment Definition of the migration.

A list of all pending batch Events is displayed. When Enter is pressed, a pop-up window displays for the user to enter the JCL library and JCL object to perform the batch migration. Events that include PREDICT objects cannot be submitted using this option and are not included in the list.

II.7.5 View JCL for a Profile

The View JCL for a Profile function displays the JCL Object for a Migration Profile.

To access the View JCL for a Profile screen, enter "E" in the Enter Code field on the Batch JCL Submission menu.

```

Valid Values: D (Default Mig), P (PREDICT Mig), B (Both)
01-12-31      N-2-O VIEW JCL FOR A PROFILE      TSI0373
11:38:00                                           TSI1

      JCL      JCL      Predict
      X  Library Program Program Migration Profile
      -  -----
      -  PAYJCL NATMIGR NATMIGP      DEV      TEST
      -  PAYJCL NATMIGA *****      TEST      PROD

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12
      ---- END ----

```

Field	Type	Description
X (optional)	N,S,P,M,D	"D" in the Select field displays the JCL program specified in the Migration Profile. "P" in the Select field displays the PREDICT JCL program specified in the Migration Profile. "B" in the Select field displays both JCL programs specified in the Migration Profile.
JCL LIBRARY (supplied)	N,S,P,O,M D	The NATURAL library that contains the JCL for migrating DDMS, METADATA, NATURAL objects, PREDICT objects, and SYSERR messages. This is assigned on the Migration Profile.
JCL PROGRAM (supplied)	N,S,D	The NATURAL object that contains the JCL for migrating DDMS, NATURAL objects, SYSERR messages, METADATA and PREDICT objects (if User-Exit 14 sets the Build-Extract variable to false). This is assigned on the Migration Profile.
PREDICT JCL PROGRAM (supplied)	P,M	The NATURAL object that contains the JCL for migrating PREDICT objects(if User-Exit 14 sets the Build-Extract variable to true). This is assigned on the Migration Profile. Contains "DISABLED" if the BUILD-EXTRACT variable in User-Exit 14 is set to FALSE.
MIGRATION PROFILE (supplied)	N,S,P,M,D	The Migration Profile identifying the JCL for migrating NATURAL objects, SYSERR messages, and PREDICT objects.

Entering "D" in the Select field for the DEV to TEST Migration Profile on the View JCL for a Profile screen, the screen below is displayed.

```

01-12-31          N-2-O VIEW JCL FOR A PROFILE          TSIO373
11:38:00  Library: N2OJCL   Program: N2OMIG   Type: DEFAULT   TSII
.....1.....2..... DB1   PRD3 ..5.....6.....7..
//NATMIGR JOB (20000),'NATURAL MIGRATION',CLASS=T,NOTIFY=&USERID
//*
//      USER-ID will be replaced automatically by N2O with
//*      *INIT-USER or the User-ID supplied to N2O by
//*      N2OUEOON when the batch migration is submitted
//*      to an internal reader.
//*
//*      Proc NATL must execute NATURAL on the FUSER local to
//*      the N2O installation.
//*
//*      &INPUT will be replaced automatically by N2O with
//*      the required parameters when the batch
//*      migration is submitted to an internal reader.
//*      For manual submission, see Select Options.
//*
//N2OSEL  EXEC NATL
//CMWKF01 DD *
&INPUT
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12
-----  END  -----  STOP

```

This screen displays the default JCL that is used to migrate NATURAL, SYSERR, and PREDICT objects. Pressing Enter continues listing the JCL for the Migration Profile.

II.7.6 3GL/OTHER Autocompile

The 3GL/OTHER Autocompile function submits 3GL compile JCL (or EXECs) to a system internal reader.

To access the 3GL/OTHER Autocompile screen, enter "F" in the Enter Code field on the Batch JCL Submission menu. Enter a starting Event and Sequence on the first screen displayed and press enter. A summary screen similar to the one below will be shown.

Type an X to submit JCL for an Event							
01-12-31		N-2-O 3GL/OTHER AUTOCOMPILE				TSI0373	
11:38:00						TSI1	
X	Event	Event Seq	From Env	To Env	3GL Type	---- Migrated ----	
-	-----	----	-----	-----	-----	Date	Time
-	COBOLTP	34	LIBT	LIBP	LIBR	01-11-27	16:08:00
-	COBOLTP	35	LIBT	LIBP	LIBR	01-11-28	16:04:00
-	COBOLTP	36	LIBT	LIBP	LIBR	01-11-29	16:01:00
Enter--PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12							
----		END	----	----	----	----	----

Field	Type	Description
X (optional)	O	"X" in the Select field submits JCL for a 3GL Autocompile. "D" in the Select field deletes JCL for a 3GL Autocompile. After pressing enter, "*" Indicates the 3GL/OTHER Autocompile JCL was successfully submitted. "N" indicates the JCL could not be located. "F" indicates an error was encountered when the JCL was submitted. "#" Indicates the JCL was deleted.
EVENT (supplied)	O	The Master Event of the migration.
EVENT SEQ (supplied)	O	The sequence number of the Event.
FROM ENV (supplied)	O	The source Environment Definition of the migration.
TO ENV (supplied)	O	The target Environment Definition of the migration.
3GL INTERFACE (supplied)	O	The 3GL interface used to migrate the 3GL/OTHER objects. Valid values are as follows: PDS, LIBR, PANV, ENDV.
MIGRATED DATE (supplied)	O	The date the Event completed the migration process.
MIGRATED TIME (supplied)	O	The time the Event completed the migration process.

II.7.7 DB2 DBRM Generation

The DB2 DBRM Generation function submits JCL (or EXECs) to a system internal reader using NATRJE. The DBRM Generation process performs the following steps:

- **Execute the Create DBRM (Data Base Request Modules) Command**
The database access statements generated in NATURAL objects are extracted and transformed to a static assembler program (DBRM).
- **Execute the DB2 Precompile**
In this step, the generated static assembler program is sent through the DB2 Precompiler. The output consists of the precompiled DBRM containing the SQL statements, and an assembler program, which contains all the database access statements, transformed from SQL into assembler statements.
- **Assemble and Link the Assembler Program**
The assembler program is then assembled and linked creating an executable load module.
- **Bind the DBRM as a Package (optional)**
This is an optional step available with DB2 V2.3. A package is a subcomponent of a Plan, and it is not executable until it is included in a Plan.

N2O provides Static SQL Support by creating Database Request Modules (DBRM) and then binding these DBRMs into a DB2 Application Plan. After an Event has completed, the Event is ready for DBRM Generation.

Once an Event has been submitted for DBRM Generation, a batch job may then be submitted to bind the DBRM(s) and/or Packages into a DB2 Application Plan.

To access the DB2 DBRM Generation screen, enter "G" in the Enter Code field on the Batch JCL Submission menu.

Valid Values : X - Submit DBRM, C - Cancel DBRM/PLAN									
01-12-31		N-2-O DB2 DBRM GENERATION						TSI0373	
11:38:00								TSI1	
Ret	S	Event	Seq	Env	Library	Date	Time	Warning	DB2
Code									Stat
----	---	-----	-----	----	-----	-----	-----	-----	----
---	---	PAYIN	1	PROD	PAYPROD	01-03-09	12:16:29	AC-ERROR	D
---	---	PAYIN	2	PROD	PAYPROD	01-03-10	09:50:37	RECOVERD	D
---	---	PAYIN	3	PROD	PAYPROD	01-03-10	10:02:41	RECOVERD	D
---	---	PAYIN	4	PROD	PAYPROD	*****	*****	RECOVERD	D
---	---	PAYIN	5	PROD	PAYPROD	*****	*****	RECOVERD	C
---	---	PAYIN	6	PROD	PAYPROD	*****	*****	RECOVERD	D
---	---	PAYIN	7	PROD	PAYPROD	01-04-05	09:03:53	RECOVERD	D
---	---	PAYIN	8	PROD	PAYPROD	*****	*****	RECOVERD	D
---	---	PAYIN	9	PROD	PAYPROD	*****	*****	RECOVERD	D
---	---	PAYIN	10	PROD	PAYPROD	*****	*****	RECOVERD	D
---	---	PAYIN	11	PROD	PAYPROD	*****	*****	RECOVERD	D
---	---	PAYIN	12	PROD	PAYPROD	01-04-05	09:47:22	RECOVERD	D
---	---	PAYIN	13	PROD	PAYPROD	*****	*****	RECOVERD	D
---	---	PAYIN	14	PROD	PAYPROD	*****	*****	RECOVERD	D
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---									
----- END -----									

Field	Type	Description
RET CODE (supplied)	O	A value appears in this column next to an Event if the job submission receives a return code greater than zero.
S (optional)	O	Valid values are as follows: X submits the DBRM. C cancels the DBRM/PLAN.
EVENT (supplied)	O	The Master Event of the migration.
SEQ (supplied)	O	The sequence number of the Event.
TARGET ENV (supplied)	N	The target Environment Definition of the migration.
TARGET LIBRARY (supplied)	N	The library to which NATURAL objects and/or SYSERR messages are to be migrated.
COMPILED DATE (supplied)	N	The date the objects were compiled using Autocompile.
COMPILED TIME (supplied)	N	The time the objects were compiled using Autocompile.
WARNING (supplied)	N	Events may contain one of the following warning messages: OVERRIDE The Event migrated to an environment without proper authorization. AC-ERROR Objects within the Event received compile errors during the Autocompile process. RECOVERED Objects within the Event received errors and the Event was automatically recovered. ***** Indicates Events with no warning message.
DB2 STAT (supplied)	O	Limits the report to Events with the specified DB2 Status. Valid values are as follows: D Indicates DBRM Ready. P Indicates Plan Ready. S Indicates Static. C Indicates Canceled.

The DBRM to be created for each program of an Event defaults to the object name. However, User-Exit 9 may identify a single DBRM Name for all objects of the Event. The Event may be re-submitted at a later date and time if an error occurs in the DBRM Generation process. To cancel DB2 processing for the Event, enter "C" in the select field.

II.7.8 DB2 Plan Bind

The DB2 Plan Bind function submits JCL (or EXECs) to the system internal reader to bind the DBRMs and/or packages into a DB2 Application Plan. After an Event has been submitted for DBRM Generation, the Event may be submitted for the DB2 Plan Bind.

To access the DB2 Plan Bind screen, enter "H" in the Enter Code field on the Batch JCL Submission menu.

```

Valid Bind Values: X - Submit C - Cancel D - Delete
01-12-31          N-2-O DB2 PLAN BIND          TSI0373
11:38:00          TSI1

Ret      -- Target --- DBRM      ----- DBRM Generated ----- DB2
Code  X  Event   Seq  Env  Library Name      Date      Time      User-ID  Stat
-----
      _  EXTRACT 2085  TST4 PAY11          01-03-02 11:20:38 PAY04    S

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
HELP  ----  ---  ---  ---  ---  ---  ---  ---  ---  ---  ---  ---  ---  ---  ---  ---  ---
MIG SUB
EXIT

```

Field	Type	Description
RET CODE (supplied)	O	A value appears in this column next to an Event if the job submission receives a return code greater than zero.
X (optional)	O	"X" in the Select field submits Bind JCL for an Event.
EVENT (supplied)	O	The Master Event of the migration.
SEQ (supplied)	O	The sequence number of the Event.
TARGET ENV (supplied)	N	The target Environment Definition of the migration.
TARGET LIBRARY (supplied)	N	The library to which NATURAL objects and/or SYSERR messages are to be migrated.
DBRM NAME (supplied)	O	The name of the DBRM generated for the Event.
DBRM GENERATED DATE (supplied)	O	The date the DBRM was generated.
DBRM GENERATED TIME (supplied)	O	The time the DBRM was generated.

(continued from previous page)

Field	Type	Description
DBRM GENERATED USER-ID (supplied)	O	The User-ID of the user who generated the DBRM.
DB2 STAT (supplied)	O	Limits the report to Events with the specified DB2 Status. Valid values are as follows: D Indicates Deleted. P Indicates Plan Ready. S Indicates Static. C Indicates Canceled.

Only those Events that have been previously submitted for DBRM Generation are displayed. The Event may be re-submitted at a later date and time if an error occurs in the Bind process.

After submitting an Event, "*" in the Select field indicates the DB2 Bind JCL was successfully submitted, "N" indicates the JCL could not be located. "F" indicates an error was encountered when the JCL was submitted. "C" indicates the job was cancelled back to DBRM Generation. "D" indicates the job was deleted.

SECTION III

PROJECT TRACKING SUBSYSTEM

III.1 Introduction

The Project Tracking Subsystem maintains information about organizational activities. It is designed to provide a framework for sites to use in developing the project information that they require. The Project Tracking Subsystem can be used to manage NATURAL and non-NATURAL application development projects. It can also be used to manage hardware and software installations, documentation efforts, and other non-programming activities.

The Project Tracking Subsystem identifies the activities that need to be performed, why they must be accomplished, when they must be completed, and how they are progressing. Based on this information, projects can be scheduled efficiently, and resources can be allocated where they are most needed.

A project consists of the following:

- TASK GROUPS
- STAGES OF A TASK
- PRIORITY VALUES
- IMPACT VALUES

The Project Tracking Subsystem section presents topics in the following order:

- PROJECT DEFINITION
- TASK LIST
- SUGGESTION BOX
- TASK UTILITIES
- PROJECT TRACKING REPORTS

To access the Project Tracking Subsystem menu, enter "P" on the N2O Main menu, enter the direct command PRJ MENU, or press PF9 on any menu.

```

01-12-31          N-2-O MAIN MENU          TSI0373
11:38:00                                     TSI1

                                Code  Function
                                ----  -
                                E    Environment Subsystem
                                M    Migration Subsystem
                                P    Project Tracking Subsystem
                                R    Reporting Subsystem
                                T    Toolbox Subsystem
                                U    User-Defined Subsystem
                                .    Terminate N-2-O Session
                                ----  -

Enter Code:  _

Direct Command:  _____ N2O MENU
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
HELP  ----  END  ENV  MIG  REP  TOL  USR  PRJ  ----  ----  EXIT

```

After following the instructions on the previous page, the Project Tracking Subsystem menu is displayed.

```

01-12-31          N-2-O PROJECT TRACKING SUBSYSTEM MENU          TSI0373
11:38:00                                         TSI1

      Code  Function
      ----  -
      A      Project Definition
      B      Task List
      C      Suggestion Box
      D      Task Utilities
      E      Project Tracking Reports
      .      Terminate Project Tracking Subsystem
      ----  -

Enter Code:  _

Direct Command: _____ PRJ MENU
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      HELP  ----  END  ENV  MIG  REP  TOL  USR  ----  ----  ----  EXIT

```

Field	Description
ENTER CODE (required)	The function to be executed. Valid values are as follows: <ul style="list-style-type: none"> A Project Definition Defines applications and activities to the Project Tracking Subsystem. B Task List Defines each element of work to be accomplished within a project. C Suggestion Box Allows users at all levels of an organization to document changes or ideas. D Task Utilities Assists users in documenting and updating all information related to a task. E Project Tracking Reports Provides access to the information stored in the Project Tracking audit trail.

III.2 Project Definition

The first step in using the Project Tracking Subsystem is defining projects. A project is a collection of related activities. The Project Tracking Subsystem maintains the characteristics of each project. Some examples of projects are: payroll applications, invoicing procedures, and software installation.

To access the Project Definition menu, enter "A" on the Project Tracking Subsystem menu or enter the direct command PRJ PROJ on any menu.

```

01-12-31      N-2-O PROJECT DEFINITION MENU      TSI0373
11:38:00                                           TSI1

Code  Function
----  -
A     Add a Project Definition
C     Copy a Project Definition
D     Delete a Project Definition
I     Inquire on a Project Definition
M     Modify a Project Definition
S     Select a Project Definition
.     Terminate Project Definition
----  -

Enter Code:  _   Project: _____

Direct Command _____ PRJ PROJ
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      HELP  ----  END  ENV  MIG  REP  TOL  USR  PRJ  ----  ----  EXIT

```

Field	Description
ENTER CODE (required)	<p>The function to be executed. Valid values are as follows:</p> <p>A Add a Project Definition Creates a Project Definition.</p> <p>C Copy a Project Definition Creates a Project Definition by copying an existing Project Definition.</p> <p>D Delete a Project Definition Removes a Project Definition.</p> <p>I Inquire on a Project Definition Displays information about a Project Definition.</p> <p>M Modify a Project Definition Updates a Project Definition.</p> <p>S Select a Project Definition Provides a list of Project Definitions that may be copied, deleted, inquired on, or modified.</p>
∞ PROJECT (required for all functions except Select)	<p>The project to be added or maintained. For the Select function, the project is the starting value.</p>

∞ indicates field-level help is available.

III.2.1 **Add a Project Definition**

Add a Project Definition creates a new Project Definition.

To add a Project Definition, enter "A" in the Enter Code field and the name of the project to be added in the Project field on the Project Definition menu.

```

01-12-31          N-2-O ADD A PROJECT DEFINITION          TSI0373
11:38:00                                     TSI1

Project   : PAYROLL
Updated   : TSI0373    01-12-31    10:09:13
Short Desc: CALCULATE COMPENSATION PACKAGE

Options:
Extended Desc : Y
Task Groups   : Y
Stages        : Y
Priority Values: Y
Impact Values  : Y

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      HELP  ---- END   ----      ----      ----      ----      ----      ----
  
```

The following Field Descriptions apply to all Project Definition functions (Add, Copy, Delete, Inquire on, and Modify).

Field	Description
PROJECT (supplied)	The name of the Project Definition to be added or maintained.
UPDATED (supplied)	The User-ID of the user who created or last updated the record and the date and time that action occurred.
SHORT DESC (required)	A 30-character description of the project.
EXTENDED DESC (required)	Indicates whether a longer description of the project can be entered or not. Y Allows a longer description to be entered. This is the default value. N Bypasses the Extended Description feature.
TASK GROUPS (required)	Indicates whether the user is able to list task groups or not. Y Allows the user to list task groups. N Bypasses the Task Groups feature.

(continued from previous page)

Field	Description
STAGES (required)	Indicates whether the user is able to list stages or not.
	Y Allows the user to list stages.
	N Bypasses the Stages feature.
PRIORITY VALUES (required)	Indicates whether the user is able to define a set of priority values for project activities.
	Y Allows the user to define a set of priority values.
	N Bypasses the Priority Values feature.
IMPACT VALUES (required)	Indicates whether the user is able to define a set of impact values for project activities.
	Y Allow the user to define a set of impact values.
	N Bypasses the Impact Values feature.

If Extended Desc option='Y' the following screen will appear to define an extended description screen.

[illegible]

Field	Description
EXTENDED DESCRIPTION (optional)	Additional freeform information for describing the project in detail.

If task group option = 'Y', the following pop up window will appear to define task groups.

```

01-12-31          N-2-O ADD A PROJECT DEFINITION          TSI0373
11:38:00                                     TSI1

Project          :  PAYROLL
+-----+1-12-31  10:09:13
|          |COMPENSATION PACKAGE
| Task Groups |
|-----|
| 1. CITYTAX_ |
| 2. FICA_    |
| 3. FEDTAX_  |
| 4. BENEFITS |
| 5. SALARY_  |
| 6. BONUSSES_|
| 7. _____|
| 8. _____|
| 9. _____|
| 10. _____|
|-----+

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      HELP  ---  END   ---  ---  ---  ---  ---  ---  ---  ---  ---  ---  ---

```

Field	Description
TASK GROUPS (optional)	Identify and organize related tasks within a project. A Task Group must be unique throughout Project Tracking.

Note: Task Groups information will not be copied because it must be unique to all of Project Tracking.

If stages option = 'Y', the following pop up window will appear to define stages.

```

01-12-31          N-2-O ADD A PROJECT DEFINITION          TSI0373
11:38:00                                     TSI1

Project          :  PAYROLL
Updated         :  +-----+
Short Desc:      | Stages of a Task |
|                |-----|
| 1. DESIGN_     | 11. _____|
| 2. ACTIVE_     | 12. _____|
| 3. PHASE 1_    | 13. _____|
| 4. TEST_       | 14. _____|
| 5. APPROVE_    | 15. _____|
| 6. PHASE 2_    | 16. _____|
| 7. COMPLETE_   | 17. _____|
| 8. _____  | 18. _____|
| 9. _____  | 19. _____|
| 10. _____  | 20. _____|
|-----+

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      HELP  ---  END   ---  ---  ---  ---  ---  ---  ---  ---  ---  ---  ---

```

Field	Description
STAGES OF A TASK (optional)	Identify the milestones for a task on its path to completion. The following stages are reserved for use by N2O: <ul style="list-style-type: none"> CANCEL Indicates a successful cancel. FAILED Indicates a failed cancel. DENIED Indicates the cancel was prevented by user-exits. DEFINED Indicates a new task that has not been started.

If priority values option = 'Y', the following pop-up window will appear to define priority values.

```

01-12-31          N-2-O ADD A PROJECT DEFINITION          TSI0373
11:38:00                                     TSI1

Project   : PAYROLL
Updated   : TSI0373   01-12-31   10:0
Short Desc: CALCULATE COMPENSATION PAC

Options:
  Extended Desc : Y
  Task Groups   : Y
  Stages        : Y
  Priority Values: Y
  Impact Values: Y

+-----+
| Priority Values |
+-----+
| High  HIGH_   |
|      MED_     |
|      LOW_     |
|              |
|              |
|              |
|              |
|              |
| Low    _____|
+-----+

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      HELP   END

```

Field	Description
PRIORITY VALUES (optional)	Identify a set of valid priorities to assign to tasks within the project. The HIGH and LOW labels establish a range for the values.

If impact values = 'Y', the following pop-up window will appear to define impact values.

01-12-31		N-2-O ADD A PROJECT DEFINITION		TSI0373																			
11:38:00				TSI1																			
Project : PAYROLL																							
Updated : TSI0373 01-12-31 10:09:13																							
Short Desc: CALCULATE COMPENSATION PACKAGE																							
Options:																							
Extended Desc : Y																							
Task Groups : Y																							
Stages : Y																							
Priority Values: Y																							
Impact Values : Y																							
<table border="1"> <tr> <th colspan="2">Impact Values</th> </tr> <tr> <td>High</td> <td>HIGH_</td> </tr> <tr> <td></td> <td>MED_</td> </tr> <tr> <td></td> <td>LOW_</td> </tr> <tr> <td></td> <td></td> </tr> <tr> <td></td> <td></td> </tr> <tr> <td></td> <td></td> </tr> <tr> <td></td> <td></td> </tr> <tr> <td>Low</td> <td></td> </tr> </table>						Impact Values		High	HIGH_		MED_		LOW_									Low	
Impact Values																							
High	HIGH_																						
	MED_																						
	LOW_																						
Low																							
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---																							
HELP ---- END ----																							

Field	Description
IMPACT VALUES (optional)	Identify a set of valid impacts to assign to tasks within the project. The HIGH and LOW labels establish a range for the values.

III.2.2 Copy a Project Definition

Copy a Project Definition creates a Project Definition by copying an existing Project Definition.

Note: Task group information will not be copied because it must be unique to all of Project Tracking.

To copy a Project Definition, enter "C" in the Enter Code field and the Project Definition to be copied in the Project field on the Project Definition menu. A pop-up window is displayed for the user to enter the new project name.

01-12-31 11:38:00	N-2-O PROJECT DEFINITION MENU	TSI0373 TSI1																				
	<table style="width: 100%;"> <tr> <th style="text-align: left;">Code</th> <th style="text-align: left;">Function</th> </tr> <tr><td>----</td><td>-----</td></tr> <tr><td>A</td><td>Add a Project Definition</td></tr> <tr><td>C</td><td>Copy a Project Definition</td></tr> <tr><td>D</td><td>Delete a Project Definition</td></tr> <tr><td>I</td><td>Inquire on a Project Definition</td></tr> <tr><td>M</td><td>Modify a Project Definition</td></tr> <tr><td>S</td><td>Select a Project Definition</td></tr> <tr><td>.</td><td>Termina</td></tr> <tr><td>----</td><td>-----</td></tr> </table>	Code	Function	----	-----	A	Add a Project Definition	C	Copy a Project Definition	D	Delete a Project Definition	I	Inquire on a Project Definition	M	Modify a Project Definition	S	Select a Project Definition	.	Termina	----	-----	
Code	Function																					
----	-----																					
A	Add a Project Definition																					
C	Copy a Project Definition																					
D	Delete a Project Definition																					
I	Inquire on a Project Definition																					
M	Modify a Project Definition																					
S	Select a Project Definition																					
.	Termina																					
----	-----																					
Enter Code: _	Project	<table style="width: 100%; border: 1px solid black;"> <tr> <td style="width: 50%; border-right: 1px solid black;">Copy Project: PAYROLL_____</td> <td style="width: 50%;"></td> </tr> <tr> <td style="border-right: 1px solid black;">To Project : ACCTSRECV_____</td> <td></td> </tr> <tr> <td style="border-right: 1px solid black;"></td> <td></td> </tr> </table>	Copy Project: PAYROLL_____		To Project : ACCTSRECV_____																	
Copy Project: PAYROLL_____																						
To Project : ACCTSRECV_____																						
<div style="display: flex; justify-content: space-between;"> Direct Command _____ PRJ PROJ </div> <div style="display: flex; justify-content: space-between;"> Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12--- </div> <div style="display: flex; justify-content: space-between;"> HELP ---- END ENV MIG REP TOL USR PRJ ---- EXIT </div>																						

All of the screens for copying a Project Definition are the same as adding a project. Refer to **Section III.2.1 Add a Project Definition** for more details.

III.2.3 Delete a Project Definition

Delete a Project Definition removes a Project Definition that no longer needs to be referenced.

If any tasks are related to the project, the user must first delete the tasks using the Task List Delete option.

To delete a Project Definition, enter "D" in the Enter Code field and the Project Definition to be deleted in the Project field on the Project Definition menu.

01-12-31 11:38:00		N-2-O DELETE A PROJECT DEFINITION		TSI0373 TSI1	
Project : PAYROLL		Updated : TSIO373 01-12-31		Short Desc : COMPENSATION PACKAGE	
Task Groups	Stages of a Task		Priority Values	Impact Values	
1. CITY TAX	1. DESIGN	11.	High	High	
2. FED TAX	2. APPROVAL1	12.			
3. FICA TAX	3. INITIATE	13.			
4. BENEFITS	4. TEST	14.			
5.	5. APPROVAL2	15.			
6.	6. USER TEST	16.			
7.	7. APPROVAL3	17.			
8.	8. COMPLETED	18.			
9.	9.	19.			
10.	10.	20.			
+-----+ Do you want to Delete? N (Y/N) +-----+					
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---					
----- END -----					

To confirm the delete request, enter "Y" in the pop-up window. To cancel the delete request, enter "N" in the pop-up window or press PF3.

III.2.4 Inquire on a Project Definition

Inquire on a Project Definition displays information about a Project Definition.

To inquire on a Project Definition, enter "I" in the Enter Code field and the Project Definition to be viewed in the Project field on the Project Definition menu.

```

01-12-31          N-2-O INQUIRE ON A PROJECT DEFINITION          TSI0373
11:38:00                                     TSI1

Project           : PAYROLL
Updated          : TSI0373    01-12-31
Short Desc       : CALCULATE COMPENSATION PACKAGE

Task Groups      Stages of a Task      Priority      Impact
-----          -
1. CITY TAX      1. DESIGN      11.          High      High
2. FED TAX       2. APPROVAL1   12.
3. FICA TAX      3. INITIATE    13.
4. BENEFITS      4. TEST      14.
5.               5. APPROVAL2   15.
6.               6. USER TEST  16.
7.               7. APPROVAL3   17.
8.               8. COMPLETED  18.
9.               9.           19.
10.              10.           20.          Low      Low

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
----- END -----

```

III.2.5 Modify a Project Definition

Modify a Project Definition updates a Project Definition.

To modify a Project Definition, enter "M" in the Enter Code field and the project to be modified in the Project field on the Project Definition menu.

```

01-12-31          N-2-O MODIFY A PROJECT DEFINITION          TSI0373
11:38:00                                     TSI1

Project           : PAYROLL
Updated          : TSI0373    01-12-31    10:09:13
Short Desc       : CALCULATE COMPENSATION PACKAGE

Options:
Extended Desc    : Y
Task Groups      : Y
Stages           : Y
Priority Values   : Y
Impact Values    : Y

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
HELP  ---- END -----

```

III.2.6 Select a Project Definition

Select a Project Definition provides a list of Project Definitions that may be copied, deleted, inquired on, or modified.

To select a Project Definition, enter "S" in the Enter Code field on the Project Definition menu. A starting value may be entered in the Project field on the Project Definition menu.

```

Valid values: C - Copy D - Delete I - Inquire M - Modify
01-12-31          N-2-O SELECT A PROJECT DEFINITION          TSI0373
11:38:00                                     TSI1

      S   Project          Short Description
      -   -----          -
      -   PAYROLL          CALCULATE COMPENSATION PACKAGE
      -   ACCSTRECV        ACCOUNTS RECEIVABLE PACKAGE

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      HELP  ----  END   ----  ----  ----  ----  ----  ----  ----  ----  ----
  
```

Field	Description
S (optional)	<p>The function to be executed. Each user's Function Profile security determines the user's valid values. Valid values are as follows:</p> <p>C Indicates Copy a Project Definition. D Indicates Delete a Project Definition. I Indicates Inquire on a Project Definition. M Indicates Modify a Project Definition.</p>

Pressing Enter pages forward on all screens until the last screen is displayed. Pressing Enter on the last screen wraps around to display the first screen again.

III.3 Task List

Each activity that is part of a project is called a task. A task is a unit of work that advances the project toward completion. The Project Tracking Subsystem stores important information about a task. This information can be used to follow the progress of the task.

To access the Task List menu, enter "B" on the Project Tracking Subsystem menu or enter the direct command PRJ TASK on any menu.

```

01-12-31          N-2-O TASK LIST MENU          TSI0373
11:38:00                                     TSI1

Code  Function
----  -
A     Add a Task
C     Copy a Task
D     Delete a Task
I     Inquire on a Task
M     Modify a Task
S     Select a Task
.     Terminate Task List
-----

Enter Code:  _   Project: _____

Task Group: _____ Task Number: _____

Direct Command _____ PRJ TASK
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
HELP  ----  END  ENV  MIG  REP  TOL  ----  PRJ  ----  ----  EXIT

```

Field	Description
ENTER CODE (required)	The function to be executed. Valid values are as follows: <ul style="list-style-type: none"> A Add a Task Creates a task. C Copy a Task Creates a task by copying an existing task. D Delete a Task Removes a task. I Inquire on a Task Displays information about a task. M Modify a Task Updates a task. S Select a Task Provides a list of tasks that may be copied, deleted, inquired on, or modified.
∞ PROJECT (required)	The name of the project.
TASK GROUP (required for all functions except Select)	The group that identifies a task.
TASK NUMBER (required for Copy, Modify, Inquire on, and Delete)	The number that uniquely identifies a task.

∞ indicates field-level help is available.

III.3.1 Add a Task

The Add a Task function creates a new task.

To add a task, enter "A" in the Enter Code field, and the project name and task group of the task to be added on the Task List menu.

01-12-31 11:38:00	N-2-O ADD A TASK Project: PAYROLL	TSIO373 TSI1
Task Group	: BENEFITS	Task Number:000001 Stage: DEFINED
Updated	: TSIO373 01-12-31 10:10:10	
Short Desc	: CALCULATE AS PERCENTAGE OF DEDUCT	
Priority	: _____	
Impact	: _____	
Change Cntl	: _____	
Time Estimate	: _____ weeks _____ days _____ hours	
Primary Contact Information:		
Name	: _____	Phone: _____
User-ID:	_____ Other: _____	
Extended Desc	: Y	
Checklist	: Y	
Additional Contacts:	Y	
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---		
----- END -----		

When adding a new task, N2O automatically assigns the task number and a stage of "Defined".

The following Field Descriptions apply to all Task List functions (Add, Copy, Delete, Inquire on, and Modify).

Field	Description
∞ PROJECT (supplied)	The project in which a task belongs.
TASK GROUP (supplied)	The group that identifies a task.
TASK NUMBER (supplied)	The number that uniquely identifies a task.
STAGE (supplied)	The progress of a task. All tasks begin at the DEFINED stage.
UPDATED (supplied)	The User-ID of the user who created or last updated the record and the date and time that action occurred.
SHORT DESC (required)	A 30-character description of the task.
PRIORITY (optional)	Displays the priority of the task. Valid values for this field are defined on the Project Definition.

∞ indicates field-level help is available.

(continued from previous page)

Field	Description
IMPACT (optional)	Displays the impact of the task. Valid values for this field are defined on the Project Definition.
CHANGE CNTL (optional)	Relates a task to a site-specific tracking number or label.
TIME ESTIMATE (optional)	Displays the projected time required to complete a task in weeks, days, or hours.
NAME (optional)	The name of the contact.
PHONE (optional)	The phone number of the contact.
USER-ID (optional)	The User-ID of the contact.
OTHER (optional)	Other information pertinent to the contact, such as e-mail address or department.
EXTENDED DESC (required)	Indicates whether a longer description of the project can be entered. Y Allows a longer description of the project to be entered. This is the default value. N Bypasses the extended description feature.
CHECKLIST (required)	Indicates whether a pop-up window that can hold specifications or reminders about a task is available or not. Y Displays the pop-up window. This is the default value. N Bypasses the pop-up window.
ADDITIONAL CONTACTS (required)	Indicates whether a pop-up window for information to be entered for up to 9 additional contacts is available or not. Y Displays the pop-up window. This is the default value. N Bypasses the pop-window.

III.3.2 Copy a Task

The Copy a Task function creates a task by copying an existing task. The Copy function copies all information from an existing task to a new task.

To copy a task, enter "C" in the Enter Code field, and the project, task group, and task number of the task to be copied in the task fields on the Task List menu.

```

01-12-31          N-2-O TASK LIST MENU          TSI0373
11:38:00                                     TSI1

Code  Function
-----
A    Add a Task
C    Copy a Task
D    Dele +-----+
I    Inqu |
M    Modi | Copy Task Group :  BENEFITS
S    Sele | Task Number:  2_____
.    Term |
-----+-----+
Enter Code:  _  Proje | To Project   :  ACCTSRECV_____
                        | Task Group   :  ANNUITY_____
                        +-----+

Direct Command _____ PRJ TASK
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      HELP  ----  END  ENV  MIG  REP  TOL  USR  PRJ  ----  ----  EXIT

```

A pop-up window is displayed for information to be entered about the new task. Refer to **Section III.3.1 Add a Task** for an explanation of copy screens.

III.3.3 Delete a Task

The Delete a Task function removes a task.

To delete a task, enter "D" in the Enter Code field, and the project, task group, and task number of the task to be deleted in the task fields on the Task List menu.

```

01-12-31          N-2-O DELETE A TASK          TSI0373
11:38:00          Project:  PAYROLL            TSI1

Task Group      :      BENEFITS      Task Number:  000001      Stage:  DEFINED

Updated        :      TSI0373  01-12-31  11:38:00
Short Desc     :      2000 Benefits changes
Priority       :
Impact        :
Change Cntl    :
Time Estimate  :      weeks      days      hours

Primary Contact Information:
Name          :                               Phone:
User-ID       :      Other:
Extended Desc  :      Y
Checklist     :      Y
Additional Contacts:  N

+-----+
| Do you want to Delete?  N (Y/N) |
+-----+

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      ----  ----  END  ----  ----  ----  ----  ----  ----  ----  ----

```

To confirm the delete request, enter "Y" in the pop-up window. To cancel the delete request, enter "N" in the pop-up window or press PF3.

III.3.4 Inquire on a Task

The Inquire on a Task function displays information about a task.

To inquire on a task, enter "I" in the Enter Code field, and the project, task group, and task number of the task to be viewed in the task fields on the Task List menu.

01-12-31 11:38:00	N-2-O INQUIRE ON A TASK Project: PAYROLL	TSI0373 TSI1
Task Group : BENEFITS Task Number:000001 Stage: DEFINED		
Updated : TSI0373 01-12-31 12:00:00		
Short Desc : _____		
Priority : _____		
Impact : _____		
Change Cntl : _____		
Time Estimate: _____ weeks _____ days _____ hours		
Primary contact Information:		
Name : _____ Phone : _____		
User-ID: _____ Other : _____		
Extended Desc : Y		
Checklist : Y		
Additional Contacts: N		
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12--- ----- END -----		

III.3.5 Modify a Task

The Modify a Task function updates a task.

To modify a task, enter "M" in the Enter Code field, and the project, task group, and task number of the task to be modified in the task fields on the Task List menu.

01-12-31 11:38:00	N-2-O MODIFY A TASK Project: PAYROLL	TSI0373 TSI1
Task Group : BENEFITS Task Number:000001 Stage: DEFINED		
Updated : TSI0373 01-12-31 12:00:00		
Short Desc : CALC AS PERCENTAGE OF DEDUCT		
Priority : _____		
Impact : _____		
Change Cntl : _____		
Time Estimate: _____ weeks _____ days _____ hours		
Primary contact Information:		
Name : _____ Phone : _____		
User-ID: _____ Other : _____		
Extended Desc : Y		
Checklist : Y		
Additional Contacts: N		
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12--- ----- END -----		

III.3.6 Select a Task

The Select a Task function provides a list of tasks that may be copied, deleted, inquired on, or modified.

To select a task, enter "S" in the Enter Code field on the Task List menu. A starting value may be entered in the Project and Task Group fields on the Task List menu.

```

Valid values: C - Copy D - Delete I - Inquire M - Modify
01-12-31      N-2-O SELECT A TASK      TSI0373
11:38:00      TSI1
----- Task -----
S  Group      Number  Short Description      Stage
-  -
-  CITY TAX    000001  ALL ACCOUNTS          DEFINED
-  FED TAX     000002  ALL ACCOUNTS          DEFINED
-  FICA TAX    000003  ALL ACCOUNTS          DEFINED
-  BENEFITS    000004  ALL ACCOUNTS          DEFINED

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      HELP  ----  END   ----  ----  ----  ----  ----  ----  ----  ----  ----

```

Field	Description
S (optional)	<p>The function to be executed. Each user's Function Profile security determines the user's valid values. Valid values are as follows:</p> <p>C Indicates Copy a Task. D Indicates Delete a Task. I Indicates Inquire on a Task. M Indicates Modify a Task.</p>

Pressing Enter pages forward on all screens until the last screen is displayed. Pressing Enter on the last screen wraps around to display the first screen again.

III.4 Suggestion Box

The Suggestion Box is a Project Tracking function that is designed to collect end-user requests for changes to projects. The Suggestion Box can also hold ideas or other types of requests from management, application programmers, etc.

To access the Suggestion Box menu, enter "C" on the Project Tracking menu or enter the direct command PRJ SUGG on any menu.

```

01-12-31          N-2-O SUGGESTION BOX MENU          TSI0373
11:38:00                                     TSI1

Code  Function
----  -
A     Add a Suggestion
C     Copy a Suggestion
D     Delete a Suggestion
I     Inquire on a Suggestion
M     Modify a Suggestion
S     Select a Suggestion
.     Terminate Suggestion Box
----  -

Enter Code:  _   Project: _____

                        Suggestion: _____

Direct Command _____ PRJ SUGG
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
HELP  ----  END  ENV  MIG  REP  TOL  USR  PRJ  ----  ----  EXIT

```

Field	Description
ENTER CODE (required)	<p>The function to be executed. Valid values are as follows:</p> <p>A Add a Suggestion Creates a suggestion.</p> <p>C Copy a Suggestion Creates a suggestion by copying an existing suggestion.</p> <p>D Delete a Suggestion Removes a suggestion.</p> <p>I Inquire on a Suggestion Displays information about a suggestion.</p> <p>M Modify a Suggestion Updates a suggestion.</p> <p>S Select a Suggestion Provides a list of suggestions that may be copied, deleted, inquired on, or modified.</p>
∞ PROJECT (required)	The project to which the suggestion applies.
SUGGESTION (required for Copy, Modify, Delete, and Inquire on)	The number that uniquely identifies a suggestion. When adding, N2O automatically generates the suggestion number.
∞ indicates field-level help is available.	

III.4.1 **Add a Suggestion**

Add a Suggestion creates a new suggestion.

To add a suggestion, enter "A" in the Enter Code field, and the project to which the suggestion applies in the Project field on the Suggestion Box menu. N2O automatically assigns the next available suggestion number to the request.

```

01-12-31          N-2-O ADD A SUGGESTION          TSI0373
11:38:00                                     TSI1

Project   :  PAYROLL
Suggestion:    100
Updated   :  TSI0373   01-12-31   10:00:00
Short Desc:  _____
Status    :  _____

Requested by:
Name      :  _____
Phone     :  _____   User-ID:  _____
Date      :  19991231   Other   :  _____

Suggestion Description:
_____
_____
_____
_____

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
HELP  ----  END   ----  ----  ----  ----  ----  ----  ----  ----  ----  ----

```

The following Field Descriptions apply to all Suggestion Box functions (Add, Copy, Delete, Inquire on, and Modify).

Field	Description
PROJECT (supplied)	The project to which the suggestion applies.
SUGGESTION (supplied)	The number that uniquely identifies the suggestion. When adding, N2O automatically generates the suggestion.
UPDATED (supplied)	The User-ID of the user who created or last updated the record and the date and time that action occurred.
SHORT DESC (required)	A 30-character description of the suggestion.
STATUS (optional)	The status of a suggestion (i.e., opens, rejected, accepted, etc.). N2O does not restrict values for this field.
NAME (optional)	The name of the contact individual responsible for the suggestion.
PHONE (optional)	The phone number of the requester.

(continued from previous page)

Field	Description
USER-ID (optional)	The User-ID of the requester.
DATE (optional)	The date the request was made. N2O automatically supplies this, but the requester may modify it.
OTHER (optional)	Other information pertinent to the requester.
SUGGESTION DESCRIPTION (optional)	Provides a description of the suggestion.

III.4.2 Copy a Suggestion

Copy a Suggestion creates a suggestion by copying an existing suggestion.

To copy a suggestion, enter "C" in the Enter Code field, the Project Definition in the Project field, and the suggestion number to be copied in the Suggestion field on the Suggestion Box menu.

```

01-12-31          N-2-O SUGGESTION BOX MENU          TSI0373
11:38:00                                     TSI1

Code  Function
-----
A    Add a Suggestion
C    Copy a Suggestion
D    Delete a Suggestion
I    Inquire on a Suggestion
M    Modify a Suggestion
S    Select a Suggestion
.    Termina +-----+
-----+-----+
Enter Code:  _   Project | Copy Project:  PAYROLL_____ |
                          | Suggestion  :   100_____ |
                          | To Project   :  ACCTSRECV_____ |
                          |                               |
                          +-----+
Direct Command _____ PRJ SUGG
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
HELP  ----  END  ENV  MIG  REP  TOL  USR  PRJ  ----  ----  EXIT

```

A pop-up window is displayed for information to be entered about the new suggestion.

III.4.3 Delete a Suggestion

Delete a Suggestion removes a suggestion.

To delete a suggestion, enter "D" in the Enter Code field, the Project Definition in the Project field, and the suggestion number to be deleted in the Suggestion field on the Suggestion Box menu.

```

01-12-31          N-2-O DELETE A SUGGESTION          TSI0373
11:38:00                                     TSI1

Project   :  PAYROLL
Suggestion:    100
Updated   :  TSI0373    01-12-31    11:34:07
Short Desc: _____
Status    :  _____

Requested by:
Name      :  _____
Phone     :  _____   User-ID:  _____
Date      :  20011231   Other   :  _____

Suggestion Description:
_____ +-----+
_____ | Do you want to Delete?  N (Y/N) |
_____ |                               |
_____ +-----+

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
----  ----  END  ----  ----  ----  ----  ----  ----  ----  ----  ----

```

To confirm the delete request, enter "Y" in the pop-up window. To cancel the delete request, press "N" in the pop-up window or press PF3.

III.4.4 Inquire on a Suggestion

Inquire on a Suggestion displays information about a suggestion.

To inquire on a suggestion, enter "I" in the Enter Code field, the Project Definition in the Project field, and the suggestion number to be viewed in the Suggestion field on the Suggestion Box menu.

01-12-31 11:38:00	N-2-O INQUIRE ON A SUGGESTION	TSI0373 TSI1
Project : PAYROLL Suggestion : 1 Updated : TSI0373 01-12-31 Short Desc : ENHANCE PAYROLL RPT1 Status : _____		
Requested by:		
Name : _____		
Phone : _____ User-ID: _____		
Date : 20011231 Other : _____		
Suggestion Description:		
ADD EMPLOYEE ADDRESS TO RPT. _____		
ALLOW SORT ORDER TO BE SPECIFIED _____		
BY THE USER. _____		

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---		
----- END -----		

III.4.5 Modify a Suggestion

Modify a Suggestion updates a suggestion.

To modify a suggestion, enter "M" in the Enter Code field, the project in the Project Definition field, and the suggestion number to be modified in the Suggestion field on the Suggestion Box menu.

01-12-31 11:38:00	N-2-O MODIFY A SUGGESTION	TSI0373 TSI1
Project : PAYROLL Suggestion : 1 Updated : TSI0373 01-12-31 Short Desc : ENHANCE PAYROLL RPT1 Status : OPEN_____		
Requested by:		
Name : _____		
Phone : _____ User-ID: _____		
Date : 20011231 Other : _____		
Suggestion Description:		
ADD EMPLOYEE ADDRESS TO RPT. _____		
ALLOW SORT ORDER TO BE SPECIFIED _____		
BY THE USER. _____		

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---		
HELP ---- END -----		

III.4.6 Select a Suggestion

Select a Suggestion provides a list of all suggestions currently recorded.

To select a suggestion, enter "S" in the Enter Code field on the Suggestion Box menu. A starting value may be entered in the Project and Suggestion fields on the Suggestion Box menu.

```

Valid values: C - Copy D - Delete I - Inquire M - Modify
01-12-31      N-2-O SELECT A SUGGESTION      TSI0373
11:38:00      TSI1

```

S	Project	Suggestion	Short Description	Status
-	PAYROLL	1	ENHANCE PAYROLL RPT1	OPEN

```

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
HELP  ----  END   ----  ----  ----  ----  ----  ----  ----  ----  ----  ----

```

Field	Description
S (optional)	The function to be executed. Each user's Function Profile security determines the user's valid values. Valid values are as follows: C Indicates Copy a Suggestion. D Indicates Delete a Suggestion. I Indicates Inquire on a Suggestion. M Indicates Modify a Suggestion.

Pressing Enter pages forward on all screens until the last screen is displayed. Pressing Enter on the last screen wraps around to display the first screen again.

III.5 Task Utilities

Most of the basic information about tasks is maintained in the Task List. However, there are circumstances that require additional information about a task. The Task Utilities allow this type of detailed information to be created and updated.

To access the Task Utilities menu, enter "D" on the Project Tracking Subsystem menu or enter the direct command PRJ TUTL on any menu.

```

01-12-31          N-2-O TASK UTILITIES MENU          TSI0373
11:38:00                                     TSI1

Code  Function
----  -
A      Update Stage for a Task
B      Cancel a Task
C      Reject a Task
D      Link Objects to a Task
E      Link Suggestions to a Task
F      Link Tasks to a Task
.      Terminate Task Utilities
----  -

Enter Code:  _

Direct Command          PRJ TUTL
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
HELP  ----  END  ENV  MIG  REP  TOL  USR  PRJ  ----  ----  EXIT

```

Field	Description
ENTER CODE (required)	The function to be executed. Valid values are as follows: <ul style="list-style-type: none"> A Update Stage for a Task Allows a task to be promoted to a new stage. B Cancel a Task Marks the stage of a task as canceled. C Reject a Task Marks the stage of a task as rejected. D Link Objects to a Task Maintains a list of objects that are affected by a particular task. E Link Suggestions to a Task Maintains a list of suggestions that are related to a task. F Link Tasks to a Task Maintains a list of tasks that are related to a particular task.

III.5.1 Update Stage for a Task

As resources are assigned to a task and activities are accomplished, the progress of a task changes. This progress is tracked by the stage of a task.

The Update Stage for a Task function allows a task to be promoted to a new stage. Usually, the task is updated to the next sequential stage. The order of the stages is determined by the Project Definition. In some cases, it may be necessary to skip stages or to return to a previous stage. User-Exit 20 is available from this utility to allow sites to override the order of the stages. User-Exit 20 can also be used to provide security to update the stages of tasks. Refer to the **N2O Administration Manual** for details on User-Exit 20.

To update a stage for a task, enter "A" on the Task Utilities menu.

01-12-31 11:38:00	N-2-O TASK UTILITIES UPDATE STAGE FOR A TASK	TSI0373 TSI1
<p>Project : PAYROLL</p> <p>Task Group : _____</p> <p>Task Number: _____</p>		
<p>Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---</p> <p>HELP ---- END ----</p>		

Field	Description
∞ PROJECT (required)	The project in which a task belongs.
TASK GROUP (optional)	The group in which a task belongs.
TASK NUMBER (optional)	The number that uniquely identifies a task.

∞ indicates field-level help is available.

To display the Update Stage for a Task select screen, enter a project on the previous screen. A task group and a task number may also be entered on the previous screen to limit the search.

```

01-12-31          N-2-0 UPDATE STAGE FOR A TASK          TSI0373
11:38:00          Project: PAYROLL                        TSI1

----- Task -----
X  Group      Number  Short Description          Stage      Message
-----
-  BENEFITS      2    CALC AS PERCENTAGE OF DEDUCT  DEFINED
-  BONUSES       1    YEAR TO DATE SUMMARY OF BONUS  DEFINED
-  CITYTAX       1    COMPUTE 99 RATE INCREASE        DEFINED
-  CITYTAX       2    CALC AS PERCENTAGE OF DEDUCT  DESIGN
-  FEDTAX        1    ADJUST TO NEW RATES             DEFINED
-  FEDTAX        2    CALC AS FEDTAX AS % OF DEDUCT  DEFINED
-  FICA          1    CALC AS PERCENTAGE OF DEDUCT  DEFINED

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      HELP  ----  END   ----  ----  ----  ----  ----  ----  ----  ----  ----

```

Field	Description
PROJECT (supplied)	The name of the project.
X (optional)	Entering "X" next to a task displays a pop-up window for the new stage, allowing comments to be entered. The new stage defaults to the next stage in the sequence defined on the Project Definition.
TASK GROUP (supplied)	The group in which a task belongs.
TASK NUMBER (supplied)	The number that uniquely identifies a task.
SHORT DESCRIPTION (supplied)	A 30-character description of the task.
STAGE (supplied)	The current stage assigned to the task.
MESSAGE (supplied)	Indicates the stage of the task has been updated.

III.5.2 **Cancel a Task**

Tasks that are in the process of being completed may be re-evaluated based on available resources. Tasks that are suspended for this reason are considered canceled.

Cancel a Task marks the stage of a task to be canceled. Tasks that are in the canceled stage may be restarted from the beginning at any time.

To cancel a task, enter "B" on the Task Utilities menu.

01-12-31 11:38:00	N-2-O TASK UTILITIES N-2-O CANCEL A TASK	TSI0373 TSI1
Project : PAYROLL Task Group : _____ Task Number: _____		
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12--- HELP ---- END ----		

Field	Description
∞ PROJECT (required)	The project in which a task is to be canceled.
TASK GROUP (optional)	The group that identifies a task.
TASK NUMBER (optional)	The number that uniquely identifies a task.

∞ indicates field-level help is available.

To display the Cancel a Task select screen, enter a project on the previous screen. A task group and a task number may also be entered on the previous screen to limit the search.

```

01-12-31          N-2-O CANCEL A TASK          TSI0373
11:38:00          Project: PAYROLL             TSI1

----- Task -----
X  Group      Number  Short Description          Stage      Message
-----
-  BENEFITS      2    CALC AS PERCENTAGE OF DEDUCT  DEFINED
-  BONUSES       1    YEAR TO DATE SUMMARY OF BONUS  DEFINED
-  CITYTAX       1    COMPUTE 99 RATE INCREASE      DEFINED
-  CITYTAX       2    CALC AS PERCENTAGE OF DEDUCT  DESIGN
-  FEDTAX        1    ADJUST TO NEW RATES           DEFINED
-  FEDTAX        2    CALC AS FEDTAX AS % OF DEDUCT  DEFINED
-  FICA          1    CALC AS PERCENTAGE OF DEDUCT  DEFINED

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      END
  
```

Field	Description
PROJECT (supplied)	The name of the project.
X (optional)	Entering "X" next to a task displays a pop-up window allowing comments to be entered and sets the task's stage to cancel.
TASK GROUP (supplied)	The group in which a task belongs.
TASK NUMBER (supplied)	The number that uniquely identifies a task.
SHORT DESCRIPTION (supplied)	A 30-character description of the task.
STAGE (supplied)	The current stage assigned to the task.
MESSAGE (supplied)	Indicates the task has been canceled.

III.5.3 **Reject a Task**

A task may reach a certain stage and not meet the requirements for being at that stage. In this situation, the task should be rejected.

Reject a Task removes a task from its current stage and places it in the prior stage. Tasks that are rejected must be restarted at the prior stage.

A canceled task may not be rejected.

To reject a task, enter "C" on the Task Utilities menu.

01-12-31 11:38:00	N-2-O TASK UTILITIES N-2-O REJECT A TASK	TSI0373 TSI1
<p>Project : PAYROLL</p> <p>Task Group : _____</p> <p>Task Number: _____</p>		
<p>Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---</p> <p>HELP ---- END ----</p>		

Field	Description
∞ PROJECT (required)	The project in which a task is to be rejected.
TASK GROUP (optional)	The group that identifies a task.
TASK NUMBER (optional)	The number that uniquely identifies a task.

∞ indicates field-level help is available.

To display a Reject a Task select screen, enter a project on the previous screen. A task group and a task number may also be entered on the previous screen to limit the search.

01-12-31 11:38:00		N-2-0 REJECT A TASK Project: PAYROLL		TSI0373 TSI1	
----- Task -----					
X	Group	Number	Short Description	Stage	Message
-	-----				
-	BENEFITS	2	CALC AS PERCENTAGE OF DEDUCT	DEFINED	
-	BONUSES	1	YEAR TO DATE SUMMARY OF BONUS	DEFINED	
-	CITYTAX	1	COMPUTE 99 RATE INCREASE	DEFINED	
-	CITYTAX	2	CALC AS PERCENTAGE OF DEDUCT	DESIGN	
-	FEDTAX	1	ADJUST TO NEW RATES	DEFINED	
-	FEDTAX	2	CALC AS FEDTAX AS % OF DEDUCT	DEFINED	
-	FICA	1	CALC AS PERCENTAGE OF DEDUCT	DEFINED	
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---					
HELP ---- END ----					

Field	Description
PROJECT (supplied)	The name of the project.
X (optional)	Entering "X" next to a task displays a pop-up window allowing comments to be entered.
TASK GROUP (supplied)	The group in which a task belongs.
TASK NUMBER (supplied)	The number that uniquely identifies a task.
SHORT DESCRIPTION (supplied)	A 30-character description of the task.
STAGE (supplied)	The current stage assigned to the task.
MESSAGE (supplied)	Indicates the task has been rejected.

III.5.4 Link Objects to a Task

In application programming, it is useful to package objects affected by a change. The Link Objects to a Task function maintains a list of objects that are affected by a task.

To link Objects to a task, enter "D" on the Task Utilities menu.

01-12-31 11:38:00	N-2-O TASK UTILITIES LINK OBJECTS TO A TASK	TSI0373 TSI1
Task Group : BENEFITS Task Number: 000003		
Options:		
View Linked Objects	Y	
Select Objects from Event/Seq	N	
Add Linked Objects	N	
Delete Linked Objects	N	
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12--- HELP ---- END ----		

Field	Description
TASK GROUP (required)	The group that identifies a task.
TASK NUMBER (required)	The number that uniquely identifies a task.
VIEW LINKED OBJECTS	Y Displays a list of objects already linked to a task. (If "Y" is entered for this option, "N" must be entered for all other options.) N Bypasses the display.
SELECT OBJECTS FROM EVENT/SEQ	Y Prompts for Event, then displays a list of Event objects, and allows objects to be linked to an object. (If "Y" is entered for this option, "N" must be entered for all other options.) N Bypasses the display.
ADD LINKED OBJECTS	Y Allows the user to add objects linked to a task. (If "Y" is entered for this option, "N" must be entered for all other options.) N Bypasses the display.
DELETE LINKED OBJECTS	Y Allows the user to remove objects linked to a task. (If "Y" is entered for this option, "N" must be entered for all other options.) N Bypasses the display.

To display the View Linked Objects screen, enter a task group and a task number on the previous screen, and a "Y" next to the View Linked Objects option.

```

Press Enter to continue
01-12-31      N-2-O LINK OBJECTS TO A TASK      TSI0373
11:38:00      VIEW LINKED OBJECTS              TSI1
               Task Group: BENEFITS  Task Number: 1
               Short Desc: ALL ACCOUNTS

               Object Name                      Type  Obj Type
               -----
PAYEVNTD      N      PROGRAM
PAY4240N      N      SUB-PGM
PAY4240S      N      SUB-RTN
PAY42401      N      MAP
PAY42411      N      MAP
PAY42412      N      MAP

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      END
  
```

Field	Description
TASK GROUP (supplied)	The group in which the task belongs.
TASK NUMBER (supplied)	The number that uniquely identifies a task.
SHORT DESC (supplied)	A 30-character description of the task.
OBJECT NAME (supplied)	The object linked to the task.
TYPE (supplied)	The following types are required when using this function to supply information to User-Exit 15: N Indicates NATURAL. S Indicates SYSERR. P Indicates PREDICT. O Indicates 3GL/OTHER.

(Continued from previous page)

Field	Description																																																																																																												
OBJ TYPE (supplied)	<p>The following object types are required when using this function to supply information to User-Exit 15 (Refer to the <i>N2O Administration Manual</i> for details on User-Exit 15). This field is not used for SYSERR messages.</p> <p>NATURAL object type</p> <table><tr><td>PARM</td><td>Indicates Parameter data area.</td></tr><tr><td>COPYCODE</td><td>Indicates Copycode.</td></tr><tr><td>GLOBAL</td><td>Indicates Global data area.</td></tr><tr><td>HELP-RTN</td><td>Indicates Helproutine.</td></tr><tr><td>LOCAL</td><td>Indicates Local data area.</td></tr><tr><td>MAP</td><td>Indicates Map.</td></tr><tr><td>SUB-PGM</td><td>Indicates Subprogram.</td></tr><tr><td>PROGRAM</td><td>Indicates Program.</td></tr><tr><td>SUB-RTN</td><td>Indicates Subroutine.</td></tr><tr><td>TEXT</td><td>Indicates Text.</td></tr><tr><td>MACRO</td><td>Indicates macro.</td></tr><tr><td>REPORT</td><td>Indicates Report.</td></tr><tr><td>EXP-MDL</td><td>Indicates ExpertModel.</td></tr><tr><td>RECORD</td><td>Indicates Recording.</td></tr><tr><td>DIALOG</td><td>Indicates Dialog.</td></tr><tr><td>CLASS</td><td>Indicates Class.</td></tr><tr><td>CMD-PROC</td><td>Indicates Processor.</td></tr><tr><td>SERVER</td><td>Indicates Server.</td></tr></table> <p>PREDICT object type</p> <table><tr><th>Type</th><th>Indicates</th><th>Predict Version</th></tr><tr><td>DA</td><td>Database</td><td></td></tr><tr><td>DC</td><td>Dataspace</td><td></td></tr><tr><td>ET</td><td>Extract</td><td></td></tr><tr><td>FI</td><td>File</td><td></td></tr><tr><td>IE</td><td>Interface</td><td>V4.1.2 and above</td></tr><tr><td>KY</td><td>Keyword</td><td></td></tr><tr><td>LS</td><td>Library Structure</td><td></td></tr><tr><td>MD</td><td>Method</td><td>V4.1.2 and above</td></tr><tr><td>MO</td><td>Module</td><td>V3.4.2 and below</td></tr><tr><td>NO</td><td>Node</td><td></td></tr><tr><td>NW</td><td>Network</td><td></td></tr><tr><td>PG</td><td>PackageList</td><td></td></tr><tr><td>PR</td><td>Program</td><td></td></tr><tr><td>PY</td><td>Property</td><td>V4.1.2 and above</td></tr><tr><td>RL</td><td>Relationship</td><td></td></tr><tr><td>RP</td><td>Report</td><td>V3.4.2 and below</td></tr><tr><td>RT</td><td>Report Listing</td><td></td></tr><tr><td>SC</td><td>Storagespace</td><td></td></tr><tr><td>SV</td><td>Server</td><td></td></tr><tr><td>SY</td><td>System</td><td></td></tr><tr><td>US</td><td>User</td><td></td></tr><tr><td>VE</td><td>Verification</td><td></td></tr><tr><td>VM</td><td>Virtual Machine</td><td></td></tr></table>	PARM	Indicates Parameter data area.	COPYCODE	Indicates Copycode.	GLOBAL	Indicates Global data area.	HELP-RTN	Indicates Helproutine.	LOCAL	Indicates Local data area.	MAP	Indicates Map.	SUB-PGM	Indicates Subprogram.	PROGRAM	Indicates Program.	SUB-RTN	Indicates Subroutine.	TEXT	Indicates Text.	MACRO	Indicates macro.	REPORT	Indicates Report.	EXP-MDL	Indicates ExpertModel.	RECORD	Indicates Recording.	DIALOG	Indicates Dialog.	CLASS	Indicates Class.	CMD-PROC	Indicates Processor.	SERVER	Indicates Server.	Type	Indicates	Predict Version	DA	Database		DC	Dataspace		ET	Extract		FI	File		IE	Interface	V4.1.2 and above	KY	Keyword		LS	Library Structure		MD	Method	V4.1.2 and above	MO	Module	V3.4.2 and below	NO	Node		NW	Network		PG	PackageList		PR	Program		PY	Property	V4.1.2 and above	RL	Relationship		RP	Report	V3.4.2 and below	RT	Report Listing		SC	Storagespace		SV	Server		SY	System		US	User		VE	Verification		VM	Virtual Machine	
PARM	Indicates Parameter data area.																																																																																																												
COPYCODE	Indicates Copycode.																																																																																																												
GLOBAL	Indicates Global data area.																																																																																																												
HELP-RTN	Indicates Helproutine.																																																																																																												
LOCAL	Indicates Local data area.																																																																																																												
MAP	Indicates Map.																																																																																																												
SUB-PGM	Indicates Subprogram.																																																																																																												
PROGRAM	Indicates Program.																																																																																																												
SUB-RTN	Indicates Subroutine.																																																																																																												
TEXT	Indicates Text.																																																																																																												
MACRO	Indicates macro.																																																																																																												
REPORT	Indicates Report.																																																																																																												
EXP-MDL	Indicates ExpertModel.																																																																																																												
RECORD	Indicates Recording.																																																																																																												
DIALOG	Indicates Dialog.																																																																																																												
CLASS	Indicates Class.																																																																																																												
CMD-PROC	Indicates Processor.																																																																																																												
SERVER	Indicates Server.																																																																																																												
Type	Indicates	Predict Version																																																																																																											
DA	Database																																																																																																												
DC	Dataspace																																																																																																												
ET	Extract																																																																																																												
FI	File																																																																																																												
IE	Interface	V4.1.2 and above																																																																																																											
KY	Keyword																																																																																																												
LS	Library Structure																																																																																																												
MD	Method	V4.1.2 and above																																																																																																											
MO	Module	V3.4.2 and below																																																																																																											
NO	Node																																																																																																												
NW	Network																																																																																																												
PG	PackageList																																																																																																												
PR	Program																																																																																																												
PY	Property	V4.1.2 and above																																																																																																											
RL	Relationship																																																																																																												
RP	Report	V3.4.2 and below																																																																																																											
RT	Report Listing																																																																																																												
SC	Storagespace																																																																																																												
SV	Server																																																																																																												
SY	System																																																																																																												
US	User																																																																																																												
VE	Verification																																																																																																												
VM	Virtual Machine																																																																																																												

(Continued from previous page)

Field	Description
	3GL category
ASMB	Indicates Assembler.
COBOL	Indicates COBOL.
FORT	Indicates FORTRAN.
PL/I	Indicates PL/I.
RPG	Indicates RPG.
DATA	Indicates DATA FILES.
JCL	Indicates JCL.
OTHER	Indicates all other objects.

III.5.5 Link Suggestions to a Task

Suggestions may be the reason a task is defined. Several suggestions can be accomplished by a single task.

Link Suggestions to a Task allows suggestions to be related to a task.

To link suggestions to a task, enter "E" on the Task Utilities menu.

01-12-31 11:38:00	N-2-O TASK UTILITIES LINK SUGGESTIONS TO A TASK	TSI0373 TSI1
<p>Task Group : BENEFITS Task Number: 3</p> <p>Options: View Linked Suggestions Y Modify Linked Suggestions N</p>		
<p>Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12--- HELP ---- END ----</p>		

Field	Description
TASK GROUP (required)	The group in which a particular task belongs.
TASK NUMBER (required)	The number of a particular task.
VIEW LINKED SUGGESTIONS (required)	Y Provides a list of suggestions linked to a task. (If "Y" is entered for this option, "N" must be entered for the remaining option.)
MODIFY LINKED SUGGESTIONS (required)	Y Allows user to modify suggestions linked to a task. (If "Y" is entered for this option, "N" must be entered for the remaining option.)

To display the View Linked Suggestions screen, enter a task group and a task number on the previous screen and a "Y" next to the View Linked Suggestions option.

```

01-12-31          N-2-O LINK SUGGESTIONS TO A TASK          TSI0373
11:38:00          VIEW LINKED SUGGESTIONS                    TSII

Task Group :  BENEFITS
Task Number:         3
Short Desc  :  UPDATE TAX CODES

Project          Suggestion          Project          Suggestion
-----
PAYROLL          32
PAYROLL          35
PAYROLL          38
PAYROLL          40
PAYROLL          53
PAYROLL          33
PAYROLL          36
PAYROLL          39
PAYROLL          51

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      END

```

Field	Description
TASK GROUP (supplied)	The group to which a particular task belongs.
TASK NUMBER (supplied)	The number of a particular task.
SHORT DESC (supplied)	A 30-character of the task.
PROJECT (supplied)	The name of the project.
SUGGESTION (supplied)	The number of the suggestion.

To display the Modify Linked Suggestions screen, enter a task group and a task number on the previous screen and a "Y" next to the Modify Linked Suggestions option.

01-12-31 11:38:00	N-2-O LINK SUGGESTIONS TO A TASK MODIFY LINKED SUGGESTIONS	TSI0373 TSII
Task Group : BENEFITS Task Number: 3 Short Desc : UPDATE TAX CODES		
Project	Suggestion	Project
-----	-----	-----
PAYROLL	32	
PAYROLL	35	
PAYROLL	38	
PAYROLL	40	
PAYROLL	53	
PAYROLL	33	
PAYROLL	36	
PAYROLL	39	
PAYROLL	51	
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12--- --- END LIST ---		

Field	Description
TASK GROUP (supplied)	The group to which a particular task belongs.
TASK NUMBER (supplied)	The number of a particular task.
SHORT DESC (supplied)	A 30-character of the task.
PROJECT (optional)	The name of the project.
SUGGESTION (optional)	The number of the suggestion.

PF4 allows selection of a suggestion from a list.

III.5.6 Link Tasks to a Task

Many activities within a project overlap one another. It is important for tracking to be able to relate any similar activities.

Link Tasks to a Task allows up to 20 tasks to be linked to a single task.

To link tasks to a task, enter "F" on the Task Utilities menu.

```

01-12-31          N-2-O TASK UTILITIES          TSI0373
11:38:00          LINK TASKS TO A TASK          TSI1

Task Group :  BENEFITS
Task Number:  1_____

Options:
View Linked Tasks      N
Modify Linked Tasks    N

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      HELP  ----  END   ----  ----  ----  ----  ----  ----  ----  ----  ----  ----

```

Field	Description
TASK GROUP (required)	The group in which a particular task belongs.
TASK NUMBER (required)	The number that uniquely identifies a task.
VIEW LINKED TASKS (required)	Y Displays a list of objects already defined to a task. (If "Y" is entered for this option, "N" must be entered for the remaining option.)
MODIFY LINKED TASKS (required)	Y Allows user to modify linked tasks. (If "Y" is entered for this option, "N" must be entered for the remaining option.)

To display the View Linked Tasks screen, enter a task group and a task number on the previous screen, and enter a "Y" next to the View Linked Tasks option.

01-12-31 11:38:00	N-2-O LINK TASKS TO A TASK VIEW LINKED TASKS	TSI0373 TSI1
Task Group : BENEFITS Task Number: 1 Short Desc : ALL ACCOUNTS		
Task Group	Task Number	Task Group Task Number
-----	-----	-----
PAY330E	42	
_____	_____	_____
_____	_____	_____
_____	_____	_____
_____	_____	_____
_____	_____	_____
_____	_____	_____
_____	_____	_____
_____	_____	_____
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12--- HELP ---- END ----		

Field	Description
TASK GROUP (supplied)	The group to which a particular task belongs.
TASK NUMBER (supplied)	The number that uniquely identifies a task.
SHORT DESC (supplied)	A 30-character description of the task.
TASK GROUP (supplied)	The task linked with this task.
TASK NUMBER (supplied)	The task number associated with the linked task.

To display the Modify Linked Tasks screen, enter a task group and a task number on the previous screen, and enter a "Y" next to the Modify Linked Tasks option.

01-12-31 11:38:00	N-2-O LINK TASKS TO A TASK MODIFY LINKED TASKS	TSI0373 TSII
Task Group : BENEFITS Task Number: 1 Short Desc : ALL ACCOUNTS		
Task Group	Task Number	Task Group Task Number
-----	-----	-----
PAY330E	42	
_____	_____	_____
_____	_____	_____
_____	_____	_____
_____	_____	_____
_____	_____	_____
_____	_____	_____
_____	_____	_____
_____	_____	_____
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12--- HELP ---- END ----		

Field	Description
TASK GROUP (supplied)	The group to which a particular task belongs. Pressing PF4 allows a selection of a task from a list.
TASK NUMBER (supplied)	The number that uniquely identifies a task.
SHORT DESC (required)	A 30-character description of the task.
TASK GROUP (optional)	The task linked with this task.
TASK NUMBER (optional)	The task number associated with the linked task.

III.6 Project Tracking Reports

To access the Project Tracking Reports menu, enter "E" on the Project Tracking Subsystem menu or enter the direct command PRJ REP on any menu.

```

01-12-31      N-2-O PROJECT TRACKING REPORTS MENU      TSI0373
11:38:00                                           TSI1

      Code  Function
      ----  -
      A    History of a Task
      B    Task Details
      C    Project Status
      D    User Status
      E    Events Related to a Task
      F    Suggestion Details
      .    Terminate Project Tracking Reports
      -    -----
Enter Code:  _

Direct Command _____ PRJ REP
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      HELP  ----  END  ENV  MIG  REP  TOL  USR  PRJ  ----  ----  EXIT

```

Field	Description
ENTER CODE (required)	The function to be executed. Valid values are as follows: <ul style="list-style-type: none"> A History of a Task Provides a history of the stages a task has passed in reverse chronological order. B Task Details Provides all information about a task. C Project Status Shows all tasks defined to a project, and the current stage of each task. D User Status Displays all tasks where a user is listed as a contact, based on User-ID. E Events Related to a Task Provides a list of all Events that influence a particular task. F Suggestion Details Provides detailed information about each suggestion within a project.

III.6.1 History of a Task

History of a Task provides a history of the stages a task has passed in reverse chronological order.

To access the History of a Task function, enter "A" on the Project Tracking Reports menu.

01-12-31 11:38:00	N-2-O PROJECT TRACKING REPORTS HISTORY OF A TASK	TSI0373 TSI1
<p>Project : PAYROLL_____</p> <p>Task Group : _____</p> <p>Task Number: _____</p> <p>Date Range : _____ - _____</p> <p>Mode : O</p>		
<p>Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---</p> <p>HELP ---- END ----</p>		

Field	Description
∞ PROJECT (required)	The name of the project.
TASK GROUP (required)	The group that identifies a task.
TASK NUMBER (required)	The number that uniquely identifies a task.
DATE RANGE (optional)	Limits output to specific time period. Dates must be formatted YYYYMMDD.
MODE (required)	Indicates how the job is executed (batch or on-line). <ul style="list-style-type: none"> O Submits JCL to the internal reader that processes the function in batch. B Processes the function on-line. (Default: O)

∞ indicates field-level help is available.

To display the History of a Task report, enter a project, task group, and task number on the previous screen.

01-12-31 11:38:00	N-2-O PROJECT TRACKING REPORTS HISTORY OF A TASK			TSIO373 TSII Page: 1
Task Group:	BENEFITS	Task Number:	3	Project: PAYROLL
Stage	Date	Time	User-ID	Comments
APPROVED	01-12-31	11:35:40	TSIO373	ALL ACCOUNTS
TESTED	00-12-04	10:23:00	TSIO373	RECENT ACCOUNTS
DEFINED	01-09-25	12:22:58	TSIO373	INITIAL ACCOUNTS
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---				
-----END-----STOP				

Field	Description
TASK GROUP (supplied)	The group that identifies a task.
TASK NUMBER (supplied)	The number that uniquely identifies a task.
PROJECT (supplied)	The name of the project.
STAGE (supplied)	The progress of a task.
DATE (supplied)	Date the task passed the specified stage.
TIME (supplied)	Time the task passed the specified stage.
USER-ID (supplied)	The User-ID responsible for updating the task to the specified stage.
COMMENTS (supplied)	The information provided when the task was updated to the specified stage.

III.6.2 Task Details

Task Details provides the details of a task. The following fields can limit this report: Project, Task Group, Task Number, Stage, Priority, and Impact.

To access the Task Details function, enter "B" on the Project Tracking Reports menu.

01-12-31 11:38:00	N-2-O PROJECT TRACKING REPORTS TASK DETAILS	TSI0373 TSI1
<p>Project : PAYROLL_____</p> <p>Task Group : _____</p> <p>Task Number: _____</p> <p>Stage : _____</p> <p>Priority : _____</p> <p>Impact : _____</p> <p>Mode : O</p>		
<p>Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---</p> <p>HELP ---- END ----</p>		

Field	Description
∞ PROJECT (required)	The name of the project.
TASK GROUP (optional)	Limits the report to tasks with the specified task group.
TASK NUMBER (optional)	The number of a task.
STAGE (optional)	Limits the report to tasks with the specified stage.
PRIORITY (optional)	Limits the report to tasks with the specified priority.
IMPACT (optional)	Limits the report to tasks with the specified impact.
MODE (required)	Indicates how the job is executed (batch or on-line). <ul style="list-style-type: none"> O Submits JCL to the internal reader that processes the function in batch. B Processes the function on-line. (Default: O)

∞ indicates field-level help is available.

To display the Task Details report screen, enter a project on the previous screen.

```

Valid values: D-Details C-Contacts L-Checklist
01-12-31      N-2-O PROJECT TRACKING REPORTS      TSI0373
11:38:00      TASK DETAILS                        TSI1
                                                    Page: 1

---- Task ----
S  Group   Number  Short Description      Stage      Prty  Impact
-----
-  BENEFITS    1  ALL ACCOUNTS          DEFINED     **    **
-  BENEFITS    2  RECENT ACCOUNTS       DEFINED     **    **
-  BENEFITS    3  INITIAL ACCOUNTS      DEFINED     **    **

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
----- END ----- STOP

```

Field	Description
S (optional)	The function to be executed. Valid values are as follows: D Displays detailed information about the task. C Displays the list of contacts for the task. L Displays the checklist items for the task.
TASK GROUP (supplied)	The group that identifies a task.
TASK NUMBER (supplied)	The number that uniquely identifies a task.
SHORT DESCRIPTION (supplied)	A 30-character description of the task.
STAGE (supplied)	The current stage of a task.
PRTY (supplied)	The priority of a task.
IMPACT (supplied)	The impact of a task.

III.6.3 Project Status

Project Status shows all tasks defined to a project, and the current stage of each task.

To access the Project Status function, enter "C" on the Project Tracking Reports menu.

01-12-31 11:38:00	N-2-O PROJECT TRACKING REPORTS PROJECT STATUS	TSI0373 TSI1
<p>Project: _____</p> <p>Mode : O</p>		
<p>Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---</p> <p>HELP ---- END ----</p>		

Field	Description
∞ PROJECT (required)	The name of the project.
MODE (required)	Indicates how the job is executed (batch or on-line).
	B Submits JCL to the internal reader that processes the function in batch.
	O Processes the function on-line. (Default: O)

∞ indicates field-level help is available.

To display the Project Status report screen, enter a project on the previous screen.

01-12-31	N-2-O PROJECT TRACKING REPORTS				TSI0373
11:38:00	PROJECT STATUS FOR PAYROLL				TSI1
					Page 1
---- Task ----					
Group	Number	Short Description	Prty	Impact	Stage

BENEFITS	000002	CALC AS PERCENTAGE OF DEDUCT	MED	MED	DEFINED
BONUSES	000001	YEAR TO DATE SUMMARY OF BONUS	LOW	LOW	DEFINED
CITYTAX	000001	COMPUTE 99 RATE INCREASE	HIGH	MED	DEFINED
CITYTAX	000002	CALC AS PERCENTAGE OF DEDUCT	MED	MED	DESIGN
FEDTAX	000001	ADJUST TO NEW RATES	HIGH	HIGH	DEFINED
FEDTAX	000002	CALC AS FEDTAX AS % OF DEDUCT	HIGH	MED	DEFINED
FICA	000001	CALC AS PERCENTAGE OF DEDUCT	MED	MED	DEFINED
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---					

END					
STOP					

The Project Status report shows all tasks that belong to the project. The Current Stage field is displayed to allow the user to quickly assess the status of the entire project.

Field	Description
TASK GROUP (supplied)	The group that identifies a task.
TASK NUMBER (supplied)	The number that uniquely identifies a task.
SHORT DESCRIPTION (supplied)	A 30-character description of the task.
PRTY (supplied)	The priority of a task.
IMPACT (supplied)	The impact of a task.
STAGE (supplied)	The current stage of a task.

III.6.4 User Status

User Status displays all tasks where a user is listed as a contact. The report is based on the User-ID of the user.

To access the User Status function, enter "D" on the Project Tracking Reports menu.

01-12-31 11:38:00	N-2-O PROJECT TRACKING REPORTS USER STATUS	TSI0373 TSI1
<p>User-ID : TSI0373_ Project : PAYROLL Date Range : _____ - _____ Primary Contact: Y Mode : O</p>		
<p>Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12--- HELP ---- END ----</p>		

Field	Description
USER-ID (required)	The User-ID.
∞ PROJECT (required)	Limits the report to tasks for the specified project.
DATE RANGE (optional)	Limits the report to a specific time period. Dates must be formatted YYYYMMDD.
PRIMARY CONTACT (required)	Indicates whether tasks are displayed only if the specified User-ID is the primary contact or all tasks where the specified User-ID is referenced.
	Y Displays only tasks where the specified User-ID is the primary contact.
	N Displays all tasks that reference the specified User-ID.
MODE (required)	Indicates how the job is executed (batch or on-line).
	B Submits JCL to the internal reader that processes the function in batch.
	O Processes the function on-line. (Default: O)

∞ indicates field-level help is available.

To display the User Status report screen, enter a User-ID on the previous screen.

Press PF5 to view Description						
01-12-31	N-2-O PROJECT TRACKING REPORTS					TSI0373
11:38:00	USER STATUS FOR TREE06					TSI1
Project	Group	Number	Stage	Date	Update Time	User-ID
PAYROLL	BENEFITS	000002	AUTHORIZED	01-10-17	10:29:02	TSI0373
PAYROLL	BENEFITS	000003	AUTHORIZED	01-08-04	16:11:44	TSI0373
PAYROLL	BENEFITS	000005	AUTHORIZED	01-07-16	15:30:57	TSI0373
PAYROLL	BENEFITS	000009	DEFINED	01-05-26	14:23:37	TSI0373
PAYROLL	BENEFITS	000010	AUTHORIZED	01-02-17	10:29:12	TSI0373
PAYROLL	BENEFITS	000011	AUTHORIZED	01-02-20	09:57:56	TSI0373
PAYROLL	BENEFITS	000014	AUTHORIZED	01-02-17	10:28:05	TSI0373
PAYROLL	BENEFITS	000015	TESTING	01-02-01	09:23:38	TSI0373
PAYROLL	BENEFITS	000016	AUTHORIZED	01-02-15	15:31:15	TSI0373
PAYROLL	BENEFITS	000017	AUTHORIZED	01-02-24	11:00:18	TSI0373
PAYROLL	BENEFITS	000018	AUTHORIZED	01-01-21	11:56:11	TSI0373
PAYROLL	BENEFITS	000020	AUTHORIZED	01-01-23	14:09:40	TSI0373
PAYROLL	BENEFITS	000022	AUTHORIZED	01-01-06	16:57:38	TSI0373
PAYROLL	BENEFITS	000023	AUTHORIZED	01-01-17	10:28:15	TSI0373
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---						
----- END ----- DESC ----- STOP						

The User Status report displays all tasks that reference the User-ID. The PF5 key toggles between the short description of the task and the Update Date, Update Time, and Update User-ID fields of the task.

Field	Description
PROJECT (supplied)	The name of the project.
TASK GROUP (supplied)	The group that identifies a task.
TASK NUMBER (supplied)	The number that identifies a task.
STAGE (supplied)	The current stage of the task.
UPDATE DATE (supplied)	The date the task was updated.
UPDATE TIME (supplied)	The time the task was updated.
UPDATE USER-ID (supplied)	The User-ID that updated the task to the specified stage.

III.6.5 Events Related to a Task

Events Related to a Task provides a list of all Events that reference a particular task.

To access the Events Related to a Task function, enter "E" on the Project Tracking Reports menu.

01-12-31 11:38:00	N-2-O PROJECT TRACKING REPORTS EVENTS RELATED TO A TASK	TSI0373 TSI1
<p>Task Group : _____</p> <p>Task Number : _____</p> <p>Mode : 0</p>		
<p>Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---</p> <p>HELP ---- END ----</p>		

Field	Description
TASK GROUP (required)	The group that identifies a task.
TASK NUMBER (required)	The number that uniquely identifies a task.
MODE (required)	Indicates how the job is executed (batch or on-line). <ul style="list-style-type: none"> O Submits JCL to the internal reader that processes the function in batch. B Processes the function on-line. (Default: O)

To display the Events Related to a Task report screen, enter a task group and task number on the previous screen.

01-12-31				N-2-0 PROJECT TRACKING REPORTS			TSI0373
11:38:00				EVENTS RELATED TO TASK			TSI1
		Task Group :	PAY330E	Task Number:	1	Page:	1
		Short Desc :	ENHANCE REPORTING SUBSYSTEM				
Event	Seq	Date	Added Time	User-ID	Date	Closed Time	User-ID
PAYOUT	171	01-02-21	10:25:02	TSI006	01-02-21	10:25:43	TSI004
PAYOUT	220	01-03-23	07:28:39	TSI006	01-03-23	07:29:07	TSI004
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---							
----- END ----- STOP							

The Events Related to a Task report shows all Events that were related to the task when they were added. This report helps to track program migrations within a project area.

Field	Description
TASK GROUP (supplied)	The group that identifies a task.
TASK NUMBER (supplied)	The number that identifies a task.
SHORT DESC (supplied)	A 30-character description of the task.
EVENT (supplied)	The name of the Event.
SEQ (supplied)	The sequence number of the Event.
ADDED DATE (supplied)	The date the Event was added.
ADDED TIME (supplied)	The time the Event was added.
ADDED USER-ID (supplied)	The User-ID that added the Event.
CLOSED DATE (supplied)	The date the Event was closed.
CLOSED TIME (supplied)	The time the Event was closed.
CLOSED USER-ID (supplied)	The User-ID that closed the Event.

III.6.6 Suggestion Details

Suggestion Details provides detailed information about each suggestion within a project.

To access the Suggestion Details function, enter "F" on the Project Tracking Reports.

01-12-31 11:38:00	N-2-O PROJECT TRACKING REPORTS SUGGESTION DETAILS	TSI0373 TSI1
<p>Project : _____</p> <p>Suggestion: _____</p> <p>Status : _____</p> <p>Mode : O</p>		
<p>Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---</p> <p>HELP ---- END ----</p>		

Field	Description
∞ PROJECT (required)	The name of the project.
SUGGESTION (optional)	The number of the suggestion to be displayed.
STATUS (optional)	Limits the report to suggestions with the specified status.
MODE (required)	Indicates how the job is executed (batch or on-line).
	O Submits JCL to the internal reader that processes the function in batch.
	B Processes the function on-line. (Default: O)

∞ indicates field-level help is available.

To display the Suggestion Details report screen, enter a project on the previous screen.

01-12-31 11:38:00	N-2-O PROJECT TRACKING REPORTS SUGGESTION DETAILS Project: PAYROLL			TSI0373 TSI1 Page: 1
X	Suggestion	Short Description	Status	Request Date
-	1	SEPARATE AUTOCOMPILE STEP	OPEN	01-02-10
-	2	LIMIT AUTOCOMP TO SINGLE USER	OPEN	01-02-10
-	3	USER-DEFINED PF-KEYS	OPEN	01-02-10
-	4	DISABLE USE OF CLEAR KEY	ACCEPTED	01-02-10
-	5	SELECT OBJECTS BY DATE/TIME	OPEN	01-02-10
-	6	STARTING OBJECT FOR ALL TYPES	OPEN	01-02-10
-	7	SELECTION BY OBJECT TYPE	OPEN	01-02-10
-	8	SELECTION BY LIFO OR FIFO	OPEN	01-02-10
-	9	NEW STATUS CODES	OPEN	01-02-10
-	10	EVENT TRIGGERED MIGRATIONS	OPEN	01-02-10
-	11	EXPAND COPYCODE IN VIEW	OPEN	01-02-10
-	12	ADD EDITOR FUNCTIONS TO VIEW	OPEN	01-02-10
-	13	ADD SCAN UTILITY TO TOOLBOX	OPEN	01-02-10
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---				
-----END-----STOP				

The Suggestion Details report shows the list of suggestions within the project.

Field	Description
PROJECT (supplied)	The name of the project.
X (optional)	Entering "X" next to a suggestion (or next to more than one suggestion) displays specific details about the suggestion.
SUGGESTION (supplied)	The number of the suggestion displayed.
SHORT DESCRIPTION (supplied)	A 30-character description of the suggestion.
STATUS (supplied)	The status assigned to the suggestion.
REQUEST DATE (supplied)	The date the suggestion was requested.

SECTION IV

REPORTING SUBSYSTEM

IV.1 Introduction

N2O maintains an audit trail of all migration activities. The Reporting Subsystem provides reports that display information retrieved from this audit trail. The Reporting Subsystem also provides reports that show relationships within the Environment Subsystem.

The Reporting Subsystem section presents topics in the following order:

- Environment Reporting
- Event Reporting
- Object Reporting
- Statistical Reporting
- Security Reporting

To access the Reporting Subsystem menu, enter "R" on the N2O Main menu or enter the direct command REP MENU or PF6 on any menu.

01-12-31 11:38:00	N-2-O MAIN MENU	TSI0373 TSI1																				
	<table> <tr> <th>Code</th> <th>Function</th> </tr> <tr> <td>-----</td> <td>-----</td> </tr> <tr> <td>E</td> <td>Environment Subsystem</td> </tr> <tr> <td>M</td> <td>Migration Subsystem</td> </tr> <tr> <td>P</td> <td>Project Tracking Subsystem</td> </tr> <tr> <td>R</td> <td>Reporting Subsystem</td> </tr> <tr> <td>T</td> <td>Toolbox Subsystem</td> </tr> <tr> <td>U</td> <td>User-Defined Subsystem</td> </tr> <tr> <td>.</td> <td>Terminate N-2-O Session</td> </tr> <tr> <td>----</td> <td>-----</td> </tr> </table>	Code	Function	-----	-----	E	Environment Subsystem	M	Migration Subsystem	P	Project Tracking Subsystem	R	Reporting Subsystem	T	Toolbox Subsystem	U	User-Defined Subsystem	.	Terminate N-2-O Session	----	-----	
Code	Function																					
-----	-----																					
E	Environment Subsystem																					
M	Migration Subsystem																					
P	Project Tracking Subsystem																					
R	Reporting Subsystem																					
T	Toolbox Subsystem																					
U	User-Defined Subsystem																					
.	Terminate N-2-O Session																					
----	-----																					
	Enter Code: _																					
Direct Command: _____		N2O MENU																				
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---																						
HELP ---- END ENV MIG REP TOL USR PRJ ---- ---- EXIT																						

After following the instructions on the previous page, the Reporting Subsystem menu is displayed.

```

01-12-31          N-2-O REPORTING SUBSYSTEM MENU          TSI0373
11:38:00                                     TSI1

          Code      Function
-----
          A      Environment Reporting
          B      Event Reporting
          C      Object Reporting
          D      Statistical Reporting
          E      Security Reporting
          .      Terminate Reporting Subsystem
          -----

Enter Code:  _

Direct Command:                                     REP MENU
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
HELP  ----  END  ENV  MIG  ----  TOL  USR  PRJ  ----  ----  EXIT

```

Field	Description
ENTER CODE (required)	<p>The function to be executed. Valid values are as follows:</p> <p>A Environment Reporting Provides reports that display relationships within the Environment Subsystem.</p> <p>B Event Reporting Provides reports that display information about Events.</p> <p>C Object Reporting Provides reports that display information about objects.</p> <p>D Statistical Reporting Provides reports that display numerical data for Events and objects.</p> <p>E Security Reporting Provides reports that detail the N2O Security definitions.</p>

Note: Pressing PF12 (STOP) exits a report and returns to the previous data entry screen. Pressing PF3 (END) exits a report and returns to the menu from which the report was accessed.

IV.2 Environment Reporting

Environment Reporting provides reports that display relationships within the Environment Subsystem.

To display the Environment Reporting menu, enter "A" on the Reporting Subsystem menu or enter the direct command REP ENV on any menu.

```

01-12-31          N-2-O ENVIRONMENT REPORTING MENU          TSI0373
11:38:00                                         TSI1

Code  Function
----  -
A     Authorized Users to an Environment
B     Node Definition Usage
C     Archive Definition Usage
D     Environment Definition Usage
E     Users Related to a Group-ID
.     Terminate Environment Reporting
----  -

Enter Code:  _

Direct Command:  REP ENV
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
HELP  ----  END  ENV  MIG  REP  TOL  USR  PRJ  ----  ----  EXIT

```

Field	Description
ENTER CODE (required)	<p>The function to be executed. Valid values are as follows:</p> <p>A Authorized Users to an Environment Displays users who are authorized to migrate objects to an environment.</p> <p>B Node Definition Usage Displays Environment Definitions and Archive Definitions that reference a Node Definition.</p> <p>C Archive Definition Usage Displays Environment Definitions that reference an Archive Definition.</p> <p>D Environment Definition Usage Displays Migration Profiles that reference an Environment Definition or an Archive Definition.</p> <p>E Users Related to a Group-ID Displays users that are assigned a Group-ID.</p>

IV.2.1 Authorized Users to an Environment

The Authorized Users to an Environment report displays users who are authorized to migrate objects to an Environment. This information is based on the Approval profiles, PREDICT profiles, and 3GL/OTHER profiles assigned to users in N2O Security. This report is not available for sites using the SECURITRE interface.

To display the Authorized Users to an Environment input screen, enter "A" on the Environment Reporting menu.

```

Enter the Target Environment
01-12-31      N-2-O ENVIRONMENT REPORTING      TSI0373
11:38:00      AUTHORIZED USERS TO AN ENVIRONMENT  TSI1

                               Env Def      : _____
                               Library       : _____
                               Detailed Report: N (Batch Only)
                               Mode         : O

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
HELP  ----  END   ----  ----  ----  ----  ----  ----  ----  ----  ----  ----

```

Field	Description
∞ ENV DEF (required)	An environment defined by the N2O Administrator.
LIBRARY (optional)	Limits the report to NATURAL and SYSERR target environments only.
DETAILED REPORT (required)	Indicates whether detailed information should be displayed when executed in batch. Y Display all detail information for reports when executed in batch (similar to entering X next to a User-ID on-line). N Display information as the online summary report screen. (Default: N)
MODE (required)	Indicates how the job is executed (batch or on-line). B Submits JCL to the internal reader that processes the function in batch. O Processes the function on-line. (Default: O)

∞ indicates field-level help is available.

Entering the necessary information in the input screen and pressing Enter displays the Authorized Users to an Environment Selection screen.

```

Type X to view User Definition
01-12-31      N-2-O PROFILE REPORT      TSI0373
11:38:00      APPROVAL PROFILE - ALL-APPR  TSI1
                                           Page: 1

      X  User-ID  Description
      -  -
      -  TSI0371  DBA
      -  TSI0372  PROJECT LEADER
      -  TSI0373  DEVELOPER

                                           5 Users assigned this profile
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      ----  END  ----  ----  ----  ----  ----  ----  ----  ----  ----  STOP

```

The Profile Report identifies profiles that enable users to migrate objects to an Environment, as well as the users assigned to those profiles. Selecting one or more users displays the User Definition(s) of the selected user(s).

Field	Description
X (optional)	"X" in the select field displays the User Definition of the User-ID.
USER-ID (supplied)	The User-ID of the user assigned to the profile.
DESCRIPTION (supplied)	A description of the User-ID.

IV.2.2 Node Definition Usage

The Node Definition Usage report displays Environment Definitions and Archive Definitions that reference a Node Definition.

To display the Node Definition Usage input screen, enter "B" on the Environment Reporting menu.

01-12-31 11:38:00	N-2-O ENVIRONMENT REPORTING NODE DEFINITION USAGE	TSI0373 TSI1
Node: _____		
Mode: O		
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12--- HELP ---- END ----		

Field	Description
∞ NODE (required)	A node defined by the N2O Administrator.
MODE (required)	Indicates how the job is executed (batch or on-line).
	B Submits JCL to the internal reader that processes the function in batch.
	O Processes the function on-line. (Default: O)

∞ indicates field-level help is available.

Entering the necessary information in the input screen and pressing Enter displays the Node Definition Usage report.

```
Press Enter to continue
01-12-31      N-2-O ENVIRONMENT REPORTING      TSI0373
11:38:00      NODE DEFINITION USAGE           TSI1
Node:  CPUL                                     Page:  1

Arch Def ARC1      Env Def DEV      Env Def PROD
ENV Def TEST

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
----- END ----- STOP
```

Field	Description
NODE (supplied)	A node defined by the N2O Administrator.
ARCH DEF (supplied)	An Archive Environment defined by the N2O Administrator.
ENV DEF (supplied)	An Environment defined by the N2O Administrator.

IV.2.3 Archive Definition Usage

The Archive Definition Usage report displays Environment Definitions that reference an Archive Definition.

To display the Archive Definition Usage input screen, enter "C" on the Environment Reporting menu.

01-12-31 11:38:00	N-2-O ENVIRONMENT REPORTING ARCHIVE DEFINITION USAGE	TSI0373 TSI1
Arch Def: _____		
Mode : O		
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12--- HELP ---- END ----		

Field	Description
∞ ARCH DEF (required)	An Archive Environment defined by the N2O Administrator.
MODE (required)	Indicates how the job is executed (batch or on-line).
	B Submits JCL to the internal reader that processes the function in batch.
	O Processes the function on-line. (Default: O)

∞ indicates field-level help is available.

Entering the necessary information in the input screen and pressing Enter displays the Archive Definition Usage report.

Press Enter to continue

01-12-31

11:38:00

N-2-O ENVIRONMENT REPORTING

ARCHIVE DEFINITION USAGE

Arch Def: ARC1

TSI0373

TSI1

Page: 1

Env Def

Env Def

Env Def

PROD

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---

-----END-----STOP

Field	Description
∞ ARCHIVE DEF (supplied)	An Archive Environment defined by the N2O Administrator.
ENV DEF (supplied)	An Environment defined by the N2O Administrator.
∞ indicates field-level help is available.	

IV.2.4 Environment Definition Usage

The Environment Definition Usage report displays Migration Profiles that reference an Environment Definition or an Archive Definition.

To display the Environment Definition Usage input screen, enter "D" on the Environment Reporting menu.

01-12-31 11:38:00	N-2-O ENVIRONMENT REPORTING ENVIRONMENT DEFINITION USAGE	TSI0373 TSI1
<p>Env Def: _____</p> <p>Mode : 0</p>		
<p>Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---</p> <p>HELP ---- END ----</p>		

Field	Description
∞ ENV DEF (required)	An Environment defined by the N2O Administrator.
MODE (required)	Indicates how the job is executed (batch or on-line).
	B Submits JCL to the internal reader that processes the function in batch.
	O Processes the function on-line. (Default: O)

∞ indicates field-level help is available.

Entering the necessary information in the input screen and pressing Enter displays the Environment Definition Usage report.

```

Press Enter to continue
01-12-31      N-2-O ENVIRONMENT REPORTING      TSI0373
11:38:00      ENVIRONMENT DEFINITION USAGE      TSI1
              Env Def: DEV                      Page: 1

      Migration Profile      Migration Profile      Migration Profile
      -----      -----      -----
      RC1 DEV      DEV DEV      DEV TEST
      PROD DEV      TEST DEV

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      END                      STOP
  
```

Field	Description
ENV DEF (supplied)	An Environment defined by the N2O Administrator.
MIGRATION PROFILE (supplied)	A Migration Profile defined by the N2O Administrator.

IV.2.5 Users Related to a Group-ID

The Users Related to a Group-ID report displays users that are assigned a Group-ID.

To display the Users Related to a Group-ID input screen, enter "E" on the Environment Reporting menu.

01-12-31 11:38:00	N-2-O ENVIRONMENT REPORTING USERS RELATED TO A GROUP-ID	TSI0373 TSI1
<p>Group-ID: _____</p> <p>Mode : O</p>		
<p>Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---</p> <p>HELP ---- END ----</p>		

Field	Description
GROUP-ID (required)	A Group-ID defined by the N2O Administrator.
MODE (required)	Indicates how the job is executed (batch or on-line).
	B Submits JCL to the internal reader that processes the function in batch.
	O Processes the function on-line. (Default: O)

Entering the necessary information in the input screen and pressing Enter displays the Users Related to a Group-ID report.

```
Press Enter to continue
01-12-31      N-2-O ENVIRONMENT REPORTING      TSI0373
11:38:00      USERS RELATED TO A GROUP-ID      TSI1
              Group-ID:  PAY                      Page:  1

              User-ID      User-ID      User-ID
              -----      -----      -----
              TSI0373      TSI0374      TSI0375

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
-----      END      -----      -----      -----      -----      STOP
```

Field	Description
GROUP-ID (supplied)	A Group-ID defined by the N2O Administrator.
USER-ID (supplied)	The users related to the Group-ID.

IV.2.6 Environment Reporting in Batch

Sample reporting JCL is provided in the MVSREPT, VMREPT, BSREPT and VSEREPT members located in the Natural library N2OBATCH.

The following table illustrates the JCL and EXECs modifications necessary to execute Environment reports in batch.

REPORT	&REPORT	&INPUT
Authorized Users to an Environment	N2OENVA	ENV-DEF,LIBRARY,DETAILED-REPORT
Node Definition Usage	N2OENVB	NODE
Archive Definition Usage	N2OENVC	ARCH DEF
Environment Definition Usage	N2OENVD	ENV DEF or ARCH DEF
Users Related to a Group-ID	N2OENVE	GROUP-ID

The &INPUT parameter list by default is delimited by commas with no spaces following the commas. To override the default delimiter, modify the value of the jcl-delimiter field in User-Exit-22 (N2OUE22N).

For descriptions of &INPUT fields, refer to field descriptions in corresponding sections of Environment Reporting.

Note: The batch reports from the N2O Reporting Subsystem and the Documentation Tools require that the NATURAL Parameter IM (Input Mode) be set to "IM=D" (Delimiter Mode).

IV.3 Event Reporting

Event Reporting provides reports that display information about Events. Each report allows users to view a list of Events based on specific requirements.

To display the Event Reporting menu, enter "B" on the Reporting Subsystem menu or enter the direct command REP EVNT on any menu.

```

01-12-31          N-2-O EVENT REPORTING MENU          TSI0373
11:38:00                                     TSI1

Code  Function
-----
A    Events Requiring Further Authorization
B    Chronology of Events
C    Events Related by Change Control
D    Event Details
E    Events Processed by Date
F    Events with Warning Messages
G    Events Pending Move
H    Events Pending Autocompile
I    Autocompile Summary for Events
.    Terminate Event Reporting
-----

Enter Code:  _

Direct Command:                                     REP EVNT
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      HELP  ----  END  ENV  MIG  REP  TOL  USR  PRJ  ----  ----  EXIT

```

Field	Description
ENTER CODE (required)	The function to be executed. Valid values are as follows:
A	Events Requiring Further Authorization Displays Events that require authorization or servicing.
B	Chronology of Events Displays the history of Events.
C	Events Related by Change Control Displays Events associated with a change request.
D	Event Details Displays all Events created using N2O.
E	Events Processed by Date Displays Events migrated within a specified date range.
F	Events with Warning Messages Displays Events that received warning messages.
G	Events Pending Move Displays deferred move Events.

(continued from previous page)

Field	Description
H	Events Pending Autocompile Displays Events that contain programs to be compiled.
I	Autocompile Summary for Events Displays compile information about Events and programs.

IV.3.1 Events Requiring Further Authorization

The Events Requiring Further Authorization report displays Events that require authorization or servicing. This report displays the added Date/User-ID and authorized Date/User-ID of pending Events.

To display the Events Requiring Further Authorization input screen, enter "A" on the Event Reporting menu.

```

01-12-31          N-2-O EVENT REPORTING          TSI0373
11:38:00          EVENTS REQUIRING FURTHER AUTHORIZATION      TSI1

                Delay      :      _____
                Detailed Report:  N (Batch Only)
                Mode        :      O

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      HELP  ----  END   ----  ----  ----  ----  ----  ----  ----  ----  ----

```

Field	Description
DELAY (required)	Indicates whether Events require either Authorization or service. AUTH displays Events requiring Authorization. SERV displays Events requiring service.
DETAILED REPORT (required)	Indicates whether detailed information should be display when executed in batch. Y Display all detail information for reports when executed in batch (similar to entering E and O on the Events Requiring Further Authorization Selection screen.) N Display information similar to the Events Requiring Further Authorization screen. (Default: N)
MODE (required)	Indicates how the job is executed (batch or on-line). B Submits JCL to the internal reader that processes the function in batch. O Processes the function on-line. (Default: O)

Entering the necessary information in the input screen and pressing Enter displays the Events Requiring Further Authorization Selection screen.

Valid Values: A - Autocompile E - Event O - Object										
01-12-31		N-2-O EVENT REPORTING						TSIO373		
11:38:00		EVENTS REQUIRING FURTHER AUTHORIZATION						TSI1		
Delay: SERV						Page: 1				
S	Event	Seq	Change Control	From Env	To Env	Event Type	----- Added Date	----- User-ID	--- Authorized Date	--- User-ID

-	PAYIN	1	E125	TEST	PROD	N	01-12-31	TSIO373	01-12-31	TSIO373
-	PAYIN	2	E039	TEST	PROD	N	01-06-01	TSIO373	01-12-31	TSIO424
-	PAYIN	3	B127	TEST	PROD	N	01-06-01	TSIO373	01-12-31	TSIO373
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---										
-----			END			-----			STOP	

Field	Description
DELAY (supplied)	The value specified to execute this report.
S (optional)	The function to be executed. Valid values are as follows: A displays autocompile details (if available) E displays Event details. O displays object details.
EVENT (supplied)	The Master Event of the migration.
SEQ (supplied)	The sequence number of the Event.
CHANGE CONTROL (supplied)	A value that relates multiple Events to a specific change request.
FROM ENV (supplied)	The source Environment Definition of the Event.
TO ENV (supplied)	The target Environment Definition of the Event. An asterisk (*) indicates the Event is a multiple target Event.
EVENT TYPE (supplied)	The types of objects requested for the Event. Valid values are as follows: N Indicates NATURAL. S Indicates SYSERR. P Indicates PREDICT. O Indicates 3GL/OTHER. D Indicates DDM. M Indicates METADATA.

(continued from previous page)

Field	Description
ADDED DATE (supplied)	The date the Event was added.
ADDED USER-ID (supplied)	The user who added the Event.
AUTHORIZED DATE (supplied)	The date the Event was last authorized.
AUTHORIZED USER-ID (supplied)	The user who last authorized the Event.

IV.3.2 Chronology of Events

The Chronology of Events report displays the history of Events. This report displays the dates and times Events were added, authorized, and closed.

To display the Chronology of Events input screen, enter "B" on the Event Reporting menu.

01-12-31 11:38:00	N-2-O ADMINISTRATIVE REPORTING CHRONOLOGY OF EVENTS	TSI0373 TSI1
<p>Event : _____</p> <p>Sequence : _____</p> <p>Date : ____ - ____ - ____ (YYYY-MM-DD)</p> <p>Detailed Report: N (Batch Only)</p> <p>Mode : 0</p>		
<p>Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---</p> <p>HELP ---- END ----</p>		

Field	Description
∞ EVENT (optional)	A Master Event that identifies the starting value of the report.
SEQUENCE (optional)	The sequence number of the Event.
DETAILED REPORT (required)	Indicates whether detailed information should be displayed when executed in batch.
	Y Display all detail information for reports when executed in batch. (Similar to entering E and O next to an Event on the Chronology of Events selection screen.)
	N Display information similar to the Chronology of Events selection screen. (Default: N)
DATE (optional)	Date the Event(s) were run.
MODE (required)	Indicates how the job is executed (batch or on-line).
	B Submits JCL to the internal reader that processes the function in batch.
	O Processes the function on-line. (Default: O)

∞ indicates field-level help is available.

Entering the necessary information in the input screen and pressing Enter displays the Chronology of Events selection screen.

Valid Values: A - Autocompile E - Event O - Object							
01-12-31				N-2-O EVENT REPORTING			
11:38:00				CHRONOLOGY OF EVENTS			
						TSI0373	
						TSI1	
						Page: 1	
S	Event	Seq	Added Date	Added Time	Authorized Date	Authorized Time	Closed Date
-	-----	----	-----	-----	-----	-----	-----
-	PAYOUT	1	01-12-14	13:40:17	01-12-14	13:47:14	01-12-14 13:47:22
-	PAYOUT	2	01-12-22	13:05:08	01-12-22	13:10:22	01-12-22 13:10:27
-	PAYOUT	3	01-12-19	10:41:08	01-12-19	10:42:17	01-12-19 10:42:42
-	PAYOUT	4	01-12-21	15:40:46	01-12-21	15:46:19	*****
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---							
----- END ----- STOP							

Field	Description
S (optional)	The function to be executed. Valid values are as follows: A displays autocompile details (if available) E displays Event details. O displays object details.
EVENT (supplied)	The Master Event of the migration.
SEQ (supplied)	The sequence number of the Event.
ADDED DATE (supplied)	The date the Event was added.
ADDED TIME (supplied)	The time the Event was added.
AUTHORIZED DATE (supplied)	The date the Event was last authorized. Asterisks in the Authorized Date field represent Events without authorization.
AUTHORIZED TIME (supplied)	The time the Event was last authorized. Asterisks in the Authorized Time field represent Events without authorization.
CLOSED DATE (supplied)	The date the Event was closed. Asterisks in the Closed Date field represent Events pending migration.
CLOSED TIME (supplied)	The time the Event was closed. Asterisks in the Closed Time field represent Events pending migration.

IV.3.3 Events Related by Change Control

The Events Related by Change Control report displays Events associated with a change request. A Change Control value relates multiple Events to a single change request throughout the application life cycle.

To display the Events Related by Change Control input screen, enter "C" on the Event Reporting menu.

01-12-31 11:38:00	N-2-O EVENT REPORTING EVENTS RELATED BY CHANGE CONTROL	TSI0373 TSI1
<p>Change Control : _____</p> <p>Added User-ID : _____</p> <p>Date Range : _____ - _____</p> <p>Detailed Report: N (Batch Only)</p> <p>Mode : 0</p>		
<p>Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---</p> <p>HELP ---- END ----</p>		

Field	Description
CHANGE CONTROL (optional)	Limits the report to Events with the specified Change Control value.
∞ ADDED USER-ID (optional)	Limits the report to Events added by the user with the specified User-ID.
DATE RANGE (optional)	Limits the report to Events migrated within the range of dates. Dates must be formatted YYYYMMDD.
DETAILED REPORT (required)	Indicates whether detailed information should be displayed when executed in batch.
	Y Display all detail information for reports when executed in batch (similar to entering E and O next to an Event on the Events Related by Change Control selection screen).
	N Display information similar to the Events Related by Change Control selection screen. (Default: N)
MODE (required)	Indicates how the job is executed (batch or on-line).
	B Submits JCL to the internal reader that processes the function in batch.
	O Processes the function on-line. (Default: O)

∞ indicates field-level help is available.

Entering the necessary information in the input screen and pressing Enter displays the Events Related by Change Control selection screen.

Valid Values: A - Autocompile E - Event O - Object											
01-12-31			N-2-O EVENT REPORTING						TSI0373		
11:38:00			EVENTS RELATED BY CHANGE CONTROL						TSI1		
										Page:	1
Change			From To		Event		-----		Closed	-----	
-											
S	Control	Event	Seq	Env	Env	Type	Extr	Date	Time	User-ID	
-	-----	-----	----	----	----	-----	----	-----	-----	-----	
-											
-	A12345	PAYOUT	1	PROD	DEV	N	NO	01-10-01	11:34:55	TSIO373	
-	A12345	PAYTEST	2	DEV	TEST	N	NO	01-10-05	08:43:21	TSIO373	
-	A12345	PAYIN	1	TEST	PROD	N	NO	*****	*****	*****	
-											
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---											
----- END ----- STOP											

Field	Description
S (optional)	The function to be executed. Valid values are as follows: A displays autocompile details (if available) E displays Event details. O displays object details.
CHANGE CONTROL (supplied)	A value that relates multiple Events to a specific change request.
EVENT (supplied)	The Master Event of the migration.
SEQ (supplied)	The sequence number of the Event.
FROM ENV (supplied)	The source Environment Definition of the Event.
TO ENV (supplied)	The target Environment Definition of the Event. An asterisk (*) indicates the Event is a multiple target Event.
EVENT TYPE (supplied)	The types of objects requested for the Event. Valid values are as follows: N Indicates NATURAL. S Indicates SYSERR. P Indicates PREDICT. O Indicates 3GL/OTHER. D Indicates DDM. M Indicates METADATA.

(continued from previous page)

Field	Description
EXTR (supplied)	Indicates whether the Event is an Extract Event or not. YES Indicates the Event is an Extract Event. NO Indicates the Event is not an Extract Event.
CLOSED DATE (supplied)	The date the Event was closed. Asterisks in the Closed Date field represent Events pending migration.
CLOSED TIME (supplied)	The time the Event was closed. Asterisks in the Closed Time field represent Events pending migration.
CLOSED USER_ID (supplied)	The user who closed the Event. Asterisks in the Closed User-ID field represent Events pending migration.

IV.3.4 Event Details

The Event Details report displays all Events created using N2O. The optional fields displayed below can limit the list of Events.

To display the Event Details input screen, enter "D" on the Event Reporting menu.

01-12-31 11:38:00	N-2-O EVENT REPORTING EVENT DETAILS	TSI0373 TSI1
<div> <div>Name</div> <div>Seq.</div> <div>-----</div> <div>-----</div> </div>		
Starting Event : _____ (Wildcard/Single)		
Ending Event : _____ (Both Blank=All)		
From Env. : _____		
To Env : _____		
Added User-ID : _____		
Event Status : _____		
DB2 Status : _____		
Detailed Report: N (Batch Only)		
Mode : O		
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12--- HELP ---- END ----		

Field	Description
∞ STARTING EVENT (optional)	A Master Event that identifies the starting value of the report. Partial names and wildcards (e.g., AAP*) may be entered.
STARTING SEQUENCE (optional)	The starting sequence number of the Event entered in Starting Event. If this field is left blank, all Event Sequences ranging from 1 to the number entered in Ending Event Sequence for the Event will be reported.
∞ ENDING EVENT (optional)	A Master Event that identifies the ending value of the report. Wildcards (e.g., AAP9*) may be entered. To report on a single Event, leave this field, Starting Event Sequence and Ending Event Sequence blank and enter the Master Event in the Starting Event field.
ENDING SEQUENCE (optional)	The ending sequence number of the Event entered in Ending Event. To report on a single Event/Sequence, leave the Ending Event and this field blank, enter the Event in the Starting Event field and enter the Event Sequence in the Starting Event Sequence field.
∞ FROM ENV (optional)	Limits the report to Events with the specified From Environment Definition.
∞ indicates field-level help is available.	

(continued from previous page)

Field	Description
∞ TO ENV (optional)	Limits the report to Events with the specified To Environment Definition.
∞ ADDED USER-ID (optional)	Limits the report to Events that were added by the User with the specified User-ID.
EVENT STATUS (optional)	Limits the report to Events with the specified Event status. For valid values refer to Appendix B N20 Event Status.
DB2 STATUS (optional)	Limits the report to Events with the specified DB2 Status. Valid values are as follows: D Indicates DBRM Ready. P Indicates Plan Ready. S Indicates Static. C Indicates Canceled.
DETAILED REPORT (required)	Indicates whether detailed information should be displayed when executed in batch. Y Display all detail information for reports when executed in batch (similar to entering E and O next to an Event on the Event Details Selection screen). N Display information similar to the Event Details Selection screen (Default: N).
MODE (required)	Indicates how the job is executed (batch or on-line). B Submits JCL to the internal reader that processes the function in batch. O Processes the function on-line. (Default: O)

∞ indicates field-level help is available.

Entering the necessary information in the input screen and pressing Enter displays the Event Details selection screen.

Valid Values: A - Autocompile E - Event O - Object										
01-12-31			N-2-O EVENT REPORTING						TSIO373	
11:38:00			EVENT DETAILS						TSI1	
								Page: 1		
S	Event	Seq	Change Control	From Env	To Env	Event Type	Extr	Added User-ID	Event Status	Warning
-										
-	PAYOUT	1	*****	PROD	DEV	N	NO	TSIO373	O	*****
-	PAYOUT	2	E20000	PROD	DEV	N	NO	TSIO373	C	*****
-	PAYOUT	3	*****	PROD	DEV	N	NO	TSIO373	O	*****
-	PAYOUT	4	*****	PROD	DEV	N	NO	TSIO373	O	*****
-	PAYOUT	6	*****	DEV	TEST	N	NO	TSIO373	O	*****
-	PAYTEST	1	E065	DEV	TEST	N	NO	TSIO373	C	*****
-	PAYTEST	2	HELP	DEV	TEST	N	NO	TSIO373	O	*****
-	PAYTEST	3	E129	TEST	*	N	NO	TSIO373	O	*****
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---										
			END	DB2						
										STOP

Pressing PF5 will toggle the output between Event Status and DB2 Status.

Field	Description
S (optional)	The function to be executed. Valid values are as follows: A displays autocompile details (if available) E displays Event details. O displays object details.
EVENT (supplied)	The Master Event of the migration.
SEQ (supplied)	The sequence number of the Event.
CHANGE CONTROL (supplied)	A value that relates multiple Events to a specific change request. An asterisk (*) indicates that Change Control was not required.
FROM ENV (supplied)	The source Environment Definition of the Event.
TO ENV (supplied)	The target Environment Definition of the Event. An asterisk (*) indicates that the Event is a multiple target Event.
EVENT TYPE (supplied)	The types of objects requested for the Event. Valid values are as follows: N Indicates NATURAL. S Indicates SYSERR. P Indicates PREDICT. O Indicates 3GL/OTHER. D Indicates DDM. M Indicates METADATA.

(continued from previous page)

Field	Description
EXTR (supplied)	Indicates whether the Event is an Extract Event or not. YES Indicates the Event is an Extract Event. NO Indicates the Event is not an Extract Event.
ADDED USER-ID (supplied)	The user who added the Event.
EVENT STATUS (supplied)	The status of the Event. For valid values refer to Appendix B N2O Event Status.
WARNING (supplied)	Events may contain one of the following warning messages: OVERRIDE Indicates the Event migrated to an environment without proper authorization. AC-ERROR Indicates programs within the Event received compile errors during the Autocompile process. RECOVERD Indicates programs within the Event received compile errors and the Event was automatically recovered.
DB2 STATUS (supplied)	The status of the DB2 processing of the Event. Valid values are as follows: D Indicates DBRM Ready. P Indicates Plan Ready. S Indicates Static. C Indicates Canceled.

Entering "E" in the S field on the previous screen and pressing Enter displays the Event Details screen.

```

Press ENTER to continue
01-12-31      N-2-O EVENT DETAILS      TSI0373
11:38:00      Event: PAYOUT Sequence: 1  TSI1
                EXTRACT EVENT

      From Env      : PROD      From Library : PAYPROD
      To Env        : DEV        To Library   : PAYDEV
      Event Status   : O

C _____
o _____
m _____
m _____
e _____
n _____
t _____
s _____

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
----- END ----- STOP

```

Field	Description
EVENT (supplied)	The Master Event of the migration.
SEQUENCE (supplied)	The sequence number of the Event.
FROM ENV (supplied)	The source Environment Definition of the Event.
FROM LIBRARY (supplied)	The source library of the migration for NATURAL objects and/or SYSERR messages.
TO ENV (supplied)	The target Environment Definition of the Event. An asterisk (*) indicates that the Event is a multiple target Event.
TO LIBRARY (supplied)	The target library of the migration for NATURAL objects and/or SYSERR messages.
EVENT STATUS (supplied)	The Status of the Event. For valid values refer to Appendix B N2O Event Status .
COMMENTS (supplied)	A 10-line comment area describing the Event.

To display further Event information, press Enter on the Event Details screen.

```

Press ENTER to continue
01-12-31      N-2-O EVENT DETAILS      TSI0373
11:38:00      Event: PAYOUT      Sequence: 1      TSI013
              Warning: AC-ERROR

              Added      : 01-03-13 09:15:17 TREE04
              Modified   : ***** ***** *****
              Authorized  : ***** ***** *****
              Closed      : 01-03-16 14:18:07 BATCH03
              Autocompiled : 01-03-16 14:18:07 BATCH03
              DBRM Generated: ***** ***** *****
              Plan Bind   : ***** ***** *****

              Migration Options
              -----

              Event Type : N      Delay      : NONE
              Verify Object: NO    Levels of Auth : 0
              Migrate XREF : N      Migration Method : COPY
              Program Doc : NO     Deferred Time : 0 hrs.

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12--
_
      END
STOP

```

Field	Description
EVENT (supplied)	The Master Event of the migration.
SEQUENCE (supplied)	The sequence number of the Event.
WARNING (supplied)	Events may contain one of the following warning messages (does not appear if Event has no warnings): <ul style="list-style-type: none"> OVERVERRIDE Indicates the Event migrated to an environment without proper authorization. AC-ERROR Indicates programs within the Event received compile errors during the Autocompile process. RECOVERD Indicates programs within the Event received compile errors and the Event was automatically recovered.
ADDED (supplied)	Lists the User-ID of the user who added the Event and the date and time that action occurred.
MODIFIED (supplied)	Lists the User-ID of the user who last modified the Event and the date and time that action occurred.
AUTHORIZED (supplied)	Lists the User-ID of the user who authorized the Event and the date and time that action occurred.
CLOSED (supplied)	Lists the User-ID of the user who closed the Event and the date and time that action occurred.
AUTOCOMPILED (supplied)	Lists the User-ID of the user who Autocompiled the Event and the date and time that action occurred.

(continued from previous page)

Field	Description
DBRM GENERATED (supplied)	Lists the User-ID of the user who generated a DBRM for the Event and the date and time that action occurred.
PLAN BIND (supplied)	Lists the User-ID of the user who last bound the DB2 plan for the Event and the date and time that action occurred.
EVENT TYPE (supplied)	Specifies the type of Event.
DELAY (supplied)	Indicates whether Events require either Authorization or service. NONE Indicates the migration may proceed immediately without authorization. AUTH Indicates the migration must be authorized through the Authorize Event menu. SERV Indicates the migration must be authorized through the Authorize Event menu and serviced through the Service Event menu.
VERIFY OBJECT (supplied)	Indicates whether NATURAL object code will be verified before the program migrates or not. YES Indicates NATURAL object code must exist for a program and that the timestamp of the object code must be greater than the timestamp of the source code or the program will be prevented from migrating. NO Indicates NATURAL object code will not be verified before the program migrates.
LEVELS OF AUTH (supplied)	The number of authorizations required when AUTH or SERV is specified in the delay field.
MIGRATE XREF (supplied)	Indicates whether PREDICT Cross-Reference data should be migrated or not. N Indicates the migration does not migrate PREDICT Cross-Reference data. S Indicates the migration should migrate all PREDICT Cross-Reference data whenever it exists. Y Indicates PREDICT Cross-Reference data must exist for a NATURAL object before the object may be selected for migration.

(continued from previous page)

Field	Description
MIGRATION METHOD (supplied)	Indicates whether the object will be deleted from the source after migration. COPY Indicates an object at the source of the migration will be placed at the target. MOVE Indicates an object at the source of the migration will be placed at the target and then deleted from the source of the migration.
PROGRAM DOC (supplied)	Indicates whether the existence of PREDICT program documentation is checked or not. N Indicates the existence of PREDICT program documentation is not checked for a NATURAL object migration. This is the default value. Y Indicates PREDICT program documentation must exist in the FROM ENV for a NATURAL object to migrate.
DEFERRED TIME (supplied)	Indicates the minimum number of hours between the migration process and the deletion process of a MOVE. This field must be 0 when COPY is specified for the Method field (Default: 0).

Entering "O" in the S field on the Event Details Selection screen and pressing Enter displays the Object Details for an Event screen.

01-12-31		N-2-O OBJECT DETAILS							TSI0373		
11:38:00		Event: PAYOUT Sequence: 1 Total Objects: 2							TSI1		
From Env: PROD		From Library: PAYPROD		To Env: DEV		To Library: PAYDEV					
X	Object	Type	Rn	X	Object	Type	Rn	X	Object	Type	Rn
--	-----	-----	--	--	-----	-----	--	--	-----	-----	--
--	A-TEST	SOURCE	--	--	A-TEST	ARC-SRC	--	--	A-TEST	ARC-OBJ	--
X	CPROG001	SOURCE	*	--	CPROG001	ARC-SRC	--	--	CPROG001	ARC-OBJ	--
--	CPROG002	SOURCE	--	--	CPROG002	ARC-SRC	--	--	CPROG002	ARC-OBJ	--
--	MENU	SOURCE	--	--	MENU	ARC-SRC	--	--	MENU	ARC-OBJ	--
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---											
-----										STOP	

Field	Description
EVENT (supplied)	The Master Event of the migration.
SEQUENCE (supplied)	The sequence number of the Event.
FROM ENV (supplied)	The source Environment Definition of the Event.
FROM LIBRARY (supplied)	The source library of the migration for NATURAL objects and/or SYSERR messages.
TO ENV (supplied)	The target Environment Definition for the Event.
TO LIBRARY (supplied)	The target library of the migration for NATURAL objects and/or SYSERR messages.
X (optional)	"X" in the Select field displays additional details about an object.
OBJECT (supplied)	The name of the NATURAL object, PREDICT object, 3GL/OTHER object, or SYSERR message.

(continued from previous page)

Field	Description
TYPE (supplied)	Valid values are as follows: ARC-EXT Indicates Archive expanded error message. ARC-OBJ Indicates Archive object. ARC-SHRT Indicates Archive short error message. ARC-SRC Indicates Archive source. EXT-MSG Indicates expanded error. OBJECT Indicates cataloged module. PURG-EXT Indicates purge expanded error message from Archive. PURG-OBJ Indicates purge object from Archive. PURG-SHT Indicates purge short error message from Archive. PURG-SRC Indicates purge source from Archive. SHORT Indicates short error message. SOURCE Indicates source module.
RN (Renamed) (supplied)	A '*' in this field indicates the object was renamed during an Extract Event. Valid for NATURAL Extract Events only.

Entering "X" in the select field on the Object Details for an Event screen and pressing Enter displays the Object Details report.

01-12-31 11:38:00	N-2-O OBJECT DETAILS		TSIO373 TSI1
Object : CPROG001	Date Saved: 01-02-01	Terminal-ID : TSIO373	
Type : Source	Time Saved: 11:38:25	NAT Version : 2.14	
Object Type: LOCAL	User-ID : TSIO373	XREF Migrated: NO	
Renamed To : LOCAL1A			
Event : E-TEST	Sequence : 25000		
From Env : TEST	From Library: PAYTEST		
To Env : ARC1	To Library : PAYPROD		
Added : 01-11-17	11:36:10	TSIO373	
Modified : *****	*****	*****	
Authorized : *****	*****	*****	
Closed : 01-11-17	11:37:50	TSIO373	
Autocompiled : *****	*****	*****	
Move Completed: *****	*****	*****	
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---			
HELP ---- END DISP ----			

Field	Description
OBJECT (supplied)	The name of the NATURAL object.
DATE SAVED (supplied)	The date the object was saved.
TERMINAL-ID (supplied)	The Terminal-ID used to save the object.
TYPE (supplied)	Valid values are as follows:
ARC-EXT	Indicates Archive expanded error message.
ARC-OBJ	Indicates Archive object.
ARC-SHRT	Indicates Archive short error message.
ARC-SRC	Indicates Archive source.
EXT-MSG	Indicates expanded error.
OBJECT	Indicates cataloged module.
PURG-EXT	Indicates purge expanded error message from Archive.
PURG-OBJ	Indicates purge object form Archive.
PURG-SHT	Indicates purge short error message from Archive.
PURG-SRC	Indicates purge source from Archive.
SHORT	Indicates short error message.
SOURCE	Indicates source module.

(continued from previous page)

Field	Description
TIME SAVED (supplied)	The time the object was saved.
NAT VERSION (supplied)	The NATURAL version under which the object was saved.
OBJECT TYPE (supplied)	The NATURAL object type.
	PARM Indicates Parameter data area. COPYCODE Indicates Copycode. GLOBAL Indicates Global data area. HELP-RTN Indicates Helproutine. LOCAL Indicates Local data area. MAP Indicates Map. SUB-PGM Indicates Subprogram. PROGRAM Indicates Program. SUB-RTN Indicates Subroutine. TEXT Indicates Text. MACRO Indicates Macro. REPORT Indicates Report. EXP-MDL Indicates ExpertModel. RECORD Indicates Recording. DIALOG Indicates Dialog. CLASS Indicates Class. CMD-PROC Indicates Processor. SERVER Indicates Server. FUNCTION. Indicates Function. ADAPTER. Indicates Adapter. MACRO. Indicates Macro.
USER-ID (supplied)	The User-ID of the user who saved the object.
XREF MIGRATED (supplied)	Indices whether the PREDICT XREF data migrated with the NATURAL object or not. YES Indicates PREDICT XREF data migrated with the NATURAL object. NO Indicates PREDICT XREF did not migrate with the NATURAL object.
RENAMED TO (supplied)	The new object name if the object was renamed in a NATURAL Extract Event.
EVENT (supplied)	The Master Event of the migration.
SEQUENCE (supplied)	The sequence number of the Event.
FROM ENV (supplied)	The source Environment Definition of the Event.
FROM LIBRARY (supplied)	The source library of the migration for NATURAL objects and/or SYSERR messages.
TO ENV (supplied)	The target Environment Definition of the Event. An asterisk (*) indicates the Event is a multiple target Event.

(continued from previous page)

Field	Description
TO LIBRARY (supplied)	The target library of the migration for NATURAL objects and/or SYSERR objects.
ADDED (supplied)	Lists the User-ID of the user who added the Event and the date and time that action occurred.
MODIFIED (supplied)	Lists the User-ID of the user who modified the Event and the date and time that action occurred.
AUTHORIZED (supplied)	Lists the User-ID of the user who authorized the Event and the date and time that action occurred.
CLOSED (supplied)	Lists the User-ID of the user who closed the Event and the date and time that action occurred.
AUTOCOMPILED (supplied)	Lists the User-ID of the user who Autocompiled the Event and the date and time that action occurred.
MOVE COMPLETED (supplied)	Lists the User-ID of the user who deleted objects from the source of the Event and the date and time that action occurred.

IV.3.5 Events Processed by Date

The Events Processed by Date report displays Events migrated within a specified date range.

Note that program N2OREPD will permit sites to execute a regularly scheduled batch job that will generate a report of all Events that processed on the previous day. N2OREPD will calculate yesterday's date and call N2OEVNTE (Events Processed by Date report), passing the calculated date. A site may customize N2OREPD to specify the detail level of the Events Processed by Date report. The default is to provide summary information. For details, refer to the program N2OREPD in the N2OLIB Library.

N2OREPD should be run in place of N2OEVNTE in a batch job.

To display the Events Processed by Date input screen, enter "E" on the Event Reporting menu.

01-12-31 11:38:00	N-2-O EVENT REPORTING EVENTS PROCESSED BY DATE	TSI0373 TSI1
<p>Event : _____</p> <p>Sequence : _____</p> <p>Date Range : _____ - _____</p> <p>Added User-ID : _____</p> <p>Detailed Report: N (Batch Only)</p> <p>Mode : O</p>		
<p>Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---</p> <p>HELP ---- END ----</p>		

Field	Description
EVENT (required)	The master Event of the migration.
SEQUENCE (optional)	The sequence number of the Event.
DATE RANGE (optional)	Limits the report to Events that migrated within the range of dates. Dates must be formatted YYYYMMDD.
ADDED USER-ID (optional)	Limits the report to Events added by a User-ID.
DETAILED REPORT (required)	Indicates whether detailed information should be display when executed in batch.
	Y Display all detail information for reports when executed in batch (similar to entering E and O next to an Event on the Events Processed by Date selection screen).
	N Display information similar to the Events Processed by Date selection screen. (Default: N)

(continued from previous page)

Field	Description
MODE (required)	Indicates how the job is executed (batch or on-line). B Submits JCL to the internal reader that processes the function in batch. O Processes the function on-line. (Default: O)

Entering the necessary information in the input screen and pressing Enter displays the Events Processed by Date selection screen.

01-12-31		N-2-O EVENT REPORTING							TSI0373	
11:38:00		EVENTS PROCESSED BY DATE							TSI1	
		Date Range 19991001 - 19991005							Page: 1	
S	Event	Seq	Change Control	From Env	To Env	Event Type	----- Date	Closed Time	----- User-ID	Warning
-	PAYOUT	30	A12345	PROD	DEV	N	01-10-01	11:34:55	TSI0373	*****
-	PAYOUT	38	A12345	PROD	DEV	N	01-10-03	12:14:16	TSI0373	*****
-	PAYTEST	45	A12345	DEV	TEST	N	01-10-05	08:43:21	TSI0373	*****
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---										
-----END-----STOP										

Field	Description
DATE RANGE (supplied)	Date range specified on previous screen.
S (optional)	The function to be executed. Valid values are as follows: A Displays autocompile details (if available) E Displays Event details. O Displays object details.
EVENT (supplied)	The Master Event of the migration.
SEQ (supplied)	The sequence number of the Event.
CHANGE CONTROL (supplied)	A value that relates multiple Events to a specific change request.
FROM ENV (supplied)	The source Environment Definition of the Event.
TO ENV (supplied)	The target Environment Definition of the Event. An asterisk (*) indicates the Event is a multiple target Event.

(continued from previous page)

Field	Description
EVENT TYPE (supplied)	<p>The types of objects requested for the Event. Valid values are as follows:</p> <p>N Indicates NATURAL.</p> <p>S Indicates SYSERR.</p> <p>P Indicates PREDICT.</p> <p>O Indicates 3GL/OTHER.</p> <p>D Indicates DDM.</p> <p>M Indicates METADATA.</p>
CLOSED DATE (supplied)	The date the Event was closed. Asterisks in the Closed Date field represent Events pending migration.
CLOSED TIME (supplied)	The time the Event was closed. Asterisks in the Closed Time field represent Events pending migration.
CLOSED USER-ID (supplied)	The user who closed the Event. Asterisks in the Closed User-ID field represent Events pending migration.
WARNING (supplied)	<p>Events may contain one of the following warning messages:</p> <p> OVERRIDE Indicates the Event migrated to an environment without proper authorization. </p> <p> AC-ERROR Indicates programs within the Event received compile errors during the Autocompile process. </p> <p> RECOVERD Indicates programs within the Event received compile errors and the Event was automatically recovered. </p> <p> ***** Indicates Events with no warning messages. </p>

IV.3.6 Events With Warning Messages

The Events with Warning Messages report displays Events that received one of the following warning messages:

OVERRIDE	The Event migrated to an Environment without proper authorization or the user who created the Event also authorized the Event.
AC-ERROR	Programs within the Event received compile errors during the Autocompile process.
RECOVERD	The Event was automatically recovered after programs within the Event received compile errors during the Autocompile process.

To display the Events with Warning Messages input screen, enter "F" on the Event Reporting menu.

01-12-31 11:38:00	N-2-O EVENT REPORTING EVENTS WITH WARNING MESSAGES	TSI0373 TSI1																								
<table> <tr> <td></td> <td>Name</td> <td>Seq.</td> </tr> <tr> <td></td> <td>-----</td> <td>-----</td> </tr> <tr> <td>Starting Event :</td> <td>_____</td> <td>_____ (Wildcard/Single)</td> </tr> <tr> <td>Ending Event :</td> <td>_____</td> <td>_____ (Both Blank=All)</td> </tr> <tr> <td>Warning :</td> <td>_____</td> <td></td> </tr> <tr> <td>Date Range :</td> <td>_____ - _____</td> <td></td> </tr> <tr> <td>Detailed Report:</td> <td colspan="2">N (Batch Only)</td> </tr> <tr> <td>Mode :</td> <td colspan="2">O</td> </tr> </table>				Name	Seq.		-----	-----	Starting Event :	_____	_____ (Wildcard/Single)	Ending Event :	_____	_____ (Both Blank=All)	Warning :	_____		Date Range :	_____ - _____		Detailed Report:	N (Batch Only)		Mode :	O	
	Name	Seq.																								
	-----	-----																								
Starting Event :	_____	_____ (Wildcard/Single)																								
Ending Event :	_____	_____ (Both Blank=All)																								
Warning :	_____																									
Date Range :	_____ - _____																									
Detailed Report:	N (Batch Only)																									
Mode :	O																									
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12--- HELP ---- END ----																										

Field	Description
∞ STARTING EVENT (optional)	A Master Event that identifies the starting value of the report. Partial names and wildcards (e.g., AAP*) may be entered.
STARTING SEQUENCE (optional)	The starting sequence number of the Event entered in Starting Event. If this field is left blank, all Event Sequences ranging from 1 to the number entered in Ending Event Sequence for the Event will be reported.
∞ ENDING EVENT (optional)	A Master Event that identifies the ending value of the report. Wildcards (e.g., AAP9*) may be entered. To report on a single Event, leave this field, Starting Event Sequence and Ending Event Sequence blank and enter the Master Event in the Starting Event field.

∞ indicates field-level help is available.

(continued from previous page)

Field	Description
ENDING SEQUENCE (optional)	The ending sequence number of the Event entered in Ending Event. To report on a single Event/Sequence, leave the Ending Event and this field blank, enter the Event in the Starting Event field and enter the Event Sequence in the Starting Event Sequence field.
WARNING (optional)	Limits the report to Events that received the specified warning. Valid values are as follows: <div> <div> OVERVERRIDE </div> <div>Indicates the Event migrated to an environment without proper authorization.</div> </div> <div> <div>AC-ERROR</div> <div>Indicates programs within the Event received compile errors during the Autocompile process.</div> </div> <div> <div>RECOVERD</div> <div>Indicates programs within the Event received compile errors and the Event was automatically recovered.</div> </div>
DATE RANGE (optional)	Limits the report to Events that migrated within the specified range of dates. Dates must be formatted YYYYMMDD.
DETAILED REPORT (required)	Indicates whether detailed information should be display when executed in batch. <div> <div>Y</div> <div>Display all detail information for reports when executed in batch (similar to entering E and O next to an Event on the Events with Warning Messages selection screen).</div> </div> <div> <div>N</div> <div>Display information similar to the Events with Warning Messages selection screen. (Default: N)</div> </div>
MODE (required)	Indicates how the job is executed (batch or on-line). <div> <div>B</div> <div>Submits JCL to the internal reader that processes the function in batch.</div> </div> <div> <div>O</div> <div>Processes the function on-line. (Default: O)</div> </div>

Entering the necessary information in the input screen and pressing Enter displays the Events with Warning Messages selection screen.

Valid Values: A - Autocompile E - Event O - Object									
01-12-31		N-2-O EVENT REPORTING						TSI0373	
11:38:00		EVENTS WITH WARNING MESSAGES						TSI1	
								Page: 1	
S	Event	Seq	Change Control	From Env	To Env	Event Type	Extr	---- Closed ----	
-	-----	-----	-----	-----	-----	-----	-----	-----	Warning
-	PAYOUT	1	A12345	PROD	DEV	N	NO	01-10-01 11:34:55	AC-ERROR
-	PAYTEST	2	A12345	DEV	TEST	N	NO	01-10-05 08:43:21	*****
-	PAYIN	1	A12345	TEST	PROD	N	NO	*****	*****
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---									
----- END ----- STOP									

Field	Description
S (optional)	The function to be executed. Valid values are as follows: A displays autocompile details (if available) E Displays Event details. O Displays object details.
EVENT (supplied)	The Master Event of the migration.
SEQ (supplied)	The sequence number of the Event.
CHANGE CONTROL (supplied)	A value that relates multiple Events to a specific change request.
FROM ENV (supplied)	The source Environment Definition of the Event.
TO ENV (supplied)	The target Environment Definition of the Event. An asterisk (*) indicates the Event is a multiple target Event.
EVENT TYPE (supplied)	The types of objects requested for the Event. Valid values are as follows: N Indicates NATURAL. S Indicates SYSERR. P Indicates PREDICT. O Indicates 3GL/OTHER. D Indicates DDM. M Indicates METADATA.

(continued from previous page)

Field	Description
EXTR (supplied)	Indicates whether the Event is an Extract Event or not. YES Indicates the Event is an Extract Event. NO Indicates the Event is not an Extract Event.
CLOSED DATE (supplied)	The date the Event was closed. Asterisks in the Closed Date field represent Events pending migration.
CLOSED TIME (supplied)	The time the Event was closed. Asterisks in the Closed Time field represent Events pending migration.
WARNING (supplied)	Events may contain one of the following warning messages: OVERRIDE Indicates the Event migrated to an environment without proper authorization. AC-ERROR Indicates programs within the Event received compile errors during the Autocompile process. RECOVERD Indicates programs within the Event received compile errors and the Event was automatically recovered.

IV.3.7 Events Pending Move

The Events Pending Move report displays Events that contain objects to be deleted.

To display the Events Pending Move input screen, enter "G" on the Event Reporting menu.

01-12-31 11:38:00	N-2-O EVENT REPORTING EVENTS PENDING MOVE	TSI0373 TSI1
<p>Added User-ID: _____</p> <p>From Library : _____</p> <p>Mode : O</p>		
<p>Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---</p> <p>HELP ---- END ----</p>		

Field	Description
∞ ADDED USER-ID (optional)	Limits the report to Events added by the user with the specified User-ID.
FROM LIBRARY (optional)	Limits the report to Events that migrated from the specified library.
MODE (required)	Indicates how the job is executed (batch or on-line).
	B Submits JCL to the internal reader that processes the function in batch.
	O Processes the function on-line. (Default: O)

∞ indicates field-level help is available.

Entering the necessary information in the input screen and pressing Enter displays the Events Pending Move report.

01-12-31 11:38:00		N-2-O EVENT REPORTING EVENTS PENDING MOVE				TSI0373 TSI1 Page: 1	
Event	Seq	Env	Library	Date	Time	Date	Time
PAYTEST	3	TST0	PAYDEV	01-12-15	11:36:19	01-12-31	12:00:00
PAYTEST	2	PRD2	PAYDEV	01-10-28	04:21:36	01-12-15	12:00:00
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---							
----- END ----- STOP							

Field	Description
EVENT (supplied)	The Master Event of the migration.
SEQ (supplied)	The sequence number of the Event.
FROM ENV (supplied)	The source Environment Definition of the Event.
FROM LIBRARY (supplied)	The source library of the migration for NATURAL objects and/or SYSERR messages.
CLOSED DATE (supplied)	The date the Event was closed.
CLOSED TIME (supplied)	The time the Event was closed.
DEFERRED DATE (supplied)	The date the deletion process can be initiated for the Event.
DEFERRED TIME (supplied)	The time the deletion process can be initiated for the Event.

IV.3.8 Events Pending Autocompile

Events Pending Autocompile displays Events that have migrated, but have not been compiled.

To display the Events Pending Autocompile input screen, enter "H" on the Event Reporting menu.

01-12-31 11:38:00	N-2-O EVENT REPORTING EVENTS PENDING AUTOCOMPILE	TSI0373 TSI1
<p>Event : _____</p> <p>Sequence : _____</p> <p>Date Range : _____ - _____</p> <p>Detailed Report: N (Batch Only)</p> <p>Mode : O</p>		
<p>Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---</p> <p>HELP ---- END ----</p>		

Field	Description
∞ EVENT (optional)	A Master Event that identifies the starting value for the report.
SEQUENCE (optional)	The sequence number of the Event.
DATE RANGE (optional)	Limits the report to Events that migrated within the specified range of dates. Dates must be formatted YYYYMMDD.
DETAILED REPORT (required)	Indicates whether detailed information should be displayed when executed in batch. Y Display all detail information for reports when executed in batch (similar to entering E and O next to an Event on the Events Pending Autocompile selection screen). N Display information similar to the Event Pending Autocompile selection screen. (Default: N)
MODE (required)	Indicates how the job is executed (batch or on-line). B Submits JCL to the internal reader that processes the function in batch. O Processes the function on-line. (Default: O)

∞ indicates field-level help is available.

Entering the necessary information in the input screen and pressing Enter displays the Events Pending Autocompile selection screen.

Valid Values: A - Autocompile E - Event O - Object										
01-12-31 N-2-O EVENT REPORTING TSI0373										
11:38:00 EVENTS PENDING AUTOCOMPILE TSI1										
Page: 1										
S	Event	Seq	Change Control	From Env	To Env	Event Type	Extr	Date	Closed Time	User-ID
-	PAYIN	1	A12345	TEST	PROD	N	NO	01-10-01	11:34:55	TSI0375
-	PAYIN	3	A12345	TEST	PROD	N	NO	01-10-05	08:43:21	TSI0375
-	PAYIN	4	A12345	TEST	PROD	N	NO	01-10-06	09:23:21	TSI0375
-	PAYIN	5	A12345	TEST	PROD	N	NO	01-10-03	12:14:16	TSI0375
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---										
----- END ----- STOP										

Field	Description
S (optional)	The function to be executed. The valid values are as follows: A displays autocompile details (if available) E Displays Event details. O Displays object details.
EVENT (supplied)	The Master Event of the migration.
SEQ (supplied)	The sequence number of the Event.
CHANGE CONTROL (supplied)	A value that relates multiple Events to a specific change request.
FROM ENV (supplied)	The source Environment Definition of the Event.
TO ENV (supplied)	The target Environment Definition of the Event. An asterisk (*) indicates the Event is a multiple target Event.
EVENT TYPE (supplied)	The object types requested for an Event. Valid values are as follows: N Indicates NATURAL. S Indicates SYSERR. P Indicates PREDICT. O Indicates 3GL/OTHER. D Indicates DDM. M Indicates METADATA.

(continued from previous page)

Field	Description
EXTR (supplied)	Indicates whether the Event is an Extract Event or not. YES Indicates the Event is an Extract Event. NO Indicates the Event is not an Extract Event.
CLOSED DATE (supplied)	The date the Event was closed. Asterisks in the Closed Date field represent Events pending migration.
CLOSED TIME (supplied)	The time the Event was closed. Asterisks in the Closed Time field represent Events pending migration.
CLOSED USER-ID (supplied)	The user who closed the Event. Asterisks in the Closed User-ID field represent Events pending migration.

IV.3.9 Autocompile Summary for Events

The Autocompile Summary for Events report displays the results of all Autocompiles performed by N2O.

To display the Autocompile Summary input screen, enter "I" on the Event Reporting menu.

01-12-31 11:38:00	N-2-O EVENT REPORTING AUTOCOMPILE SUMMARY FOR EVENTS	TSI0373 TSI1
	Name Seq.	
	----- -----	
Starting Event :	_____	(Wildcard/Single)
Ending Event :	_____	(Both Blank=All)
Date Range :	_____ - _____	
Detailed Report:	N (Batch Only)	
Mode :	O	
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12--- HELP ---- END -----		

Field	Description
∞ STARTING EVENT (optional)	A Master Event that identifies the starting value of the report. Partial names and wildcards (e.g., AAP*) may be entered.
STARTING SEQUENCE (optional)	The starting sequence number of the Event entered in Starting Event. If this field is left blank, all Event Sequences ranging from 1 to the number entered in Ending Event Sequence for the Event will be reported.
∞ ENDING EVENT (optional)	A Master Event that identifies the ending value of the report. Wildcards (e.g., AAP9*) may be entered. To report on a single Event, leave this field, Starting Event Sequence and Ending Event Sequence blank and enter the Master Event in the Starting Event field.
ENDING SEQUENCE (optional)	The ending sequence number of the Event entered in Ending Event. To report on a single Event/Sequence, leave the Ending Event and this field blank, enter the Event in the Starting Event field and enter the Event Sequence in the Starting Event Sequence field.
DATE RANGE (optional)	Limits the report to Events compiled within the range of dates. Dates must be formatted YYYYMMDD.

∞ indicates field-level help is available.

(continued from previous page)

Field	Description
DETAILED REPORT (required)	Indicates whether detailed information should be displayed when executed in batch. Y Display all detail information for reports when executed in batch (similar to entering X next to an Event onto the Autocompile Summary for Events selection screen). N Display information similar to the Autocompile Summary for Events selection screen (Default: N).
MODE (required)	Indicates how the job is executed (batch or on-line). B Submits JCL to the internal reader that processes the function in batch. O Processes the function on-line. (Default: O)

Entering the necessary information in the input screen and pressing Enter displays the Autocompile Summary for Events selection screen. This report shows all Events that required Autocompile.

Valid Values: X - Autocompile Details									
01-12-31		N-2-O EVENT REPORTING						TSI0373	
11:38:00		AUTOCOMPILE SUMMARY						TSI1	
								Page:	1
X	Event	Seq	Change Control	---- Closed ----		--Autocompiled --			
				Date	Time	Date	Time	Warning	
-	-----	----	-----	-----	-----	-----	-----	-----	
-	PAYIN	1	*****	01-11-05	17:00:46	01-11-05	17:05:49	OVERRIDE	
-	PAYIN	3	*****	01-12-04	10:45:07	01-12-04	11:27:47	*****	
-	PAYIN	4	*****	01-12-04	11:04:32	01-12-04	11:26:05	*****	
-	PAYIN	5	*****	01-12-15	12:14:48	01-12-15	12:46:39	*****	
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---									
----- END				----- STOP					

Field	Description
X (optional)	"X" in the select field displays Autocompile Details about the Event.
EVENT (supplied)	The Master Event of the migration.
SEQ (supplied)	The sequence number of the Event.
CHANGE CONTROL (supplied)	A value that relates multiple Events to a specific change request.
CLOSED DATE (supplied)	The date the Event was closed.
CLOSED TIME (supplied)	The time the Event was closed.
AUTOCOMPILED DATE (supplied)	The date the Event was Autocompiled. "Canceled" indicates the Autocompile process was canceled for the Event.
AUTOCOMPILED TIME (supplied)	The time the Event was Autocompiled. "Canceled" indicates the Autocompile process was canceled for the Event.

(continued from previous page)

Field	Description
WARNING (supplied)	Event contains one of the following warning messages: OVERRIDE Indicates the Event migrated to an environment without proper authorization. AC-ERROR Indicates programs within the Event received compile errors during the Autocompile process. RECOVERD Indicates programs within the Event received compile errors and the Event was automatically recovered.

Selecting an Event on the previous screen (using an 'X') displays the Autocompile Details report.

01-12-31	N-2-O AUTOCOMPILE DETAILS				TSI0373
11:38:00	Event: PAYIN		Sequence: 3		TSI1
From Env: TEST		From Library: PAYTEST		To Env: PROD	To Library: PAYPROD
Target		Object	----- Autocompiled -----		
XREF	Object	Type	Date	Time	User-ID
-----	-----	-----	-----	-----	-----
*	CINCLUDE	COPYCODE	01-03-15	10:17:32	TSI0373
*	PROGRAM1	PROGRAM	01-03-15	10:17:35	TSI0373
	LOCAL1	LOCAL	01-03-15	10:17:40	TSI0373
*	SUBRTN1	SUB-RTN	Error	82	1060
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---					
----	----	END	----	----	STOP

Field	Description
EVENT (supplied)	The Master Event of the migration.
SEQUENCE (supplied)	The sequence number of the Event.
FROM ENV (supplied)	The source Environment Definition of the Event.
FROM LIBRARY (supplied)	The source library of the migration for NATURAL objects and/or SYSERR messages.
TO ENV (supplied)	The target Environment Definition of the Event.
TO LIBRARY (supplied)	The target library of the migration for NATURAL objects and/or SYSERR messages.
TARGET XREF (supplied)	(*) indicates the program was not migrated but was compiled using the XREF at the target feature.
OBJECT (supplied)	The NATURAL object compiled by Autocompile.

(continued from previous page)

Field	Description
OBJECT TYPE (supplied)	The NATURAL object type. PARM Indicates Parameter data area. COPYCODE Indicates Copycode. GLOBAL Indicates Global data area. HELP-RTN Indicates Helproutine. LOCAL Indicates Local data area. MAP Indicates Map. SUB-PGM Indicates Subprogram. PROGRAM Indicates Program. SUB-RTN Indicates Subroutine. TEXT Indicates Text. MACRO Indicates Macro. REPORT Indicates Report. EXP-MDL Indicates ExpertModel. RECORD Indicates Recording. DIALOG Indicates Dialog. CLASS Indicates Class. CMD-PROC Indicates Processor. SERVER Indicates Server. FUNCTION. Indicates Function. ADAPTER. Indicates Adapter. MACRO. Indicates Macro.
AUTOCOMPILED DATE (supplied)	The date the NATURAL object was Autocompiled. "Error" indicates an error occurred during the compilation process.
AUTOCOMPILED TIME (supplied)	The time the NATURAL object was Autocompiled. Also displays the error number received during the compile process.
AUTOCOMPILED USER-ID (supplied)	The user who Autocompiled the NATURAL object. Also displays the line number of the error.

IV.3.10 Event Reporting in Batch

Sample reporting JCL is provided in the MVSREPT, VMREPT, BSREPT and VSEREPT members located in the Natural library N2OBATCH.

Note that program N2OREPD will permit sites to execute a regularly scheduled batch job that will generate a report of all Events that processed on the previous day. N2OREPD will calculate yesterday's date and call N2OEVNTE (Events Processed by Date report), passing the calculated date. A site may customize N2OREPD to specify the detail level of the Events Processed by Date report. The default is to provide summary information. For details, refer to the program N2OREPD in the N2OLIB Library.

N2OREPD should be run in place of N2OEVNTE in a batch job.

The following table illustrates the JCL and EXECs modifications necessary to execute Event reports in batch.

REPORT	&REPORT	&INPUT
Events Requiring Further Authorization	N2OEVNTA	DELAY,DETAILED-REPORT
Chronology of Events	N2OEVNTB	EVENT,SEQUENCE,START-DATE,DETAILED-REPORT
Events Related by Change Control	N2OEVNTC	CHANGE CONTROL,ADDED USER-ID,DATE-1,DATE-2,DETAILED-REPORT
Event Details	N2OEVNTD	STARTING-EVENT,STARTING-SEQ,ENDING-EVENT,ENDING-SEQ,FROM-ENV,TO-ENV,ADDED-USER-ID EVENT-STATUS,DB2-STATUS,DETAILED-REPORT
Events Processed by Date – <i>To generate a report of the previous day's migrations, use N2OREPD as noted above</i>	N2OEVNTE	EVENT,SEQUENCE,DATE-1,DATE-2,ADDED-USER-ID,DETAILED-REPORT
Events with Warning Messages	N2OEVNTF	STARTING-EVENT,STARTING-SEQ,ENDING-EVENT,ENDING-SEQ,WARNING,DATE-1,DATE-2,DETAILED-REPORT

REPORT	&REPORT	&INPUT
Events Pending Move	N2OEVNTG	ADDED USER-ID,FROM LIBRARY
Events Pending Autocompile	N2OEVNTH	EVENT,SEQUENCE,DATE-1,DATE-2,DETAILED-REPORT
Autocompile Summary for Events	N2OEVNTI	STARTING-EVENT,STARTING-SEQ,ENDING-EVENT,ENDING-SEQ,DATE-1,DATE-2,DETAILED-REPORT

The &INPUT parameter list by default is delimited by commas with no spaces following the commas. To override the default delimiter, modify the value of the jcl-delimiter field in User-Exit-22 (N2OUE22N).

For descriptions of &INPUT fields, refer to field descriptions in corresponding sections of Event Reporting.

Note: The batch reports from the N2O Reporting Subsystem and the Documentation Tools require that the NATURAL Parameter IM (Input Mode) be set to "IM=D" (Delimiter Mode).

IV.4 Object Reporting

Object Reporting provides reports that display information about NATURAL objects, PREDICT objects, 3GL/OTHER objects, and SYSERR messages.

To display the Object Reporting menu, enter "C" on the Reporting Subsystem menu or enter the direct command REP OBJ on any menu.

```

01-12-31          N-2-O OBJECT REPORTING MENU          TSI0373
11:38:00                                     TSI1

      Code  Function
      ----  -
      A    History of an Environment
      B    History of an Object
      C    Directory List
      D    Directory Compare
      E    Cross Reference
      F    Checked Out Objects
      G    Objects Archived by N2OPURGE
      H    Archive Version Summary
      I    Events Pending for an Object
      .    Terminate Object Reporting
      ----  -

      Enter Code: _   Type : N

Direct Command:                                     REP OBJ
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      HELP  ----  END  ENV  MIG  REP  TOL  USR  PRJ  ----  ----  EXIT

```

Field	Description
ENTER CODE (required)	<p>The function to be executed. Valid values are as follows:</p> <p>A History of an Environment Displays objects migrated to an environment.</p> <p>B History of an Object Displays the complete audit trail of an object.</p> <p>C Directory List Displays a list of objects from an environment.</p> <p>D Directory Compare Displays the differences between two environments.</p> <p>E Cross Reference Displays objects that are related to an object.</p> <p>F Checked Out Objects Displays objects checked out from a BASE environment.</p> <p>G Objects Archived by N2OPURGE Displays NATURAL objects archived using the N2OPURGE utility.</p> <p>H Archive Version Summary Displays Events which performed archiving for an object.</p> <p>I Events Pending for an Object Displays Events pending for an object.</p>
∞ TYPE (required)	<p>One of four object types can be selected. Valid values include the following:</p> <p>N Indicates NATURAL. P Indicates PREDICT. S Indicates SYSERR. O Indicates 3GL/OTHER. D Indicates DDM. M Indicates METADATA.</p>

∞ indicates field-level help is available.

IV.4.1 History of an Environment

The History of an Environment report displays objects that migrated to an environment.

To display the History of an Environment input screen for NATURAL objects, enter "A" in the Enter Code field and "N" in the Type field on the Object Reporting menu.

01-12-31 11:38:00	N-2-O OBJECT REPORTING HISTORY OF AN ENVIRONMENT	TSI0373 TSI1
Library : _____		
Env Def : _____		
Date Range : _____ - _____		
Detailed Report: N (Batch Only)		
Mode : O		
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12--- HELP ---- END ----		

Field	Type	Description
LIBRARY (required)	N,S	The target library of the migration for NATURAL objects and/or SYSERR messages.
∞ ENV DEF (optional)	N,S,P,O,D,M	Limits the report to objects migrated to the specified Environment Definition.
DATE RANGE (optional)	N,S,P,O,D,M	Limits the report to objects migrated within the specified range of dates. Dates must be formatted YYYYMMDD.
DETAILED REPORT (required)	N,S,P,O,D,M	Indicates whether detailed information should be displayed when executed in batch. Y Display all detail information for reports when executed in batch (similar to entering X next to an object on the Object Reporting menu screen). N Display information similar to the History of an Environment selection screen (Default: N).
MODE (required)		Indicates how the job is executed (batch or on-line). B Submits JCL to the internal reader that processes the function in batch. O Processes the function on-line. (Default: O)

∞ indicates field-level help is available.

Entering the necessary information in the input screen and pressing Enter displays the History of an Environment report.

Type X for Info or D for Event Details								
01-12-31			N-2-O OBJECT REPORTING				TSI0373	
11:38:00			HISTORY OF AN ENVIRONMENT				TSI1	
			LIBRARY: PAYDEV				Page: 1	
S	Date	Object	Object Type	To Env	Message	Mig S/C	Extr	Event Seq
-	01-04-10	PAY5210S	SUB-RTN	DEV	REPLACE	S	NO	PAYOUT 250
-	01-04-10	PAYRECV3	PROGRAM	DEV	REPLACE	S	NO	PAYOUT 249
-	01-04-10	PAY19721	MAP	DEV	REPLACE	S	NO	PAYREJ 52
-	01-04-10	PAY19711	MAP	DEV	REPLACE	S	NO	PAYREJ 52
-	01-04-06	PAY3150S	SUB-RTN	DEV	REPLACE	S	YES	EXTRACT 3251
-	01-04-06	PAY1146N	SUB-PGM	DEV	REPLACE	S	YES	EXTRACT 3251
-	01-04-06	PAY1510S	SUB-RTN	DEV	REPLACE	S	NO	PAYOUT 248
-	01-04-06	PAY138D1	MAP	DEV	REPLACE	S	NO	PAYOUT 247
-	01-04-06	PAY19981	MAP	DEV	REPLACE	S	NO	PAYOUT 246
-	01-04-06	PAY19951	MAP	DEV	REPLACE	S	NO	PAYOUT 246
-	01-04-06	PAY19911	MAP	DEV	REPLACE	S	NO	PAYOUT 246
-	01-04-06	PAY19901	MAP	DEV	REPLACE	S	NO	PAYOUT 246
-	01-04-06	PAY1998S	SUB-RTN	DEV	REPLACE	S	NO	PAYREJ 51
Enter--PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11--PF12---								
----- END ----- STOP								

Field	Type	Description
LIBRARY (supplied)	N,S	The name of the NATURAL library.
CATEGORY (supplied)	O	The 3GL/OTHER category.
DATE (supplied)	N,S,P,O,D,M	The date an object was migrated to the environment.
OBJECT (supplied)	N,S,P,O,D,M	The name of the NATURAL object, PREDICT object, 3GL/OTHER object, or SYSERR message.
S (optional)	N,S,P,O,D,M	"X" displays information about the Event/Utility. "D" displays the Event Details report for that event.
OBJECT TYPE (supplied)	N	The NATURAL object type.
	PARAM	Indicates Parameter data area.
	COPYCODE	Indicates Copycode.
	GLOBAL	Indicates Global data area.
	HELP-RTN	Indicates Helproutine.
	LOCAL	Indicates Local data area.
	MAP	Indicates Map.
	SUB-PGM	Indicates Subprogram.
	PROGRAM	Indicates Program.
	SUB-RTN	Indicates Subroutine.
	TEXT	Indicates Text.
	MACRO	Indicates Macro.
	REPORT	Indicates Report.
	EXP-MDL	Indicates ExpertModel.
	RECORD	Indicates Recording.
	DIALOG	Indicates Dialog.
	CLASS	Indicates Class.
	CMD-PROC	Indicates Processor.
	SERVER	Indicates Server.
	FUNCTION.	Indicates Function.
	ADAPTER.	Indicates Adapter.
	MACRO.	Indicates Macro.

(continued from previous page)

Continued from previous page

Field	Type	Description																																																																								
	P	<p>The PREDICT object type.</p> <table><tr><th>Type</th><th>Indicates</th><th>Predict Version</th></tr><tr><td>DA</td><td>Database</td><td></td></tr><tr><td>DC</td><td>Dataspace</td><td></td></tr><tr><td>ET</td><td>Extract</td><td></td></tr><tr><td>FI</td><td>File</td><td></td></tr><tr><td>IE</td><td>Interface</td><td>V4.1.2 and above</td></tr><tr><td>KY</td><td>Keyword</td><td></td></tr><tr><td>LS</td><td>Library Structure</td><td></td></tr><tr><td>MD</td><td>Method</td><td>V4.1.2 and above</td></tr><tr><td>MO</td><td>Module</td><td>V3.4.2 and below</td></tr><tr><td>NO</td><td>Node</td><td></td></tr><tr><td>NW</td><td>Network</td><td></td></tr><tr><td>PG</td><td>PackageList</td><td></td></tr><tr><td>PR</td><td>Program</td><td></td></tr><tr><td>PY</td><td>Property</td><td>V4.1.2 and above</td></tr><tr><td>RL</td><td>Relationship</td><td></td></tr><tr><td>RP</td><td>Report</td><td>V3.4.2 and below</td></tr><tr><td>RT</td><td>Report Listing</td><td></td></tr><tr><td>SC</td><td>Storagespace</td><td></td></tr><tr><td>SV</td><td>Server</td><td></td></tr><tr><td>SY</td><td>System</td><td></td></tr><tr><td>US</td><td>User</td><td></td></tr><tr><td>VE</td><td>Verification</td><td></td></tr><tr><td>VM</td><td>Virtual Machine</td><td></td></tr></table>	Type	Indicates	Predict Version	DA	Database		DC	Dataspace		ET	Extract		FI	File		IE	Interface	V4.1.2 and above	KY	Keyword		LS	Library Structure		MD	Method	V4.1.2 and above	MO	Module	V3.4.2 and below	NO	Node		NW	Network		PG	PackageList		PR	Program		PY	Property	V4.1.2 and above	RL	Relationship		RP	Report	V3.4.2 and below	RT	Report Listing		SC	Storagespace		SV	Server		SY	System		US	User		VE	Verification		VM	Virtual Machine	
Type	Indicates	Predict Version																																																																								
DA	Database																																																																									
DC	Dataspace																																																																									
ET	Extract																																																																									
FI	File																																																																									
IE	Interface	V4.1.2 and above																																																																								
KY	Keyword																																																																									
LS	Library Structure																																																																									
MD	Method	V4.1.2 and above																																																																								
MO	Module	V3.4.2 and below																																																																								
NO	Node																																																																									
NW	Network																																																																									
PG	PackageList																																																																									
PR	Program																																																																									
PY	Property	V4.1.2 and above																																																																								
RL	Relationship																																																																									
RP	Report	V3.4.2 and below																																																																								
RT	Report Listing																																																																									
SC	Storagespace																																																																									
SV	Server																																																																									
SY	System																																																																									
US	User																																																																									
VE	Verification																																																																									
VM	Virtual Machine																																																																									
	O	<p>The 3GL/OTHER object type of a category. Specific object types are determined when an object is enrolled.</p> <table><tr><td>ASMB</td><td>Indicates all types of Assembler.</td></tr><tr><td>COBOL</td><td>Indicates all types of COBOL.</td></tr><tr><td>FORT</td><td>Indicates all types of FORTRAN.</td></tr><tr><td>PL/I</td><td>Indicates all PL/I types.</td></tr><tr><td>RPG</td><td>Indicates RPG.</td></tr><tr><td>DATA</td><td>Indicates DATA FILES.</td></tr><tr><td>JCL</td><td>Indicates JCL, CLIST, CNTL.</td></tr><tr><td>OTHER</td><td>Indicates all other types.</td></tr></table>	ASMB	Indicates all types of Assembler.	COBOL	Indicates all types of COBOL.	FORT	Indicates all types of FORTRAN.	PL/I	Indicates all PL/I types.	RPG	Indicates RPG.	DATA	Indicates DATA FILES.	JCL	Indicates JCL, CLIST, CNTL.	OTHER	Indicates all other types.																																																								
ASMB	Indicates all types of Assembler.																																																																									
COBOL	Indicates all types of COBOL.																																																																									
FORT	Indicates all types of FORTRAN.																																																																									
PL/I	Indicates all PL/I types.																																																																									
RPG	Indicates RPG.																																																																									
DATA	Indicates DATA FILES.																																																																									
JCL	Indicates JCL, CLIST, CNTL.																																																																									
OTHER	Indicates all other types.																																																																									
LANGUAGES (supplied)	S	The SYSERR messages migrated.																																																																								
FILE TYPE (supplied)	P	The PREDICT file type (e.g., A is ADABAS, C is Conceptual, etc.).																																																																								

(continued from previous page)

Field	Type	Description
TO ENV (supplied)	N,S,P,O,D,M	The target Environment Definition of the migrated object.
MESSAGE (supplied)	N,S,P,O,D,M	Valid messages are: ADD, REPLACE, WARNING, and RECOVERED.
MIG S/C (supplied)	N,O	The form of the object migrated. S Indicates only the source form of the program may be selected. C Indicates only the cataloged form of the program may be selected. S/C Indicates both forms of the program may be selected.
MIG S/L (supplied)	S	The form of the migrated SYSERR message.
EXTR (supplied)	N,S,P,O,D,M	Indicates whether the Event is an Extract Event or not. YES Indicates the Event is an Extract Event. NO Indicates the Event is not an Extract Event.
EVENT (supplied)	N,S,P,O,D,M	The Master Event of the migration.
SEQ (supplied)	N,S,P,O,D,M	The sequence number of the Event.

IV.4.2 History of an Object

The History of an Object report displays a complete audit trail of an object. This report identifies Events that migrated and archived the object and utilities that updated the Checkout/Checkin status of the object.

To display the History of an Object input screen for NATURAL objects, enter "B" in the Enter Code field and "N" in the Type field on the Object Reporting menu.

01-12-31 11:38:00	N-2-O OBJECT REPORTING HISTORY OF AN OBJECT	TSI0373 TSI1
Object : _____ Library : _____ Date Range : _____ - _____		
List Events : A (All/Closed/Open) Detailed Report: N (Batch Only) Mode : O		
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12--- HELP ---- END ----		

Field	Type	Description
OBJECT (required)	N,S,P,O,D,M	Displays the history of a DDM, METADATA, NATURAL object, PREDICT object, 3GL/OTHER object, or SYSERR message.
LIBRARY (optional)	N,S	Limits the report to NATURAL objects or SYSERR messages for the library.
DATE RANGE (optional)	N,S,P,O,D,M	Limits the report to objects migrated within the specified range of dates. Dates must be formatted YYYYMMDD.
List Events	N,S,P,O,D,M	Limit the history displayed to 'A'll, 'O'pen, or 'C'losed Events
DETAILED REPORT (required)	N,S,P,O,D,M	Indicates whether detailed information should be displayed when executed in batch. <div> <div>Y</div> <div>Display all detail information for reports when executed in batch (similar to entering X next to an object on the History of an Object selection screen).</div> </div> <div> <div>N</div> <div>Display information similar to the History of an Object selection screen (Default: N).</div> </div>
MODE (required)	N,S,P,O,D,M	Indicates how the job is executed (batch or on-line). <div> <div>B</div> <div>Submits JCL to the internal reader that processes the function in batch.</div> </div> <div> <div>O</div> <div>Processes the function on-line (Default: O).</div> </div>

(continued from previous page)

Field	Type	Description																																																																								
∞ OBJECT TYPE (required)	P	Limits the report to PREDICT objects for the specified PREDICT object type. Valid values are as follows: <table><tr><td>Type</td><td>Indicates</td><td>Predict Version</td></tr><tr><td>DA</td><td>Database</td><td></td></tr><tr><td>DC</td><td>Dataspace</td><td></td></tr><tr><td>ET</td><td>Extract</td><td></td></tr><tr><td>FI</td><td>File</td><td></td></tr><tr><td>IE</td><td>Interface</td><td>V4.1.2 and above</td></tr><tr><td>KY</td><td>Keyword</td><td></td></tr><tr><td>LS</td><td>Library Structure</td><td></td></tr><tr><td>MD</td><td>Method</td><td>V4.1.2 and above</td></tr><tr><td>MO</td><td>Module</td><td>V3.4.2 and below</td></tr><tr><td>NO</td><td>Node</td><td></td></tr><tr><td>NW</td><td>Network</td><td></td></tr><tr><td>PG</td><td>PackageList</td><td></td></tr><tr><td>PR</td><td>Program</td><td></td></tr><tr><td>PY</td><td>Property</td><td>V4.1.2 and above</td></tr><tr><td>RL</td><td>Relationship</td><td></td></tr><tr><td>RP</td><td>Report</td><td>V3.4.2 and below</td></tr><tr><td>RT</td><td>Report Listing</td><td></td></tr><tr><td>SC</td><td>Storagespace</td><td></td></tr><tr><td>SV</td><td>Server</td><td></td></tr><tr><td>SY</td><td>System</td><td></td></tr><tr><td>US</td><td>User</td><td></td></tr><tr><td>VE</td><td>Verification</td><td></td></tr><tr><td>VM</td><td>Virtual Machine</td><td></td></tr></table>	Type	Indicates	Predict Version	DA	Database		DC	Dataspace		ET	Extract		FI	File		IE	Interface	V4.1.2 and above	KY	Keyword		LS	Library Structure		MD	Method	V4.1.2 and above	MO	Module	V3.4.2 and below	NO	Node		NW	Network		PG	PackageList		PR	Program		PY	Property	V4.1.2 and above	RL	Relationship		RP	Report	V3.4.2 and below	RT	Report Listing		SC	Storagespace		SV	Server		SY	System		US	User		VE	Verification		VM	Virtual Machine	
Type	Indicates	Predict Version																																																																								
DA	Database																																																																									
DC	Dataspace																																																																									
ET	Extract																																																																									
FI	File																																																																									
IE	Interface	V4.1.2 and above																																																																								
KY	Keyword																																																																									
LS	Library Structure																																																																									
MD	Method	V4.1.2 and above																																																																								
MO	Module	V3.4.2 and below																																																																								
NO	Node																																																																									
NW	Network																																																																									
PG	PackageList																																																																									
PR	Program																																																																									
PY	Property	V4.1.2 and above																																																																								
RL	Relationship																																																																									
RP	Report	V3.4.2 and below																																																																								
RT	Report Listing																																																																									
SC	Storagespace																																																																									
SV	Server																																																																									
SY	System																																																																									
US	User																																																																									
VE	Verification																																																																									
VM	Virtual Machine																																																																									
∞ CATEGORY (required)	O	Limits the report to 3GL/OTHER objects from the specified 3GL category. Valid values are as follows: <table><tr><td>ASMB</td><td>Indicates all types of Assembler.</td></tr><tr><td>COBOL</td><td>Indicates all types of COBOL.</td></tr><tr><td>FORT</td><td>Indicates all types of FORTRAN.</td></tr><tr><td>PL/I</td><td>Indicates all PL/I types.</td></tr><tr><td>RPG</td><td>Indicates RPG.</td></tr><tr><td>DATA</td><td>Indicates DATA FILES.</td></tr><tr><td>JCL</td><td>Indicates JCL, CLIST, CNTL.</td></tr><tr><td>OTHER</td><td>Indicates all other types.</td></tr></table>	ASMB	Indicates all types of Assembler.	COBOL	Indicates all types of COBOL.	FORT	Indicates all types of FORTRAN.	PL/I	Indicates all PL/I types.	RPG	Indicates RPG.	DATA	Indicates DATA FILES.	JCL	Indicates JCL, CLIST, CNTL.	OTHER	Indicates all other types.																																																								
ASMB	Indicates all types of Assembler.																																																																									
COBOL	Indicates all types of COBOL.																																																																									
FORT	Indicates all types of FORTRAN.																																																																									
PL/I	Indicates all PL/I types.																																																																									
RPG	Indicates RPG.																																																																									
DATA	Indicates DATA FILES.																																																																									
JCL	Indicates JCL, CLIST, CNTL.																																																																									
OTHER	Indicates all other types.																																																																									

∞ indicates field-level help is available.

Entering the necessary information in the input screen and pressing Enter displays the History of an Object selection screen.

01-12-31 11:38:00		N-2-O OBJECT REPORTING HISTORY OF AN OBJECT Object: MENU Open and Closed Events						TSIO373 TSII Page: 1		
X	Date	Event/ Utility	Seq	From Env	To Env	Message	Mig S/C	Arch S/C	Purg S/C	Added User-ID
-	01-10-16	PAYIN	67	TEST	PROD	REPLACE	S	S	***	TSIO374
-	01-10-14	EXTRACT	3209	PROD	TEST	REPLACE	S	S	***	TSIO376
-	01-10-13	PAYQA	112	DEV	TEST	REPLACE	S	S	***	TSIO376
-	01-08-13	PAYOUT	205	PROD	DEV	REPLACE	S	S	***	TSIO374
-	01-08-12	CANCEL		PROD	DEV	REPLACE	***	***	***	TSIO374
-	01-08-11	CHECKOUT		PROD	DEV	*****	***	***	***	TSIO376
-	01-05-13	EXTRACT	3122	PROD	TEST	*****	S	***	***	TSIO374
-	01-05-08	EXTRACT	3116	PROD	TEST	REPLACE		C	***	TSIO374
-	01-05-03	PAYIN	20	TEST	PROD	REPLACE	S	S/C	***	TSIO374
-	01-03-19	PAYQA	30	DEV	TEST	REPLACE	S/C	C	***	TSIO376
-	01-03-19	PAYOUT	99	PROD	DEV	REPLACE	S	***	S	TSIO376
-	01-02-23	EXTRACT	2980	DEV	TEST	REPLACE		C	***	TSIO374
-	01-02-22	EXTRACT	2978	PROD	TEST	REPLACE	C	***	C	TSIO374
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---										
----- END ----- OPEN ----- STOP										

Field	Type	Description
OBJECT (supplied)	N,S,P,O,D,M	The name of the NATURAL object, PREDICT object, 3GL/OTHER object, or SYSERR message.
3GL CATEGORY (supplied for 3GL only)	O	The 3GL/OTHER object category.
X (optional)	N,S,P,O,D,M	"X" displays information about the Event/Utility. "D" displays the Event Details report for that event. "X" next to a utility displays details about the utility.
DATE (supplied)	N,S,P,O,D,M	The migration date of an Event or the date a utility was executed.
EVENT/ UTILITY (supplied)	N,S,P,O,D,M	The Event that migrated the object or the utility that updated the Checkout/Checkin status of the object.
SEQ (supplied)	N,S,P,O,D,M	The sequence number of the Event.
FROM ENV (supplied)	N,S,P,O,D,M	The source Environment Definition of the Event.
TO ENV (supplied)	N,S,P,O,D,M	The target Environment Definition of the Event. An asterisk (*) indicates the Event is a multiple target Event.
MESSAGE (supplied)	N,S,P,O,D,M	Valid messages are: ADD, REPLACE, WARNING, RENAME, and RECOVERED.

(continued from previous page)

Field	Type	Description
MIG S/C (supplied)	N,S,P,O,D,M	The form of the object migrated.
		S Indicates only the source form of the program may be selected.
		C Indicates only the cataloged form of the program may be selected.
		S/C Indicates both forms of the program may be selected.
ARCH S/C (supplied)	N,S,O	The form of the object archived.
		S Indicates only the source form of the program may be selected.
		C Indicates only the cataloged form of the program may be selected.
		S/C Indicates both forms of the program may be selected.
PURG S/C (supplied)	N,S,O	The form of the object purged.
		S Indicates only the source form of the program may be selected.
		C Indicates only the cataloged form of the program may be selected.
		S/C Indicates both forms of the program may be selected.
ADDED USER-ID (supplied)	N,S,P,O,D,M	The User-ID of the user who added the Event or executed the utility.

PF5 is available to toggle between displaying Open and Closed Events, Open Events only or Closed Events only.

IV.4.3 Directory List

The Directory List report displays objects of an environment along with the date and time of the source and object code for each object.

To display the Directory List input screen for NATURAL objects, enter "C" in the Enter Code field and "N" in the Type field on the Object Reporting menu.

01-12-31 11:38:00	N-2-O OBJECT REPORTING DIRECTORY LIST	TSI0373 TSI1
<div> <div>Env Def</div> <div>:</div> <div>_____</div> </div> <div> <div>Library</div> <div>:</div> <div>_____</div> </div> <div> <div>Starting Value:</div> <div>:</div> <div>_____</div> </div> <div> <div>Ending Value</div> <div>:</div> <div>_____</div> </div> <div> <div>Mode</div> <div>:</div> <div>0</div> </div>		
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12--- HELP ---- END ----		

Field	Type	Description
∞ ENV DEF (required)	N,S,P,O,D,M	The source Environment Definition serving for the report.
LIBRARY (required)	N,S	The library containing the NATURAL objects or SYSERR messages.

∞ indicates field-level help is available.

(continued from previous page)

Field	Type	Description																																																																								
∞ OBJECT TYPE (required)	P	<p>The PREDICT object type for PREDICT objects. Valid values are as follows:</p> <table> <tr> <th>Type</th><th>Indicates</th><th>Predict Version</th></tr> <tr><td>DA</td><td>Database</td><td></td></tr> <tr><td>DC</td><td>Dataspace</td><td></td></tr> <tr><td>ET</td><td>Extract</td><td></td></tr> <tr><td>FI</td><td>File</td><td></td></tr> <tr><td>IE</td><td>Interface</td><td>V4.1.2 and above</td></tr> <tr><td>KY</td><td>Keyword</td><td></td></tr> <tr><td>LS</td><td>Library Structure</td><td></td></tr> <tr><td>MD</td><td>Method</td><td>V4.1.2 and above</td></tr> <tr><td>MO</td><td>Module</td><td>V3.4.2 and below</td></tr> <tr><td>NO</td><td>Node</td><td></td></tr> <tr><td>NW</td><td>Network</td><td></td></tr> <tr><td>PG</td><td>PackageList</td><td></td></tr> <tr><td>PR</td><td>Program</td><td></td></tr> <tr><td>PY</td><td>Property</td><td>V4.1.2 and above</td></tr> <tr><td>RL</td><td>Relationship</td><td></td></tr> <tr><td>RP</td><td>Report</td><td>V3.4.2 and below</td></tr> <tr><td>RT</td><td>Report Listing</td><td></td></tr> <tr><td>SC</td><td>Storagespace</td><td></td></tr> <tr><td>SV</td><td>Server</td><td></td></tr> <tr><td>SY</td><td>System</td><td></td></tr> <tr><td>US</td><td>User</td><td></td></tr> <tr><td>VE</td><td>Verification</td><td></td></tr> <tr><td>VM</td><td>Virtual Machine</td><td></td></tr> </table>	Type	Indicates	Predict Version	DA	Database		DC	Dataspace		ET	Extract		FI	File		IE	Interface	V4.1.2 and above	KY	Keyword		LS	Library Structure		MD	Method	V4.1.2 and above	MO	Module	V3.4.2 and below	NO	Node		NW	Network		PG	PackageList		PR	Program		PY	Property	V4.1.2 and above	RL	Relationship		RP	Report	V3.4.2 and below	RT	Report Listing		SC	Storagespace		SV	Server		SY	System		US	User		VE	Verification		VM	Virtual Machine	
Type	Indicates	Predict Version																																																																								
DA	Database																																																																									
DC	Dataspace																																																																									
ET	Extract																																																																									
FI	File																																																																									
IE	Interface	V4.1.2 and above																																																																								
KY	Keyword																																																																									
LS	Library Structure																																																																									
MD	Method	V4.1.2 and above																																																																								
MO	Module	V3.4.2 and below																																																																								
NO	Node																																																																									
NW	Network																																																																									
PG	PackageList																																																																									
PR	Program																																																																									
PY	Property	V4.1.2 and above																																																																								
RL	Relationship																																																																									
RP	Report	V3.4.2 and below																																																																								
RT	Report Listing																																																																									
SC	Storagespace																																																																									
SV	Server																																																																									
SY	System																																																																									
US	User																																																																									
VE	Verification																																																																									
VM	Virtual Machine																																																																									
∞ CATEGORY (required)	O	<p>The 3GL/OTHER category for 3GL/OTHER objects. Valid values are as follows:</p> <table> <tr><td>ASMB</td><td>Indicates</td><td>all types of Assembler.</td></tr> <tr><td>COBOL</td><td>Indicates</td><td>all types of COBOL.</td></tr> <tr><td>FORT</td><td>Indicates</td><td>all types of FORTRAN.</td></tr> <tr><td>PL/I</td><td>Indicates</td><td>all PL/I types.</td></tr> <tr><td>RPG</td><td>Indicates</td><td>RPG.</td></tr> <tr><td>DATA</td><td>Indicates</td><td>DATA FILES.</td></tr> <tr><td>JCL</td><td>Indicates</td><td>JCL, CLIST, CNTL.</td></tr> <tr><td>OTHER</td><td>Indicates</td><td>all other types.</td></tr> </table>	ASMB	Indicates	all types of Assembler.	COBOL	Indicates	all types of COBOL.	FORT	Indicates	all types of FORTRAN.	PL/I	Indicates	all PL/I types.	RPG	Indicates	RPG.	DATA	Indicates	DATA FILES.	JCL	Indicates	JCL, CLIST, CNTL.	OTHER	Indicates	all other types.																																																
ASMB	Indicates	all types of Assembler.																																																																								
COBOL	Indicates	all types of COBOL.																																																																								
FORT	Indicates	all types of FORTRAN.																																																																								
PL/I	Indicates	all PL/I types.																																																																								
RPG	Indicates	RPG.																																																																								
DATA	Indicates	DATA FILES.																																																																								
JCL	Indicates	JCL, CLIST, CNTL.																																																																								
OTHER	Indicates	all other types.																																																																								
STARTING VALUE (optional)	N,S,P,O,D,M	The starting value of the object list.																																																																								

∞ indicates field-level help is available.

(continued from previous page)

Field	Type	Description
ENDING VALUE (optional)	N,S,P,O,D,M	The ending value of the object list.
MODE (required)	N,S,P,O ,D,M	Indicates how the job is executed (batch or on-line). B Submits JCL to the internal reader that processes the function in batch. O Processes the function on-line. (Default: O)

Entering the necessary information in the input screen and pressing Enter displays the Directory List report.

01-12-31 11:38:00	N-2-O OBJECT REPORTING DIRECTORY LIST Env Def: DEV Library: PAYDEV						TSI0373 TSI1 Page: 1
Object	Object Type	Date	Time	User-ID	Date	Time	User-ID
ACE	PROGRAM	01-09-30	14:47:47	TREE06	*****	*****	*****
BENWORK	MAP	01-04-13	17:24:44	TREE08	*****	*****	*****
B1	PROGRAM	01-04-11	15:59:55	TREE08	01-04-11	15:59:55	TREE08
CADAERRD	COPYCODE	01-03-31	16:39:48	BATCH02	*****	*****	*****
CADDREP	COPYCODE	01-03-31	16:39:49	BATCH02	*****	*****	*****
CALSAVE	MAP	01-04-13	12:12:15	TREE04	01-03-31	18:09:34	BATCH02
CARARCH	PROGRAM	01-03-20	15:36:07	TREE04	01-03-31	18:59:10	BATCH02
CAROUT	PROGRAM	*****	*****	*****	01-12-22	13:47:38	TREE04
TEST	PROGRAM	01-04-11	14:13:32	TREE04	01-03-31	18:59:20	BATCH02
TEST	PROGRAM	01-03-30	17:01:40	TREE04	01-03-31	18:59:34	BATCH02
TEST	PROGRAM	01-04-11	17:04:55	TREE04	*****	*****	*****
CCDATE	COPYCODE	01-03-31	16:39:51	BATCH02	*****	*****	*****
CDELDTLS	COPYCODE	01-03-31	16:39:53	BATCH02	*****	*****	*****
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12-							
----- END ----- STOP							

Field	Type	Description
ENV DEF (supplied)	N,S,P,O,D,M	The source Environment Definition for the report.
LIBRARY (supplied)	N,S	The library containing the NATURAL objects or SYSERR messages.
OBJECT (supplied)	N,S,P,O,D,M	The name of the NATURAL object, PREDICT object, 3GL/OTHER object, or SYSERR message.
OBJECT TYPE (supplied)	N	The NATURAL object type
	PARAM	Indicates Parameter data area.
	COPYCODE	Indicates Copycode.
	GLOBAL	Indicates Global data area.
	HELP-RTN	Indicates Helproutine.
	LOCAL	Indicates Local data area.
	MAP	Indicates Map.
	SUB-PGM	Indicates Subprogram.
	PROGRAM	Indicates Program.
	SUB-RTN	Indicates Subroutine.
	TEXT	Indicates Text.
	MACRO	Indicates Macro.
	REPORT	Indicates Report.
	EXP-MDL	Indicates ExpertModel.
	RECORD	Indicates Recording.
	DIALOG	Indicates Dialog.
	CLASS	Indicates Class.
	CMD-PROC	Indicates Processor.
	SERVER	Indicates Server.
	FUNCTION.	Indicates Function.
	ADAPTER.	Indicates Adapter.
	MACRO.	Indicates Macro.

(continued from previous page)

Field	Type	Description																																																																								
	P	PREDICT object type																																																																								
		<table><tr><th>Type</th><th>Indicates</th><th>Predict Version</th></tr><tr><td>DA</td><td>Database</td><td></td></tr><tr><td>DC</td><td>Dataspace</td><td></td></tr><tr><td>ET</td><td>Extract</td><td></td></tr><tr><td>FI</td><td>File</td><td></td></tr><tr><td>IE</td><td>Interface</td><td>V4.1.2 and above</td></tr><tr><td>KY</td><td>Keyword</td><td></td></tr><tr><td>LS</td><td>Library Structure</td><td></td></tr><tr><td>MD</td><td>Method</td><td>V4.1.2 and above</td></tr><tr><td>MO</td><td>Module</td><td>V3.4.2 and below</td></tr><tr><td>NO</td><td>Node</td><td></td></tr><tr><td>NW</td><td>Network</td><td></td></tr><tr><td>PG</td><td>PackageList</td><td></td></tr><tr><td>PR</td><td>Program</td><td></td></tr><tr><td>PY</td><td>Property</td><td>V4.1.2 and above</td></tr><tr><td>RL</td><td>Relationship</td><td></td></tr><tr><td>RP</td><td>Report</td><td>V3.4.2 and below</td></tr><tr><td>RT</td><td>Report Listing</td><td></td></tr><tr><td>SC</td><td>Storagespace</td><td></td></tr><tr><td>SV</td><td>Server</td><td></td></tr><tr><td>SY</td><td>System</td><td></td></tr><tr><td>US</td><td>User</td><td></td></tr><tr><td>VE</td><td>Verification</td><td></td></tr><tr><td>VM</td><td>Virtual Machine</td><td></td></tr></table>	Type	Indicates	Predict Version	DA	Database		DC	Dataspace		ET	Extract		FI	File		IE	Interface	V4.1.2 and above	KY	Keyword		LS	Library Structure		MD	Method	V4.1.2 and above	MO	Module	V3.4.2 and below	NO	Node		NW	Network		PG	PackageList		PR	Program		PY	Property	V4.1.2 and above	RL	Relationship		RP	Report	V3.4.2 and below	RT	Report Listing		SC	Storagespace		SV	Server		SY	System		US	User		VE	Verification		VM	Virtual Machine	
Type	Indicates	Predict Version																																																																								
DA	Database																																																																									
DC	Dataspace																																																																									
ET	Extract																																																																									
FI	File																																																																									
IE	Interface	V4.1.2 and above																																																																								
KY	Keyword																																																																									
LS	Library Structure																																																																									
MD	Method	V4.1.2 and above																																																																								
MO	Module	V3.4.2 and below																																																																								
NO	Node																																																																									
NW	Network																																																																									
PG	PackageList																																																																									
PR	Program																																																																									
PY	Property	V4.1.2 and above																																																																								
RL	Relationship																																																																									
RP	Report	V3.4.2 and below																																																																								
RT	Report Listing																																																																									
SC	Storagespace																																																																									
SV	Server																																																																									
SY	System																																																																									
US	User																																																																									
VE	Verification																																																																									
VM	Virtual Machine																																																																									
	O	3GL category																																																																								
		<table><tr><td>ASMB</td><td>Indicates Assembler.</td></tr><tr><td>COBOL</td><td>Indicates COBOL.</td></tr><tr><td>FORT</td><td>Indicates FORTRAN.</td></tr><tr><td>PL/I</td><td>Indicates PL/I.</td></tr><tr><td>RPG</td><td>Indicates RPG.</td></tr><tr><td>DATA</td><td>Indicates DATA FILES.</td></tr><tr><td>JCL</td><td>Indicates JCL.</td></tr><tr><td>OTHER</td><td>Indicates all other objects.</td></tr></table>	ASMB	Indicates Assembler.	COBOL	Indicates COBOL.	FORT	Indicates FORTRAN.	PL/I	Indicates PL/I.	RPG	Indicates RPG.	DATA	Indicates DATA FILES.	JCL	Indicates JCL.	OTHER	Indicates all other objects.																																																								
ASMB	Indicates Assembler.																																																																									
COBOL	Indicates COBOL.																																																																									
FORT	Indicates FORTRAN.																																																																									
PL/I	Indicates PL/I.																																																																									
RPG	Indicates RPG.																																																																									
DATA	Indicates DATA FILES.																																																																									
JCL	Indicates JCL.																																																																									
OTHER	Indicates all other objects.																																																																									
SOURCE DATE (supplied)	N	The date the source code was saved.																																																																								
SOURCE TIME (supplied)	N	The time the source code was saved.																																																																								
SOURCE USER-ID (supplied)	N	The User-ID of the user who saved the source code.																																																																								

(continued from previous page)

Field	Type	Description
OBJECT DATE (supplied)	N	The date the object code was compiled.
OBJECT TIME (supplied)	N	The time the object code was compiled.
OBJECT USER-ID (supplied)	N	The User-ID of the user who compiled the object code.
SYSERR LANGUAGE (supplied)	S	The SYSERR languages available for the SYSERR message.
FILE TYPE (supplied)	P	The PREDICT file type (e.g., A is ADABAS, U is ADABAS Userview, etc.). Only displays when object type "FI" is selected.
DATE (supplied)	P	The date the PREDICT object was saved.
CATEGORY (supplied)	O	The 3GL/OTHER Category of the 3GL/OTHER objects.
DDM Dbid (supplied)	D	Database number that the DDM will point to.
DDM Fnr (supplied)	D	File number that the DDM will point to.
DDM ADA 6 Support (supplied)	D	Marked with an X if the DDM was created in NATURAL 2.3 or above and will allow a Dbid and/or Fnr greater than 255.
Description (supplied)	M	Description of the UDE – User Defined Entities

IV.4.4 **Directory Compare**

The Directory Compare report displays the differences between two environments.

To display the Directory Compare input screen for NATURAL objects, enter "D" in the Enter Code field and "N" in the Type field on the Object Reporting menu.

01-12-31 11:38:00	N-2-O OBJECT REPORTING DIRECTORY COMPARE	TSI0373 TSI1
<div style="display: flex; justify-content: space-around;"> <div>Env Def</div> <div>: _____</div> <div>Base</div> <div>_____</div> <div>Compare</div> <div>_____</div> </div>		
Library : _____		
Source/Object : _____		
Starting Value: _____		
Ending Value : _____		
Verify Timestamps: N		
Verify Existence : N		
Mode : O		
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12--- HELP ---- END ----		

Field	Type	Description
∞ ENV DEF (required)	N,S,P,O,D,M	The Environment Definitions serving as the source for the report.
LIBRARY (required)	N,S	The libraries containing the NATURAL objects or SYSERR messages.
SOURCE/ OBJECT (required)	N	The forms of the NATURAL objects to be compared: S Indicates source code. C Indicates object code.
STARTING VALUE (optional)	N,S,P,O,D,M	The starting value of the object list.
ENDING VALUE (optional)	N,S,P,O,D,M	The ending value of the object list.
VERIFY TIMESTAMPS (required)	N,P	Limits the report to objects that have different dates and times (defaults to "N").
VERIFY EXISTENCE (required)	N,S,P,O,D,M	Limits the report to objects that exist in one environment but not in another environment (defaults to "N").

∞ indicates field-level help is available.

(continued from previous page)

Field	Type	Description																																																																								
MODE (required)	N,S,P,O	Indicates how the job is executed (batch or on-line). B Submits JCL to the internal reader that processes the function in batch. O Processes the function on-line (Default: O).																																																																								
∞ OBJECT TYPE (required)	P	The PREDICT object type for PREDICT objects Valid values are as follows: <table><tr><th>Type</th><th>Indicates</th><th>Predict Version</th></tr><tr><td>DA</td><td>Database</td><td></td></tr><tr><td>DC</td><td>Dataspace</td><td></td></tr><tr><td>ET</td><td>Extract</td><td></td></tr><tr><td>FI</td><td>File</td><td></td></tr><tr><td>IE</td><td>Interface</td><td>V4.1.2 and above</td></tr><tr><td>KY</td><td>Keyword</td><td></td></tr><tr><td>LS</td><td>Library Structure</td><td></td></tr><tr><td>MD</td><td>Method</td><td>V4.1.2 and above</td></tr><tr><td>MO</td><td>Module</td><td>V3.4.2 and below</td></tr><tr><td>NO</td><td>Node</td><td></td></tr><tr><td>NW</td><td>Network</td><td></td></tr><tr><td>PG</td><td>PackageList</td><td></td></tr><tr><td>PR</td><td>Program</td><td></td></tr><tr><td>PY</td><td>Property</td><td>V4.1.2 and above</td></tr><tr><td>RL</td><td>Relationship</td><td></td></tr><tr><td>RP</td><td>Report</td><td>V3.4.2 and below</td></tr><tr><td>RT</td><td>Report Listing</td><td></td></tr><tr><td>SC</td><td>Storagespace</td><td></td></tr><tr><td>SV</td><td>Server</td><td></td></tr><tr><td>SY</td><td>System</td><td></td></tr><tr><td>US</td><td>User</td><td></td></tr><tr><td>VE</td><td>Verification</td><td></td></tr><tr><td>VM</td><td>Virtual Machine</td><td></td></tr></table>	Type	Indicates	Predict Version	DA	Database		DC	Dataspace		ET	Extract		FI	File		IE	Interface	V4.1.2 and above	KY	Keyword		LS	Library Structure		MD	Method	V4.1.2 and above	MO	Module	V3.4.2 and below	NO	Node		NW	Network		PG	PackageList		PR	Program		PY	Property	V4.1.2 and above	RL	Relationship		RP	Report	V3.4.2 and below	RT	Report Listing		SC	Storagespace		SV	Server		SY	System		US	User		VE	Verification		VM	Virtual Machine	
Type	Indicates	Predict Version																																																																								
DA	Database																																																																									
DC	Dataspace																																																																									
ET	Extract																																																																									
FI	File																																																																									
IE	Interface	V4.1.2 and above																																																																								
KY	Keyword																																																																									
LS	Library Structure																																																																									
MD	Method	V4.1.2 and above																																																																								
MO	Module	V3.4.2 and below																																																																								
NO	Node																																																																									
NW	Network																																																																									
PG	PackageList																																																																									
PR	Program																																																																									
PY	Property	V4.1.2 and above																																																																								
RL	Relationship																																																																									
RP	Report	V3.4.2 and below																																																																								
RT	Report Listing																																																																									
SC	Storagespace																																																																									
SV	Server																																																																									
SY	System																																																																									
US	User																																																																									
VE	Verification																																																																									
VM	Virtual Machine																																																																									
∞ CATEGORY (required)	O	The 3GL/OTHER category for 3GL/OTHER objects. Valid values are as follows: ASMB Indicates Assembler. COBOL Indicates COBOL. FORT Indicates FORTRAN. PL/I Indicates PL/I types. RPG Indicates RPG. DATA Indicates DATA FILES. JCL Indicates JCL, CLIST, CNTL. OTHER Indicates all other types.																																																																								

∞ indicates field-level help is available.

Entering the necessary information in the input screen and pressing Enter displays the Directory Compare report.

01-12-31 11:38:00		N-2-O OBJECT REPORTING DIRECTORY COMPARE			TSIO373 TSI1 Page: 1		
		PAYD PAYDEV			PAYD PAYPROD		
Object	Object Type	Date	Time	User-ID	Date	Time	User-ID
ACE761	PROGRAM	01-09-30	14:47:47	TSIO376	*****	*****	*****
BENWORK	MAP	01-04-13	17:24:44	TSIO378	*****	*****	*****
BLOOM	PROGRAM	01-04-11	15:59:55	TSIO378	*****	*****	*****
PAYERRD	COPYCODE	01-03-31	16:39:48	BATCH02	01-01-31	17:42:06	BATCH01
PAYFREP	COPYCODE	01-03-31	16:39:49	BATCH02	01-01-31	17:42:13	BATCH01
PAYLSAVE	SUB-PGM	01-04-13	12:12:15	TSIO374	*****	*****	*****
PAYARCH	PROGRAM	01-03-20	15:36:07	TSIO374	*****	*****	*****
PAYR	PROGRAM	01-04-11	14:13:32	TSIO374	*****	*****	*****
PAYR	PROGRAM	01-03-30	17:01:40	TSIO374	*****	*****	*****
PAYR	PROGRAM	01-04-11	17:04:55	TSIO374	*****	*****	*****
PAY	COPYCODE	01-03-31	16:39:51	BATCH02	*****	*****	*****
PAYT	COPYCODE	*****	*****	*****	01-01-31	17:42:15	BATCH01
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---							
		END					
							STOP

Field	Type	Description
OBJECT (supplied)	N,S,P,O	The NATURAL object compiled by Autocompile.
OBJECT TYPE (supplied)	N	The NATURAL object type.
	PARM	Indicates Parameter data area.
	COPYCODE	Indicates Copycode.
	GLOBAL	Indicates Global data area.
	HELP-RTN	Indicates Helproutine.
	LOCAL	Indicates Local data area.
	MAP	Indicates Map.
	SUB-PGM	Indicates Subprogram.
	PROGRAM	Indicates Program.
	SUB-RTN	Indicates Subroutine.
	TEXT	Indicates Text.
	MACRO	Indicates Macro.
	REPORT	Indicates Report.
	EXP-MDL	Indicates ExpertModel.
	RECORD	Indicates Recording.
	DIALOG	Indicates Dialog.
	CLASS	Indicates Class.
	CMD-PROC	Indicates Processor.
	SERVER	Indicates Server.
	FUNCTION.	Indicates Function.
	ADAPTER.	Indicates Adapter.
	MACRO.	Indicates Macro.

(continued from previous page)

Field	Type	Description
	P	The PREDICT object type of the PREDICT objects.
		Type Indicates Predict Version
		DA Database
		DC Dataspace
		ET Extract
		FI File
		IE Interface V4.1.2 and above
		KY Keyword
		LS Library Structure
		MD Method V4.1.2 and above
		MO Module V3.4.2 and below
		NO Node
		NW Network
		PG PackageList
		PR Program
		PY Property V4.1.2 and above
		RL Relationship
		RP Report V3.4.2 and below
		RT Report Listing
		SC Storagespace
		SV Server
		SY System
		US User
		VE Verification
		VM Virtual Machine
	O	The actual object type of a category. Specific member types are determined when an object is enrolled.
		ASMB Indicates Assembler.
		COBOL Indicates COBOL.
		FORT Indicates FORTRAN.
		PL/I Indicates PL/I.
		RPG Indicates RPG.
		DATA Indicates DATA FILES.
		JCL Indicates JCL.
		OTHER Indicates all other objects.
SOURCE DATE (supplied)	N	The date the source code was saved.
SOURCE TIME (supplied)	N	The time the source code was saved.

(continued from previous page)

Field	Type	Description
SOURCE USER-ID (supplied)	N	The User-ID of the user who saved the source code.
OBJECT DATE (supplied)	N	The date the object code was compiled.
OBJECT TIME (supplied)	N	The time the object code was compiled.
OBJECT USER-ID (supplied)	N	The User-ID of the user who compiled the object code.
SYSERR LANGUAGE (supplied)	S	The languages found for the SYSERR message (e.g., E, F, G, etc.).
FILE TYPE (supplied)	P	The PREDICT file type (e.g., A is ADABAS, U is ADABAS userviews, etc.).
DATE (supplied)	P	The date the PREDICT object was saved.
CATEGORY (supplied)	O	The 3GL/OTHER category. ASMB Indicates Assembler. COBOL Indicates COBOL. FORT Indicates FORTRAN. PL/I Indicates PL/I. RPG Indicates RPG. DATA Indicates DATA FILES. JCL Indicates JCL. OTHER Indicates all other objects.
DDM Dbid (supplied)	D	Database number that the DDM will point to.
DDM Fnr (supplied)	D	File number that the DDM will point to.
DDM ADA 6 Support (supplied)	D	Marked with an X if the DDM was created in NATUR above and will allow a Dbid and/or Fnr greater than 2
Description (supplied)	M	Description of the UDE – User Defined Entities

IV.4.5 Cross-Reference

The Cross-Reference report identifies external references to programs of a NATURAL or 3GL object.

To display the Cross-Reference input screen for NATURAL objects, enter "E" in the Enter Code field and "N" in the Type field on the Object Reporting menu.

01-12-31 11:38:00	N-2-O OBJECT REPORTING CROSS REFERENCE	TSI0373 TSI1
<p>Env Def: _____ Library: _____ Object : _____ Mode : O</p>		
<p>Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12--- HELP ---- END ----</p>		

Field	Type	Description
∞ ENV DEF (required)	N,O	An environment defined to N2O.
LIBRARY (required)	N	The library containing the NATURAL object.
OBJECT (required)	N,O	The NATURAL or 3GL/OTHER object.
MODE (required)	N,O	Indicates how the job is executed (batch or on-line). B Submits JCL to the internal reader that processes the function in batch. O Processes the function on-line (Default: O).
∞ CATEGORY (required)	O	Identifies the 3GL/OTHER category for 3GL/OTHER objects. Valid values are as follows: ASMB Indicates all types of Assembler. COBOL Indicates all types of COBOL. FORT Indicates all types of FORTRAN. PL/I Indicates all PL/I types. RPG Indicates RPG. DATA Indicates DATA FILES. JCL Indicates JCL, CLIST, CNTL. OTHER Indicates all other types.

∞ indicates field-level help is available.

Entering the necessary information in the input screen and pressing Enter displays the Cross-Reference report.

```

Press ENTER to display invoked programs
01-12-31      N-2-O OBJECT REPORTING      TSI0373
11:38:00      CROSS REFERENCE              TSI1
                                           Page: 1

      The following programs are affected by changes to MENU

      PAYMENU      PAYERROR      PAYREAD

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
-----      END      -----      STOP

```

A list of affected programs is displayed.

If source is available, pressing enter displays a list of invoked, stacked and called programs.

```

Press ENTER to display invoked programs
01-12-31      N-2-O OBJECT REPORTING      TSI0373
11:38:00      CROSS REFERENCE              TSI1
                                           Page: 2

      The following programs are invoked by MENU

      N20111N      N20112N      N20113N      N20114N      N20115N      N20116N
      N20116N      N20117N      N20118N      N20119N      N20120N      PAYREAD
      PAYERROR

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
-----      END      -----      STOP

```


IV.4.6 Checked-out Objects

The Checked-out Objects report displays objects checked out from a BASE environment or all BASE environments. This report identifies programs a user has checked out.

To display the Checked-out Objects input screen for NATURAL objects, enter "F" in the Enter Code field and "N" in the Type field on the Object Reporting menu.

01-12-31 11:38:00	N-2-O OBJECT REPORTING CHECKED-OUT OBJECTS	TSI0373 TSI1
<p>BASE Env : _____</p> <p>BASE Library : _____</p> <p>Object : _____</p> <p>Current Env : _____</p> <p>Current Library : _____</p> <p>Checkout User-ID: TSI0373__</p> <p>Checkout Date : _____</p> <p>Mode : 0</p>		
<p>Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---</p> <p>HELP ---- END ----</p>		

Field	Type	Description
∞ BASE ENV (optional)	N,S,P,O,D,M	The Environment Definition used to check out objects. When blank, all objects checked out to the specified user-ID will be reported.
BASE LIBRARY (optional)	N,S	Limits the report to NATURAL objects or SYSERR messages checked out of the BASE library.
OBJECT (optional)	N,S,P,O,D,M	Limits the report to the NATURAL objects, PREDICT objects, 3GL/OTHER objects, or SYSERR messages specified. An (*) may be used as a wildcard character to start the report with objects prefixed by a string.
∞ CURRENT ENV (optional)	N,S,P,O,D,M	Limits the report to objects checked out to an Environment Definition.
CURRENT LIBRARY (optional)	N,S	Limits the report to NATURAL objects or SYSERR messages checked out to a library.
∞ CHECKOUT USER-ID (optional)	N,S,P,O,D,M	Limits the report to objects checked out by the user with the specified User-ID. (Defaults to current User-ID)
CHECKOUT DATE (optional)	N,S,P,O, ,D,M	Limits the report to objects checked out on the specified date. Dates must be formatted YYYYMMDD.

∞ indicates field-level help is available.

(continued from previous page)

Field	Type	Description																																																																								
MODE (required)	N,S,P,O,D,M	Indicates how the job is executed (batch or on-line). B Submits JCL to the internal reader that processes the function in batch. O Processes the function on-line (Default: O).																																																																								
∞ OBJECT TYPE (required)	P	Identifies the PREDICT object type for PREDICT objects. Valid values are as follows: <table><tr><th>Type</th><th>Indicates</th><th>Predict Version</th></tr><tr><td>DA</td><td>Database</td><td></td></tr><tr><td>DC</td><td>Dataspace</td><td></td></tr><tr><td>ET</td><td>Extract</td><td></td></tr><tr><td>FI</td><td>File</td><td></td></tr><tr><td>IE</td><td>Interface</td><td>V4.1.2 and above</td></tr><tr><td>KY</td><td>Keyword</td><td></td></tr><tr><td>LS</td><td>Library Structure</td><td></td></tr><tr><td>MD</td><td>Method</td><td>V4.1.2 and above</td></tr><tr><td>MO</td><td>Module</td><td>V3.4.2 and below</td></tr><tr><td>NO</td><td>Node</td><td></td></tr><tr><td>NW</td><td>Network</td><td></td></tr><tr><td>PG</td><td>PackageList</td><td></td></tr><tr><td>PR</td><td>Program</td><td></td></tr><tr><td>PY</td><td>Property</td><td>V4.1.2 and above</td></tr><tr><td>RL</td><td>Relationship</td><td></td></tr><tr><td>RP</td><td>Report</td><td>V3.4.2 and below</td></tr><tr><td>RT</td><td>Report Listing</td><td></td></tr><tr><td>SC</td><td>Storagespace</td><td></td></tr><tr><td>SV</td><td>Server</td><td></td></tr><tr><td>SY</td><td>System</td><td></td></tr><tr><td>US</td><td>User</td><td></td></tr><tr><td>VE</td><td>Verification</td><td></td></tr><tr><td>VM</td><td>Virtual Machine</td><td></td></tr></table>	Type	Indicates	Predict Version	DA	Database		DC	Dataspace		ET	Extract		FI	File		IE	Interface	V4.1.2 and above	KY	Keyword		LS	Library Structure		MD	Method	V4.1.2 and above	MO	Module	V3.4.2 and below	NO	Node		NW	Network		PG	PackageList		PR	Program		PY	Property	V4.1.2 and above	RL	Relationship		RP	Report	V3.4.2 and below	RT	Report Listing		SC	Storagespace		SV	Server		SY	System		US	User		VE	Verification		VM	Virtual Machine	
Type	Indicates	Predict Version																																																																								
DA	Database																																																																									
DC	Dataspace																																																																									
ET	Extract																																																																									
FI	File																																																																									
IE	Interface	V4.1.2 and above																																																																								
KY	Keyword																																																																									
LS	Library Structure																																																																									
MD	Method	V4.1.2 and above																																																																								
MO	Module	V3.4.2 and below																																																																								
NO	Node																																																																									
NW	Network																																																																									
PG	PackageList																																																																									
PR	Program																																																																									
PY	Property	V4.1.2 and above																																																																								
RL	Relationship																																																																									
RP	Report	V3.4.2 and below																																																																								
RT	Report Listing																																																																									
SC	Storagespace																																																																									
SV	Server																																																																									
SY	System																																																																									
US	User																																																																									
VE	Verification																																																																									
VM	Virtual Machine																																																																									
∞ CATEGORY (required)	O	Identifies the 3GL/OTHER category for 3GL/OTHER objects. Valid values are as follows: <table><tr><td>ASMB</td><td>Indicates Assembler.</td></tr><tr><td>COBOL</td><td>Indicates COBOL.</td></tr><tr><td>FORT</td><td>Indicates FORTRAN.</td></tr><tr><td>PL/I</td><td>Indicates PL/I types.</td></tr><tr><td>RPG</td><td>Indicates RPG.</td></tr><tr><td>DATA</td><td>Indicates DATA FILES.</td></tr><tr><td>JCL</td><td>Indicates JCL, CLIST, CNTL.</td></tr><tr><td>OTHER</td><td>Indicates all other types.</td></tr></table>	ASMB	Indicates Assembler.	COBOL	Indicates COBOL.	FORT	Indicates FORTRAN.	PL/I	Indicates PL/I types.	RPG	Indicates RPG.	DATA	Indicates DATA FILES.	JCL	Indicates JCL, CLIST, CNTL.	OTHER	Indicates all other types.																																																								
ASMB	Indicates Assembler.																																																																									
COBOL	Indicates COBOL.																																																																									
FORT	Indicates FORTRAN.																																																																									
PL/I	Indicates PL/I types.																																																																									
RPG	Indicates RPG.																																																																									
DATA	Indicates DATA FILES.																																																																									
JCL	Indicates JCL, CLIST, CNTL.																																																																									
OTHER	Indicates all other types.																																																																									

∞ indicates field-level help is available.

Entering the necessary information in the input screen and pressing Enter displays the Checked-out Objects report. When a BASE environment is specified on the Checked-Out Objects Input screen, the following report is generated.

Type X to display additional details									
01-12-31		N-2-O OBJECT REPORTING						TSI0373	
11:38:00		CHECKED-OUT OBJECTS						TSI1	
								Page: 1	
X	Object	Object Type	Checkout User-ID	--- BASE --- Env Library	- Previous - Env Library	-- Current -- Env Library	-- Library		
-	-----	-----	-----	-----	-----	-----	-----	-----	
-	CMIGUTIL	COPYCODE	TREE06	PROD PAYPROD	DEV PAYDEV	TEST	PAYTEST		
-	PAYDCOCI	PROGRAM	TREE06	PROD PAYPROD	PROD PAYPROD	DEV	PAYDEV		
-	PAYENVA	PROGRAM	TREE06	PROD PAYPROD	DEV PAYDEV	TEST	PAYTEST		
-	PAYENVB	PROGRAM	TREE06	PROD PAYPROD	DEV PAYDEV	TEST	PAYTEST		
-	PAYENVC	PROGRAM	TREE06	PROD PAYPROD	DEV PAYDEV	TEST	PAYTEST		
-	PAYENVV	PROGRAM	TREE06	PROD PAYPROD	DEV PAYDEV	TEST	PAYTEST		
-	PAYENVE	PROGRAM	TREE06	PROD PAYPROD	DEV PAYDEV	TEST	PAYTEST		
-	PAYEVNTA	PROGRAM	TREE06	PROD PAYPROD	DEV PAYDEV	TEST	PAYTEST		
-	PAYEVNTB	PROGRAM	TREE06	PROD PAYPROD	DEV PAYDEV	TEST	PAYTEST		
-	PAYEVNTC	PROGRAM	TREE06	PROD PAYPROD	DEV PAYDEV	TEST	PAYTEST		
-	PAYEVNTD	PROGRAM	TREE06	PROD PAYPROD	DEV PAYDEV	TEST	PAYTEST		
-	PAYEVNTE	PROGRAM	TREE06	PROD PAYPROD	DEV PAYDEV	TEST	PAYTEST		
-	PAYEVNTF	PROGRAM	TREE06	PROD PAYPROD	DEV PAYDEV	TEST	PAYTEST		
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---									
-----				END	-----	-----	-----	-----	STOP

Field	Type	Description
X	N,S,P,O,D,M	"X" selects an object for additional details.
(optional)		
OBJECT	N,S,P,O,D,M	The DDMS, METADATA, NATURAL object, PREDICT object, 3GL/OTHER object, or SYSERR message.
(supplied)		
OBJECT TYPE	N	The NATURAL object type.
(supplied)		
		PARM Indicates Parameter data area. COPYCODE Indicates Copycode. GLOBAL Indicates Global data area. HELP-RTN Indicates Helproutine. LOCAL Indicates Local data area. MAP Indicates Map. SUB-PGM Indicates Subprogram. PROGRAM Indicates Program. SUB-RTN Indicates Subroutine. TEXT Indicates Text. MACRO Indicates Macro. REPORT Indicates Report. EXP-MDL Indicates ExpertModel. RECORD Indicates Recording. DIALOG Indicates Dialog. CLASS Indicates Class. CMD-PROC Indicates Processor. SERVER Indicates Server. FUNCTION. Indicates Function. ADAPTER. Indicates Adapter. MACRO. Indicates Macro.
	S	The SYSERR messages (e.g., E, G, F, etc.).

(continued from previous page)

Field	Type	Description																																																																								
	P	The PREDICT object type.																																																																								
		<table> <tr> <th>Type</th><th>Indicates</th><th>Predict Version</th></tr> <tr><td>DA</td><td>Database</td><td></td></tr> <tr><td>DC</td><td>Dataspace</td><td></td></tr> <tr><td>ET</td><td>Extract</td><td></td></tr> <tr><td>FI</td><td>File</td><td></td></tr> <tr><td>IE</td><td>Interface</td><td>V4.1.2 and above</td></tr> <tr><td>KY</td><td>Keyword</td><td></td></tr> <tr><td>LS</td><td>Library Structure</td><td></td></tr> <tr><td>MD</td><td>Method</td><td>V4.1.2 and above</td></tr> <tr><td>MO</td><td>Module</td><td>V3.4.2 and below</td></tr> <tr><td>NO</td><td>Node</td><td></td></tr> <tr><td>NW</td><td>Network</td><td></td></tr> <tr><td>PG</td><td>PackageList</td><td></td></tr> <tr><td>PR</td><td>Program</td><td></td></tr> <tr><td>PY</td><td>Property</td><td>V4.1.2 and above</td></tr> <tr><td>RL</td><td>Relationship</td><td></td></tr> <tr><td>RP</td><td>Report</td><td>V3.4.2 and below</td></tr> <tr><td>RT</td><td>Report Listing</td><td></td></tr> <tr><td>SC</td><td>Storagespace</td><td></td></tr> <tr><td>SV</td><td>Server</td><td></td></tr> <tr><td>SY</td><td>System</td><td></td></tr> <tr><td>US</td><td>User</td><td></td></tr> <tr><td>VE</td><td>Verification</td><td></td></tr> <tr><td>VM</td><td>Virtual Machine</td><td></td></tr> </table>	Type	Indicates	Predict Version	DA	Database		DC	Dataspace		ET	Extract		FI	File		IE	Interface	V4.1.2 and above	KY	Keyword		LS	Library Structure		MD	Method	V4.1.2 and above	MO	Module	V3.4.2 and below	NO	Node		NW	Network		PG	PackageList		PR	Program		PY	Property	V4.1.2 and above	RL	Relationship		RP	Report	V3.4.2 and below	RT	Report Listing		SC	Storagespace		SV	Server		SY	System		US	User		VE	Verification		VM	Virtual Machine	
Type	Indicates	Predict Version																																																																								
DA	Database																																																																									
DC	Dataspace																																																																									
ET	Extract																																																																									
FI	File																																																																									
IE	Interface	V4.1.2 and above																																																																								
KY	Keyword																																																																									
LS	Library Structure																																																																									
MD	Method	V4.1.2 and above																																																																								
MO	Module	V3.4.2 and below																																																																								
NO	Node																																																																									
NW	Network																																																																									
PG	PackageList																																																																									
PR	Program																																																																									
PY	Property	V4.1.2 and above																																																																								
RL	Relationship																																																																									
RP	Report	V3.4.2 and below																																																																								
RT	Report Listing																																																																									
SC	Storagespace																																																																									
SV	Server																																																																									
SY	System																																																																									
US	User																																																																									
VE	Verification																																																																									
VM	Virtual Machine																																																																									
CHECKOUT USER-ID (supplied)	N,S,P,O	The User-ID of the user who has the object checked-out.																																																																								
BASE ENV (supplied)	N,S,P,O	The BASE Environment Definition.																																																																								
BASE LIBRARY (supplied)	N,S	The BASE library.																																																																								
PREVIOUS ENV (supplied)	N,S,P,O	The previous checkout Environment Definition.																																																																								
PREVIOUS LIBRARY (supplied)	N,S	The previous checkout library.																																																																								
CURRENT ENV (supplied)	N,S,P,O	The current checkout Environment Definition.																																																																								

(continued from previous page)

Field	Type	Description
CURRENT LIBRARY (supplied)	N,S	The current checkout library.
CATEGORY (supplied)	O	The 3GL/OTHER category.
		ASMB Indicates Assembler.
		COBOL Indicates COBOL.
		FORT Indicates FORTRAN.
		PL/I Indicates PL/I.
		RPG Indicates RPG.
		DATA Indicates DATA FILES.
		JCL Indicates JCL.
		OTHER Indicates All other objects.

Selecting an object on the previous screen (using an 'X') and pressing Enter displays additional details for a checked-out object.

01-12-31 11:38:00		N-2-O OBJECT REPORTING CHECKED-OUT OBJECTS				TSI0373 TSI1	
Object	Object Type	Checkout User-ID	Env	BASE Library	-- Previous Env	-- Current Env	
CDELDTLS	COPYCODE	TREE06	PROD	PAYPROD	DEV	PAYDEV	TEST PAYTEST
----- Checkout -----							
		Event	Sequence	Date	Time		
		PAYOUT	232	01-03-29	08:34:19		
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---							
----- END ----- STOP							

Field	Type	Description
OBJECT (supplied)	N,S,P,O, D,M	The NATURAL object, PREDICT object, 3GL/OTHER object, or SYSERR message.
OBJECT TYPE (supplied)	N	The NATURAL object type.
	PARM	Indicates Parameter data area.
	COPYCODE	Indicates Copycode.
	GLOBAL	Indicates Global data area.
	HELP-RTN	Indicates Helproutine.
	LOCAL	Indicates Local data area.
	MAP	Indicates Map.
	SUB-PGM	Indicates Subprogram.
	PROGRAM	Indicates Program.
	SUB-RTN	Indicates Subroutine.
	TEXT	Indicates Text.
	MACRO	Indicates Macro.
	REPORT	Indicates Report.
	EXP-MDL	Indicates ExpertModel.
	RECORD	Indicates Recording.
	DIALOG	Indicates Dialog.
	CLASS	Indicates Class.
	CMD-PROC	Indicates Processor.
	SERVER	Indicates Server.
	FUNCTION.	Indicates Function.
	ADAPTER.	Indicates Adapter.
	MACRO.	Indicates Macro.
CHECKOUT USER-ID (supplied)	N,S,P,O,D,M	The User-ID of the user who has the object checked-out.
BASE ENV (supplied)	N,S,P,O,D,M	The BASE Environment Definition.

(continued from previous page)

Field	Type	Description
BASE LIBRARY (supplied)	N,S	The BASE library.
PREVIOUS ENV (supplied)	N,S,P,O,D,M	The previous checkout Environment Definition.
PREVIOUS LIBRARY (supplied)	N,S	The previous checkout library.
CURRENT ENV (supplied)	N,S,P,O, ,D,M	The current checkout Environment Definition.
CURRENT LIBRARY (supplied)	N,S	The current checkout library.
CHECKOUT EVENT (supplied)	N,S,P,O, ,D,M	The Master Event that checked out the object.
CHECKOUT SEQUENCE (supplied)	N,S,P,O, ,D,M	The sequence number of the Event used to check out the utility.
CHECKOUT DATE (supplied)	N,S,P,O, ,D,M	The date the object was checked out.
CHECKOUT TIME (supplied)	N,S,P,O,D,M	The time the object was checked out.
CATEGORY (supplied)	O	The 3GL/OTHER category. ASMB Indicates Assembler. COBOL Indicates COBOL. FORT Indicates FORTRAN. PL/I Indicates PL/I. RPG Indicates RPG. DATA Indicates DATA FILES. JCL Indicates JCL. OTHER Indicates all other objects.

When no BASE Environment is specified on the Checked-Out Objects Input screen, the user is notified with the following message:

```

01-12-31          N-2-O OBJECT REPORTING          TSI0373
11:38:00          CHECKED-OUT OBJECTS              TSI1

      |-----|
      | NO BASE ENVIRONMENT SPECIFIED.              |
      | ALL OBJECTS IN ALL ENVIRONMENTS              |
      | WILL BE DISPLAYED FOR USER MLS1 .            |
      | HIT ENTER TO CONTINUE OR PF3 TO EXIT.        |
      |-----|

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      HELP  ----  END   ----  ----  ----  ----  ----  ----  ----  ----  ----

```

Pressing PF3 returns the user to the Checked-Out Objects entry screen. Pressing enter generates the following report of all checked-out objects in all environments for a User-Id:

```

01-12-31          N-2-O Object Reporting          TSI0373
11:38:00          All Checked Out Objects for      TSI1
                  User Id:  MLS1                  Page: 1

      Typ --- Base ---- -- Current -- -- Checkout --
      Object Name  Env  Library  Env  Library  Event  Seq
-----
PAY0001           S  PROD PAYPROD  DEV  PAYDEV  PAYOUT  29
PAY0002           P  PROD PAYPROD  DEV  PAYDEV  PAYOUT  29
PAY0003           P  PROD PAYPROD  DEV  PAYDEV1 PAYOUT  1

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      ----  ----  END   ----  ----  ----  ----  ----  ----  ----  STOP

```


Field	Type	Description
USER ID (supplied)	N,S,P,O, ,D,M	The User-ID of the user who has the object checked-out.
OBJECT NAME (supplied)	N,S,P,O, ,D,M	The DDMS, METADATA, NATURAL object, PREDICT object, 3GL/OTHER object, or SYSERR message.
TYP (supplied)	N	<p>The NATURAL object type.</p> <p>A Indicates Parameter data area.</p> <p>C Indicates Copycode.</p> <p>G Indicates Global data area.</p> <p>H Indicates Helproutine.</p> <p>L Indicates Local data area.</p> <p>M Indicates Map.</p> <p>N Indicates Subprogram.</p> <p>P Indicates Program.</p> <p>S Indicates Subroutine.</p> <p>T Indicates Text.</p> <p>O Indicates Macro.</p> <p>R Indicates Report.</p> <p>Y Indicates ExpertModel.</p> <p>Z Indicates Recording.</p> <p>3 Indicates Dialog.</p> <p>4 Indicates Class.</p> <p>5 Indicates Processor.</p> <p>K Indicates Server.</p> <p>7 Indicates Function.</p> <p>8 Indicates Adapter.</p> <p>O Indicates Macro.</p>
	S	The SYSERR messages (e.g., E, G, F, etc.).

(continued from previous page)

Field	Type	Description																																																																								
	P	The PREDICT object type.																																																																								
		<table> <tr> <th>Type</th><th>Indicates</th><th>Predict Version</th></tr> <tr><td>DA</td><td>Database</td><td></td></tr> <tr><td>DC</td><td>Dataspace</td><td></td></tr> <tr><td>ET</td><td>Extract</td><td></td></tr> <tr><td>FI</td><td>File</td><td></td></tr> <tr><td>IE</td><td>Interface</td><td>V4.1.2 and above</td></tr> <tr><td>KY</td><td>Keyword</td><td></td></tr> <tr><td>LS</td><td>Library Structure</td><td></td></tr> <tr><td>MD</td><td>Method</td><td>V4.1.2 and above</td></tr> <tr><td>MO</td><td>Module</td><td>V3.4.2 and below</td></tr> <tr><td>NO</td><td>Node</td><td></td></tr> <tr><td>NW</td><td>Network</td><td></td></tr> <tr><td>PG</td><td>PackageList</td><td></td></tr> <tr><td>PR</td><td>Program</td><td></td></tr> <tr><td>PY</td><td>Property</td><td>V4.1.2 and above</td></tr> <tr><td>RL</td><td>Relationship</td><td></td></tr> <tr><td>RP</td><td>Report</td><td>V3.4.2 and below</td></tr> <tr><td>RT</td><td>Report Listing</td><td></td></tr> <tr><td>SC</td><td>Storagespace</td><td></td></tr> <tr><td>SV</td><td>Server</td><td></td></tr> <tr><td>SY</td><td>System</td><td></td></tr> <tr><td>US</td><td>User</td><td></td></tr> <tr><td>VE</td><td>Verification</td><td></td></tr> <tr><td>VM</td><td>Virtual Machine</td><td></td></tr> </table>	Type	Indicates	Predict Version	DA	Database		DC	Dataspace		ET	Extract		FI	File		IE	Interface	V4.1.2 and above	KY	Keyword		LS	Library Structure		MD	Method	V4.1.2 and above	MO	Module	V3.4.2 and below	NO	Node		NW	Network		PG	PackageList		PR	Program		PY	Property	V4.1.2 and above	RL	Relationship		RP	Report	V3.4.2 and below	RT	Report Listing		SC	Storagespace		SV	Server		SY	System		US	User		VE	Verification		VM	Virtual Machine	
Type	Indicates	Predict Version																																																																								
DA	Database																																																																									
DC	Dataspace																																																																									
ET	Extract																																																																									
FI	File																																																																									
IE	Interface	V4.1.2 and above																																																																								
KY	Keyword																																																																									
LS	Library Structure																																																																									
MD	Method	V4.1.2 and above																																																																								
MO	Module	V3.4.2 and below																																																																								
NO	Node																																																																									
NW	Network																																																																									
PG	PackageList																																																																									
PR	Program																																																																									
PY	Property	V4.1.2 and above																																																																								
RL	Relationship																																																																									
RP	Report	V3.4.2 and below																																																																								
RT	Report Listing																																																																									
SC	Storagespace																																																																									
SV	Server																																																																									
SY	System																																																																									
US	User																																																																									
VE	Verification																																																																									
VM	Virtual Machine																																																																									
BASE ENV (supplied)	N,S,P,O,D,M	The BASE Environment Definition.																																																																								
BASE LIBRARY (supplied)	N,S	The BASE library.																																																																								
CURRENT ENV (supplied)	N,S,P,O,D,M	The current checkout Environment Definition.																																																																								
CURRENT LIBRARY (supplied)	N,S	The current checkout library.																																																																								
CHECKOUT EVENT (supplied)	N,S,P,O,D,M	The Event or Utility used to check out the object.																																																																								
CHECKOUT SEQ (supplied)	N,S,P,O,D,M	The Sequence Number associated with the Check-out Event.																																																																								

IV.4.7 Objects Archived by N2OPURGE

The Objects Archived by N2OPURGE report displays NATURAL objects archived using the N2OPURGE utility. This report is only available for NATURAL objects (N).

To display the Objects Archived by N2OPURGE input screen, enter "G" in the Enter Code field and "N" in the Type field on the Object Reporting menu.

01-12-31 11:38:00	N-2-O OBJECT REPORTING OBJECTS ARCHIVED BY N2OPURGE	TSI0373 TSI1
<p>Object : _____</p> <p>Env Def : _____</p> <p>Library : _____</p> <p>Date Range: _____ - _____</p> <p>Mode : 0</p>		
<p>Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---</p> <p>HELP ---- END ----</p>		

Field	Type	Description
OBJECT (optional)	N	The name of a NATURAL object.
∞ ENV DEF (optional)	N	The Environment Definition that contained the NATURAL object.
LIBRARY (optional)	N	The library that contained the NATURAL object.
DATE RANGE (optional)	N	Limits the report to objects migrated within the specified range of dates. Dates must be formatted YYYYMMDD.
MODE (required)	N	Indicates how the job is executed (batch or on-line).
	B	Submits JCL to the internal reader that processes the function in batch.
	O	Processes the function on-line (Default: O).

∞ indicates field-level help is available.

Entering the necessary information in the input screen and pressing Enter displays the Objects Archived by N2OPURGE report.

01-12-31 11:38:00		N-2-O OBJECT REPORTING OBJECTS ARCHIVED BY N2OPURGE				TSI0373 TSI1 Page: 1	
S	Object	-----From-----		Arch	Arch	Date	Time
	Type	Env	Library	Def	S/C		
-	MENU	PROGRAM	TEST	PAYTEST	ARC1	S/C	01-08-19 17:10:08
-	MENU	PROGRAM	TEST	PAYTEST	ARC1	S	01-10-05 08:22:14
-	MENU	PROGRAM	DEV	PAYDEV	ARC1	S/C	01-11-15 15:50:43
-	MENU	PROGRAM	DEV	PAYDEV	ARC1	S	01-09-16 15:20:34
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---							
----- END ----- STOP							

Field	Type	Description
S	N	"X" selects an object for additional details.
(optional)		
OBJECT	N	The NATURAL object archived and deleted.
(supplied)		
OBJECT TYPE	N	The NATURAL object type.
(supplied)		
		PARM Indicates Parameter data area.
		COPYCODE Indicates Copycode.
		GLOBAL Indicates Global data area.
		HELP-RTN Indicates Helproutine.
		LOCAL Indicates Local data area.
		MAP Indicates Map.
		SUB-PGM Indicates Subprogram.
		PROGRAM Indicates Program.
		SUB-RTN Indicates Subroutine.
		TEXT Indicates Text.
		MACRO Indicates Macro.
		REPORT Indicates Report.
		EXP-MDL Indicates ExpertModel.
		RECORD Indicates Recording.
		DIALOG Indicates Dialog.
		CLASS Indicates Class.
		CMD-PROC Indicates Processor.
		SERVER Indicates Server.
		FUNCTION. Indicates Function.
		ADAPTER. Indicates Adapter.
		MACRO. Indicates Macro.
FROM ENV	N	The Environment Definition that contained the
(supplied)		NATURAL object.
FROM LIBRARY	N	The library that contained the NATURAL object.
(supplied)		

(continued from previous page)

Field	Type	Description
ARCH DEF (supplied)	N	The Archive Definition used to archive the NATURAL object.
ARCH S/C (supplied)	N	The form of the object archived and deleted. S Indicates only the source form of the program may be selected. C Indicates only the cataloged form of the program may be selected. S/C Indicates both forms of the program may be selected.
DATE (supplied)	N	The date the NATURAL object was archived and deleted.
TIME (supplied)	N	The time the NATURAL object was archived and deleted.

IV.4.8 Archive Version Summary

The Archive Version Summary report displays all Events that archived an object.

To display the Archive Version Summary input screen for NATURAL objects, enter "H" in the Enter Code field and "N" in the Type field on the Object Reporting menu.

01-12-31 11:38:00	N-2-O OBJECT REPORTING ARCHIVE VERSION SUMMARY	TSI0373 TSI1
<p>Object : _____</p> <p>Library : _____</p> <p>Date Range : _____ - _____</p> <p>Detailed Report: N (Batch Only)</p> <p>Mode : O</p>		
<p>Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---</p> <p>HELP ---- END ----</p>		

This report is only available for NATURAL objects (N), 3GL/OTHER members (O), and SYSERR messages (S).

Field	Type	Description
OBJECT (required)	N,S,O	Displays the archive history of a NATURAL object, PDS object, or SYSERR message.
LIBRARY (optional)	N,S	Limits the report to NATURAL objects or SYSERR messages for the specified library.
DATE RANGE (optional)	N,S,O	Limits the report to objects migrated within the range of dates. Dates must be formatted YYYYMMDD.
DETAILED REPORT (required)		<p>Indicates whether detailed information should be displayed when executed in batch.</p> <p>Y Display all detail information for reports when executed in batch (similar to entering X next to an object on the Archive Version Summary selection screen).</p> <p>N Display information similar to the Archive Version Summary selection screen (Default: N).</p>
MODE (required)	N,S,O	<p>Indicates how the job is executed (batch or on-line).</p> <p>B Submits JCL to the internal reader that processes the function in batch.</p> <p>O Processes the function on-line (Default: O).</p>

Entering the necessary information in the input screen and pressing Enter displays the Archive Version Summary selection screen.

Type X to display Event Details or Utility Details								
01-12-31			N-2-O OBJECT REPORTING				TSI0373	
11:38:00			ARCHIVE VERSION SUMMARY				TSI1	
			Object: PAYROLL				Page: 1	
X	Date	Event/ Utility	Seq	Change Control	From Env	To Env	Arch S/C	Added User-ID
-	-----	-----	-----	-----	-----	-----	-----	-----
-	01-11-01	PAYIN	99	*****	PROD	ARC1	S	TSI0374
-	01-11-01	EXTRACT	98	*****	TEST	ARC1	C	TSI0374
-	01-09-01	PAYTEST	1	*****	TEST	ARC1	S/C	TSI0375
-	01-09-25	PAYOUT	3307	*****	DEV	ARC1	S/C	TSI0374
-	01-07-10	PAYIN	3261	*****	PROD	ARC1	S/C	TSI0375
-	01-06-20	PAYTEST	3068	*****	TEST	ARC1	S/C	TSI0374
-	01-06-16	EXTRACT	1	*****	TEST	ARC1	S	TSI0375
-	01-05-20	PAYIN	70	*****	PROD	ARC1	S/C	TSI0375
-	01-05-14	PAYTEST	2697	*****	TEST	ARC1	S	TSI0374
-	01-04-22	PAYOUT	1924	*****	TEST	ARC1	S/C	TSI0375
-	01-03-04	EXTRACT	965	*****	TEST	ARC1	S	TSI0375
-	01-01-04	EXTRACT	964	*****	TEST	ARC1	S	TSI0374
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---								
			END	STOP				

Field	Type	Description
OBJECT (supplied)	N,S,O	The name of the object for executing this report.
X (optional)	N,S,O	"X" displays Event/Utility Details.
DATE (supplied)	N,S,O	The migration date of an Event or the date the utility was executed.
EVENT/ UTILITY (supplied)	N,S,O	The Master Event of the migration.
SEQ (supplied)	N,S,O	The sequence number of the Event.
CHANGE CONTROL (supplied)	N,S,O	A value that relates multiple Events to a specific change request.
FROM ENV (supplied)	N,S,O	The source Environment Definition of the Event.
TO ENV (supplied)	N,S,O	The target Environment Definition of the Event.

(continued from previous page)

Field	Type	Description
ARCH S/C (supplied)	N,S,O	The form of the object archived. S Indicates only the source form of the program may be selected. C Indicates only the cataloged form of the program may be selected. S/C Indicates both forms of the program may be selected.
ADDED USER-ID (supplied)	N,S,O	The user who added the Event or executed the utility.

IV.4.9 Events Pending for an Object

The Events Pending for an Object report displays all Events pending for an object.

To display the Events Pending for an Object input screen for NATURAL objects, enter "I" in the Enter Code field and "N" in the Type field on the Object Reporting menu and press Enter.

01-12-31 11:38:00	N-2-O OBJECT REPORTING EVENTS PENDING FOR AN OBJECT	TSI0373 TSI1
<p>Object : _____</p> <p>Added User-ID: _____</p> <p>Mode : O</p>		
<p>Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---</p> <p>HELP ---- END ----</p>		

Field	Type	Description
OBJECT (required)	N,S,P,O, ,D,M	The DDMS, METADATA, NATURAL object, PREDICT object, 3GL/OTHER object, or SYSERR message.
∞ ADDED USER-ID (optional)	N,S,P,O, ,D,M	Limits the report to Events added by a user with the specified User-ID.
MODE (required)	N,S,P,O, ,D,M	Indicates how the job is executed (batch or on-line). <div> <div>B</div> <div>Submits JCL to the internal reader that processes the function in batch.</div> </div> <div> <div>O</div> <div>Processes the function on-line (Default: O).</div> </div>

∞ indicates field-level help is available.

Entering the necessary information in the input screen and pressing Enter displays the Events Pending for an Object report.

01-12-31 11:38:00		N-2-O OBJECT REPORTING EVENTS PENDING FOR AN OBJECT Object: PAY1111N					TSI0373 TSI1 Page: 1	
Event	Seq	Extr	Mig Type	From Env	To Env	----- Date	Added Time	----- User-ID
PAYIN	83	NO	S	TEST	PROD	01-04-06	16:59:56	TSI0373
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---								
----- END ----- STOP								

Field	Type	Description
OBJECT (supplied)	N,S,P,O, ,D,M	The NATURAL object, PREDICT object, 3GL/OTHER object, or SYSERR message.
EVENT (supplied)	N,S,P,O, ,D,M	The Master Event of the migration.
SEQ (supplied)	N,S,P,O, ,D,M	The sequence number of the Event.
EXTR (supplied)	N,S,P,O, ,D,M	Indicates whether the Event is an Extract Event or not. YES Indicates the Event is an Extract Event. NO Indicates the Event is not an Extract Event.
MIG TYPE (supplied)	N,S,P,O, ,D,M	The form of the object migrated. S Indicates only the source form of the program may be selected. C Indicates only the cataloged form of the program may be selected. S/C Indicates both forms of the program may be selected.
FROM ENV (supplied)	N,S,P,O,D,M	The source Environment Definition of the Event.
TO ENV (supplied)	N,S,P,O,D,M	The target Environment Definition of the Event. An asterisk (*) indicates the Event is a multiple target Event.

(continued from previous page)

Field	Type	Description
ADDED DATE (supplied)	N,S,P,O,D,M	The date the Event was added.
ADDED TIME (supplied)	N,S,P,O,D,M	The time the Event was added.
ADDED USER-ID (supplied)	N,S,P,O,D,M	The User-ID of the user who added the Event.

Object Reporting in Batch

Sample reporting JCL is provided in the MVSREPT, VMREPT, BSREPT and VSEREPT members located in the Natural library N2OBATCH.

Note: The batch reports from the N2O Reporting Subsystem and the Documentation Tools require that the NATURAL Parameter IM (Input Mode) be set to "IM=D" (Delimiter Mode).

The following tables illustrate the JCL and EXECs modifications necessary to execute Object reports in batch.

History of an Environment

TYPE	&REPORT	&INPUT
N,S	N2OOBJA	TYPE,DETAILED-REPORT LIBRARY,ENV-DEF,DATE-1,DATE-2
P	N2OOBJA	TYPE,DETAILED-REPORT OBJECT-TYPE,ENV-DEF,DATE-1,DATE-2
O	N2OOBJA	TYPE,DETAILED-REPORT CATEGORY,ENV-DEF,DATE-1,DATE-2

History of an Object

TYPE	&REPORT	&INPUT
N,S	N2OOBJB	TYPE,DETAILED-REPORT OBJECT,LIBRARY,DATE-1,DATE-2
P	N2OOBJB	TYPE,DETAILED-REPORT OBJECT,OBJECT-TYPE,DATE-1,DATE-2
O	N2OOBJB	TYPE,DETAILED-REPORT OBJECT,CATEGORY,DATE-1,DATE-2

----- indicates that inputs are on separate lines.

Directory List

TYPE	&REPORT	&INPUT
N,S	N2OOBJC	TYPE ENV-DEF,LIBRARY STARTING-VALUE,ENDING-VALUE
P	N2OOBJC	TYPE ENV-DEF,OBJECT-TYPE STARTING-VALUE,ENDING-VALUE
O	N2OOBJC	TYPE ENV-DEF,CATEGORY STARTING-VALUE,ENDING-VALUE, ENDEVOR-SYSTEM,ENDEVOR-SUBSYSTEM

Directory Compare

TYPE	&REPORT	&INPUT
N	N2OOBJD	TYPE BASE-ENV-DEF,COMPARE-ENV-DEF,BASE-LIBRARY, COMPARE-LIBRARY,BASE-SOURCE-OBJECT, COMPARE-SOURCE-OBJECT STARTING-VALUE,ENDING-VALUE, VERIFY-TIMESTAMPS,VERIFY-EXISTENCE
S	N2OOBJD	TYPE BASE-ENV-DEF,COMPARE-ENV-DEF,BASE-LIBRARY, COMPARE-LIBRARY STARTING-VALUE,ENDING-VALUE,VERIFY-EXISTENCE
P	N2OOBJD	TYPE BASE-ENV-DEF,COMPARE-ENV-DEF,OBJECT TYPE STARTING-VALUE,ENDING-VALUE, VERIFY-TIMESTAMPS,VERIFY-EXISTENCE
O	N2OOBJD	TYPE BASE-ENV-DEF,COMPARE-ENV-DEF,CATEGORY STARTING-VALUE,ENDING-VALUE,VERIFY-EXISTENCE BASE-ENDEVOR-SYSTEM,BASE-ENDEVOR-SUBSYSTEM COMPARE-ENDEVOR-SYSTEM, COMPARE-ENDEVOR-SUBSYSTEM

Cross-Reference

TYPE	&REPORT	&INPUT
N	N2OOBJE	TYPE ENV-DEF,LIBRARY,OBJECT
O	N2OOBJE	TYPE ENV-DEF,CATEGORY,OBJECT

----- indicates that inputs are on separate lines.

Checked-out Objects

TYPE	&REPORT	&INPUT
A	N2OOBJF	TYPE,CHECKOUT-USERID
N,S	N2OOBJF	TYPE ----- BASE-ENV,BASE-LIBRARY,OBJECT,CURR-ENV CURR-LIBRARY,CHECKOUT-USERID,CHECKOUT-DATE
P	N2OOBJF	TYPE ----- BASE-ENV,OBJECT-TYPE,OBJECT,CURR-ENV CHECKOUT-USERID,CHECKOUT-DATE
O	N2OOBJF	TYPE ----- BASE-ENV,CATEGORY,OBJECT,CURR-ENV CHECKOUT-USERID,CHECKOUT-DATE, ENDEVOR-SYSTEM,ENDEVOR-SUBSYSTEM

Objects Archived by N2OPURGE

TYPE	&REPORT	&INPUT
N	N2OOBJG	TYPE ----- OBJECT,ENV-DEF,LIBRARY

----- indicates that inputs are on separate lines.

Archive Version Summary

TYPE	&REPORT	&INPUT
N,S	N2OOBJH	TYPE,DETAILED-REPORT ----- OBJECT,LIBRARY,DATE-1,DATE-2
O	N2OOBJH	TYPE,DETAILED-REPORT ----- OBJECT,DATE-1,DATE-2

Events Pending for an Object

TYPE	&REPORT	&INPUT
N	N2OOBJI	TYPE ----- OBJECT,CREATE-USERID

----- indicates that inputs are on separate lines.

The &INPUT parameter list by default is delimited by commas with no spaces following the commas. To override the default delimiter, modify the value of the jcl-delimiter field in User-Exit-22 (N2OUE22N).

For descriptions of &INPUT fields, refer to field descriptions in corresponding sections of Object Reporting.

IV.5 Statistical Reporting

Statistical Reporting provides numerical data about Events and objects.

To display the Statistical Reporting menu, enter "D" on the Reporting Subsystem menu or enter the direct command REP STAT on any menu.

```

01-12-31          N-2-O STATISTICAL REPORTING MENU          TSI0373
11:38:00                                     TSI1

Code  Function
-----
A  Events Pending Autocompile for a Library
B  Events Pending for an Environment
C  Objects Migrated
D  Objects Migrated by a User
E  Objects Migrated for an Event
F  Objects Migrated by Change Control
.  Terminate Statistical Reporting
-  -----

Enter Code:  _

Direct Command:  REP STAT
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
HELP  ----  END  ENV  MIG  REP  TOL  USR  PRJ  ----  ----  EXIT

```

Field	Description
ENTER CODE (required)	<p>The function to be executed. Valid values are as follows:</p> <p>A Events Pending Autocompile for a Library Displays the number of Events pending Autocompile for libraries.</p> <p>B Events Pending for an Environment Displays the number of Events pending a migration to an environment.</p> <p>C Objects Migrated Displays the number of objects migrated within a range of dates.</p> <p>D Objects Migrated by a User Displays the number of objects migrated by a user.</p> <p>E Objects Migrated for an Event Displays the number of objects migrated with an Event.</p> <p>F Objects Migrated by Change Control Displays the number of objects migrated for a specific change control number.</p>

IV.5.1 Events Pending Autocompile for a Library

The Events Pending Autocompile for a Library report displays the number of Events pending Autocompile for all libraries in an environment.

To display the Events Pending Autocompile for a Library input screen, enter "A" on the Statistical Reporting menu.

01-12-31 11:38:00	N-2-O STATISTICAL REPORTING EVENTS PENDING AUTOCOMPILE FOR A LIBRARY	TSI0373 TSI1
Env Def: _____		
Mode : O		
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12--- HELP ---- END ----		

Field	Description
∞ ENV DEF (required)	An Environment defined to N2O.
MODE (required)	Indicates how the job is executed (batch or on-line).
	B Submits JCL to the internal reader that processes the function in batch.
	O Processes the function on-line (Default: O).

∞ indicates field-level help is available.

Entering the necessary information on the input screen and pressing Enter displays the Events Pending Autocompile for a Library report.

01-12-31 11:38:00	N-2-O STATISTICAL REPORTING EVENTS PENDING AUTOCOMPILE FOR A LIBRARY Env Def: PAYD		TSI0373 TSI1 Page: 1
Library	Nbr	Library	Nbr
-----	---	-----	---
PAYPROD	1	PAYTEST	1
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12--- ----- END ----- STOP			

Field	Description
ENV DEF (supplied)	An Environment defined to N2O.
LIBRARY (supplied)	The library with Events pending Autocompile.
NBR (supplied)	The number of Events pending Autocompile for a library.

IV.5.2 Events Pending for an Environment

The Events Pending for an Environment report displays the number of Events pending a migration to an environment.

To display the Events Pending for an Environment input screen, enter "B" on the Statistical Reporting menu.

01-12-31 11:38:00	N-2-O STATISTICAL REPORTING EVENTS PENDING FOR AN ENVIRONMENT	TSI0373 TSI1 Page: 1
Env Def: _____ Library: _____ Mode : O		
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12--- ----- END ----- STOP		

Field	Description
∞ ENV DEF (required)	Limits the report to Events that migrate to the specified Environment Definition.
LIBRARY (optional)	Limits the report to Events that migrate to the specified library.
MODE (required)	Indicates how the job is executed (batch or on-line).
	B Submits JCL to the internal reader that processes the function in batch.
	O Processes the function on-line (Default: O).

∞ indicates field-level help is available.

Entering the necessary information in the input screen and pressing Enter displays the Events Pending for an Environment report.

```

Press ENTER to continue
01-12-31      N-2-O STATISTICAL REPORTING      TSI0373
11:38:00      EVENTS PENDING FOR AN ENVIRONMENT  TSI1
              Env Def:  DEV                      Page:  1

              Event Count:  10

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
-----  END  -----  STOP
  
```

Field	Description
ENV DEF (supplied)	An N2O environment selected for the report.
EVENT COUNT (supplied)	The number of Events waiting to be processed for the specified environment.

IV.5.3 Objects Migrated

The Objects Migrated report displays the number of objects migrated within a range of dates. As this report is CPU intensive, it is recommended that this report be executed in batch.

To display the Objects Migrated input screen, enter "C" on the Statistical Reporting menu and press Enter.

01-12-31 11:38:00	N-2-O STATISTICAL REPORTING OBJECTS MIGRATED	TSI0373 TSI1
Date Range: _____ - _____		
Mode : O		
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12--- HELP ---- END ----		

Field	Description
DATE RANGE (optional)	Limits the report to objects migrated within the specified range of dates. Dates must be formatted YYYYMMDD.
MODE (required)	Indicates how the job is executed (batch or on-line). B Submits JCL to the internal reader that processes the function in batch. O Processes the function on-line (Default: O).

Entering the necessary information on the input screen and pressing Enter displays the Object Migrated report.

01-12-31 11:38:00	N-2-O STATISTICAL REPORTING OBJECTS MIGRATED Date Range: 20010401 - 20010414	TSI0373 TSI1 Page: 1
<p>NATURAL</p> <p>Source: 1233</p> <p>Object: 475</p> <p>SYSERR</p> <p>Short : 16</p> <p>Long : 0</p> <p>PREDICT : 0</p> <p>3GL/Other: 9</p>		
<p>Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---</p> <p>HELP ---- END ---- ---- ---- ---- ---- ---- ---- STOP</p>		

Field	Description
DATE RANGE (supplied)	Selected range of dates for the report.
NATURAL SOURCE (supplied)	The number of objects with NATURAL source code migrated.
NATURAL OBJECT (supplied)	The number of objects with NATURAL object code migrated.
SYSERR SHORT (supplied)	The number of SYSERR short messages migrated.
SYSERR LONG (supplied)	The number of SYSERR extended messages migrated.
PREDICT (supplied)	The number of PREDICT objects migrated.
3GL/OTHER (supplied)	The number of 3GL/OTHER members migrated.

IV.5.4 **Objects Migrated by a User**

The Objects Migrated by a User report displays the number of objects migrated by a user. As this report is CPU intensive, it is recommended that this report be executed in batch.

To display the Objects Migrated by a User input screen, enter "D" on the Statistical Reporting menu and press Enter.

01-12-31 11:38:00	N-2-O STATISTICAL REPORTING OBJECTS MIGRATED BY A USER USER-ID : TSI1	TSI0373 TSI1
<p>Added User-ID: _____</p> <p>Date Range : _____ - _____</p> <p>Mode : O</p>		
<p>Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---</p> <p>HELP ---- END ----</p>		

Field	Description
USER-ID (supplied)	The User-ID selected for the report.
∞ ADDED USER-ID (required)	The user who added the Events to migrate the objects.
DATE RANGE (optional)	Limits the report to objects that migrated within the specified range of dates. Dates must be formatted YYYYMMDD.
MODE (required)	Indicates how the job is executed (batch or on-line). <div> B Submits JCL to the internal reader that processes the function in batch. O Processes the function on-line (Default: O). </div>

∞ indicates field-level help is available.

Entering the necessary information in the input screen and pressing Enter displays the Objects Migrated by a User report.

01-12-31 11:38:00	N-2-O STATISTICAL REPORTING OBJECTS MIGRATED BY A USER USER-ID: TSI1	TSI0373 TSI1 Page: 1
<p>NATURAL</p> <p>Source: 86</p> <p>Object: 8</p> <p>SYSERR</p> <p>Short : 1</p> <p>Long : 0</p> <p>PREDICT : 0</p> <p>3GL/Other: 0</p>		
<p>Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---</p> <p>----- END ----- STOP</p>		

Field	Description
NATURAL SOURCE (supplied)	The number of objects with NATURAL source code migrated.
NATURAL OBJECT (supplied)	The number of objects with NATURAL object code migrated.
SYSERR SHORT (supplied)	The number of SYSERR short messages migrated.
SYSERR LONG (supplied)	The number of SYSERR extended messages migrated.
PREDICT (supplied)	The number of PREDICT objects migrated.
3GL/OTHER (supplied)	The number of 3GL/OTHER members migrated.

IV.5.5 Objects Migrated for an Event

The Objects Migrated for an Event report displays the number of objects migrated with an Event.

To display the Objects Migrated for an Event input screen, enter "E" on the Statistical Reporting menu and press Enter.

01-12-31 11:38:00	N-2-O STATISTICAL REPORTING OBJECTS MIGRATED FOR AN EVENT	TSI0373 TSI1
<p>Event : _____</p> <p>Sequence: _____</p> <p>Mode : O</p>		
<p>Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---</p> <p>HELP ---- END ----</p>		

Field	Description
∞ EVENT (required)	The Master Event for the migration.
SEQUENCE (required)	The sequence number of the Event.
MODE (required)	Indicates how the job is executed (batch or on-line).
	B Submits JCL to the internal reader that processes the function in batch.
	O Processes the function on-line. (Default: O)

∞ indicates field-level help is available.

Entering the necessary information in the input screen and pressing Enter displays the Objects Migrated for an Event report.

```

Press ENTER to continue
01-12-31      N-2-O STATISTICAL REPORTING      TSI0373
11:38:00      OBJECTS MIGRATED FOR AN EVENT      TS11
              Event:PAYIN   Sequence :1          Page:      1

              NATURAL
                Source:  4
                Object:  0

              SYSERR
                Short :  0
                Long  :  0

              PREDICT :  0

              3GL/Other: 0

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
-----END-----STOP
  
```

Field	Description
EVENT (supplied)	The master event of the migration.
SEQUENCE (supplied)	The sequence number of the event.
NATURAL SOURCE (supplied)	The number of objects with NATURAL source code migrated.
NATURAL OBJECT (supplied)	The number of objects with NATURAL object code migrated.
SYSERR SHORT (supplied)	The number of SYSERR short messages migrated.
SYSERR LONG (supplied)	The number of SYSERR extended messages migrated.
PREDICT (supplied)	The number of PREDICT objects migrated.
3GL/OTHER (supplied)	The number of 3GL/OTHER members migrated.

IV.5.6 Objects Migrated by Change Control

The Objects Migrated by Change Control report displays the number of objects migrated with a specific change control number.

To display the Objects input screen, enter "F" on the Statistical Reporting menu and press Enter.

01-12-31 11:38:00	N-2-O STATISTICAL REPORTING OBJECTS MIGRATED BY CHANGE CONTROL	TSI0373 TSI1
Change Control: _____		
Mode : O		
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12--- HELP ---- END ----		

Field	Description
∞ CHANGE CONTROL (required)	The change control number to be reported on.
MODE (required)	Indicates how the job is executed (batch or on-line).
	B Submits JCL to the internal reader that processes the function in batch.
	O Processes the function on-line. (Default: O)

∞ indicates field-level help is available.

Entering the necessary information in the input screen and pressing Enter displays the Objects by Change Control report.

```

Press ENTER to continue
01-12-31      N-2-O STATISTICAL REPORTING      TSI0373
11:38:00      OBJECTS MIGRATED BY CHANGE CONTROL      TSI1
                  Change Control: TESTING      Page:      1

      NATURAL
      Source:   4
      Object:   0

      SYSERR
      Short :   0
      Long  :   0

      PREDICT   :   0

      3GL/Other: 0

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
-----  END  ----- STOP

```

Field	Description
CHANGE CONTROL (supplied)	The specified change control number.
NATURAL SOURCE (supplied)	The number of objects with NATURAL source code migrated.
NATURAL OBJECT (supplied)	The number of objects with NATURAL object code migrated.
SYSERR SHORT (supplied)	The number of SYSERR short messages migrated.
SYSERR LONG (supplied)	The number of SYSERR extended messages migrated.
PREDICT (supplied)	The number of PREDICT objects migrated.
3GL/OTHER (supplied)	The number of 3GL/OTHER members migrated.

IV.5.7 Statistical Reporting in Batch

Sample reporting JCL is provided in the MVSREPT, VMREPT, BSREPT and VSEREPT members located in the Natural library N2OBATCH.

Note: The batch reports from the N2O Reporting Subsystem and the Documentation Tools require that the NATURAL Parameter IM (Input Mode) be set to "IM=D" (Delimiter Mode).

The following table illustrates the JCL and EXECs modifications necessary to execute Statistical reports in batch.

REPORT	&REPORT	&INPUT
Events Pending Autocompile for a Library	N2OSTATA	ENV-DEF
Events Pending for an Environment	N2OSTATB	ENV-DEF,LIBRARY
Objects Migrated	N2OSTATC	DATE-1,DATE-2
Objects Migrated by a User	N2OSTATD	ADDED USER-ID,DATE-1,DATE-2
Objects Migrated for an Event	N2OSTATE	EVENT,SEQUENCE

The &INPUT parameter list by default is delimited by commas with no spaces following the commas. To override the default delimiter, modify the value of the jcl-delimiter field in User-Exit-22 (N2OUE22N).

For descriptions of &INPUT fields, refer to field descriptions in corresponding sections of Statistical Reporting.

IV.6 Security Reporting

Security Reporting provides reports that display information about N2O Security definitions.

To display the Security Reporting menu, enter "E" on the Reporting Subsystem menu or enter the direct command REP SEC on any menu.

```

01-12-31          N-2-O SECURITY REPORTING MENU          TSI0373
11:38:00                                     TSI1

      Code  Function
      -----
      A    N2O User Security
      B      User Groups
      C      Event Authorization
      D      Approval Profiles
      E      Function Profiles
      F      Migration Profiles
      G      Predict Profiles
      H      3GL Profiles
      .      Terminate Security Reporting
-----
Enter Code:  _

Direct Command:                                     REP SEC
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      HELP  ----  END   ENV   MIG   REP   TOL   USR   PRJ   ----  ----  EXIT

```

Field	Description
ENTER CODE (required)	<p>The function to be executed. Valid values are as follows:</p> <p>A N2O User Security Displays N2O User Definitions.</p> <p>B User Groups Displays N2O Groups and Users Definitions defined to them.</p> <p>C Event Authorization Displays a list of Events requiring Authorization and the users that can authorize them.</p> <p>D Approval Profiles Displays N2O Approval Profiles.</p> <p>E Function Profiles Displays N2O Function Profiles</p> <p>F Migration Profiles Displays N2O Migration Profiles.</p> <p>G Predict Profiles Displays N2O Predict Profiles.</p> <p>H 3GL Profiles Displays N2O 3GL Profiles.</p>

IV.6.1 N2O User Security

The N2O User Security report displays the N2O User Definitions.

To display the N2O User Security input screen, enter "A" on the Security Reporting menu.

```

05-01-01      N-2-O SECURITY REPORTING      TSI0373
18:08:40      N2O USER SECURITY              TSI1

                                Userid:  *_____ ( Wildcard / Single )

                                Mode   :    O

                                Batch Display Options
                                -----
                                Approval Status = YES Only. N
                                User Definitions..... N
                                Migration Profiles..... N

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      HELP  ----  END   ----  ----  ----  ----  ----  ----  ----  ----  ----

```

Field	Description
∞ USERID (required)	Userids that are displayed by the report. (wildcard permitted)
MODE (required)	Indicates how the job is executed (batch or on-line). B Submits JCL to the internal reader that processes the function in batch. O Processes the function on-line (Default: O).
BATCH DISPLAY OPTIONS	
APPROVAL STATUS = YES ONLY (required)	Indicates if only User Definitions that can authorize their own events should be displayed (Approval Status = YES in the USER Definition) . Y Display only User Definitions that can authorize their own events N Display All User Definitions (Default: N).
USER DEFINITIONS (required)	Indicates amount of detail displayed for each User Definition. Y Display all User Definition details. N Display only User Definition's Userid and Description (Default: N).

∞ indicates field-level help is available.

(continued from previous page)

Field	Type	Description
MIGRATION PROFILES (required)		Indicates if the Migration Profiles that the user has access to should be displayed (determined from all Approval Profiles assigned to the specified user id).
	Y	Display the Migration Profiles the user has access to.
	N	Do not display the Migration Profiles the user has access to (Default: N).

Entering the necessary information on the input screen and pressing Enter displays the N2O User Security report.

Valid values: F- Function Prof, A- Approval Prof, U- User Def						
05-02-11		N-2-O SECURITY REPORTING			TSI0373	
19:49:51		N2O USER SECURITY			TSI1	
X User	Description	Appl Status	Xref	Predict View	Group	
-	-	-	-	-	-	
-	N2OREPT	N2O REPORT	USERIDS	NO	NONE	NONE
-	USER	SYSTEM		YES	NONE	ADMIN
-	USER0	AUTH ONLY		NO	NONE	AUTH
-	USER1	AUTH ONLY		NO	NONE	AUTH
-	USER2	AUTH ONLY		NO	NONE	AUTH
-	USER3	AUTH ONLY		NO	NONE	AUTH
-	USER4	AUTH ONLY		NO	NONE	AUTH
-	USER5	AUTH ONLY		NO	NONE	AUTH
-	USER6	AUTH ONLY		NO	NONE	AUTH
-	USER7	AUTH ONLY		NO	NONE	AUTH
-	USER8	AUTH ONLY		NO	NONE	AUTH
-	USER9	AUTH ONLY		NO	NONE	AUTH
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---						
----- END ----- STOP						

Field	Description
X (optional)	The function to be executed. Valid values are as follows: F displays N2O Functions the specified userid has access to (determined from all Function Profiles assigned to the userid). A displays Approval Profiles the specified userid has access to U displays N2O User Definition.
User (supplied)	The User-ID of the User Definition.
Desc (supplied)	A description of the User.
Approval Status (supplied)	Valid values are as follows: YES The user can authorize his/her own Events. NO A user can not authorize his/her own Events.

(continued from previous page)

Field	Description
∞ XREF (supplied)	<p>Determines if N2O will present an object selection list of cross referenced modules when requesting an Event. Possible values are as follows:</p> <p>LIST An XREF selection list is displayed.</p> <p>NONE A list of XREF'd objects is not displayed.</p> <p>BOTH A user can decide between list and none when requesting a migration.</p>
PREDICT Views (supplied)	<p>Determines if N2O will present a PREDICT userview selection list when requesting an Event. Possible values are as follows:</p> <p>LIST A PREDICT userview selection list is displayed.</p> <p>NONE A list of PREDICT userviews is not displayed.</p> <p>BOTH A user can decide between list and none when requesting a migration.</p>
Group-ID (supplied)	<p>A value that relates multiple users.</p> <p>This value links a group of users for authorization purposes.</p>

IV.6.2 User Groups

The User Groups report displays information related to Groups assigned to N2O User Definitions.

To display the User Groups input screen, enter "B" on the Security Reporting menu.

```

05-02-11      N-2-O SECURITY REPORTING      TSI0373
20:29:29      N2O GROUP SECURITY            TSI1

Group:  *_____ ( Wildcard / Single )

Mode :    O

Batch Display Options
-----
List Users..... N
User Definitions..... N
User Functions..... N
Migration Profiles..... N

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
----- END ----- STOP

```

Field	Description
∞ GROUP (required)	Groups that are displayed by the report. (wildcard permitted)
MODE (required)	Indicates how the job is executed (batch or on-line). B Submits JCL to the internal reader that processes the function in batch. O Processes the function on-line (Default: O).
BATCH DISPLAY OPTIONS	
LIST USERS (required)	Indicates if User Definitions defined to the displayed groups should be displayed. Y Display User Definitions defined to Group. N Display only the Groups. (Default: N).
USER DEFINITIONS (required)	Indicates the amount of detail displayed for each User Definition (Requires LIST USERS = Y) Y Display all User Definitions details. N Display only Userid and Description (Default: N).

∞ indicates field-level help is available.

(continued from previous page)

Field	Description
MIGRATION PROFILES (required)	Indicates if the Migration Profiles that the user has access to should be displayed (Requires LIST USERS = Y).
Y	Display the Migration Profiles that the user has access to (determined from all Approval Profiles assigned to the userid).
N	Do not display the Migration Profiles that the user has access to (Default: N).

Entering the necessary information in the input screen and pressing Enter displays the User Groups report.

```

Valid values: U - Users
05-02-11      N-2-O SECURITY REPORTING      TSI0373
21:04:08      N2O GROUP SECURITY              TSI1

      X      Group      Users in      X      Users in      X      Users in
      -      -      -      -      -      -      -      -
      -      ADMIN      3
      -      AUTH      29

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      --- END ---
  
```

Field	Description
X (optional)	The function to be executed. Valid values are as follows: U displays User Definitions that contain the group.
Group (supplied)	A value that relates multiple users.
Users in Group (supplied)	Number of User Definition that contain the Group.

IV.6.3 Event Authorization

The Event Authorization report displays events that require authorization or servicing.

This report will only show events that have the Master Event's Lock Event field set to ENV or ALL.

To display the Event Authorization input screen, enter "C" on the Security Reporting menu and press Enter.

```

05-02-11      N-2-O SECURITY REPORTING      TSI3101
21:17:27      N2O EVENT AUTHORIZATION      TSI3

Event:  *_____ ( Wildcard / Single )

Mode :    O

Batch Display Options
-----
Authorizers..... N
Master Event..... N
Migration Profiles. N

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      HELP  ----  END  ----  ----  ----  ----  ----  ----  ----  ----  ----  ----

```

Field	Description
∞ EVENT (required)	Event displayed requiring Authorization or Servicing. (wildcard permitted)
MODE (required)	Indicates how the job is executed (batch or on-line). B Submits JCL to the internal reader that processes the function in batch. O Processes the function on-line (Default: O).
BATCH DISPLAY OPTIONS	
LIST USERS (required)	Indicates if User Definitions that can authorize or service the events should be displayed (determined from all Approval Profiles assigned to the userid). Y Display User Definitions that can authorize or service the event. N Display only the Events (Default: N).
MASTER EVENT (required)	Indicates amount of detail displayed for each Master Event. Y Display the Master Event details N Display only the Master Event and Description. (Default: N)
MIGRATION PROFILES (required)	Indicates if the Migration Profiles used by the event should be displayed. Y Display the Migration Profiles used by the event. N Do not display the Migration Profiles used by the event. (Default: N).

Entering the necessary information on the input screen and pressing Enter displays the Event Authorization report.

```

Valid values: A - Authorizers, E - Event or M - Mig Profile
05-02-11          N-2-O SELECT A MASTER EVENT          TSI0373
22:33:49                                     TSI1

      S      Event      --- From ---      --- To ---      Lock      Lvl
      -      -----      Env  Library      Env  Library      Evnt  Delay  Auth
      -      -----      ---  ---          ---  ---          ---  ---  ---
      -      AEVENT      DEV  PAYDEV          PROD PAYBAS          ALL  AUTH  4

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
HELP  ----  END   ----  ----  ----  ----  ----  ----  ----  ----  ----  STOP

```

Field	Description
S (optional)	The function to be executed. Valid values are as follows: A displays the User Definitions that can authorize the event (determined from all Approval Profiles assigned to the userid). E displays the Master Event. M displays the Migration Profiles used by the Master event.
Event (supplied)	The Master Event.
From Env (supplied)	The source Environment Definition (defined on the Master Event).
From Library (supplied)	The NATURAL library from which the NATURAL objects/SYSERR messages are migrated (defined on the Master Event).
To Env (supplied)	The target Environment Definition of the Event. An "*" indicates the Event is a Multiple Target Event (defined on the Master Event).
To Library (supplied)	The NATURAL library where the NATURAL objects/SYSERR messages are placed by the migration. An "*" indicates the Event is a Multiple Target Event (defined on the Master Event).
Lock Event (supplied)	Determines if the user can modify the From/To Environment and library information (defined on the Master Event) when requesting an Event. Possible values are as follows: ENV The From/To Environment fields cannot be modified by the user.

(continued from previous page)

Field	Description
	ALL The From/To Environment and library fields cannot be modified by the user.
	NO Indicates all From/To fields are modifiable. Note : Master Events defined with 'NO' are NOT displayed.
Delay (supplied)	Determines if a requested Event requires additional authorization before executing. Possible values are as follows: AUTH The Event must be authorized using the Authorize an Event function. SERV The Event must be authorized using the Authorize an Event function and serviced using the Service an Event function.
Levels of Auth (supplied)	The number of authorizations required when AUTH or SERV is specified.

IV.6.4 Approval Profiles

The Approval Profiles report displays the N2O Approval Profiles.

To display the Approval Profiles input screen, enter "D" on the Security Reporting menu and press Enter.

```

05-02-14          N-2-O SECURITY REPORTING          TSI0373
14:55:42          N2O Approval PROFILES             TSI1

Approval Profiles: *_____ ( Wildcard / Single )

Mode              : O

Batch Display Options
-----
Approval Profile... N
Users..... N

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      HELP  ----  END   ----  ----  ----  ----  ----  ----  ----  ----  ----

```

Field	Description
∞ APPROVAL PROFILE (required)	Approval Profiles that are displayed by the report. (wildcard permitted)
MODE (required)	Indicates how the job is executed (batch or on-line). B Submits JCL to the internal reader that processes the function in batch. O Processes the function on-line (Default: O).
BATCH DISPLAY OPTIONS	
APPROVAL PROFILE (required)	Indicates amount of detail displayed for each Approval Profile. Y Display all the details of the Approval Profiles. N Display only the Approval Profile and Description (Default: N).
USERS (required)	Indicates if the User Definitions that contain the Approval Profile should be displayed. Y Display the User Definitions that contain the Approval Profile. N Do not display the User Definitions that contain the Approval Profile. (Default: N)

∞ indicates field-level help is available.

Entering the necessary information in the input screen and pressing Enter displays the Approval Profiles report.

Valid Values: I - Inquire, U - Users					
05-11-28			N-2-O SELECT AN APPROVAL PROFILE		VLM1
15:29:25					SC0TCP15
S	Profile	Description	Date	Time	User-ID
-	-----	-----	-----	-----	-----
-	N2OAPPR	N2O APPROVAL PROFILE	04-03-19	20:01:56	PDL1
-	TREAPPR	TRE APPROVAL PROFILE	04-03-19	20:02:10	PDL1
-	TRMAPPR	TRM APPROVAL PROFILE	04-03-19	20:02:26	PDL1
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---					
----- END ----- STOP					

Field	Description
S (optional)	The function to be executed. Valid values are as follows: I display the Approval Profile. U display the Users assigned to the Approval Profile (in their User Definition).
Profile (supplied)	The Approval Profile.
Description (supplied)	A brief description of the Approval Profile.
Date (supplied)	Date that the Approval Profile was created or last updated.
Time (supplied)	Time that the Approval Profile was created or last updated.
User-ID (supplied)	User-ID of the user who created or last updated the Approval Profile.

IV.6.5 Function Profiles

The Function Profiles report displays the N2O Function Profiles.

To display the Function Profiles input screen, enter "E" on the Security Reporting menu and press Enter.

```

05-02-14          N-2-O SECURITY REPORTING          TSI0373
14:55:42          N2O FUNCTION PROFILES             TSI1

Function Profiles: *_____ ( Wildcard / Single )

Mode              :   O

Batch Display Options
-----
Function Profile... N
Users.....       N

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      HELP  ----  END   ----  ----  ----  ----  ----  ----  ----  ----  ----

```

Field	Description
∞ FUNCTION PROFILE (required)	Function Profiles that are displayed by the report. (wildcard permitted)
MODE (required)	Indicates how the job is executed (batch or on-line). B Submits JCL to the internal reader that processes the function in batch. O Processes the function on-line (Default: O).
BATCH DISPLAY OPTIONS	
FUNCTION PROFILE (required)	Indicates amount of detail displayed for each Function Profile. Y Display all the details of the Function Profiles. N Display only the Function Profile and Description (Default: N).
USERS (required)	Indicates if the User Definitions that contain the Function Profile should be displayed. Y Display the User Definitions assigned to the Function Profile. N Do not display the User Definitions assigned to the Function Profile. (Default: N)

∞ indicates field-level help is available.

Entering the necessary information in the input screen and pressing Enter displays the Function Profiles report.

Valid values: F - Function Profile or U - Users					
05-02-14	N-2-O SELECT A FUNCTION PROFILE				TSI0373
15:17:13					TSI1
S	Profile	Description	Date	Time	User-ID
-	-----	-----	-----	-----	-----
-	ALL-FUNC	ALL FUNCTIONS ALLOWED	04-12-01	22:35:50	TSI1
-	AUTHUSER	AUTH ONLY	04-10-04	21:42:29	TSI1
-	INQFUNC	TEST	04-10-13	17:19:05	TSI1
-	NOAUTH	NO AUTH	04-10-04	21:43:08	TSI1
-	REPTONLY	REPORTS ONLY	04-10-22	21:40:21	TSI1
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---					
----- END ----- STOP					

Field	Description
S (optional)	The function to be executed. Valid values are as follows: F display the Function Profile. U display the Users assigned to the Function Profile (in the User Definition).
Profile (supplied)	The Function Profile.
Description (supplied)	A brief description of the Function Profile.
Date (supplied)	Date that the Function Profile was created or last updated.
Time (supplied)	Time that the Function Profile was created or last updated.
User-ID (supplied)	User-ID of the user who created or last updated the Function Profile.

IV.6.6 Migration Profiles

The Migration Profiles report displays the N2O Migration Profiles.

To display the Migration Profiles input screen, enter "F" on the Security Reporting menu and press Enter.

05-02-14 15:34:33	N-2-O SECURITY REPORTING N2O MIGRATION PROFILE	TSI0373 TSI1
----------------------	---	-----------------

Migration Profile: *___ - *___ (Wildcard / Single)

Mode : O

Batch Display Options

Migration Profile Details: N

Migration Profile Users...: N

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---

HELP ---- END ----

Field	Description
∞ MIGRATION PROFILE (required)	Migration Profiles that are displayed by the report. The source and target Environment Definitions (wildcard permitted)
MODE (required)	Indicates how the job is executed (batch or on-line). <ul style="list-style-type: none"> B Submits JCL to the internal reader that processes the function in batch. O Processes the function on-line (Default: O).
BATCH DISPLAY OPTIONS	
MIGRATION PROFILE DETAILS (required)	Indicates amount of detail displayed for each Migration Profile. <ul style="list-style-type: none"> Y Display all the details of the Migration Profiles. N Display only the Migration Profile and Description (Default: N).
MIGRATION PROFILE USERS (required)	Determines if the User Definitions that are assigned an Approval Profile containing the requested Migration Profile are displayed. <ul style="list-style-type: none"> Y Display the User Definitions assigned an Approval Profile containing the specific Migration Profile. N Do not display the User Definitions assigned an Approval Profile containing the specific Migration Profile (Default: N)

∞ indicates field-level help is available.

Entering the necessary information in the input screen and pressing Enter displays the Migration Profile report.

Valid values: I - Inquire or U - Users										
05-02-14			N-2-O SELECT A MIGRATION PROFILE						TSI0373	
16:34:29									TSI1	
	From	To				Migration		Mig	Pgm	Ver
S	Env	Env	Mode	Type	Delay	Method	Autocompile	XREF	Doc	Obj
-	-	-	-	-	-	-	-	-	-	-
-	ARC1	PROD	BOTH	BOTH	NONE	COPY	NO	N	NO	NO
-	DEV	ARC1	BOTH	BOTH	NONE	COPY	NO	N	NO	NO
-	DEV	PROD	BOTH	BOTH	NONE	BOTH	STOW	N	NO	NO
-	PROD	ARC1	BOTH	BOTH	NONE	COPY	NO	N	NO	NO
-	PROD	DEV	BOTH	SOURCE	NONE	COPY	STOW	N	NO	NO
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---										
-----END-----STOP										

Field	Description
S (optional)	The function to be executed. Valid values are as follows: I displays the Migration Profile. U displays the Users assigned an applicable Approval Profile.
From Env To Env (supplied)	The Migration Profile.
Mode (supplied)	Mode assigned to the Migration Profile. Possible values are as follows: <div> <div>ONLINE</div> <div>Indicates the migration will be performed on-line.</div> </div> <div> <div>BATCH</div> <div>Indicates the migration will be performed by a batch job.</div> </div> <div> <div>BOTH</div> <div>Indicates ONLINE or BATCH may be specified by the user at migration time.</div> </div>
Type (supplied)	Determines the type of code that will migrate when this migration profile is executed. Possible values are as follows: <div> <div>SOURCE</div> <div>source code will be migrated.</div> </div> <div> <div>OBJECT</div> <div>object code will be migrated.</div> </div> <div> <div>BOTH</div> <div>both source and object code will be migrated.</div> </div>

(continued from previous page)

Field	Description
Delay	Determines if a requested Event requires additional authorization before executing. Possible values are as follows:
(supplied)	AUTH The Event must be authorized using the Authorize an Event function.
	SERV The Event must be authorized using the Authorize an Event function and serviced using the Service an Event function.
	NONE The migration may proceed immediately without authorization.
Migration Method	Indicates if the objects are copied or moved (deleted on the TO environment). Possible values are as follows:
(supplied)	COPY An object at the source of a migration will be placed at the target (defaults to COPY).
	MOVE An object at the source of a migration will be placed at the target and then deleted from the source of the migration.
	BOTH The user may specify COPY or MOVE at migration time.
Autocompile	Instructs N2O to catalog, stow, or take no action on the migrated objects. Possible values are as follows:
(supplied)	CAT Autocompile will occur for Events that migrate NATURAL objects or 3GL members. NATURAL objects will be CATALOGed at the target.
	STOW Autocompile will occur for Events that migrate NATURAL objects or 3GL members. NATURAL objects will be STOWed at the target.
	NO Autocompile will not occur for Events using this Migration Profile.

(continued from previous page)

Field	Description
Migrate XREF (supplied)	<p>Determines whether or not Predict Cross-Reference Data must exist before allowing an object to be selected for migration. Possible values are as follows:</p> <p>Y PREDICT Cross-Reference data MUST exist and will be migrated. A message of 'No XREF' will appear on the Object Selection Screen if the object fails this test.</p> <p>S PREDICT Cross-Reference data will be migrated if it exists.</p> <p>N PREDICT Cross-Reference data will not be verified or migrated.</p>
Program Doc (supplied)	<p>Instructs N2O to validate that an object has been documented in Predict before allowing it to be selected for migration. Possible values are as follows:</p> <p>YES PREDICT object documentation must exist in the From Environment before a NATURAL object may be selected to be migrated.</p> <p>NO PREDICT object documentation will not be verified or migrated.</p>
Verify Object (supplied)	<p>N2O can insure that an object has object code that was created after the last source code timestamp. Possible values are as follows:</p> <p>YES NATURAL compiled code with a timestamp greater than the source code must exist for the object to be migrated.</p> <p>NO NATURAL compiled code timestamps will not be verified before the object migrates</p>

IV.6.7 Predict Profiles

The Predict Profiles report displays N2O Predict Profiles.

To display the Predict Profiles input screen, enter "G" on the Security Reporting menu and press Enter.

```

05-02-14          N-2-O SECURITY REPORTING          TSI0373
17:26:28          N2O PREDICT PROFILES              TSI1

Predict Profiles:  *_____ ( Wildcard / Single )

Mode              :    O

Batch Display Options
-----
PREDICT Profile... N
Users..... N

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
HELP  ----  END   ----  ----  ----  ----  ----  ----  ----  ----  ----  ----  ----

```

Field	Description
∞ PREDICT PROFILE (required)	Predict Profiles that are displayed by the report. (wildcard permitted)
MODE (required)	Indicates how the job is executed (batch or on-line).
	B Submits JCL to the internal reader that processes the function in batch.
	O Processes the function on-line (Default: O).
BATCH DISPLAY OPTIONS	
PREDICT PROFILE (required)	Indicates amount of detail displayed for each Predict Profile.
	Y Display all the details of the Predict Profiles.
	N Display only the Predict Profile and Description (Default: N).
USERS (required)	Indicates if the User Definitions that contain the Predict Profile should be displayed.
	Y Display the User Definitions that contain the Predict Profiles.
	N Do not display the User Definitions that contain the Predict Profiles. (Default: N)

∞ indicates field-level help is available

Entering the necessary information in the input screen and pressing Enter displays the Predict Profiles report.

```
Valid Values: P - Predict Profile or U - Users
05-02-14      N-2-O SELECT A PREDICT PROFILE      TSI0373
17:54:04      TSI1

  S   Profile  Description                      Date      Time      User-ID
  -   -
  -   ALL-PRED ALL PREDICT PROFILES           04-03-02  15:21:45  TSI1

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
-----END-----STOP
```

Field	Description
S (optional)	The function to be executed. Valid values are as follows: P displays the Predict Profile. U displays Users assigned the specific Predict Profile in their User Definition.
Profile (supplied)	The Predict Profile.
Description (supplied)	A brief description of the Predict Profile.
Date (supplied)	Date the Predict Profile was created or last updated.
Time (supplied)	Time the Predict Profile was created or last updated.
Updated (supplied)	User-ID of the user who created or last updated the Predict Profile.

IV.6.8 3GL Profiles

The 3GL Profiles report displays N2O 3GL Profiles.

To display the 3GL Profiles input screen, enter "H" on the Security Reporting menu and press Enter.

```

05-02-14          N-2-O SECURITY REPORTING          TSI0373
17:26:28          N2O 3GL PROFILES                  TSI1

3GL Profiles:  *_____ ( Wildcard / Single )

Mode           :   O

Batch Display Options
-----
3GL Profile...   . N
Users.....      N

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
HELP  ----  END   ----  ----  ----  ----  ----  ----  ----  ----  ----  ----

```

Field	Description
∞ 3GL PROFILE (required)	3GL Profiles that are displayed by the report. (wildcard permitted)
MODE (required)	Indicates how the job is executed (batch or on-line). B Submits JCL to the internal reader that processes the function in batch. O Processes the function on-line (Default: O).
BATCH DISPLAY OPTIONS	
3GL PROFILE (required)	Indicates amount of detail displayed for each 3GL Profile. Y Display all the details of the 3GL Profiles. N Display only the 3GL Profile and Description (Default: N).
USERS (required)	Indicates if the User Definitions containing the 3GL Profile should be displayed. Y Display the User Definitions containing the 3GL Profiles. N Do not display the User Definitions containing the 3GL Profiles. (Default: N)

∞ indicates field-level help is available

Entering the necessary information in the input screen and pressing Enter displays the 3GL Profiles report.

```
Valid Values: 3 - 3GL Profile or U - Users
05-02-14          N-2-O SELECT A 3GL PROFILE          TSI0373
17:54:04                                TSI1

  S   Profile  Description                               Date    Time    User-ID
  -   -
  -   ALL-3GL  ALL 3GL                                04-04-21 18:12:15 TSI1

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
-----END-----STOP
```

Field	Description
X (optional)	The function to be executed. Valid values are as follows: 3 displays the 3GL Profile details. U displays the Users assigned the specific 3GL Profile in their User Definition.
Profile (supplied)	The 3GL Profile.
Description (supplied)	A brief description of the 3GL Profile.
Date (supplied)	Date the 3GL Profile was created or last updated.
Time (supplied)	Time the 3GL Profile was created or last updated.
Updated (supplied)	User-ID of the user who created or last updated the 3GL Profile.

IV.6.9 **Security Reporting in Batch**

Sample reporting JCL is provided in the MVSREPT, VMREPT, BSREPT and VSEREPT members located in the Natural library N2OBATCH.

Note: The batch reports from the N2O Reporting Subsystem and the Documentation Tools require that the NATURAL Parameter IM (Input Mode) be set to "IM=D" (Delimiter Mode).

The following table illustrates the JCL and EXECs modifications necessary to execute Statistical reports in batch.

REPORT	&REPORT	&INPUT
N2O User Security	N2OSECA	USERID
		APPL-STATUS,VIEW-USER-DEFS, MIGRATION-PROFILES (N,N,N,N)
User Groups	N2OSECB	GROUP
		VIEW-USERS,VIEW-USER-DEF, VIEW-MIGRATION-PROFILE (N,N,N,N)
Event Authorization	N2OSECC	EVENT
		AUTHORIZERS,VIEW-EVENT-DETAILS, VIEW-MIGRATION-PROFILE (N,N,N)
Approval Profiles	N2OSECD	Approval-Profile VIEW-APPROVAL-PROFILE,VIEW-USERS
Function Profiles	N2OSECE	FUNCTION-PROFILE
		VIEW-FUNCTION-PROFILE, VIEW-USERS (N,N)
Migration Profiles	N2OSECF	FROM-ENV,TO-ENV
		VIEW-MIGRATION-PROFILE, VIEW-USERS (N,N)
Predict Profiles	N2OSECG	PREDICT-PROFILE
		VIEW-PREDICT-PROFILE,VIEW-USERS (N,N)
3GL Profiles	N2OSECH	3GL-PROFILE
		VIEW-3GL-PROFILE,VIEW-USERS (N,N)

----- indicates that inputs are on separate lines.

The &INPUT parameter list by default is delimited by commas with no spaces following the commas. To override the default delimiter, modify the value of the jcl-delimiter field in User-Exit-22 (N2OUE22N).

For descriptions of &INPUT fields, refer to field descriptions in corresponding sections of Security Reporting.

This page intentionally left blank.

SECTION V

TOOLBOX SUBSYSTEM

V.1 Introduction

The Toolbox Subsystem supplies application development tools for the N2O Administrator and application programmers. The Toolbox Subsystem consists of four functions:

1. Documentation Tools
2. Maintenance Tools
3. Programmer Tools
4. Utility Tools

Documentation Tools assist in documenting and debugging NATURAL applications by providing utilities to display/print NATURAL objects, File Layouts, Descriptor X-REF (Cross-Reference) Information, Object Flow Analysis, Object X-REF, SYSERR Messages, and Archived 3GL Objects.

Maintenance Tools maintain NATURAL applications by providing utilities to delete and recover objects.

Programmer Tools aid in the development of NATURAL applications by providing utilities to compare, list, and scan objects in a NATURAL development environment.

Utility tools provide facilities to assist in resolving exception situations that may arise when using N2O.

To access the Toolbox Subsystem menu, enter "T" on the N2O Main menu. Entering the direct command TOL MENU or pressing PF7 on any menu also accesses the Toolbox Subsystem menu.

```

01-12-31          N-2-O MAIN MENU          TSI0373
11:38:00          TSI1

Code  Function
----  -
E     Environment Subsystem
M     Migration Subsystem
P     Project Tracking Subsystem
R     Reporting Subsystem
T     Toolbox Subsystem
.     Terminate N-2-O Session
----  -

Enter Code:  _

Direct Command:  N2O MENU
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
HELP  ----  END  ENV  MIG  REP  TOL  USR  PRJ  ----  ----  EXIT

```

```
01-12-31      N-2-O TOOLBOX SUBSYSTEM MENU      TSI0373
11:38:00                                           TSI1

              Code  Function
              ----  -
              D      Documentation Tools
              M      Maintenance Tools
              P      Programmer Tools
              T      Utility Tools
              .      Terminate Toolbox Subsystem
              ----  -

Enter Code:  _

Direct Command:                                     TOL MENU
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      HELP  ----  END  ENV  MIG  REP  ----  USR  PRJ  ----  ----  EXIT
```

Field	Description
ENTER CODE (required)	<p>The function to be executed. Valid values are as follows:</p> <p>D Documentation Tools Display/print NATURAL objects, File Layouts, Descriptor X-REF Information, Object Flow Analysis, Object X-REF, SYSERR Messages, and Archived 3GL Objects.</p> <p>M Maintenance Tools Delete and recover objects.</p> <p>P Programmer Tools Compare, list, and scan objects.</p> <p>T Utility Tools Diagnostic programs for exception situations.</p>

Additional security may be provided for all tools in the Toolbox Subsystem using User-Exit 12. Refer to the *N2O Administrator Manual* for details on User-Exit 12.

V.2 Documentation Tools

The N2O Documentation Tools provide utilities to display/print NATURAL objects, File Layouts, Descriptor X-REF information, Object Flow Analysis, Object X-REF, SYSERR Messages, and Archived 3GL Objects from a specified local/ archive environment.

To access the Documentation Tools menu, enter "D" on the Toolbox Subsystem menu or the direct command TOL DOC on any menu.

```
01-12-31          N-2-O DOCUMENTATION TOOLS MENU          TSI0373
11:38:00                                         TSI1

      Code      Function
      ----      -
      A      Natural Object Listing
      B      Map Listing
      C      Data Area Listing
      D      File Layouts
      E      Descriptor X-REF Information
      F      Object Flow Analysis
      G      Object X-REF
      H      Syserr Message Listing
      I      Archived 3GL Object Listing
      .      Terminate Documentation Tools
      -      -----

      Enter Code: _

      Direct Command:_____TOL DOC
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      HELP ---- END  ENV  MIG  REP  ----  USR  PRJ  ----  ----  EXIT
```

Field	Description
ENTER CODE (required)	<p>The function to be executed. Valid values are as follows:</p> <p>A Natural Object Listing Displays/prints NATURAL Source Code.</p> <p>B Map Listing Displays/prints Map(s).</p> <p>C Data Area Listing Displays/prints Data Area(s).</p> <p>D File Layouts Displays/prints File Information from PREDICT or NATURAL DDMs.</p> <p>E Descriptor X-REF Information Displays/prints X-REF Information for a file's Descriptor(s).</p> <p>F Object Flow Analysis Displays/prints a breakdown of a NATURAL object's flow showing processing loops and statement blocks.</p>

(Continued from previous page)

Field	Description
G	Object X-REF Displays/prints X-REF Information for NATURAL object(s).
H	SYSERR Message Listing Displays/prints SYSERR messages.
I	Archived 3GLObject Listing Displays/prints Archived 3GL Objects.

The following PF-keys are provided for all Documentation Tool options:

PF-key	Function	Description
PF1/PF13	HELP	Provide information about the current screen.
PF3/PF15	END	Return to the Documentation Tools Menu.
PF12/PF24	STOP	Return to the previous screen.

V.2.1 Natural Object Listing

The Natural Object Listing utility displays/prints NATURAL source code. Additionally, at the start of each object, NATURAL directory information and information about the archiving event (if applicable) is displayed/printed.

To enable the paging up/down in Natural Object Listing, ADAV7 should be specified in the NTDB macro. Refer to the N2O Administrator Manual **Section II.3.8 Installation Procedure step 8**.

To access the Natural Object Listing screen, enter "A" on the Documentation Tools menu.

```

01-12-31                      N-2-O DOCUMENTATION TOOLS                      TSI0373
11:38:00                      NATURAL OBJECT LISTING                        TSI1

Print Object(s)
- Env Def.....: TEST
- Library.....: PAYTEST_
- Starting Object.....: PAY* (Wildcard/Single)
- Ending Object.....: (Both Blank=All)

Within Range, Exclude
- Object Types.....: AGHLMT_

Options
- Explode Copycode.....: N (Yes/No)
- Explode Data Areas....: N (Yes/No)
- Format Maps.....: Y (Yes/No/Both)
- Format Data Areas.....: Y (Yes/No)
- Display Object X-REF.: N (Yes/No)
- Force Uppercase.....: N (Yes/No)
- Route Output.....: S (Screen/Printer)
- Mode.....: O (On-line/Batch)

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
HELP ---- END ----
```

Field	Description
∞ ENV DEF	The Environment Definition containing the object(s) to be displayed/printed. Remote Environments Definitions are not valid.
LIBRARY (required)	The NATURAL library containing the object(s) to be displayed/printed.
STARTING OBJECT (optional)	The starting value of the object(s) to be displayed/printed. Partial names and wildcards (e.g., AAP*) may be entered.
ENDING OBJECT (optional)	The ending value of the object(s) to be displayed/printed. Wildcards (e.g., AAP9*) may be entered. To display/print a single object, leave this field blank and enter the object's name in the Starting Object field.

∞ indicates field-level help is available.

(Continued from previous page)

Field	Description
∞ WITHIN RANGE, EXCLUDE OBJECT TYPES (optional)	<p>Identifies NATURAL object types to be excluded from being displayed/printed when specifying a range of objects. This option is ignored when a single object is displayed/printed. Valid values are as follows:</p> <p>P Program</p> <p>S Subroutine</p> <p>N Subprogram</p> <p>M Map</p> <p>H Helproutine</p> <p>L Local Data Area</p> <p>A Parameter Data Area</p> <p>G Global Data Area</p> <p>C Copycode</p> <p>T Text</p> <p>O Macro</p> <p>R Report</p> <p>Y ExpertModel</p> <p>Z Recording</p> <p>3 Dialog</p> <p>4 Class</p> <p>5 Processor</p> <p>K Server</p> <p>(default: "MHLAGT")</p>
EXPLODE COPYCODE (required)	<p>Y Embeds the source code of any copycode referenced within the displayed/printed object.</p> <p>N Does not embed the source code of copycode referenced within the displayed/printed object. (default: "N")</p>
EXPLODE DATA AREAS (required)	<p>Y Embeds the source of any data areas referenced within the displayed/ printed object.</p> <p>N Does not embed the source of data areas referenced within the displayed/printed object. (default: "N")</p>

∞ indicate field-level help is available.

(continued from previous page)

Field		Description
FORMAT MAPS (required)	Y	Displays/prints the map as the NATURAL Map editor presents it. Displays/prints a list of variables used by the map, all help routines used by the Map, and all processing/verification rules used by the Map (Similar to Map Listing Utility). (default: "Y")
	N	Displays/prints map(s) in source format (similar to NATURAL List command).
	B	Displays/prints map(s) as the NATURAL Map editor presents it and in source format.
FORMAT DATA AREAS (required)	Y	Displays/prints data area(s) in the format as they would appear in the NATURAL Data Area editor. (default: "Y")
	N	Displays/prints data area(s) in source format (similar to NATURAL List command).
DISPLAY OBJECT X-REF (required)	Y	Displays/prints PREDICT object X-REF information related to the object following the object listing (similar to Object X-REF utility).
	N	Does not display/print PREDICT object X-REF information related to the object. (default: "N")
FORCE UPPERCASE (required)	Y	Converts lowercase to uppercase.
	N	Does not convert lowercase to uppercase. (default: "N")
ROUTE OUTPUT (required)	S	Routes output to screen. (default: "S")
	P	Routes output to NATURAL Printer 1 (CMPRT01).

Note: When printing to CMPRT01 (NATURAL printer 1) during an on-line session, it is recommended that the user determine if CMPRT01 is available. This can be done by using the NATURAL "GLOBALS" and/or "SYSFILE" command (refer to the *NATURAL Utilities Manual* for more information). The N2O Documentation Tools will detect that CMPRT01 is unavailable on the first attempt to write the output. A subsequent attempt to print to the unavailable CMPRT01 may result in a NAT954 or similar error and termination of the current NATURAL session.

MODE (required)		Indicates how the job is to be executed (batch or on-line).
	B	Submits JCL to the internal reader that processes the function in batch. In Batch Mode, the output is automatically routed to NATURAL Printer 1.
	O	Processes the function on-line. (default: "O")

When the Environment Definition entered is an N2O Archive Definition, a pop-up window is displayed. One of the following fields must be provided:

- a) An Archive Date, which must be entered using the YYYYMMDD format.
 - 1) When printing a single object
A list of archive versions is generated and displayed, starting at the most recent archive and continuing until the specified Archive Date. One of the versions must be chosen from this list.
 - 2) When printing a range of objects
Displays the first version of each object located on the archive file for the specified range archived before or at the specified date.
- b) An Archive Version Number, which allows N2O to go directly to the Archive file and read the specified version. The Archive Version Number may be between -1 and -99.

V.2.2 Map Listing

The Map Listing utility displays/prints NATURAL maps as they appear in the NATURAL Map editor. Maps may also be displayed/printed with the field table, a list of help routines, and a list of processing/verification rules used by the map. Additionally, at the start of each map, NATURAL directory information and information about the archiving event (if applicable) is displayed/printed.

To access the Map Listing screen, enter "B" on the Documentation Tools menu.

```

01-12-31                      N-2-O DOCUMENTATION TOOLS                      TSI0373
11:33:00                      MAP LISTING                                   TSI1

Print Map(s)
- Env Def.....: TEST
- Library.....: PAYTEST_
- Starting Map.....: PAYM* (Wildcard/Single)
- Ending Map.....: (Both Blank=All)

Options
- Show Fields & Rules...: N (Yes/No)
- Force Uppercase.....: N (Yes/No)
- Route Output.....: S (Screen/Printer)
- Mode.....: O (On-line/Batch)

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
HELP ---- END ----
```

Field	Description
∞ ENV DEF	The Environment Definition containing the map(s) to be displayed/printed. Remote Environments Definitions are not valid.
LIBRARY (required)	The NATURAL library containing the map(s) to be displayed/printed.
STARTING MAP (optional)	The starting value of the map(s) to be displayed/printed. Partial names and wildcards (e.g., AAP*) may be entered.
ENDING MAP (optional)	The ending value of the map(s) to be displayed/printed. Wildcards (e.g., AAP9*) may be entered. To display/print a single map, leave this field blank and enter the map name in the Starting Map field.

∞ indicate field-level help is available.

(Continued from previous page)

Field	Description	
SHOW FIELDS AND RULES (required)	Y	Displays/prints the map as the NATURAL Map editor presents it. Includes a list of variables used by the map, a list of the map's help routines and all processing/ verification rules used by the Map.
	N	Displays/prints only the map as the NATURAL Map editor presents it. (default: "N")
FORCE UPPERCASE (required)	Y	Converts lowercase to uppercase.
	N	Does not convert lowercase to uppercase. (default: "N")
ROUTE OUTPUT (required)	S	Routes output to screen. (default: "S")
	P	Routes output to NATURAL Printer 1 (CMPRT01).

Note: When printing to CMPRT01 (NATURAL printer 1) during an on-line session, it is recommended that the user determine if CMPRT01 is available. This can be done by use of the NATURAL "GLOBALS" and/or "SYSFILE" command (refer to the *NATURAL Utilities Manual* for more information). The N2O Documentation Tools will detect that CMPRT01 is unavailable on the first attempt to write the output. A subsequent attempt to print to the unavailable CMPRT01 may result in a NAT954 or similar error and termination of the current NATURAL session.

MODE (required)	Indicates how the job is to be executed (batch or on-line).	
	B	Submits JCL to the internal reader to process the function in batch. In Batch Mode, the output is automatically routed to NATURAL Printer 1.
	O	Processes the function on-line. (default: "O")

The following is sample output from the Map Listing function. The Show Fields and Rules option was set to "Y". This sample shows how map fields, help routines, and rules will be displayed when printing Formatted Maps using the N2O Documentation tools.

```

Alphanumeric Fields
  non-protected Input field      (INPUT-ALPHA)      AAAAAAAA
  modifiable Output field       (#OUTPUT-ALPHA)    XXXXXXXX
  write protected Output field   (#PROTECT-ALPHA)   ZZZZZZZZ
Binary Fields
  non-protected Input field      (#INPUT-BINARY)    CCCCCCCC
  modifiable Output field       (#OUTPUT-BINARY)    HHHHHHHH
  write protected Output field   (#PROTECT-BINARY)  BBBBBBBB
Numeric Fields
  non-protected Input field      (#INPUT-NUMERIC)    11111111
  modifiable Output field       (#OUTPUT-NUMERIC)    99999999
  write protected Output field   (#PROTECT-NUMERIC)  00000000
Numeric Decimal Fields
  non-protected Input field      (#INPUT-NUM-DEC)    1111.111
  modifiable Output field       (#OUTPUT-NUM-DEC)    9999.999
  write protected Output field   (#PROTECT-NUM-DEC)  0000.000
Packed Fields
  non-protected Input field      (#INPUT-PACKED)    44444444
  modifiable Output field       (#OUTPUT-PACKED)    88888888
  write protected Output field   (#PROTECT-PACKED)  22222222
Packed Decimal Fields
  non-protected Input field      (#INPUT-PACKED-DEC)    4444.444
  modifiable Output field       (#OUTPUT-PACKED-DEC)    8888.888
  write protected Output field   (#PROTECT-PACKED-DEC)  2222.222
Float Fields
  non-protected Input field      (#INPUT-FLOAT)      555555555555555555
  modifiable Output field       (#OUTPUT-FLOAT)      FFFFFFFFFFFFFFFFFF
  write protected Output field   (#PROTECT-FLOAT)    333333333333333333
Integer Fields
  non-protected Input field      (#INPUT-INTEGER)     77777777
  modifiable Output field       (#OUTPUT-INTEGER)     11111111
  write protected Output field   (#PROTECT-INTEGER)    66666666
Date Fields
  non-protected Input field      (#INPUT-DATE)        MMMMMMMM
  modifiable Output field       (#OUTPUT-DATE)        DDDDDDDD
  write protected Output field   (#PROTECT-DATE)        YYYYYYYY
Time Fields
  non-protected Input field      (#INPUT-TIME)        SSSSSSSS
  modifiable Output field       (#OUTPUT-TIME)        TTTTTTTT
  write protected Output field   (#PROTECT-TIME)        RRRRRRRR
Logical Fields
  non-protected Input field      (#INPUT-LOGICAL)      O
  modifiable Output field       (#OUTPUT-LOGICAL)      L
  write protected Output field   (#PROTECT-LOGICAL)      N

Field      Format  Occurrences  From
INPUT-ALPHA      A8          TEST-DDM
#INPUT-BINARY    B4
#INPUT-DATE      D
#INPUT-FLOAT     F4
#INPUT-INTEGER   I4
#INPUT-LOGIC     L
#INPUT-NUM-DEC   N5.3
#INPUT-NUMERIC   N8
#INPUT-PACKED    P8
#INPUT-PACKED-DEC P6.2
#INPUT-TIME      T
#OUTPUT-ALPHA    A8
#OUTPUT-BINARY   B4
#OUTPUT-DATE     D
#OUTPUT-FLOAT    F4
#OUTPUT-INTEGER  I4
#OUTPUT-LOGIC    L

```

(Continued on next page)

(Continued from previous page)

```
#OUTPUT-NUM-DEC      N5.3
#OUTPUT-NUMERIC      N8
#OUTPUT-PACKED        P8
#OUTPUT-PACKED-DEC    P6.2
#OUTPUT-TIME          T
#PROTECT-ALPHA        A8
#PROTECT-BINARY       B4
#PROTECT-DATE         D
#PROTECT-FLOAT        F4
#PROTECT-INTEGER      I4
#PROTECT-LOGIC        L
#PROTECT-NUM-DEC      N5.3
#PROTECT-NUMERIC      N8
#PROTECT-PACKED       P8
#PROTECT-PACKED-DEC   P6.2
#PROTECT-TIME         T
```

```
+-----+
|Help routines|
+-----+
|Field          |Help routine|
+-----+
|Map Default    |'MAPHELP', 'MAP1PM|
| #INPUT-DATE   |'MAPFHELP'|
+-----+
```

```
+-----+
|Processing Rules|
+-----+
|Field: TEST-DDM.INPUT-ALPHA ----- Rank : 01|
+-----+
```

```
Type.....: PREDICT Automatic ( Verification: INPUT-ALPHA )
Ver Status...: Automatic
Comment(s)...: Example of an Automatic rule
Description...:
=====
Verification additional description
=====
Example Automatic rule extended description
Ver. Type....: User-defined
Code.....: IF & = ' '
            REINPUT 'FIELD CANNOT BE BLANK' MARK *&
            END-IF
```

```
+-----+
|Field: OUTPUT-ALPHA ----- Rank : 10|
+-----+
```

```
Type.....: PREDICT Free ( Verification: CHECK-UPPER )
Ver Status...: Free
Comment(s)...: example of a free rule
Description...:
=====
Verification additional description
=====
Example free rule extended description
Ver. Type....: Range of values
Value(s).....: A
               Z
Code:.....: *
            * PROCESSING RULE: CHECK-UPPER WAS GENERATED BY PREDICT
            * VERIFICATION-TYPE: RANGE ON: 99-12-31 AT: 14:24
            *
            IF NOT(& EQ 'A' THRU 'Z')
            REINPUT
              'FIELD VALUES MUST BE IN RANGE FROM: A TO Z '
              MARK *&
            END-IF
```


The following are fields and descriptions for the Processing Rules section of the report.

Field	Description
FIELD (all types)	The name of the map field.
RANK (all types)	The rank of the corresponding processing/ verification rules.
TYPE (all types)	<p>The manner in which the rule is defined to the map. Valid values are as follows:</p> <p>PREDICT Automatic The rule is a PREDICT Automatic Verification rule linked to the field through a DDM. Following this type, the PREDICT Verification name is displayed.</p> <p>PREDICT Free The rule is a PREDICT Verification rule linked to the field through the Map editor by using the Verification Name. Following this type, the PREDICT Verification name is displayed.</p> <p>Inline The rule was entered directly into the map using the map editor.</p>
VER STATUS (PREDICT types only)	<p>The Status of the Verification according to PREDICT.</p> <p>Automatic Free</p> <div style="border: 1px solid black; padding: 5px;"> <p>Note: Automatic Verification rules can be shown as Type : PREDICT Free. This occurs when automatic rule is used as a free rule. (Refer to the <i>PREDICT Reference Manual</i> for more information.)</p> </div>
COMMENT(S) (PREDICT types only)	The PREDICT comments for the corresponding Verification.
DESCRIPTION (PREDICT types only)	The PREDICT extended description for the corresponding Verification.

(Continued from previous page)

Field	Description
VER TYPE (PREDICT types only)	The types of Verification. Valid values are as follows: <ul style="list-style-type: none"> Equal to Greater than Less than Not equal to Range of values Table of values User routine Range but not Not in range Unknown
VALUE(S) (PREDICT types only with value(s) defined)	The valid values used to perform the Verification. (Refer to the <i>PREDICT Reference Manual</i> for more information.)
CODE (all types)	The actual NATURAL code of the rule. For PREDICT types, this code is stored in PREDICT. For Inline type, this code is stored in the map.

When the Environment Definition entered is an N2O Archive Definition, a pop-up window is displayed. One of the following fields must be provided:

1. An Archive Date, which must be entered using the YYYYMMDD format.
 - 1) When printing a single object
A list of archive versions is generated and displayed, starting at the most recent archive and continuing until the specified Archive Date. One of the versions must be chosen from this list.
 - 2) When printing a range of objects
Displays the first version of each object located on the archive file for the specified range archived before or at the specified date.
- b) An Archive Version Number, which allows N2O to go directly to the Archive file and read the specified version. The Archive Version Number may be between -1 and -99.

V.2.3 Data Area Listing

The Data Area Listing Utility displays/prints NATURAL data areas (Global, Local, and Parameter) as they appear in the NATURAL Data Area editor. Additionally, at the start of each data area, NATURAL directory information and information about the archiving event (if applicable) is displayed/printed.

To enable the paging up/down in Data Area Listing, ADAV7 should be specified in the NTDB macro. Refer to the N2O Administrator Manual **Section II.3.8 Installation Procedure step 8**.

To access the Data Area Listing screen, enter "C" on the Documentation Tools menu.

```
01-12-31          N-2-O DOCUMENTATION TOOLS          TSI0373
11:33:00          DATA AREA LISTING                  TSI1

Print Data Area(s)
- Env Def.....: TEST
- Library.....: PAYTEST_
- Starting Data Area....: PAYL* (Wildcard/Single)
- Ending Data Area.....: (Both Blank=All)

Options
- Force Uppercase.....: N (Yes/No)
- Route Output.....: S (Screen/Printer)
- Mode.....: O (On-line/Batch)

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
HELP ---- END ----
```

Field	Description
∞ ENV DEF	The Environment Definition containing the data area(s) to be displayed/printed. Remote Environments Definitions are not valid.
LIBRARY (required)	The NATURAL library containing the data area(s) to be displayed/printed.
STARTING DATA AREA (optional)	The starting value of the data area(s) to be displayed/printed. Partial names and wildcards (e.g., AAP*) may be entered.
ENDING DATA AREA (optional)	The ending value of the data area(s) to be displayed/printed. Wildcards (e.g., AAP9*) may be entered. To display/print a single data area, leave this field blank and enter the data area name in the Starting Data Area field.
FORCE UPPERCASE (required)	Y Converts lowercase to uppercase. N Does not convert lowercase to uppercase. (default: "N")

∞ indicate field-level help is available.

(Continued from previous page)

Field	Description	
ROUTE OUTPUT (required)	S	Routes output to screen. (default: "S")
	P	Routes output to NATURAL Printer 1 (CMPRT01).

Note: When printing to CMPRT01 (NATURAL printer 1) during an on-line session, it is recommended that the user determine if CMPRT01 is available. This can be done by use of the NATURAL "GLOBALS" and/or "SYSFILE" command (refer to the *NATURAL Utilities Manual* for more information). The N2O Documentation Tools will detect that CMPRT01 is unavailable on the first attempt to write the output. A subsequent attempt to print to the unavailable CMPRT01 may result in a NAT954 or similar error, and termination of the current NATURAL session.

MODE (required)	Indicates how the job is to be executed (batch or on-line).	
	B	Submits JCL to the internal reader that processes the function in batch. In Batch Mode, the output is automatically routed to NATURAL Printer 1.
	O	Processes the function on-line. (default: "O")

When the Environment Definition entered is an N2O Archive Definition, a pop-up window is displayed. One of the following fields must be provided:

- a) An Archive Date, which must be entered using the YYYYMMDD format.
 - 1) When printing a single object
A list of archive versions is generated and displayed, starting at the most recent archive and continuing until the specified Archive Date. One of the versions must be chosen from this list.
 - 2) When printing a range of objects
Displays the first version of each object located on the archive file for the specified range archived before or at the specified date.
- b) An Archive Version Number, which allows N2O to go directly to the Archive file and read the specified version. The Archive Version Number may be between -1 and -99.

V.2.4 File Layouts

The File Layouts utility displays/prints File Layouts from PREDICT or NATURAL DDMs.

The Dbid Nr displayed in the header of the File Layout Report, is the Database ID number found in the Data Repository.

If PREDICT is the Data Repository, the Dbid Nr is the number defined to the database object linked to the file. If no database is linked to the file, the Dbid Nr is "UNKN". If DDM is the Data Repository, the Dbid Nr is the number of the database defined in the DDM.

To access the File Layouts screen, enter "D" on the Documentation Tools menu.

```
01-12-31          N-2-O DOCUMENTATION TOOLS          TSI0373
11:33:00          FILE LISTING                      TSI1

Print File(s)
- Env Def.....: TEST
- Starting file..: PAYROLL-FILE_____ (Wildcard/Single)
- Ending File....: _____ (Both Blank=All)
- With Keyword...: _____ (Optional)

Options
- Detail Level...: E (Extended Description/Long/Short)
- Data Repository: P (PREDICT/DDM)
- Force Uppercase: N (Yes/No)
- Route Output...: S (Screen/Printer)
- Mode.....: O (On-line/Batch)

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
HELP  ---  END  ---  ---  ---  ---  ---  ---  ---  ---  ---  ---  ---
```

Field	Description
∞ ENV DEF	The Environment Definition containing the file(s) to be displayed/printed. Remote Environments and Archive Definitions are not valid.
STARTING FILE (optional)	The starting value of the file(s) to be displayed/printed. Partial names and wildcards (e.g., AAP*) may be entered.
ENDING FILE (optional)	The ending value of the file(s) to be displayed/printed. Wildcards (e.g., AAP9*) may be entered. To display/print a single file, leave this field blank and enter the filename in the Starting File field.
WITH KEYWORD (optional)	PREDICT file descriptions with this keyword will be selected. This option is ignored when data repository is equal to "D".
∞ indicate field-level help is available.	

(Continued from previous page)

Field		Description
DETAIL LEVEL (required)	E	Displays/prints extended descriptions, all file and field comments, keywords, and owners. (default: "E")
	L	Displays/prints all file and field comments, keywords, and owners.
	S	Displays/prints all file comments and the first line of field comments.
DATA REPOSITORY (required)	P	Reads file information from PREDICT. (default: "P")
	D	Reads file information from NATURAL DDMs. Information obtained from the DDM does not have extended descriptions, file comments, keywords, and owners. Field comments will be shown only if the DDM(s) was generated with them.
FORCE UPPERCASE (required)	Y	Converts lowercase to uppercase.
	N	Does not convert lowercase to uppercase. (default: "N")
ROUTE OUTPUT (required)	S	Routes output to screen. (default: "S")
	P	Routes output to NATURAL Printer 1 (CMPRT01).

Note: When printing to CMPRT01 (NATURAL printer 1) during an on-line session, it is recommended that the user determine if CMPRT01 is available. This can be done by use of the NATURAL "GLOBALS" and/or "SYSFILE" command (refer to the *NATURAL Utilities Manual* for more information). The N2O Documentation Tools will detect that CMPRT01 is unavailable on the first attempt to write the output. A subsequent attempt to print to the unavailable CMPRT01 may result in a NAT954 or similar error, and termination of the current NATURAL session.

MODE (required)		Indicates how the job is to be executed (batch or on-line).
	B	Submits JCL to the internal reader to process the function in batch. In Batch Mode, the output is automatically routed to NATURAL Printer 1.
	O	Processes the function on-line. (default: "O")

V.2.5 Descriptor X-REF Information

The Descriptor X-REF Information utility produces a report on descriptor usage using PREDICT Cross-Reference data. This report will only show NATURAL objects that were compiled with XREF=ON. Since this report is CPU intensive, it is recommended that this report be executed in batch.

The Dbid Nr displayed in the header of the Descriptor X-REF Report is the Database ID number defined to the database object linked to the file. If no database is linked to the file, the Dbid Nr is "UNKN".

To access the Descriptor X-REF Information screen, enter "E" on the Documentation Tools menu.

```

01-12-31                      N-2-O DOCUMENTATION TOOLS                      TSI0373
11:33:00                      DESCRIPTOR X-REF INFORMATION                      TSI1

Print X-REF Info for File(s)
- Env Def.....: TEST
- Starting file..: PAYROLL-FILE_____ (Wildcard/Single)
- Ending File....: _____ (Both Blank=All)

Options
- Report Type....: S (Summary/Detail)
- Force Uppercase: N (Yes/No)
- Route Output...: S (Screen/Printer)
- Mode.....: O (On-line/Batch)

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11--PF12---
HELP  ---- END  ----  ----  ----  ----  ----  ----  ----  ----  ----  ----

```

Field	Description
∞ ENV DEF	The Environment Definition containing the file(s) to be cross-referenced. Remote Environments and Archive Definitions are not valid.
STARTING FILE (optional)	The starting value of the file(s) to be cross-referenced. Partial names and wildcards (e.g., AAP*) may be entered.
ENDING FILE (optional)	The ending value of the file(s) to be cross-referenced. Wildcards (e.g., AAP9*) may be entered. To display/print a single file, leave this field blank and enter the filename in the Starting File field.

"∞" indicate field-level help is available.

(Continued from previous page)

Field	Description	
REPORT TYPE	S	Provides a Summary report including the file name, descriptor type, field name, field format, and field length. It also lists the number of times each descriptor is used in a search, update, read, delete, and view. (default: "S")
	D	Provides a Detail report including the above information with the addition of up to 660 object names in which the descriptor is used.
FORCE UPPERCASE (required)	Y	Converts lowercase to uppercase.
	N	Does not convert lowercase to uppercase. (default: "N")
ROUTE OUTPUT (required)	S	Routes output to screen. (default: "S")
	P	Routes output to NATURAL Printer 1 (CMPRT01).

Note: When printing to CMPRT01 (NATURAL printer 1) during an on-line session, it is recommended that the user determine if CMPRT01 is available. This can be done by use of the NATURAL "GLOBALS" and/or "SYSFILE" command (refer to the *NATURAL Utilities Manual* for more information). The N2O Documentation Tools will detect that CMPRT01 is unavailable on the first attempt to write the output. A subsequent attempt to print to the unavailable CMPRT01 may result in a NAT954 or similar error, and termination of the current NATURAL session.

MODE (required)	Indicates how the job is to be executed (batch or on-line).	
	B	Submits JCL to the internal reader to process the function in batch. In Batch Mode, the output is automatically routed to NATURAL Printer 1.
	O	Processes the function on-line. (default: "O")

V.2.6 Object Flow Analysis

The Object Flow Analysis utility displays/prints NATURAL object(s) and will identify processing loops and statement blocks. For DEFINE DATA /Data areas, the lengths of all fields for each level are accumulated and displayed/printed. Refer to the example in this sub-section. Additionally, at the start of each object, NATURAL directory information and information about the archiving event (if applicable) is displayed/printed.

To access the Object Flow Analysis screen, enter "F" on the Documentation Tools menu.

```

01-12-31                      N-2-O DOCUMENTATION TOOLS                TSI0373
11:33:00                      OBJECT FLOW ANALYSIS                     TSI1

Print Flow Analysis Object(s)
- Env Def.....: TEST
- Library.....: PAYTEST_
- Starting Object.....: PAY* (Wildcard/Single)
- Ending Object.....: (Both Blank=All)

Options
- Force Uppercase.....: N (Yes/No)
- Route Output.....: S (Screen/Printer)
- Mode.....: O (On-line/Batch)

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
HELP ---- END ----
```

Field	Description
∞ ENV DEF	The Environment Definition containing the object(s) to be analyzed. Remote Environments Definitions are not valid.
LIBRARY (required)	The NATURAL library containing the object(s) to be analyzed.
STARTING OBJECT (optional)	The starting value of the object(s) to be analyzed. Partial names and wildcards (e.g., AAP*) may be entered.
ENDING OBJECT (optional)	The ending value of the object(s) to be analyzed. Wildcards (e.g., AAP9*) may be entered. To analyze a single object, leave this field blank and enter the object's name in the Starting Object field.
FORCE UPPERCASE (required)	Y Converts lowercase to uppercase. N Does not convert lowercase to uppercase. (default: "N")

∞ indicate field-level help is available.

(Continued from previous page)

Field	Description	
ROUTE OUTPUT (required)	S	Routes output to screen. (default: "S")
	P	Routes output to NATURAL Printer 1 (CMPRT01).

Note: When printing to CMPRT01 (NATURAL printer 1) during an on-line session, it is recommended that the user determine if CMPRT01 is available. This can be done by use of the NATURAL "GLOBALS" and/or "SYSFILE" command (refer to the *NATURAL Utilities Manual* for more information). The N2O Documentation Tools will detect that CMPRT01 is unavailable on the first attempt to write the output. A subsequent attempt to print to the unavailable CMPRT01 may result in a NAT954 or similar error, and termination of the current NATURAL session.

MODE (required)	Indicates how the job is to be executed (batch or on-line).	
	B	Submits JCL to the internal reader that processes the function in batch. In Batch Mode, the output is automatically routed to NATURAL Printer 1.
	O	Processes the function on-line. (default: "O")

When the Environment Definition entered is an N2O Archive Definition, a pop-up window is displayed. One of the following fields must be provided:

- a) An Archive Date, which must be entered using the YYYYMMDD format.
 - 1) When printing a single object
A list of archive versions is generated and displayed, starting at the most recent archive and continuing until the specified Archive Date. One of the versions must be chosen from this list.
 - 2) When printing a range of objects
Displays the first version of each object located on the archive file for the specified range archived before or at the specified date.
- b) An Archive Version Number, which allows N2O to go directly to the Archive file and read the specified version. The Archive Version Number may be between -1 and -99.

The following is sample output from the Object Flow Analysis utility:

```

0010 ** Example Object Flow Analysis
0020 DEFINE DATA LOCAL
0030 1 #I (N4)
0040 1 #J (N4)
0050 1 #A (A10/1:100)
0060 1 #B (A10/1:100)
0070 END-DEFINE
0080 **
0090 REPEAT
| +-----FOR #I EQ 1 TO 100
| | +-----IF #A(#I) GT #B(#I)
| | | MOVE #A(#I) TO #B(#I)
| | +-----ELSE
| | | WRITE 'DATA ERROR'
| | | <--ESCAPE ROUTINE
| | +-----END-IF
| |
| +-----END-FOR
+-----END-REPEAT
0100 FOR #I EQ 1 TO 100
0110 IF #A(#I) GT #B(#I)
0120 MOVE #A(#I) TO #B(#I)
0130 ELSE
0140 WRITE 'DATA ERROR'
0150 ESCAPE ROUTINE
0160 END-IF
0170 ADD 1 TO #J
0180 END-FOR
0190 END-REPEAT
0200 **
0210 ...

```

Note: The Object Analysis Flow utility relies on the mode (Report or Structured) defined to the object to determine the beginning and ending of the Looping/Control structures.

An object containing Structured mode code, but saved in Report mode, will be analyzed as a Report mode object (i.e., IFs use DO/DOEND, and Processing Loops are closed with LOOP).

An object containing Report mode code but saved in Structured mode will be analyzed as a Structured mode object (i.e., IFs end with END-IF, and Processing Loops are closed with the appropriate END- Statement).

The NATURAL compiler will not allow the user to stow an object with either of the cases above. Copycode is not stowed, therefore it can contain the opposite mode of code than the saved mode of the object.

To receive the correct results, change the mode of the Copycode to match the current programming mode and resave it.

Note: The accumulation of level field lengths for DEFINE DATA / data areas requires a valid field length after the field name. Fields from views without a valid field length are ignored for the accumulation.

Arrays that define the array index notation with a constant will return "CONST" as the length.

V.2.7 Object X-REF

The Object X-REF utility displays/prints PREDICT Cross-Reference information for NATURAL object(s) identifying copycode, data areas, DDMs, files, programs, subroutines, subprograms, SYSERRs, and views referenced. Variables within data areas, DDMs, and views are also identified. This report requires that all NATURAL objects are compiled with XREF=ON. Additionally, at the start of each object, NATURAL directory information and the first block of comments found in the object is displayed/printed.

To access the Object X-REF screen, enter "G" on the Documentation Tools menu.

01-12-31 11:33:00	N-2-O DOCUMENTATION TOOLS OBJECT X-REF	TSI0373 TSI1
<p>Print Object X-REF(s)</p> <p>- Env Def.....: TEST</p> <p>- Library.....: PAYTEST_</p> <p>- Starting Object.....: PAY*_____ (Wildcard/Single)</p> <p>- Ending Object.....: _____ (Both Blank=All)</p>		
<p>Options</p> <p>- Force Uppercase.....: N (Yes/No)</p> <p>- Route Output.....: S (Screen/Printer)</p> <p>- Mode.....: O (On-line/Batch)</p>		
<p>Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---</p> <p>HELP ---- END ----</p>		

Field	Description
∞ ENV DEF	The Environment Definition containing the object(s) to be cross-referenced. Remote Environments and Archive Definitions are not valid.
LIBRARY (required)	The NATURAL library containing the object(s) to be cross-referenced.
STARTING OBJECT (optional)	The starting value of the object(s) to be cross-referenced. Partial names and wildcards (e.g., AAP*) may be entered.
ENDING OBJECT (optional)	The ending value of the object(s) to be cross-referenced. Wildcards (e.g., AAP9*) may be entered. To cross-reference a single object, leave this field blank and enter the object's name in the Starting Object field.
FORCE UPPERCASE (required)	Y Converts lowercase to uppercase. N Does not convert lowercase to uppercase. (default: "N")

∞ indicate field-level help is available.

(Continued from previous page)

Field	Description	
ROUTE OUTPUT (required)	S	Routes output to screen. (default: "S")
	P	Routes output to NATURAL Printer 1 (CMPRT01).
<div> Note: When printing to CMPRT01 (NATURAL printer 1) during an on-line session, it is recommended that the user determine if CMPRT01 is available. This can be done by use of the NATURAL "GLOBALS" and/or "SYSFILE" command (refer to the <i>NATURAL Utilities Manual</i> for more information). The N2O Documentation Tools will detect that CMPRT01 is unavailable on the first attempt to write the output. A subsequent attempt to print to the unavailable CMPRT01 may result in a NAT954 or similar error, and termination of the current NATURAL session. </div>		
MODE (required)	Indicates how the job is to be executed (batch or on-line).	
	B	Submits JCL to the internal reader that processes the function in batch. In Batch Mode, the output is automatically routed to NATURAL Printer 1.
	O	Processes the function on-line. (default: "O")

The following is a sample Object X-REF Report.

Modules used :+-----+			
	PERFORM	FEDTAXS	
	PERFORM	CTYTAXS	CALCULATE-CITY-TAX
	PERFORM	*UNKNOWN	CALCULATE-LOCAL-TAX
	CALLNAT	PAYCHKP	
	MAP	PAYTAXM	
+-----+			

The first column of the output specifies what NATURAL statement invokes the referenced module. For external subroutines, the next column will show the actual (or short) subroutine name. If the subroutine is performed using the long name, the long name appears in the third column. If N2O cannot locate a subroutine containing the long name, *UNKNOWN will appear. For all other NATURAL statements, the object referenced is identified in the second column. The third column is blank.

V.2.8 SYSERR Message Listing

The SYSERR Message Listing Utility displays/prints NATURAL SYSERR(s) (Long, Short, or Both).

To access the SYSERR Message Listing screen, enter "H" on the Documentation Tools menu.

```

01-12-31          N-2-O DOCUMENTATION TOOLS          TSI0373
11:33:00          SYSERR MESSAGE LISTING              TSI1

Print SYSERR(s)
- Env Def.....: TEST
- Library.....: PAYTEST_
- Starting SYSERR...: 1*_____ (Wildcard/Single)
- Ending SYSERR...: _____ (Both Blank=All)
- SYSERR Type.....: US          (U/US/UL)
- SYSERR Language...: *_____ (1-8, *=All)

Options
- Force Uppercase...: N (Yes/No)
- Route Output.....: S (Screen/Printer)
- Mode.....: O (On-line/Batch)

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
HELP ---- END ---- ---- ---- ---- ---- ---- ---- ---- ----

```

Field	Description
∞ ENV DEF	The Environment Definition containing the SYSERR(s) to be displayed/printed. Remote Environments Definitions are not valid.
LIBRARY (required)	The NATURAL library containing the SYSERR(s) to be displayed/printed.
STARTING SYSERR (optional)	The starting value of the SYSERR(s) to be displayed/printed. Partial names and wildcards (e.g., 11*) may be entered.
ENDING SYSERR (optional)	The ending value of the SYSERR(s) to be displayed/printed. Wildcards (e.g., 11*) may be entered. To display/print a single SYSERR, leave this field blank and enter the SYSERR number in the Starting SYSERR field.
SYSERR TYPE (required)	The type of SYSERR message to be displayed/printed. Valid values are as follows: <ul style="list-style-type: none"> US User-supplied short message. UL User-supplied long message. U Both short and long messages.

∞ indicate field-level help is available.

(Continued from previous page)

Field	Description	
SYSERR LANGUAGE (required)	<p>The language(s) of SYSERR message to be displayed/printed. Valid values are single alphanumeric characters in the ranges 1 - 9, A - Z and a - y. These values are equivalent to the values available for the *LANGUAGE system variable.</p> <p>(* can be used to display all languages)</p>	
FORCE UPPERCASE (required)	Y	Converts lowercase to uppercase.
	N	Does not convert lowercase to uppercase. (default: "N")
ROUTE OUTPUT (required)	S	Routes output to screen. (default: "S")
	P	Routes output to NATURAL Printer 1 (CMPRT01).
<div> <p>Note: When printing to CMPRT01 (NATURAL printer 1) during an on-line session, it is recommended that the user determine if CMPRT01 is available. This can be done by use of the NATURAL "GLOBALS" and/or "SYSFILE" command (refer to the <i>NATURAL Utilities Manual</i> for more information). The N2O Documentation Tools will detect that CMPRT01 is unavailable on the first attempt to write the output. A subsequent attempt to print to the unavailable CMPRT01 may result in a NAT954 or similar error, and termination of the current NATURAL session.</p> </div>		
MODE (required)	Indicates how the job is to be executed (batch or on-line).	
	B	Submits JCL to the internal reader that processes the function in batch. In Batch Mode, the output is automatically routed to NATURAL Printer 1.
	O	Processes the function on-line. (default: "O")

When the Environment Definition entered is an N2O Archive Definition, a pop-up window is displayed. One of the following fields must be provided:

- a) An Archive Date, which must be entered using the YYYYMMDD format.
 - 1) When printing a single object
A list of archive versions is generated and displayed, starting at the most recent archive and continuing until the specified Archive Date. One of the versions must be chosen from this list.
 - 2) When printing a range of objects
Displays the first version of each object located on the archive file for the specified range archived before or at the specified date.
- b) An Archive Version Number, which allows N2O to go directly to the Archive file and read the specified version. The Archive Version Number may be between -1 and -99.

V.2.9 Archived 3GL Object Listing

The Archived 3GL Object Listing utility displays/prints Archived 3GL code. Additionally, at the start of each object, information about the archiving event is displayed/printed.

To enable the paging up/down in Archived 3GL Object Listing, ADAV7 should be specified in the NTDB macro. Refer to the N2O Administrator Manual **Section II.3.8 Installation Procedure step 8**.

To access the Archived 3GL Object Listing, enter "I" on the Documentation Tools menu.

Note: This utility can only be used by N2O/3GL customers.

```

01-12-31          N-2-O DOCUMENTATION TOOLS          TSI0373
11:37:57          ARCHIVED 3GL OBJECT LISTING          TSI1

Print Archived 3GL Object(s)
- Archive Def....: _____
- Category.....: _____
- Starting Object: _____ (Wildcard/Single)
- Ending Object..: _____ (Both Blank=All)
- Archive Date...: _____ (YYYYMMDD or -NN)

Options
- Count Lines....: Y (Yes/No)
- Force Uppercase: N (Yes/No)
- Route Output...: S (Screen/Printer)
- Mode.....: O (On-line/Batch)

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12--
HELP  ----  END   ----  ----  ----  ----  ----  ----  ----  ----  ----

```

Field	Description
∞ ARCHIVE DEF	The Archive Definition containing the object(s) to be printed.
∞ CATEGORY (required)	The 3GL/Other category of the Object to be printed. Valid values are as follows: <div> ASMB Indicates all types of Assembler. COBOL Indicates all types of COBOL. FORT Indicates all types of FORTRAN. PL/I Indicates all PL/I types. RPG Indicates RPG. DATA Indicates DATA FILES. JCL Indicates JCL, CLIST, CNTL. OTHER All other types. </div>
STARTING OBJECT (optional)	The starting value of the object(s) to be printed. Partial names and wildcards (e.g., AAP*) may be entered.
ENDING OBJECT (optional)	The ending value of the object(s) to be printed. Wildcards (e.g., AAP9*) may be entered. To print a single object, leave this field blank and enter the object's name in the Starting Object field.

∞ indicate field-level help is available.

(Continued from previous page)

Field	Description
∞ ARCHIVE DATE (required)	<p>The version of the archived to be displayed</p> <p>Valid values are as follows:</p> <p>An Archive Date, The Archive Date must be entered using the YYYYMMDD format.</p> <p>When printing a single object:</p> <p>A list of archive versions is generated and displayed, starting at the most recent archive and continuing until the specified Archive Date. One of the versions must be chosen from this list.</p> <p>When printing a range of objects:</p> <p>Displays the first version of each object located on the archive file for the specified range archived before or at the specified date.</p> <p>An Archive Version Number, which allows N2O to go directly to the Archive file and read the specified version. The Archive Version Number may be between -1 and -99.</p>
COUNT LINES (required)	<p>Y Generates line numbers on the left side of the output. (default: "Y")</p> <p>N Displays output without generating line numbers.</p>
FORCE UPPERCASE (required)	<p>Y Converts lowercase to uppercase.</p> <p>N Does not convert lowercase to uppercase. (default: "N")</p>
ROUTE OUTPUT (required)	<p>S Routes output to screen. (default: "S")</p> <p>P Routes output to NATURAL Printer 1 (CMPRT01).</p>

∞ indicate field-level help is available.

Note: When printing to CMPRT01 (NATURAL printer 1) during an on-line session, it is recommended that the user determine if CMPRT01 is available. This can be done by use of the NATURAL "GLOBALS" and/or "SYSFILE" command (refer to the *NATURAL Utilities Manual* for more information). The N2O Documentation Tools will detect that CMPRT01 is unavailable on the first attempt to write the output. A subsequent attempt to print to the unavailable CMPRT01 may result in a NAT954 or similar error, and termination of the current NATURAL session.

(Continued from previous page)

Field	Description
MODE (required)	Indicates how the job is to be executed (batch or on-line).
	B Submits JCL to the internal reader that processes the function in batch. In Batch Mode, the output is automatically routed to NATURAL Printer 1.
	O Processes the function on-line. (default: "O")

V.2.10 Batch Documentation Process

The following is an example of OS/390 (MVS) JCL used to run the Batch Documentation process. JCL examples are shown only for OS/390 (MVS) in this section. VSE JCL, VM EXECs, and BS2000 JCL are located in **Appendix E VSE JCL**, **Appendix F VM EXECs**, and **Appendix G BS2000 JCL** respectively. (JCL and EXECs will need to be tailored to accommodate site-specific needs.) The N2O installation tape contains sample JCL in the library N2OBATCH for the program name specified.

OS/390 (MVS) JCL:

MVSREPT

```
//BATCHREP JOB (nnn), 'N-2-O Batch Report', CLASS=A, NOTIFY=&USERID
//REPORT EXEC PGM=NATL
//CMPRT01 DD SYSOUT=A
//CMSYNIN DD *
LOGON N2OLIB
&REPORT
&INPUT
FIN
/*
//
```

Note: The batch reports from the N2O Reporting Subsystem and the Documentation Tools require that the NATURAL Parameter IM (Input Mode) be set to "IM=D" (Delimiter Mode).

The following table illustrates the names of the variables (for &INPUT) whose values will be replaced in the input stream by the on-line submit function of N2O. These values are required in order to execute Documentation reports in batch.

REPORT	&REPORT	&INPUT
Natural Object Listing	N2ODYPPP	ENV-DEF,LIB,START-OBJ,END-OBJ, ARCHIVE-DATE,EXCLUDE-TYPES, EXPLODE-COPYCODE, EXPLODE-DATAAREAS,FORMAT-MAPS, FORMAT-DATAAREAS,DISPLAY-XREF, MAKE-UPPER
Map Listing	N2ODYMPP	ENV-DEF,LIB,START-MAP,END-MAP, ARCHIVE-DATE,SHOW-FIELDS, MAKE-UPPER
Data Area Listing	N2ODYVPP	ENV-DEF,LIB,START-DATAAREA, END-DATAAREA,ARCHIVE-DATE, MAKE- UPPER
File Layouts	N2ODYFPP	ENV-DEF,START-FILE,END-FILE KEYWORD,DETAIL-LEVEL, DATA-REPOS,MAKE-UPPER

REPORT	&REPORT	&INPUT
Descriptor X-REF Information	N2ODYDPP	ENV-DEF,START-FILE,END-FILE, REPORT-TYPE,MAKE-UPPER
Object Flow Analysis	N2ODYAPP	ENV-DEF,LIBRARY,START-OBJ, END-OBJ,ARCHIVE-DATE, MAKE-UPPER
Object X-REF	N2ODYXPP	ENV-DEF,LIBRARY,START-OBJ, END-OBJ,MAKE-UPPER
SYSERR Message Listing	N2ODYSPP	ENV-DEF,LIBRARY,START-ERR, END-ERR,ERR-TYPE,ERR-LANG, ARCHIVE-DATE,MAKE-UPPER
Archived 3GL Object Listing	N2ODYOPP	ARCH-DEF,LIBRARY,START-OBJ, END-OBJ, ARCHIVE-DATE, COUNT-LINES,MAKE-UPPER

----- indicates that inputs are on separate lines.

The &INPUT parameter list by default is delimited by commas with no spaces following the commas. To override the default delimiter, modify the value of the jcl-delimiter field in User-Exit-22 (N2OUE22N).

For descriptions of &INPUT fields, refer to field descriptions in corresponding sections of Documentation Tools.

V.3 Maintenance Tools

Maintenance Tools provide utilities to delete and recover objects.

To display the Maintenance Tools menu, enter "M" on the Toolbox Subsystem menu or enter the direct command TOL MAIN on any menu.

01-12-31 11:38:00	N-2-O MAINTENANCE TOOLS MENU	TSIO373 TSI1
	Code Function	

	A N2OPURGE Utility	
	B Recover from an Archive Backup	
	C Archive Backup Report	
	D Recover from an Event Backup	
	. Terminate Maintenance Tools	

Enter Code: _	Type: N	
Direct Command: _____ TOL MAIN		
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---		
HELP ---- END ENV MIG REP TOL USR PRJ ---- ---- EXIT		

Field	Description
ENTER CODE (required)	<p>The function to be executed. Valid values are as follows:</p> <p>A N2OPURGE Utility Archives and deletes a NATURAL object and provides an audit trail.</p> <p>B Recover from an Archive Backup Recovers NATURAL objects, PDS objects, and SYSERR messages purged from an N2O Archive file.</p> <p>C Archive Backup Report Provides a report of all objects stored on an Archive Backup file.</p> <p>D Recover from an Event Backup Recovers Events purged from the N2O Migration file.</p>
TYPE (required)	<p>Valid values for the N2OPURGE utility are Natural objects (N), 3GL/OTHER (PDS objects only) (O), SYSERR messages (S), and Predict(P).</p> <p>Valid values for the Recover from an Archive Backup are NATURAL objects (N), 3GL/OTHER objects (PDS only) (O), and SYSERR messages (S).</p>

V.3.1 N2OPURGE Utility

The N2OPURGE utility deletes objects from the N2O Master Catalog and the following:

1. NATURAL objects or NATURAL SYSERRs from the NATURAL FUSER
2. NATURAL DDMs from the PREDICT FDIC
3. 3GL Objects from a PDS

If specified, the Natural object, SYSERR, or 3GL PDS source will also be archived to the N2O-Archive File, providing an audit trail of the purge.

To access the N2OPURGE Utility screen, enter "A" on the Maintenance Tools menu.

01-12-31 11:38:00	N-2-O MAINTENANCE TOOLS N2OPURGE UTILITY	TSI0373 TSI1
Env Def: PROD Library: PAYLIB Object: PAYPGMA Archive: Y Mode: O		
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12--- HELP ---- END ----		

Field	Type	Description
∞ ENV DEF (required)	N,S,D,O	The Environment Definition where the object is located.
LIBRARY (required)	N,S	The library where the NATURAL object or SYSERR is located.
OBJECT (required)	N,S,D,O	The object to be purged. ""Generates a selection list of all objects in the library. The ""may also be used as a wildcard character to select objects prefixed by a string (e.g.,N2O*).
CATEGORY (required)	O	The 3GL/Other category of the number to be recovered. Valid values are as follows: ASMB Indicates all types of Assembler. COBOL Indicates all types of COBOL. FORT Indicates all types of FORTRAN. PL/I Indicates all PL/I types. RPG Indicates RPG. DATA Indicates DATA FILES. JCL Indicates JCL, CLIST, CNTL. OTHER All other types.
OBJECT (required)	N,S,D,O	The object to be purged.

ARCHIVE
(required)

N,S,O

Indicates whether the object should be archived before it is purged or not. This option is not available for DDMs

Y Indicates the object should be archived before it is purged.

Note: Objects archived by N2OPURGE have an archive event name of N2OPURGE and a sequence number 1.

N Indicates no archiving should be performed.

∞ indicates field-level help is available.

MODE
(required)

N,S,D,O

Indicates how the job is executed (batch or on-line).

B Submits JCL to the internal reader, which processes the function in batch. (required for 3GL PDS Objects)

O Processes the function on-line. (default: O)

Entering the necessary information in the input screen and pressing Enter displays the N2OPURGE Utility report. A sample N2OPURGE Utility report screen is shown below.

01-12-31 11:38:00	N-2-O MAINTENANCE TOOLS N2OPURGE UTILITY	TSI0373 TSI1
<pre> +-----+ PROG3A Source Archived from PROD PAYPROD PROG3A Object Archived from PROD PAYPROD PROG3A Source Deleted from PROD PAYPROD PROG3A Object Deleted from PROD PAYPROD N2O Catalog Master not found for PROG3A in PAYPROD +-----+ </pre>		
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12--- HELP ---- END ---- ---- ---- ---- ---- ---- ---- ---- ---- ----		

To return to the N2OPURGE Utility screen, press Enter.

When wildcarding is specified (*in the Object field) and Enter is pressed on the initial N2OPURGE Utility screen, the popup below is displayed.

01-12-31 11:38:00	N-2-O MAINTENANCE TOOLS N2OPURGE UTILITY	TSI0373 TSI1
<pre> +-----+ N2OPURGE mass purge has been Invoked for the Environment: PROD All Objects in the Library: PAYPROD will be Purged Would you like a selection list: Y Enter=Continue PF3=Abort +-----+ </pre>		
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12--- HELP ---- END ---- ---- ---- ---- ---- ---- ---- ---- ---- ----		

Entering an "N" for the selection list in the popup and pressing Enter will invoke the N2OPURGE Utility to purge all objects that match the wildcard.

Entering a "Y" for the selection list in the popup and pressing Enter displays the N2OPURGE Utility Object Selection List screen. A sample N2OPURGE Utility Object Selection List screen is shown below.

Select Objects to Purge				N2OPURGE Object Selection List				TSI0373	
01-12-31				Env: PROD Library: PAYXPROD				TSI1	
11:38:24									
X	Object	Object Type	S/C	Purge Result	X	Object	Object Type	S/C	Purge Result
-	CITYTAXC	COPYCODE	S		-	CITYTAXM	MAP	S/C	
-	CITYTAXP	PROGRAM	S/C		-	FEDTAXC	COPYCODE	S	
-	FEDTAXM	MAP	S/C		-	FEDTAXP	PROGRAM	S/C	
-	FICAC	COPYCODE	S		-	FICAM	MAP	S/C	
-	FICAP	PROGRAM	S/C		-	KAH0100M	MAP	S/C	
-	KAH0100P	PROGRAM	S/C		-	KAH1080	PROGRAM	S/C	
-	KHBIBM	MAP	S/C		-	LIFEINSC	COPYCODE	S	
-	LIFEINSM	MAP	S/C		-	LIFEINSP	PROGRAM	S/C	
-	PAYBATCH	PROGRAM	S/C		-	PAYCOPY	COPYCODE	S	
-	PAYKH	PROGRAM	S/C		-	PAYROLL	PROGRAM	S/C	
-	PAY0100M	MAP	S/C		-	PAY0100P	PROGRAM	S/C	
-	PAY0100T	MAP	S/C		-	PAY0110M	MAP	S/C	
-	PAY0110P	PROGRAM	S/C		-	PAY0110T	MAP	S/C	
-	PAY0120M	MAP	S/C		-	PAY0120P	PROGRAM	S/C	
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11--PF12 -									
----- END ----- STOP									

Field	Type	Description
ENV (supplied)	N,S,D,O	The Environment Definition where the NATURAL object is located.
LIBRARY (supplied)	N,S	The library where the NATURAL object is located.
CATEGORY (required)	O	The 3GL/Other category of the object to be recovered. Valid values are as follows: ASMB Indicates all types of Assembler. COBOL Indicates all types of COBOL. FORT Indicates all types of FORTRAN. PL/I Indicates all PL/I types. RPG Indicates RPG. DATA Indicates DATA FILES. JCL Indicates JCL, CLIST, CNTL. OTHER All other types.
X (optional)	N,S,D,O	"X" in the Select field purges the object.
OBJECT (supplied)	N,S,D,O	The object to be purged.
OBJECT TYPE (supplied)	N	Identifies the type of NATURAL object.
S/C (supplied)	N	S Indicates only the source form of the program may be selected. C Indicates only the cataloged form of the program may be selected. S/C Indicates both forms of the program may be selected.

(Continued from previous page)

Field	Type	Description
PURGE RESULT (supplied)	N	<p>Indicates the success or failure of the requested purge:</p> <p>Chkout Indicates the purged was prevented because the object is checked out.</p> <p>Error Indicates a failed purge.</p> <p>No ARCH Indicates a failed purge because Archiving is specified and Environment Definition does not have an Archive Definition.</p> <p>Uexit12 Indicates the purge was prevented by user-exit 12.</p> <p>3GL ENV Indicates a failed purge because Environment Definition is a 3GL Environment.</p> <p>Column 1 "S" indicates Object's source code has been purged</p> <p>Column 2 "C" indicates Object's object code has been purged</p> <p>Column 3 "S" indicates Object's source code has been archived</p> <p>Column 4 "C" indicates Object's object code has been archived</p> <p>Column 5 "X" indicates Object's XREF data has been purged</p> <p>Column 6 "M" indicates Object's master record has been purged</p>

Job Steps for the Batch N2OPURGE Utility

The job steps for the Batch N2OPURGE utility are described below.

N2OPURGE of Natural, SYSERR, and DDMs

N2OPURGE

This step is controlled by card image input. Control cards specify which object is to be purged.

N2OPURGE is a NATURAL object that verifies security in User-Exit 12, checks for a valid environment, and builds the output parameter file CMWKF01. Refer to the **N2O Administrator Manual** for details on User-Exit 12.

This step must be executed from a NATURAL FUSER that is local to the N2O Installation.

PURGE and ARCHIVE

N2OPURG1 is a NATURAL object that inputs CMWKF01, the output parameter file from N2OPURGE. This step must be executed from a NATURAL FUSER local to where the object is located. N2OPURG1 reads the input cards, which identify the Environment Definition where the NATURAL object is located and the object to be purged. An output dataset of acknowledgment records is created as CMWKF02.

N2OPURGE ACKNOWLEDGMENT

N2OPURG2 is a NATURAL object that must be executed from a NATURAL FUSER that is local to the N2O installation. Acknowledgment records created by step N2OPURG1 are input as CMWKF02 to update the N2O Migration file.

N2OPURGE of 3GL PDS objects

The standard N2O3GL JCL program (executing N2OSEL) located in the N2O JCL library is used to build/submit the N2OPURGE of 3GL PDS objects (uses member PDSPURGE). N2O3GL processing is documented in the N2O Administrator Manual Section V.5.1 Overview of 3GL Batch Processing.

IEBTPCH is used to write the specified objects to the SYSUT1 work file. An IDCAMS delete step is used to delete the objects.

N2OPURG3 is a Natural object that must be executed from a Natural FUSER that is local to the N2O installation. N2O is updated with an acknowledgement of the delete by reading the IDCAMS delete output.

Note: Sites that have N2OPURGE'd objects that were not archived, should execute program CONV531P to update existing N2OPURGE'd detail records, allowing them to be displayed on the History of an Environment and History of an Object reports. CONV531P can be executed online or batch. It should be run in an environment that has access to the N2O Migration file.

Batch N2OPURGE Utility JCL – Natural, SYSERR, and DDMs

JCL examples are shown only for OS/390 (MVS) in this section. VSE JCL, VM EXECs, and BS2000 JCL are located in **Appendix E VSE JCL**, **Appendix F VM EXECs**, and **Appendix G BS2000 JCL** respectively.

The following sample JCL may be used to execute the N2OPURGE utility in batch. The sample assumes that both the N2O files and NATURAL FUSER file where the object is to be purged are on the same node. Sample Batch N2OPURGE JCL is provided on the N2O installation tape in the library N2OBATCH as object "MVSPURGE".

When submitting the JCL manually, replace the &INPUT with the Object Type, Environment Definition, library, object name, and the archive option (Y or N) for each object to be purged (separated by ' '). Valid values for Object Type are N (NATURAL), S (SYSERR messages), and P (PREDICT).

Multiple records may be specified when manually submitted. "9999" must be specified for the Environment Definition to terminate input.

MVSPURGE

```
//N2OPURGE JOB (20000),'BATCH N2OPURGE',CLASS=T,NOTIFY=&USERID
/*
//N2OPURGE EXEC PGM=NATBATCH
//CMWKFO1 DD DSN=N2OPURGE.LIST,DISP=(,CATLG),
//          DCB=(RECFM=VB,LRECL=123,BLKSIZE=127),
//          UNIT=SYSDA,SPACE=(TRK,(12,12))
//CMPRINT DD SYSOUT=*
//CMSYNIN DD *
LOGON N2OLIB
N2OPURGE
&INPUT
FIN
/*
//N2OPURG1 EXEC PGM=NATBATCH
//CMWKFO1 DD DSN=N2OPURGE.LIST,DISP=(OLD,DELETE)
//CMWKFO2 DD DSN=N2OPURGE.ACKN,DISP=(,CATLG),
//          DCB=(RECFM=VB,LRECL=290,BLKSIZE=294),
//          UNIT=SYSDA,SPACE=(TRK,(12,12))
//CMPRINT DD SYSOUT=*
//CMSYNIN DD *
LOGON SYSTEM
N2OPURG1
FIN
/*
//N2OPURG2 EXEC PGM=NATBATCH
//CMWKFO2 DD DSN=N2OPURGE.ACKN,DISP=(OLD,DELETE)
//CMPRINT DD SYSOUT=*
//CMSYNIN DD *
LOGON N2OLIB
N2OPURG2
FIN
/*
```

Batch 3GL PDS N2OPURGE Utility JCL

Available for z/OS sites only.

The following sample JCL may be used to execute the 3GL PDS N2OPURGE utility in batch. The sample assumes that both the N2O files and 3GL PDS where the object is to be purged are on the same node. Sample Batch 3GL PDS N2OPURGE JCL is provided on the N2O installation tape in the library N2OBATCH as object "MVS3PRGE". It is required the JCL be renamed to PDSPURGE and customized for site standards. Note that the NPACKN step in PDSPURGE should execute using a Natural Nucleus where N2O is installed.

User exit, N2OUE33N is called to customize the N2OPURGE of 3GL PDS objects.

The following job will be submitted using the standard N2O3GL JCL (executes N2OSELT) program located in the N2O JCL library.

```
MVS3PRGE
//PDSPURG JOB (ACCOUNTING),'PDS N2OPURGE',CLASS=A,NOTIFY=&SYSUID
//*
//*****
//***
//* THIS IS SAMPLE JCL FOR THE 3GL N2OPURGE UTILITY
//* THIS SHOULD BE RENAMED TO PDSPURGE
//***
//****
//*****
//*
//* &INCLUDE PRTPCH will be automatically replaced with the IEBTPCH
//* commands necessary to punch the members to a workfile.
//*
//NPPUNCH EXEC PGM=IEBTPCH
//SYSPRINT DD SYSOUT=*
//SYSUT1 DD DSN=&PDS,DISP=(SHR,KEEP),UNIT=SYSDA
//SYSUT2 DD DSN=&&TEMP,DISP=(NEW,PASS,DELETE),
// UNIT=SYSDA,SPACE=(TRK,(15,15))
//SYSIN DD *
&INCLUDE PRTPCH
/*
//*****
//*
//* &INCLUDE DELETE will be replaced automatically by N2O with
//* IDCAMS cards to delete each member that were migrated
//* if MOVE is specified for the Migration Profile.
//*
//NPDELETE EXEC PGM=IDCAMS,COND=(8,LT)
//SYSPRINT DD DSN=&&DELOUT,
// DCB=(RECFM=VB,LRECL=125,BLKSIZE=129),
// DISP=(NEW,PASS,DELETE),
// UNIT=SYSDA,SPACE=(TRK,(5,5))
//DD1 DD DISP=SHR,DSN=&PDS
//SYSIN DD *
&INCLUDE DELETE
/*
//*****
//* N2OPURG3 RUNS ON THE FUSER WHERE N2O IS INSTALLED.
//* IT REQUIRES A NATURAL NUC WITH ACCESS TO THE N2O-ADMINISTRATION
//* N2O-MIGRATION FILES AND ANY N2O-ARCHIVE FILE DEFINED TO THE 3GL
//* ENVIRONMENT WHERE THE 3GL N2OPURGE OCCURS.
//*****
//NPACKN EXEC NATBATCH
//CMWKF01 DD *
&N2OPURGE
/*
//CMWKF02 DD DSN=&&TEMP,DISP=(OLD,PASS,DELETE)
//CMWKF03 DD DSN=&&DELOUT,DISP=(OLD,PASS,DELETE)
//CMPRINT DD SYSOUT=*
//CMSYNIN DD *
LOGON N2OLIB
N2OPURG3
FIN
/*
//*****
```

V.3.2 Recover from an Archive Backup (Batch Only)

The Recover from an Archive Backup recovers NATURAL objects, PDS objects, and SYSERR messages purged from an Archive file.

To access the Recover from an Archive Backup screen, enter "B" on the Maintenance Tools menu.

If Checkout/Checkin is active, then the Checkout/Checkin rules are verified before recovery.

01-12-31 11:38:00	N-2-O MAINTENANCE TOOLS RECOVER FROM AN ARCHIVE BACKUP	TSI0373 TSI1
Event : _____ Sequence : _____ Object : _____ From Env : _____ From Library : _____ To Env : _____ To Library : _____ Source/Object: _____ Backup DSN : _____		
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12--- HELP ---- END ----		

Field	Type	Description
∞ EVENT (required)	N,S,O	The name of the Event that archived the NATURAL object, PDS object, or SYSERR message.
SEQUENCE (required)	N,S,O	The sequence number of the Event.
OBJECT (required)	N,S,O	The name of the NATURAL object, PDS object, or SYSERR message.
∞ FROM ENV (required)	N,S,O	The source environment of the recovery for NATURAL objects, PDS objects, or SYSERR messages.
FROM LIBRARY (required)	N,S,O	The source library of the recovery for NATURAL objects or SYSERR messages.
∞ TO ENV (required)	N,S,O	The target environment of the recovery for NATURAL objects, PDS objects, or SYSERR messages.
TO LIBRARY (required)	N,S	The target library of the recovery for NATURAL objects or SYSERR messages.

∞ indicates field-level help is available.

(Continued from previous page)

Field	Type	Description
SOURCE/ OBJECT (required)	N,O	<p>The type of NATURAL object to be recovered. Valid values are as follows:</p> <p>S NATURAL source code or PDS object.</p> <p>C NATURAL object code.</p> <p>S/C Both source and object code for NATURAL objects.</p>
SYSERR TYPE (required)	S	<p>The type of SYSERR message to be recovered. Valid values are as follows:</p> <p>US User-supplied short message.</p> <p>UL User-supplied long message.</p> <p>U Both short and long messages.</p>
CATEGORY (required)	O	<p>The 3GL/Other category of the number to be recovered. Valid values are as follows:</p> <p>ASMB Indicates all types of Assembler.</p> <p>COBOL Indicates all types of COBOL.</p> <p>FORT Indicates all types of FORTRAN.</p> <p>PL/I Indicates all PL/I types.</p> <p>RPG Indicates RPG.</p> <p>DATA Indicates DATA FILES.</p> <p>JCL Indicates JCL, CLIST, CNTL.</p> <p>OTHER All other types.</p>
BACKUP DSN (required)	N,S,O	<p>The name of the Archive backup dataset to be used in the recovery.</p>

Job Steps for the Recover from an Archive Backup Utility

The Recover from an Archive Backup process recovers an object from an Archive Backup dataset created by the Archive Purge utility. This process is executed in batch. If Checkout/Checkin is active, the Recover from an Archive Backup utility validates checkout rules before recovering the object. Following the recovery, this utility updates the N2O Migration file with the results of the recovery.

N2ORAB1

N2ORAB1 is a NATURAL object that performs the first step of the Recover from an Archive Backup utility. This step must be executed from the NATURAL FUSER that is local to the N2O installation. N2ORAB1 reads a control card from the input workfile CMWKF01. The control card specifies which Object is to be recovered.

If a user submits the recovery through a system internal reader, N2O replaces &INPUT in CMWKF01 with the correct control card. If a user submits the recovery manually, the user must create the control cards in the workfile.

N2ORAB1 verifies the control card parameters and the recovery rules for Checkout/Checkin. If the object can be recovered, an output record is written to CMWKF02.

N2ORAB2

N2ORAB2 is a NATURAL object that recovers NATURAL objects and SYSERR messages from an Archive Backup.

This step must be executed from the NATURAL FUSER that is the target of the recovery. N2ORAB2 reads the N2ORAB1 output records from CMWKF01 and locates the correct Object in the backup dataset, CMWKF02.

If a user submits the recovery through a system internal reader, N2O replaces &BACKUP with the dataset name. If a user submits the recovery manually, the dataset name must be placed in the JCL and EXECs.

N2ORAB2 recovers the object from the backup dataset to the target FUSER, and writes an acknowledgment record to CMWKF03.

N2ORAB2T

N2ORAB2T is a NATURAL object that recovers PDS objects from an Archive Backup. This step must be executed from the environment that is the target of the recovery. N2ORAB2T reads the N2ORAB1 output records from CMWKF01 and locates the correct member in the backup dataset, CMWKF02.

If a user submits the recovery through a system internal reader, N2O replaces &BACKUP with the dataset name. If a user submits the recovery manually, the dataset name must be placed in the JCL and EXECs.

N2ORAB2T recovers the object from the backup dataset to the correct PDS member, CMWKF05. If a user submits the recovery through a system internal reader, N2O replaces &MEMBER with the PDS member name. If a user submits the recovery manually, the member name must be placed in the JCL.

N2ORAB2T recovers the member from the backup dataset to a PDS member, and writes an acknowledgment record to CMWKF03.

N2ORAB3

N2ORAB3 is a NATURAL object that performs the third step of the Recover from an Archive Backup utility. This step must execute from a NATURAL FUSER that is local to the N2O installation. N2ORAB3 reads the acknowledgment records from N2ORAB2 or N2ORAB2T, and creates a record of the recovery that can be identified as RCVR-BKP on the History of an Object report.

Archive Back Up Recovery JCL for NATURAL Objects and SYSERR Messages

JCL examples are shown only for OS/390 (MVS) in this section. VSE JCL, VM EXECs, and BS2000 JCL are located in **Appendix E VSE JCL**, **Appendix F VM EXECs**, and **Appendix G BS2000 JCL** respectively.

The N2O installation tape contains sample JCL in the library N2OBATCH for the program name specified. In step 2 of the JCL below, the name of workfile 2 must be changed to the name of the Archive Backup dataset. The name of workfile 2 may also be found by selecting Object Details on the Event Details Report.

MVS RAB

```
//N2ORAB JOB (ACCT),'RECOVER ARCH BACKUP',CLASS=A,NOTIFY=&USERID
/*
/* * &INPUT will be replaced automatically by N2O with:
/* * - Type of Object (N, S)
/* * - Name of Event which archived the Object
/* * - Sequence of Event which archived the Object
/* * - Environment where Object was archived from
/* * - Library where Object was archived from
/* * - Environment where Object should be recovered to
/* * - Library where Object should be recovered to
/* * - Object name (NATURAL program, SYSERR number)
/* * - US, UL, or U
/* * Examples:
/* * N CHECKIN 271 PROD N2OPROD TEST N2OTEST PAYROLLP S
/* * S CHECKIN 271 PROD N2OPROD TEST N2OTEST 1015 US
/*
//N2ORAB1 EXEC PGM=NATBATCH
//CMWK01 DD *
&INPUT
/*
//CMWK02 DD DSN=REC.PARMS,DISP=(NEW,PASS,DELETE),
// SPACE=(TRK,(5,5),RLSE),UNIT=SYSDA,
// DCB=(RECFM=VB,BLKSIZE=193,LRECL=189)
//CMPRINT DD SYSOUT=*
//CMSYNIN DD *
LOGON N2OLIB
N2ORAB1
FIN
/*
//N2ORAB2 EXEC PGM=NATBATCH
//CMWK01 DD DSN=REC.PARMS,DISP=(OLD,DELETE,CATLG)
//CMWK02 DD DSN=&BACKUP,DISP=(OLD,KEEP,KEEP),
//CMWK03 DD DSN=REC.ACKN,DISP=(NEW,PASS,DELETE),
// SPACE=(TRK,(5,5),RLSE),UNIT=SYSDA,
// DCB=(RECFM=VB,BLKSIZE=193,LRECL=189)
//CMPRINT DD SYSOUT=*
//CMSYNIN DD *
LOGON SYSTEM
N2ORAB2
FIN
/*
//N2ORAB3 EXEC PGM=NATBATCH
//CMWK01 DD DSN=REC.ACKN,DISP=(OLD,DELETE,CATLG)
//CMPRINT DD SYSOUT=*
//CMSYNIN DD *
LOGON N2OLIB
N2ORAB3
FIN
/*
```

Recovery JCL for PDS Objects

MVSRAB

```
//N2ORAB JOB (ACCT),'RECOVER ARCH BACKUP',CLASS=A,NOTIFY=&USERID
/*
/* &INPUT will be replaced automatically by N2O with:
/* - O for 3GL/Other Member
/* - Name of Event which archived the Member
/* - Sequence of Event which archived the Member
/* - Environment where Member was archived from
/* - Environment where Member should be recovered to
/* - Member name
/* - Category
/* - S for Source
/* Examples:
/* O CHECKIN 271 PROD TEST COBPROG COBOL S
/*
//N2ORAB1 EXEC PGM=NATBATCH
//CMWKF01 DD *
&INPUT
/*
//CMWKF02 DD DSN=REC.PARMS,DISP=(NEW,PASS,DELETE),
// SPACE=(TRK,(5,5),RLSE),UNIT=SYSDA,
// DCB=(RECFM=VB,BLKSIZE=193,LRECL=189)
//CMPRINT DD SYSOUT=*
//CMSYNIN DD *
LOGON N2OLIB
N2ORAB1
FIN
/*
/*
//N2ORAB2T EXEC PGM=NATBATCH
//CMWKF01 DD DSN=REC.PARMS,DISP=(OLD,DELETE,CATLG)
//CMWKF02 DD DSN=&BACKUP,DISP=(OLD,KEEP,KEEP),
//CMWKF03 DD DSN=REC.ACKN,DISP=(NEW,PASS,DELETE),
// SPACE=(TRK,(5,5),RLSE),UNIT=SYSDA,
// DCB=(RECFM=VB,BLKSIZE=193,LRECL=189)
//CMWKF05 DD DSN=&PDS(&MEMBER),DISP=SHR
//CMPRINT DD SYSOUT=*
//CMSYNIN DD *
LOGON SYSTEM
N2ORAB2T
FIN
/*
/*
//N2ORAB3 EXEC PGM=NATBATCH
//CMWKF01 DD DSN=REC.ACKN,DISP=(OLD,DELETE,CATLG)
//CMPRINT DD SYSOUT=*
//CMSYNIN DD *
LOGON N2OLIB
N2ORAB3
FIN
/*
```

V.3.3 Archive Backup Report (Batch Only)

The Archive Backup Report displays all objects stored on an Archive Backup dataset. The Archive Backup Report is available in batch only.

To access the Archive Backup Report submit screen, enter "C" on the Maintenance Tools menu.

01-12-31 11:38:00	N-2-O MAINTENANCE TOOLS ARCHIVE BACKUP REPORT	TSI0373 TSI1
Backup Data Set Name: _____		
This Report Available in Batch Only		
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12--- HELP ---- END ----		

Field	Type	Description
BACKUP DSN (required)	N,S,O	The name of the Archive backup dataset to be reported.

Entering the Backup Dataset Name on the input screen and pressing Enter submits JCL to the internal reader, which produces the report in batch.

01-12-31 11:39:52		N-2-O OBJECT REPORTING ARCHIVE BACKUP REPORT							Page 1
		BACKUP DATA SET: PROD.ARC.BKUP							
Event/ Utility	Seq	From Env	Archive Date	Backup Date	Arc S/C	Library/ 3GL Type	Object Name	Seq/ Lng	Arch Def
DEV2PROD	6	PROD	20000211	01-02-21	S	PAYDEV	MSLOC1T	0001	ARCP
DEV2PROD	6	PROD	20000211	01-02-21	S	PAYDEV	MSLOC2T	0001	ARCP
DEV2PROD	6	PROD	20000211	01-02-21	S	PAYDEV	MSPGM1T	0001	ARCP
DEV2PROD	6	PROD	20000211	01-02-21	S	PAYDEV	MSPGM1T	0002	ARCP
DEV2PROD	6	PROD	20000211	01-02-21	S	PAYDEV	MSPGM1T	0003	ARCP
DEV2PROD	6	PROD	20000211	01-02-21	S	PAYDEV	MSPGM1T	0004	ARCP
DEV2PROD	6	PROD	20000211	01-02-21	S	PAYDEV	MSPGM1T	0005	ARCP
DEV2PROD	6	PROD	20000211	01-02-21	S	PAYDEV	MSPGM2T	0006	ARCP
DEV2PROD	6	PROD	20000211	01-02-21	S	PAYDEV	MSPGM2T	0007	ARCP
DEV2PROD	9	PROD	20000213	01-02-21	S	PAYDEV	0001	0001	ARCP
DEV2PROD	9	PROD	20000213	01-02-21	S	PAYDEV	0002	0001	ARCP
DEV2PROD	9	PROD	20000213	01-02-21	S	PAYDEV	0003	0001	ARCP
DEV2PROD	9	PROD	20000213	01-02-21	S	PAYDEV	0004	0001	ARCP
DEV2PROD	9	PROD	20000213	01-02-21	L	PAYDEV	0001	0001	ARCP
DEV2PROD	9	PROD	20000213	01-02-21	L	PAYDEV	0002	0001	ARCP
DEV2PROD	9	PROD	20000213	01-02-21	L	PAYDEV	0004	0001	ARCP

Field	Type	Description
BACKUP DATA SET (supplied)	N,S,O	The name of the Archive backup dataset being reported.
Event/Utility (supplied)	N,S,O	The Master Event of the migration.
SEQ (supplied)	N,S,O	The sequence number of the Event.
FROM ENV (supplied)	N,S,O	The source Environment Definition of the Event.
ARCHIVE DATE (supplied)	N,S,O	The date the object was Archived.
BACKUP DATE (supplied)	N,S,O	The date the Archive file was backed up.
ARCH S/C (supplied)	N,S,O	The form of the object archived. S indicates only the source form of the Program was archived. C indicates only the object form of the Program was archived. S/C indicates both forms of the program were Archived.
LIBRARY/3GL TYPE (supplied)	N,S O	The library that contained the Natural object or SYSERR message. The category of the 3GL object.
OBJECT NAME (supplied)	N,S,O	The name of the archived object.
ARCH DEF (supplied)	N,S,O	The Archive Definition used to archive the object.

Work File Reporting in Batch

The following JCL is an example of OS/390 (MVS) JCL used to support the Batch Reporting process when a work file is used as input. A JCL example is shown only for OS/390 (MVS) in this section. VSE JCL, VM EXECs, and BS2000 JCL are located in **Appendix E VSE JCL**, **Appendix F VM EXECs**, and **Appendix G BS2000 JCL** respectively. JCL and EXECs should be tailored to accommodate site-specific needs. The N2O installation tape contains sample JCL in the library N2OBATCH for the program name specified.

OS/390 (MVS) JCL:

MVSWKRP

```
//BATCHREP JOB (nnn), 'N-2-O Batch Report', CLASS=A, NOTIFY=&USERID
//REPORT EXEC PGM=NATL
//CMPRINT DD SYSOUT=*
//CMPRT01 DD SYSOUT=*
//CMSYNIN DD *
LOGON N2OLIB
N2OTOLC
&INPUT
FIN
//CMWKF01 DD DSN=&BACKUP, DISP=SHR
/*
//
```

The following tables illustrate the JCL and EXECs modifications necessary to execute the Archive Backup Report in batch.

Archive Backup Report

&Report	&INPUT	&BACKUP
N2OTOLC	Backup Data Set Name	Backup Data Set Name

V.3.4 Recover from an Event Backup (Batch Only)

The Recover from an Event Backup recovers events purged from the N2O Migration file.

To access the Recover from an Event Backup screen, enter "D" on the Maintenance Tools menu.

05-02-14 21:27:20	N-2-O MAINTENANCE TOOLS RECOVER FROM AN EVENT BACKUP	TSI0373 TSI1
Backup DSN : _____		
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12--- HELP ---- END ----		

Field	Type	Description
BACKUP DSN (required)	N	The name of the event backup dataset created by the Event Purge process to be used in the recovery.

Job Steps for the Recover from an Event Backup Utility

The Recover from an Event Backup process recovers events to the N2O Migration file from an Event Backup dataset created by the Event Purge utility. This process is executed in batch.

N2OREB

N2OREB is a NATURAL object that recovers events from an Event Backup.

This step must be executed from the NATURAL FUSER where N2O is installed. N2OREB reads the events from the backup dataset, CMWKF01.

If a user submits the recovery through a system internal reader, N2O replaces &BACKUP with the dataset name. If a user submits the recovery manually, the dataset name must be placed in the JCL and EXECs.

N2OREB recovers the events from the backup dataset to the migration file.

Event Back Up Recovery JCL

JCL examples are shown only for OS/390 (MVS) in this section. VSE JCL, VM EXECs, and BS2000 JCL are located in **Appendix E VSE JCL**, **Appendix F VM EXECs**, and **Appendix G BS2000 JCL** respectively.

The N2O installation tape contains sample JCL in the library N2OBATCH for the program name specified. In step 1 of the JCL below, the name of workfile 1 must be changed to the name of the Archive Backup dataset.

MVSREB

```
//N2OREB JOB (ACCT),'RECOVER EVENT BACKUP',CLASS=A,NOTIFY=&USERID
//*
//N2OREB1 EXEC PGM=NATBATCH
//CMWKF01 DD DSN=&BACKUP,DISP=SHR
//CMPRINT DD SYSOUT=*
//CMPRT01 DD SYSOUT=*
//CMSYNIN DD *
LOGON N2OLIB
N2OREB
FIN
/*
//
```


V.4 Programmer Tools

Programmer Tools provides utilities to compare, list, and scan NATURAL objects.

To access the Programmer Tools menu, enter "P" on the Toolbox Subsystem menu or the direct command TOL PROG on any menu.

```
01-12-31      N-2-O PROGRAMMER TOOLS MENU      TSI0373
11:38:00                                           TSI1

      Code  Function
      ----  -
      C      Object Compare
      D      Source Compare
      S      N2OSCAN Utility
      .      Terminate Programmer Tools
      ----  -

Enter Code: _   Type: _

Direct Command: _____ TOL PROG
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      HELP  ----  END  ENV  MIG  REP  TOL  USR  PRJ  ----  ----  EXIT
```

Field	Type	Description
ENTER CODE (required)		The function to be executed. Valid values are as follows:
	N	C Object Compare Displays the differences between the object code of two NATURAL objects.
	N	D Source Compare Displays the differences between the source code of two NATURAL objects.
	N	S N2OSCAN Utility Allows execution of scans of NATURAL source code and the viewing and maintaining of scan output.
TYPE (supplied)		The type of objects to be compared and listed. Valid values are as follows:
	N	Indicates NATURAL.

V.4.1 Object Compare

The Object Compare utility displays the differences between the object code of two NATURAL objects. These objects may be located in any FUSER or any N2O Archive file.

To access the Object Compare utility, enter "C" on the Programmer Tools menu.

```

01-12-31          N-2-O PROGRAMMER TOOLS          TSI0373
11:38:00          OBJECT COMPARE UTILITY          TSI1

                                Base      Compare
                                Object    Object

Env Def:  _____
Library:  _____
Object:    _____

                                Options
                                -----
Mode.....0

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
-----  END  -----

```

Field	Type	Description
∞ ENV DEF (required)	N	The Environment Definitions/Archive Definitions where the NATURAL objects are located.
LIBRARY (required)	N	The libraries where the NATURAL objects are located.
OBJECT (required)	N	The name of the NATURAL objects to be compared.
MODE (required)	N	Indicates how the job is executed (batch or on-line).
	B	Submits JCL to the internal reader, which processes the function in batch.
	O	Processes the function on-line. (default: O)

∞ indicates field-level help is available.

When either the base or compare object resides in an N2O Archive file, a pop-up window is displayed. One of the following fields must be provided:

- An Archive Date, which generates and displays a list of archive versions starting at the most recent archive and continuing until the specified Archive Date. One of the versions must be chosen from this list. The Archive Date must be entered using the YYYYMMDD format.
- An Archive Version Number, which allows N2O to go directly to the Archive file and read the specified version. The Archive Version Number may be between -1 and -99.

The screen below displays information about the two object codes.

```

01-12-31                      OBJECT COMPARE UTILITY                      TSI0373
11:38:00                      TSI1

PAYPROD / MENU                Type      : PROGRAM      Structured Mode
Library      : PAYPROD User-ID   : BATCH02 Jobname     : BATCH02
Date Catalg: 01-07-23 Time Catalg: 01:37:14 Terminal-ID: BATCH02
NATURAL Ver: 2.16              GDA Name  : PAYGDA
Size in user area (USIZE) : 5234 Bytes  GDA Date   : 01-07-22
Size in buffer pool      : 7564 Bytes  GDA Time    : 22:34:58
Size in source area (ESIZE) : 7704 Bytes
Number subroutines (PERFORM): 1          LS= 132 PS= 60
-----
PAYTEST / MENU                Type      : PROGRAM      Structured Mode
Library      : PAYTEST User-ID   : BATCH01 Jobname     : BATCH01
Date Catalg: 01-07-23 Time Catalg: 19:41:34 Terminal-ID: BATCH01
NATURAL Ver: 2.16              GDA Name  : PAYGDA
Size in user area (USIZE) : 5234 Bytes  GDA Date   : 01-07-23
Size in buffer pool      : 7564 Bytes  GDA Time    : 22:31:31
Size in source area (ESIZE) : 7704 Bytes
Number subroutines (PERFORM): 1          LS= 132 PS= 60

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
----- END -----

```

Pressing Enter on the previous screen displays the result of the Object Compare utility.

```

01-12-31                      OBJECT COMPARE UTILITY                      TSI0373
11:38:00                      TSI1

                                DBID   FNR   Pgm Name  Library
                                ----   ---   -
Base
Object: 1      231   MENU     PAYPROD
-----
Compare
Object: 1      231   MENU     PAYTEST

The two object codes do not match.

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
----- END -----

```

This screen is displayed at the end of each object comparison. The message indicates the results of the comparison.

V.4.2 Source Compare

The Source Compare utility identifies differences between the source code of NATURAL objects located on an FUSER or an N2O Archive file local to N2O. The ability to compare a single pair of objects, a range of objects or two NATURAL libraries is provided. If a range of objects or NATURAL libraries is compared, any unique objects (objects existing in only one location) are ignored. To access the Source Compare Utility screen, enter "D" on the Programmer Tools menu.

```

01-12-31          N-2-O PROGRAMMER TOOLS          TSI0373
11:38:00          SOURCE COMPARE UTILITY          TSI1

      Base      Compare
Env Def.....:  _____
Library.....:  _____
Starting Object:  _____ (Wildcard/Single)
Ending Object...:  _____ (Both Blank=All)

      Option(s)
----- Ignore ----- Show -----
Object Comments..... Y (Yes/No)      Statistics Only... N ( Yes/No)
Spacing..... N (Yes/No)      Source code Only.. N (Yes/No)
Range Positions..... _____ Missing Objects... N(Yes/No)
Identical Objects N (Yes/No/Show) Range Statistics.. N (Yes/No)
-----
Minimum number of lines for a MATCHING Block 0 (0-9)
Maximum number of lines compared..... 120 (0-9999 0=No Limit)
Expand Matching.. N (Yes/No)      Mode..... O (On-line/Batch)

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11-PF12---
HELP  ---  END  ---  ---  ---  ---  ---  ---  ---  ---  ---  ---  ---

```

Field	Type	Description
∞ BASE/COMPARE ENV DEF (required)	N	The Environment Definitions/Archive Definitions where the NATURAL objects are located.
BASE /COMPARE LIBRARY (required)	N	The libraries where the NATURAL objects are located.
BASE STARTING OBJECT (optional)	N	The starting value of the NATURAL object(s) in the base library to be compared. Partial names and wildcards (e.g., AAP*) may be entered. Wildcards and Ranges do not work against a Remote environment.
BASE ENDING OBJECT (optional)	N	The ending value of the NATURAL object(s) in the base library to be compared. Partial names and wildcards (e.g., AAP*) may be entered. To compare a single object, leave this field blank and enter the object's name in the Starting Object field.

"∞" indicates field-level help is available.

(Continued from previous page)

Field	Type	Description
COMPARE STARTING OBJECT (optional)	N	The value of the NATURAL object(s) in the compare library to be compared. If the Compare Starting Object field is left blank, the Base Starting Object and Compare Starting Object are considered the same.
COMPARE ENDING OBJECT (optional)	N	The ending value of the NATURAL object(s) in the compare library to be compared. Partial names and wildcards (e.g., AAP*) may be entered. If the Compare Ending Object field is left blank, the Base Ending Object and Compare Ending Object are considered the same.
IGNORE COMMENTS (required)	N	Indicates whether comment lines are included when comparing each pair of objects. Y Ignores all comment lines when comparing a pair of objects. A comment line contains "/*", "/* */", or "/* */" in the first two non-blank positions of any line. Inline comments (comments at the end of a source line) are ignored. (default: Y) N Includes comment lines when comparing a pair of objects.
SHOW STATISTICS ONLY (required)	N	Indicates whether all differences in each pair of objects are displayed. Y Displays a page of statistics without viewing a listing of line by line differences between a pair of objects. N Displays a listing of line by line differences in a pair of objects followed by a page of statistics. (default: N)
IGNORE SPACING (required)	N	Indicates whether spacing is ignored when comparing a pair of objects. Y Ignores spacing when comparing a pair of objects. Before comparing objects, all spaces are extracted from each line. Spaces between two single quotes are not removed. N Includes spacing when comparing a pair of objects. (default: N)

(Continued from previous page)

Field	Type	Description
SHOW SOURCE CODE ONLY (required)	N	Indicates whether the page of statistics for each pair of objects is displayed. Y Displays line by line differences in a pair of objects without a page of statistics. N Displays line by line differences in a pair of objects followed by a page of statistics. (default: N)
IGNORE POSITIONS (optional)	N	Indicates which positions are ignored for synchronizing objects in the specified range between the base and compare libraries. This parameter is valid if a range is entered. 12345678 The number(s) of the position(s) ignored for the synchronization of object names (e.g., APGM12 equals BPGM22 when IGNORE POSITIONS is set to position 1 and 5 e.g., IGNORE POSITION is set to 15). (default: None except when two wildcards are entered. Under that condition, the positions that are not equal in the wildcards will be automatically set (e.g., wildcards PGM* & BAK* would cause IGNORE POSITIONS to set at 123 and wildcards PGM1* & PGM2* would cause IGNORE POSITIONS to set at 4. This is in addition to any positions entered).
SHOW MISSING OBJECTS (required)	N	Indicates whether missing objects within the specified range are displayed in a pop-up window on-line or CMPRT01 in BATCH. This parameter is valid only if a range is entered. Y Displays the missing objects within the specified range in the base and compare libraries. N Ignores missing objects within the specified range, in the base and compare libraries. (default: N)
IGNORE IDENTICAL OBJECTS (required)	N	Indicates whether identical objects within the specified range are displayed or not. This parameter is valid if a range is entered. Y Ignores objects within the specified range that are identical. S Displays the names of objects within the specified range that are identical in a popup window online or CMPRT01 in BATCH. N Displays all information about all objects within the specified range that are identical. (default: N)

(Continued from previous page)

Field	Type	Description
SHOW RANGE STATISTICS (required)	N	Indicates whether cumulative statistics totals for a range of objects are displayed. This parameter is valid if a range is entered.
		Y Collects and displays the cumulative statistics totals for all objects within the specified range in the base and compare libraries.
		N Does not collect and display the cumulative statistics totals for all objects within the specified range in the base and compare libraries. (default: N)
MINIMUM NUMBER OF LINES FOR A MATCHING BLOCK (required)	N	0 - 9 Indicates the minimum number of concurrent lines that must match for a block of code to be considered matching. (default: 0)
MAXIMUM NUMBER OF LINES COMPARED (required)	N	0 - 9999 Indicates the maximum number of concurrent lines that will be scanned in a pair of objects to locate matching code. (default: 120)
EXPAND MATCHING (required)	N	Indicates whether matching source code in each pair of objects will be expanded.
		Y Displays all code in a block of matching source code.
		N Displays only the first and last line of a block of matching source code. (default: N)
MODE (required)	N	Indicates how the job is executed (batch or on-line).
		B Submits JCL to the internal reader, which processes the function in batch.
		O Processes the function on-line. (default: O)

When either the base or compare object resides in an N2O Archive file, a pop-up window is displayed. One of the following fields must be provided:

- a) An Archive Date, The Archive Date must be entered using the YYYYMMDD format.
 - 1) When comparing a single object

A list of archive versions is generated and displayed, starting at the most recent archive and continuing until the specified Archive Date. One of the versions must be chosen from this list.
 - 2) When comparing a range of objects

Displays the first version of each object located on the archive file for the specified range archived before or at the specified date.
- b) An Archive Version Number, which allows N2O to go directly to the Archive file and read the specified version. The Archive Version Number may be between -1 and -99.

The screen below is displayed to show the differences found between a pair of objects.

```

01-12-31          N-2-O SOURCE COMPARE UTILITY          Report Page:  1
11:38:00          Source Code          Object Page:  1
Base >>>>: Env Def: D230 Library: LIB-ONE    PROGRAM : PGM-ONE Mode: REPORT
>>>> Comp: Env Def: D230 Library: LIB-TWO    PROGRAM : PGM-TWO Mode: REPORT
===== .....1.....2.....3.....4.....5.....6.....
a) 0010 0010 * THIS IS A PROGRAM IN THE PAYROLL SYSTEM WHICH
    ....<<< MATCHING BLOCK >>>
    0050 0050 MOVE 1 TO #INDEX

b) 0060 ---- ADD 3 TO #TOTAL
    0070 ---- IF #TAX-1 = #TAX-2
    0080 ---- DO
    0090 ---- WRITE 'THE FIGURES DO NOT MATCH' DOEND
c) ---- 0060 ADD 2 TO #TOTAL

d) 0100 0070 * CALCULATION ROUTINE
    ...<<< MATCHING BLOCK >>>
    0140 0110 SUBTRACT 1 FROM #REMAINDER

e) 0150 --- RESET #I #J

f) 0160 0120 *
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      END INFO      LEFT RIGHT
  
```

The first and second columns contain line numbers from the base object and compare object respectively. The remainder of the screen is used to display the source associated with each line number. The footnotes below highlight the differences in the sample comparison.

- a)/d) Represent Matching Blocks. A Matching Block begins when the Compare utility finds a line from the base object that matches a line from the compare object. It continues until the Compare utility finds a line from the base object that does not have a corresponding match in the compare object. The message <<< MATCHING BLOCK >>> is displayed between the first and last matching lines of the Matching Block when EXPAND MATCHING is set to "N".
- b)/e) Represent lines that exist in the base object, but have no matches in the Compare Program.
- c) Represents a line that exists in the compare object, but has no match in the base object.
- f) Represents a Matching Block with only one line.

PF-Key	Function	Description
PF3/PF15	END	Return to Source Compare Screen.
PF4/PF16	INFO	Display date and time saved, User-ID, Terminal ID, and NATURAL version for the base and compare objects.
PF10/PF22	LEFT	Scroll screen left.
PF11/PF23	RIGHT	Scroll screen right.

The following screen(s) display summary statistics generated by the Source Compare utility. Information is provided about the NATURAL objects being compared, the number of NATURAL source lines and comment lines and the total number of lines in each object. These screens also indicate which options were in effect for this comparison.

For non-Archive Environments, the screen below is displayed.

01-12-31	N-2-O SOURCE COMPARE UTILITY						Report Page:	2	
11:38:00	Statistics						Object Page:	2	
	Env	Dbid	Fnr	Library	Object	Type	Date	Time	Ver
Base :	D230	230	54	LIB-ONE	PGM-ONE	PROGRAM	2001/01/13	10:47:54	2.2.8
Compare:	D230	230	54	LIB-TWO	PGM-TWO	PROGRAM	2001/02/08	09:23:21	2.2.8
	Mode	Terminal Userid		OS	TP	Mon	Trans	Size	
Base :	STRUCT	TSITERM		TSI300C	MVS/ESA	TSO	TDEV	1,470 Bytes	
Compare:	STRUCT	TSITERM		TSI300D	MVS/ESA	TSO	TPRD	1,873 Bytes	
	Source	Comment		Total					
	Lines	Lines		Lines					
Base :	7	+	9	=	16				
Compare:	4	+	8	=	12				
11 Lines match in both objects									
Options were as follows: Ignore Comments - Y Ignore Positions - 123									
Ignore Spacing - Y Ignore Identical Objects - Y									
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---									
----- END -----									

Comparing Archive Environments produces the statistical page shown below. The additional information of Archive Date, Archive Time, Archive Event, Archive Event Sequence, and Original Environment is displayed.

01-12-31	N-2-O SOURCE COMPARE UTILITY							Report Page:	2
11:38:00	Statistics							Object Page:	2
	Env	Dbid	Fnr	Library	Object	Type	Date	Time	Ver
Base :	A230	230	55	LIB-ONE	PGM-ONE	PROGRAM	2001/01/13	10:47:54	2.2.8
Compare:	A230	230	55	LIB-TWO	PGM-TWO	PROGRAM	2001/02/08	09:23:21	2.2.8
	Mode	Terminal	Userid	OS	TP	Mon	Trans	Size	
Base :	STRUCT	TSITERM	TSI300C	MVS/ESA	TSO	TDEV		1,470	Bytes
Compare:	STRUCT	TSITERM	TSI300D	MVS/ESA	TSO	TPRD		1,873	Bytes
	Source	Comment	Total	Archive	Archive	Archive	Event	Org	
	Lines	Lines	Lines	Date	Time	Event	Seq	Env	
Base :	7	+	9	=	16	2001/01/06	14:19:37	DEV2PROD	138 D230
Compare:	4	+	8	=	12	2001/01/06	14:18:54	DEV2PROD	135 D230
11 Lines match in both objects									
Options were as follows: Ignore Comments - Y									
Ignore Spacing - Y									
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---									
END									

The following screens display range statistics generated by the Source Compare utility. In BATCH, the following screens are combined.

01-12-31	N-2-O SOURCE COMPARE UTILITY					Report Page: 4
11:38:00	Range Statistics					Object Page: 1
	Env	Dbid	Fnr	Library	Start Object	End Object
	-----	-----	-----	-----	-----	-----
Base :	D230	230	54	LIB-ONE	PGM*	
Compare:	D230	230	54	LIB-TWO	BAK*	

	Unique	Compared Objects			Total	
	Objects	Identical	Different	Total	Objects	
	-----	-----	-----	-----	-----	
Base :	28	30	7	37	65	
Compare :	1				38	

	Compared Lines			Total		
	Source	Comment				
	-----	-----		-----		
Base :		568 +	122 =	690		
Compare :		568 +	122 =	690		
503 Lines match in both Libraries						
Options were as follows:						
Ignore Comments - Y Ignore Positions - 123						
Ignore Spacing - Y Ignore Identical Objects - Y						
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---						
----- END -----						

If a range of objects is entered and the Range Statistics option is set to “Y”, the screen shown above is displayed. The total number of identical, changed, and unique NATURAL objects being compared, the total number of NATURAL source lines and comment lines, and the total number of lines for the range of objects are displayed. This screen also indicates what range was entered and which options were in effect for the comparison.

01-09-05 16:04:47	N-2-O SOURCE COMPARE UTILITY Range Statistics by Object Type						Report Page: 9 Object Page: 2
	Env	Dbid	Fnr	Library	Start Object	End Object	
Base :	LBAS	3	9	LYNNP1			
Compare:	LDEV	3	9	LYNNT1			
	GDA	PDA	LDA	COPY	TEXT	SRTN	SPGM
Identical	0	0	0	0	0	0	2
Different	0	0	0	0	0	0	0
In Both	0	0	0	0	0	0	2
Unique	0	0	0	0	0	0	0
Base :	0	0	0	0	0	0	0
Compare:	0	0	0	0	0	2	0
Total	0	0	0	0	0	2	2
Base :	0	0	0	0	0	0	0
Compare:	0	0	0	0	0	2	2
	MAP	PGM	MAC	REP			
	0	5	0				
	0	0	0				
	0	0	5				
	0	0	0				
	0	4	19				
	0	0	0				
	0	5	0				
	0	4	24				
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---							
----- END -----							

If a range of objects is entered and the Range Statistics option is set to “Y”, the screen shown above is also displayed. Statistics for the total number of identical, changed, and unique NATURAL objects for each NATURAL object type being compared is displayed. This screen also indicates what range was entered for the comparison. PF11 will scroll the screen to the right, PF10 will scroll the screen to the left.

Job Step for the Batch Source Compare Utility

The automated submission of JCL for a batch comparison is provided as an alternative to on-line NATURAL object comparisons. Batch comparisons provide hard copy output and can be executed when on-line activity is at a minimum.

The following is a description of the job step for a batch source compare:

N2O3110B

The JCL and EXECs used for manual submission of batch comparisons varies slightly from the sample JCL. The &INPUT card must be replaced with three input cards for which a description and example are provided below. When submitting the comparison through an internal reader, these input cards are automatically placed in the JCL and EXECs.

1. The first input card supplies information about the base object and must include the following parameters separated by commas:
 - BASE ENVIRONMENT or ARCHIVE Definition
 - BASE LIBRARY
 - BASE STARTING OBJECT name (not required)
 - BASE ENDING OBJECT name (Blank for printing of one Object) (not required)
 - ARCHIVE DATE or ARCHIVE VERSION (Blank if BASE ENVIRONMENT is not an ARCHIVE Definition)

2. The second input card supplies information about the compare object and must include the following parameters separated by commas:
 - COMPARE ENVIRONMENT or ARCHIVE Definition
 - COMPARE LIBRARY
 - COMPARE STARTING OBJECT name (not required)
 - COMPARE ENDING OBJECT name (Blank for printing of one Object) (not required)
 - ARCHIVE DATE or ARCHIVE VERSION (Blank if COMPARE ENVIRONMENT is not an ARCHIVE Definition)

3. The last input record supplies information for the following options:
 - IGNORE COMMENTS (Y/N)
 - SHOW STATISTICS ONLY (Y/N)
 - IGNORE SPACING (Y/N)
 - SHOW SOURCE CODE ONLY (Y/N)
 - IGNORE POSITIONS (12345678) (Blank for single object)
 - SHOW MISSING OBJECTS (Y/N) (N for single object)
 - IGNORE IDENTICAL OBJECTS (Y/N) (N for single object)
 - SHOW RANGE STATISTICS (Y/N) (N for single object)
 - MINIMUM NUMBER OF LINES FOR A MATCHING BLOCK (0-9)
 - MAXIMUM NUMBER OF LINES COMPARED (0-9999)
 - EXPAND MATCHING (Y/N)

The following is an example of what the three input records might contain:

```
ARC1,PAYROLL,MENU,,,-1
PRD1,PAYROLL,MENU,,
Y,N,N,N,,N,N,N,0,120,N
```

In this example, the base object is found in the Archive file and is the most recent Archive version of object MENU. The compare object is found on the PRD1 Environment. All default options have been selected.

Batch Source Compare JCL (for local environments)

The following JCL is an example of JCL used to execute batch source compare. JCL examples are shown only for OS/390 (MVS) in this section. VSE JCL, VM EXECs, and BS2000 JCL are located in **Appendix E VSE JCL**, **Appendix F VM EXECs**, and **Appendix G BS2000 JCL** respectively. JCL and EXECs should be tailored to accommodate site-specific needs. The N2O installation tape contains sample JCL in the library N2OBATCH for the program name specified.

OS/390 (MVS) JCL:

MVSCOMPS

```
//N2OCOMPS JOB (ACCOUNTING), 'COMPSOURCE', CLASS=A, TIME=40
//*
//N2OCOMPS EXEC PGM=NATBATCH
//*
//CMPRINT DD SYSOUT=*
//CMPRT01 DD SYSOUT=*
//CMPRT02 DD SYSOUT=*
//CMSYNIN DD *
LOGON N2OLIB
N2O3110B
&INPUT
FIN
/*
//
```

Note: The BATCH report from the N2O Source Compare utility require that the NATURAL Parameter IM (Input Mode) be set to "IM=D" (Delimiter Mode).

Batch Source Compare JCL (for Remote Environments)

The following JCL is an example of JCL used to execute batch source compare against remote environments. JCL examples are shown only for OS/390 (MVS) in this section. VSE JCL, VM EXECs, and BS2000 JCL are located in **Appendix E VSE JCL**, **Appendix F VM EXECs**, and **Appendix G BS2000 JCL** respectively. JCL and EXECs should be tailored to accommodate site-specific needs. The N2O installation tape contains sample JCL in the library N2OBATCH for the program name specified.

OS/390 (MVS) JCL:

MVSCOMPR

```
//N2OCMPR JOB 'REMOTE SOURCE COMPARE' MSGLEVEL=1,
// CLASS=C, MSGCLASS=X, REGION=4M, NOTIFY=&SYSUID
//*
//***
//* THIS IS SAMPLE JCL FOR N2O SOURCE COMPARE BETWEEN TWO REMOTE
//* ENVIRONMENTS
//* This step must be executed where N2O is installed
//***
```

Continued on next page

Continued from previous page

```
//GCPARM EXEC PGM=NATBATCH
//CMPRINT DD SYSOUT=*
//CMPRT01 DD SYSOUT=*
//CMPRT02 DD SYSOUT=*
//CMWKF01 DD DSN=N2O.SRCCR.PARMA1,DISP=(NEW,PASS,DELETE),
//          DCB=(RECFM=FB,LRECL=80,BLKSIZE=84),
//          UNIT=SYSDA,SPACE=(TRK,(1,1))
//CMWKF02 DD DSN=N2O.SRCCR.PARMA2,DISP=(NEW,PASS,DELETE),
//          DCB=(RECFM=FB,LRECL=80,BLKSIZE=84),
//          UNIT=SYSDA,SPACE=(TRK,(1,1))
//CMSYNIN DD *
LOGON N2OLIB
N2O3110B
&INPUT
FIN
/*
/*
/* This step must be executed on base environment
/*
//RRTM1 EXEC PGM=NATBATCH
//CMPRINT DD SYSOUT=*
//CMPRT01 DD SYSOUT=*
//CMPRT02 DD SYSOUT=*
//CMWKF01 DD DSN=N2O.SRCCR.PARMA1,DISP=(OLD,DELETE,DELETE)
//CMWKF02 DD DSN=N2O.SRCCR.PARMB1,DISP=(NEW,PASS,DELETE),
//          DCB=(RECFM=FB,LRECL=187,BLKSIZE=191),
//          UNIT=SYSDA,SPACE=(TRK,(1,1))
//CMWKF03 DD DSN=N2O.SRCCR.OUTPUT1,DISP=(NEW,PASS,DELETE),
//          DCB=(RECFM=FB,LRECL=133,BLKSIZE=137),
//          UNIT=SYSDA,SPACE=(TRK,(1,1))
//CMSYNIN DD *
LOGON SYSTEM
N2O3110C
FIN
/*
/*
/* This step must be executed on compare environment
/*
//RRTM2 EXEC PGM=NATBATCH
//CMPRINT DD SYSOUT=*
//CMPRT01 DD SYSOUT=*
//CMPRT02 DD SYSOUT=*
//CMWKF01 DD DSN=N2O.SRCCR.PARMA2,DISP=(OLD,DELETE,DELETE)
//CMWKF02 DD DSN=N2O.SRCCR.PARMB2,DISP=(NEW,PASS,DELETE),
//          DCB=(RECFM=FB,LRECL=187,BLKSIZE=191),
//          UNIT=SYSDA,SPACE=(TRK,(1,1))
//CMWKF03 DD DSN=N2O.SRCCR.OUTPUT2,DISP=(NEW,PASS,DELETE),
//          DCB=(RECFM=FB,LRECL=133,BLKSIZE=137),
//          UNIT=SYSDA,SPACE=(TRK,(1,1))
//CMSYNIN DD *
LOGON SYSTEM
N2O3110C
FIN
/*
/*
/* This step must be executed where N2O is installed
/*
//COMPW EXEC PGM=NATBATCH
//CMPRINT DD SYSOUT=*
//CMPRT01 DD SYSOUT=*
//CMPRT02 DD SYSOUT=*
//CMWKF01 DD DSN=N2O.SRCCR.PARMB1,DISP=(OLD,DELETE,DELETE)
//CMWKF02 DD DSN=N2O.SRCCR.OUTPUT1,DISP=(OLD,DELETE,DELETE)
//CMWKF03 DD DSN=N2O.SRCCR.PARMB2,DISP=(OLD,DELETE,DELETE)
//CMWKF04 DD DSN=N2O.SRCCR.OUTPUT2,DISP=(OLD,DELETE,DELETE)
//CMSYNIN DD *
LOGON SYSTEM
N2O3110D
FIN
/*
```

V.4.3 N2OSCAN Utility

The N2OSCAN Utility performs a scan of NATURAL source code for a set of user-specified strings over a user-specified range of NATURAL objects and stores scan results on the N2O-MIGRATION file for subsequent on-line query and batch reporting.

Input to N2OSCAN - Scan Parm Set

Prior to a scan, the user must specify:

1. the environment/library range/object range to scan
2. string(s) for which to scan

by entering these values into a Scan Parm Set. Scan Parm Sets are created, edited, and saved in the NATURAL Program Editor as standard NATURAL Text objects. (Sample Scan Parm Sets delivered with the N2OSCAN Utility may be found in library N2OSCAN.)

A Scan Parm Set consists of a set of Header ParmS, defining the default scan range, and at least one Detail Line, specifying string(s) which to scan. Refer to **Section V.4.3.1 Scan Parm Sets** for more detailed information.

Output from N2OSCAN - Scan Output Set

Upon execution, N2OSCAN scans for the strings over the range specified in the selected Scan Parm Set and outputs the results into a Scan Output Set (a set of records physically stored on the N2O-MIGRATION file). A Scan Output Set consists of:

1. detailed recording of all "hits" (indicating strings-found and line-specific location of strings-found)
2. summary data -- outlining scan statistics at the object, library, and full Scan Output Set level.

All levels of summary and detail in Scan Output Sets may be viewed on-line and in batch reports. Additionally, the source of a scanned NATURAL object may be viewed on-line with "hits" highlighted or may be printed in batch with "hits" highlighted or underlined.

Note: A glossary of N2OSCAN terminology may be found in **Appendix J N2OSCAN Glossary**.

V.4.3.1 Scan Parm Sets

Prior to executing a scan using the N2OSCAN Utility, a user must specify:

1. the environment/library/object range to scan
2. string(s) for which to scan

by entering these values into a Scan Parm Set.

Scan Parm Sets are created, edited, and saved in the NATURAL Program Editor as standard NATURAL Text Objects. The library N2OSCAN is the default library for Scan Parm Sets.

The following is a sample Scan Parm Set:

```
0010 ENV=PROD,START-LIB=LIB01,END-LIB=LIB99,
0020 START-OBJ=PGM1000P,END-OBJ=PGM1999P,DELIM=< >
0020 *
0030 I,Y,DATE
0040 E,N,UPDATE
```

When the Scan Parm Set is submitted for execution, it will result in a scan of all NATURAL source objects in the N2O Environment, PROD, from Library LIB01 through LIB99, Objects PGM1000P through PGM1999P.

A Scan Parm Set consists of a set of Header Parms (defining the default scan range) and at least one Detail Line (specifying string(s) to scan).

HEADER PARMS

Header Parms are entered onto a maximum of the first six non-N2OSCAN comment lines of a Scan Parm Set. They consist of the following:

REQUIRED HEADER PARM

Environment Header Parm

Only the Environment Header Parm is required; all other Header Parms are optional. The Environment Header Parm is entered in the format

ENV=xxxx or ENVIRONMENT=xxxx

where xxxx is a valid N2O Environment on a local Node.

Note: The Environment Header Parm must be entered at the beginning of the first non-N2OSCAN comment line. NATURAL Text objects that do not have this value at the beginning of the first non-comment line will not be recognized by the N2OSCAN Utility as Scan Parm Sets.

OPTIONAL HEADER PARMS

Any of the following, separated by a comma, may appear following the required Environment Header Parm:

Start Library Parm

Entered in the format:

START-LIB=xxxxxxx or START-LIBRARY=xxxxxxx

where xxxxxxx is the starting value of the library range to be scanned.

End Library Parm

Entered in the format:

END-LIB=xxxxxxx or END-LIBRARY=xxxxxxx

where xxxxxxx is the ending value of the library range to be scanned.

Note: If a Start Library Parm is specified but an End Library Parm is not, only the single library specified in the Start Library Parm will be scanned.

Start Object Parm

Entered in the format:

START-OBJ=xxxxxxx or START-OBJECT=xxxxxxx

where xxxxxxx is the starting value of the object range to be scanned.

End Object Parm

Entered in the format:

END-OBJ=xxxxxxx or END-OBJECT=xxxxxxx

where xxxxxxx is the ending value of the object range to be scanned.

Note: If a Start Object Parm is specified but an End Object Parm is not, only the single object specified in the Start Object Parm will be scanned.

Delimiter Override Parm

Entered in the format:

DELIM=<xxxxxxx> or DELIMITER=<xxxxxxx>
or DELIMITERS=<xxxxxxx>

where xxxxxxx is a set of up to 32 special characters to serve as the override delimiter set for a scan. If omitted, the default NATURAL delimiter set (all characters with hexadecimal value less than the hexadecimal value of lower case 'a') will apply. This optional parameter may not be needed for many scans.

Note: All range values (Start and End Parms) entered as Header Parms are default values only and may be overridden at scan execution time. The Delimiter Override Parm, if entered in the Scan Parm Set, cannot be overridden at scan execution time.

DETAIL LINES

At least one, and up to 50, Detail Lines may be entered following the Header Parm.

Detail Lines are entered in the format:

x,y,zzz

where x is the Include/Exclude Indicator, y is the Absolute Scan Indicator, and zzzzzzzz is the Scan String (of up to 32 characters).

Include/Exclude Indicator

Valid values are **I** ("include") or **E** ("exclude").

If the value is I, then the associated Scan String becomes an Inclusion String used in Inclusion Processing (see the following).

If the value is **E**, then the associated Scan String becomes an Exclusion String used in Exclusion Processing (see the following).

Absolute Scan Indicator

Valid values are **Y** ("yes") or **N** ("no").

If the value is **Y**, then the Scan Process will examine target source lines for the associated Scan String value, ignoring delimiters.

If the value is **N**, then the Scan Process will examine target source for the associated Scan String value surrounded by delimiters.

Scan String

A case-sensitive string (up to 32 characters in length) used as input to Scan Processing (see the following).

THE SCAN PROCESS

The Scan Process examines target source code one line at a time, performing the Inclusion Process followed by the Exclusion Process.

Inclusion Process

A target source line is examined for all Inclusion Strings defined in the Scan Parm Set. If an Inclusion String is found, then a Hit is registered and the complete space-delimited string identified in the target source line is designated as a Found String. A Found String is passed on to the Exclusion Process.

Exclusion Process

A Found String passed from the Inclusion Process is examined for all Exclusion Strings defined in the Scan Parm Set. If an Exclusion String is found, then the Hit is canceled. If no Exclusion String is found, then the Hit data is stored in the Scan Output Set.

V.4.3.2 N2OSCAN Utility

Entering an 'S' on the Programmer Tools Menu or entering the direct command TOL SCAN accesses the N2OSCAN Utility Menu.

```

01-12-31          N2OSCAN Utility
TSI0373
11:38:00                      TSI1

      Code  Function
      ----  -
      A      Environment Scan
      B      Library Scan
      C      Select Scan Output Set
      D      Delete Scan Output Set
      E      Administrative Delete Scan Output Set
      .      Terminate Scan Utility
      -      -
      -      -

      Enter Code: _   User ID: _____

Direct Command: _____ TOL SCAN
Enter--PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12
      HELP  ----- END   ENV   MIG   REP   TOL   USR   PRJ   ----- EXIT

```

Field	Description
Enter Code (modifiable, required)	<p>The function to be executed. A user's Function Profile determines the valid values. Valid values are as follows:</p> <p>A Environment Scan Execute, inquire on, or select a Scan Parm Set for a scan of an Environment.</p> <p>B Library Scan Execute, inquire on, or select a Scan Parm Set for a scan of a library.</p> <p>C Select Scan Output Set Select a Scan Output Set for which to view summary statistics or detail.</p> <p>D Delete Scan Output Set Select a Scan Output Set to delete. Only Scan Output Sets belonging to the user will be displayed.</p> <p>E Administrative Delete Scan Output Set Select a Scan Output Set to delete. This option will list ALL Scan Output Sets.</p>
User ID (modifiable, optional)	<p>If entered, serves as starting value of selection lists displayed with Code options C, D, or E above.</p>

V.4.3.2.1 Environment Scan Utility

The Environment Scan Utility permits scans to be conducted on an entire Environment, a range of libraries, a single library, a range of objects, or a single object.

Entering an 'A' on the N2OSCAN Utility Menu accesses the Environment Scan Utility. (Refer to Section V.4.3.2.2 Library Scan Utility for details on all options.)

```
01-12-31          N2OSCAN Utility          TSI0373
11:38:00                                     TSI1

Code  Function
-----
C    Check a Scan Parm Set
E    Edit a Scan Parm Set (Exits N2O)
I    Inquire on Scan Parm Set
S    Select Scan Parm Set
X    Execute Scan
.    Terminate Scan Utility
-----

Enter Code: _      Scan Parm Set: _____
                  Parm Set Library: N2OSCAN_

Direct Command: _____ TOL SCEN
Enter---PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12
        HELP  ----- END  ENV  MIG  REP  TOL  USR  PRJ  ----- EXIT
```

Field	Description
Enter Code (modifiable, required)	<p>The function to be executed. A user's Function Profile determines the valid values. Valid values are as follows:</p> <p>C Check a Scan Parm Set Validate the Header Parms and Detail Lines of a Scan Parm Set.</p> <p>E Edit a Scan Parm Set (exits N2O) Exit N2O and use the NATURAL program editor to edit a Scan Parm Set.</p> <p>I Inquire on Scan Parm Set View a Scan Parm Set.</p> <p>S Select Scan Parm Set Provides a list of Scan Parm Sets that may be inquired on, checked, edited, or executed.</p> <p>X Execute Scan Checks and executes the specified Scan Parm Set.</p>
Scan Parm Set (modifiable, required for code 'C', 'E', 'I' or 'X')	<p>A Scan Parm Set to be checked, edited, inquired on, selected, or executed. (If specified with Select option, the starting Scan Parm Set on the Select Screen.)</p>
Parm Set Library (modifiable, required for code 'C', 'E', 'I' or 'X')	<p>The library in which the Scan Parm Set is stored. (defaults to "N2OSCAN")</p>

V.4.3.2.2 Library Scan Utility

The Library Scan Utility Menu permits scans to be conducted on an entire library, a range of objects, or a single object.

Entering a 'B' on the N2OSCAN Utility Menu accesses the Library Scan Utility.

```

01-12-31          N-2-O Library Scan Utility          TSI0373
11:38:00                                     TSI1

Code  Function
-----
C    Check a Scan Parm Set
E    Edit a Scan Parm Set (Exits N2O)
I    Inquire on Scan Parm Set
S    Select Scan Parm Set
X    Execute Scan
.    Terminate Scan Utility
-----

Enter Code: _      Scan Parm Set: _____
                  Parm Set Library: N2OSCAN_

Direct Command: _____ TOL SCLI
Enter---PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12
      HELP  ----- END  ENV  MIG  REP  TOL  USR  PRJ  ----- EXIT

```

Field	Description
Enter Code (modifiable, required)	<p>The function to be executed. A user's Function Profile determines the valid values. Valid values are as follows:</p> <p>C Check a Scan Parm Set Validate the Header Parms and Detail Lines of a Scan Parm Set.</p> <p>E Edit a Scan Parm Set (exits N2O) Exit N2O and use the NATURAL program editor to edit a Scan Parm Set.</p> <p>I Inquire on Scan Parm Set View a Scan Parm Set.</p> <p>S Select Scan Parm Set Provides a list of Scan Parm Sets that may be inquired on, checked, edited, or executed.</p> <p>X Execute Scan Checks and executes the specified Scan Parm Set.</p>
Scan Parm Set (modifiable, required for code 'C', 'E', 'I' or 'X')	A Scan Parm Set to be checked, edited, inquired on, selected, or executed. (If specified with Select option, the starting Scan Parm Set on the Select Screen.)
Parm Set Library (modifiable, required for code 'C', 'E', 'I' or 'X')	The library in which the Scan Parm Set is found. (defaults to "N2OSCAN")

V.4.3.2.2.1 Select Scan Parm Set Function

The Select Scan Parm Set function provides a list of Scan Parm Sets that may be inquired on, checked, edited, or executed. This screen will display all Scan Parm Sets in the specified library.

Entering an 'S' on the Environment Scan Function Menu or the Library Scan Function Menu accesses the Select Scan Parm Set function.

```
Valid Values: I=Inquire, C=Check, X=Execute, E=Edit(exits N2O)
01-12-31      N-2-O Select Scan Parm Set                      TSI0373
11:38:00      Starting Scan Parm Set: SCANDEV Library: N2OSCAN TSI1

Invalid      Scan      Start      End      Start      End
Hdr          S Parm Set Env Library Library Object Object
-----
***          _ SCANDEV DEV PAY001 PAY001 CALC1  CALC2
              _ SCANPRD PRD TAX001 TAX002 PSTTAX PSTX99

Enter---PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12
        HELP  ----- END ----- UP      DOWN ----- LIB -----
```

PF10 List Scan Parm Sets in a different library. (A pop-up window permits user to specify the different library)

Field	Description
Starting Scan Parm Set (modifiable)	Value with which to begin the selection list.
Library (display-only)	Indicates library in which currently displayed Scan Parm Sets are stored. May be modified by using PF10 Key.
Invalid Hdr (display-only)	Indicates the validity of a Scan Parm Set's Header Parm. Valid values are as follows: Blank Valid Header Parm. *** Invalid Header Parm.

(continued from previous page)

Field	Description
S (modifiable)	<p>The function to be executed. A user's Function Profile Security determines the user's valid values. Valid values are as follows:</p> <p>C Check the Scan Parm Set Validate the Header Parm's and Detail Lines of a Scan Parm Set.</p> <p>E Edit the Scan Parm Set (exits N2O) Exit N2O and use the NATURAL program editor to edit a Scan Parm Set.</p> <p>I Inquire on the Scan Parm Set View a Scan Parm Set.</p> <p>X Execute the Scan Parm Set Check and Execute the specified Scan Parm Set.</p>
Scan Parm Set (display-only)	Name of the Scan Parm Set.
Env (display-only)	N2O Environment on which the scan will be executed.
Start Library (display-only)	Scan Parm Set's default Start Library Default starting value for the range of libraries to be scanned.
End Library (display-only)	Scan Parm Set's default End Library Default ending value for the range of libraries to be scanned.
Start Object (display-only)	Scan Parm Set's default Start Object Default starting value for the range of objects to be scanned.
End Object (display-only)	Scan Parm Set's default End Object Default ending value for the range of objects to be scanned.

V.4.3.2.2.2 Check Scan Parm Set Function

The Check Scan Parm Set function verifies that the format of the Scan Parm Set is valid. The Header Parms are examined for a valid local N2O Environment, a valid range of libraries (if specified), and a valid range of objects (if specified). The pop-up window shown below details the results of the check function.

Note: The Check Scan Parm Set function can be accessed from outside of N2O by entering N2OSCAN at the NEXT prompt or on the command line in the NATURAL Program Editor.

Entering a 'C' ("check") on the Select Scan Parm Set function invokes the Check Scan Parm Set function. (The 'X' ("execute") option also invokes the Check Scan Parm Set function prior to performing a scan)

```
Valid Values: I=Inquire, C=Check, X=Execute, E=Edit(exits N2O)
01-12-31      N-2-O Select Scan Parm Set      TSI0373
11:38:00 Starting Scan Parm Set: _____ Library: _____ TSI1

Scan Parm Set: SCANDEV Library: N2OSCAN
Has the Following Errors

Parm Set Header Errors      Detail Lines with Errors
-----
Invalid Scan Environment    0070 0080 0110 0200 0210
Invalid Start Library       0250 0290 0300 0310 0320
Invalid Start Object

                        ADDITIONAL DETAIL ERRORS MAY EXIST
```

The Check Scan Parm Set function pop-up window shown above displays the function's results to the user. The following messages may appear:

Scan Header Messages:

All Scan Header Info is Valid

The Header Parms of the Scan Parm Set are valid.

Parm Set Header Errors

The Scan Parm Set that was checked contains invalid Header Parm values. The messages below detail Header Parm errors that may be found.

Invalid Scan Environment

The environment specified was not a local N2O Environment.

Invalid Start Library

A range of libraries was specified and the starting library value was greater than the end library value.

Invalid Start Object

A range of objects was specified and the starting object was greater than the end object.

Scan Detail Messages:

All Detail Lines are Valid

All Detail Lines in the Scan Parm Set are valid.

Detail Lines with Errors

The Scan Parm Set contains invalid Detail Lines. The line numbers of lines with invalid criteria are listed below this message.

Additional Detail Errors May Exist

The Scan Parm Set contained at least 10 Detail Lines with errors. The remaining Detail Lines were not checked and may also contain errors.

Parm Set contains more than 50 Detail Lines

A Scan Parm Set may contain no more than 50 Detail Lines of search criteria. A Scan may be executed with this Scan Parm Set, but additional Detail Lines over 50 will be ignored.

V.4.3.2.2.3 Execute Scan Function

The Execute Scan function executes a scan using the Scan Parm Set as input. Prior to execution, the Check Scan Parm Set function is invoked. If the Scan Parm Set contains no errors, a Scan Execution Parameters pop-up window appears so that the user may view the Scan Parm Set's default scan range values and modify the scan range, if desired. This window is shown below.

Entering an 'X' on the Select Scan Parm Set function screen or an 'X' on the Environment or Library Scan function screens invokes the Execute Scan function.

Valid Values : I = Inquire, C = Check, E = Edit, X = Execute

01-12-31 N-2-O Select Scan Parm Set TSI0373

11:38:00 Starting Scan Parm Set: SCANDEV Library: N2OSCAN TSI1

Invalid Sc
Hdr S Pa

*** SC
SC
SC
SC
SC
SC
SC
SC
SC
SC
X SCANPR
SCANPR
SCANPR
SCANPR4 PRD TAX001 TAX002 PSTTAX PSTX99
SCANPR5 PRD TAX001 TAX002 PSTTAX PSTX99

N2O Scan Execution Parameters

Scan Parm Set: SCANPRD

Environment: PRD1

Start Library: TAX001

End Library: TAX002

Start Object: PSTTAX

End Object: PSTX99

Mode: 0

Press <Enter> to Scan, PF3 to Cancel

Enter---PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12

HELP ----- END ----- UP DOWN ----- LIB -----

Field	Description
Scan Parm Set (display-only)	Name of the Scan Parm Set.
Environment (modifiable <i>[if Environment Scan]</i> , display-only <i>[if Library Scan]</i>)	N2O Environment on which the scan will be executed.
Start Library or Library (modifiable, <i>[required for Library Scan]</i>)	Either: (a) starting value for the range of libraries to be scanned (if Environment Scan), or (b) library to be scanned (if Library Scan or if End Library is blank).
End Library (modifiable, <i>[not available for Library Scan]</i>)	Ending value for the range of libraries to be scanned (if Environment Scan). If left blank, Start Library is the only library that will be scanned.

(continued from previous page)

Field	Description
Start Object (modifiable)	Starting value for the range of objects to be scanned. If End Object is left blank, Start Object is the only object that will be scanned.
End Object (modifiable)	Ending value for the range of objects to be scanned. If left blank, Start Object is the only object that will be scanned.
Mode (modifiable)	Indicates how the job is to be executed (batch or on-line). Valid values are: B submits JCL to the internal reader, which processes the function in batch. O processes the function on-line. (default: O)

The fields that appear in the Scan Execution Parameters window vary, depending on whether the Environment Scan function or the Library Scan function was used to access this window. The Library Scan function requires a library value and does not permit overriding of the Environment, nor does it permit the specification of a library range.

The default scan range values from the Scan Parm Set may be overridden in this window based on the following rules.

Environment Level Scans

1. An "*" may be specified for wildcarding on both the Start and End Library values.

For example, if Start Library value is "MYLIB*" and End Library is left blank, the resultant scan range will be from "MYLIB" through "MYLIB999".

Additionally, if Start Library value is "MYLIB001" and End Library value is "PAYLIB*", the resultant scan range will be from "MYLIB001" through "PAYLIB99".

2. Both Start and End Library fields may be left blank.

This results in a scan of the entire environment.

Library Level Scans

A library is required. Wildcarding with an "*" is not permitted.

All Scans - Start and End Object values

1. An "*" may be specified for wildcarding on both the Start and End Object values.

For example, if Start Object value is "MYPGM*" and End Object is left blank, the resultant scan range will be from "MYPGM" through "MYPGM999".

Additionally, if Start Library value is "MYPGM001" and End Library value is "PAYPGM*", the resultant scan range will be from "MYPGM001" through "PAYPGM99".

2. Both Start and End Library fields may be left blank.

This results in a scan of the entire library.

Online Scan Execution

If the scan was selected to run on-line, pressing Enter begins the scan execution process. If a previous scan by the same user was based on the same scan criteria, a pop-up window will inform the user that an identical scan already exists and output from this scan will overlay it. The scan can be aborted by pressing PF3 or executed by pressing Enter.

The amount of time it takes a scan to execute is dependent on the scan range specified. Since some scans may take an extended period of time, a pop-up window showing the scan's progress will appear. **DO NOT PRESS ANY KEYS** while the scan is in progress. This will cause the scan to abort. (Aborted scans may be deleted using the Scan Output Set Delete functions.)

Scans may also be executed in batch.

Once the scan completes, a pop-up window will appear giving the user the choice to go directly to the Select Scan Output Screen (to view the scan's output) by pressing Enter, or to return to the N2OSCAN Utility Menu by pressing PF3.

Batch Scan Execution

If the scan was selected to run in batch, pressing Enter will submit JCL to the internal reader that will execute the scan function in batch. The output of the scan will be available as a Scan Output Set.

Manual Batch Scan Execution

The manual N2OSCAN Batch Scan Execution permits batch execution of either an Environment or Library scan using an existing Scan Parm Set. The N2O installation tape contains sample JCL in the library N2OBATCH for the program name specified.

The OS/390 (MVS) JCL to run this program is shown below.

MVSSCBX

```
//N2OSCBX EXEC PGM=NATBATCH
//*  CPRINT CONTAINS ANY MESSAGES/ERRORS PRODUCED DURING
//*  EXECUTION OF N2OSCBX
//CPRINT      DD SYSOUT=*
//CMSYNIN     DD *
LOGON N2OLIB
N2OSCBX
FIN
//CMWKF01     DD *
UID,SPS-LIB,SPS,ENV,STARTLIB,ENDLIB,STARTOBJ,ENDOBJ
/*
```

The &INPUT parameter list by default is delimited by commas with no spaces following the commas. To override the default delimiter, modify the value of the jcl-delimiter field in User-Exit-22 (N2OUE22N).

The layout for the record in CMWKF01 is as follows:
(All values are required)

Values	Description
Userid	User ID of the user who is to own the scan.
ScanParmSetLibrary	Library of the Scan Parm Set.
ScanParmSet	Scan Parm Set that is input to the scan.
Environment	N2O Environment in which the scan is to be executed.
Start Library	Starting value for the range of libraries to be scanned. If ENDLIB is blank, STARTLIB is the only library to be scanned.
End Library	Ending value for the range of libraries to be scanned. If blank, STARTLIB is the only library to be scanned.
Start Object	Starting value for the range of objects to be scanned. If ENDOBJ is blank, STARTOBJ is the only object to be scanned.
End Object	Ending value for the range of objects to be scanned. If blank, STARTOBJ is the only object to be scanned.

V.4.3.2.3 Select Scan Output Set Function

The Select Scan Output Set function provides a list of Scan Output Sets for scans that completed successfully. Summary statistics may be inquired on, or a list of libraries scanned may be selected.

Entering a 'C' on the N2OSCAN Utility Menu accesses the Select Scan Output Set function.

```

I=Inq, L=Lib Sel List, D=Online Del, B=Batch Del, S=String Found Rep
01-12-31      N-2-O Select Scan Output Set      TSI0373
11:38:00      TSI1
                Starting User ID: TSI004__

S  User ID      Scan      Start      End      Start      End      Date/Time
   Parm Set Env  Library  Library  Object    Object    Completed
- - - - -
_ TSI004      SCANDEV  DEV  PAY001  PAY001  CALC1    CALC2    01/08/01 11:34
_ TSI004      SCANPRD  PRD  TAX001  TAX002  PSTTAX   PSTX99   01/08/01 11:54
- - - - -

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12
      HELP  ----- END  ----- UP      DOWN  -----

```

Field	Description
Starting User ID (modifiable)	Value with which to begin the selection list.
S (modifiable)	The function to be executed. Valid values are as follows: <ul style="list-style-type: none"> I Inquire on the summary statistics of the Scan Output Set. L Lists all libraries scanned. B Batch Delete of the selected Scan Output Set. S String Found Report. Provides a hardcopy of all strings found in the selected Scan Output Set. D Online delete of the selected Scan Output Set.
User ID (display-only)	User ID of the user who submitted the scan.
Scan Parm Set (display-only)	Name of the Scan Parm Set.
Env (display-only)	N2O Environment on which the scan was executed.
Start Library (display-only)	Starting value for the range of libraries that were scanned. If End Library is blank, Start Library is the only library that was scanned.
End Library (display-only)	Ending value for the range of libraries that were scanned. If blank, Start Library is the only library that was scanned.

(continued from previous page)

Field	Description
Start Object (display-only)	Starting value for the range of objects that were scanned. If End Object is blank, Start Object is the only object that was scanned.
End Object (display-only)	Ending value for the range of objects that were scanned. If blank, Start Object is the only object that was scanned.
Date/Time Completed	Date and time at which the scan was completed.

V.4.3.2.3.1 Summary of Scan Output (Inquire Function)

The Summary of Scan Output pop-up window displays summary statistics for a Scan Output Set.

Entering an 'I' on the Select Scan Output Set screen accesses the Summary of Scan Output Set pop-up window.

Summary of Scan Output Set				Completed: 2001/12/31 11:38:00 Status: C		
User ID: TREE18		Start Library: PAY001				
Scan Parm Set: SCPRD1		End Library:				
Environment: PROD		Start Object: PAYPGM1				
		End Object: PAYPGM6				
Libraries	Libraries	% Libs	Objects	Objects	% Objs	
Hit	Total	Hit	Hit	Total	Hit	
-----	-----	-----	-----	-----	-----	
	3	6	50.0	50	100	50.0
LINE DATA						
Lines	Lines	% Lns	Non-Comment	Non-Comment	%NonCm	
Hit	Total	Hit	Lines Hit	Lines Total	Lns Hit	
-----	-----	-----	-----	-----	-----	
	1,000	2,000	50.0	250	1,000	25.0

Field	Description
Completed (display-only)	Date and time scan was completed.
User ID (display-only)	User ID of the user who submitted the scan.
Start Library (display-only)	Starting value for the range of libraries that were scanned. If End Library is blank, Start Library is the only library that was scanned.
Status (display-only)	Status of the scan. Only Scan Output Sets of status "C" (closed, scan completed successfully) are shown in this window.
Scan Parm Set (display-only)	Name of Scan Parm Set used as input for the scan.
End Library (display-only)	Ending value for the range of libraries that were scanned. If blank, Start Library is the only library that was scanned.
Environment (display-only)	N2O Environment the scan was executed in.
Start Object (display-only)	Starting value for the range of objects that were scanned. If End Object is blank, Start Object is the only object that was scanned.

(continued from previous page)

Field	Description
End Object (display-only)	Ending value for the range of objects that were scanned. If blank, Start Object is the only object that was scanned.
Libraries Hit (display-only)	The number of libraries scanned that contain at least one object with a Scan Hit.
Libraries Total (display-only)	The total number of libraries scanned.
% Libs Hit (display-only)	Libraries Hit expressed as a percentage of Libraries Total.
Objects Hit (display-only)	The number of objects scanned that contain at least one Scan Hit.
Objects Total (display-only)	The total number of objects scanned.
% Objs Hit (display-only)	Objects Hit expressed as a percentage of Objects Total.
Lines Hit (display-only)	The number of lines scanned that contain at least one Scan Hit.
Lines Total (display-only)	The total number of lines scanned.
% Lns Hit (display-only)	Lines Hit expressed as a percentage of Lines Total.
Non-Comment Lines Hit (display-only)	The number of non-comment lines scanned that contain at least one Scan Hit.
Non-Comment Lines Total (display-only)	The total number of non-comment lines scanned.
% NonCm Lns Hit (display-only)	Non-Comment Lines Hit expressed as a percentage of Non-Comment Lines Total.

V.4.3.2.3.2 Select Library Scan Output Set (List Libs Scanned)

The Select Library Scan Output Set function displays statistical information about the libraries that were scanned.

This screen is accessed by placing an 'L' in the 'S' (select) field on the Select Scan Output Screen and pressing Enter.

```

Valid values:  O=Object Selection List, R=Output Standard Report
01-12-31      N-2-O SELECT LIBRARY SCAN OUTPUT SET      TSI0373
11:38:00                                           TSI1

      User ID: TREE18      Environment: PROD
      Scan Parm Set: SCPRD1  Start Library: PAY001  Start Object: PAYPGM1
                                End Library:         End Object: PAYPGM6
Start List at Library: _____

      Objects Objects %Objs  Lines   Lines   % Lns NonComm NonComm %NonC
S Library   Hit  Total   Hit    Hit    Total   Hit  Lns Hit  Lns Tot  LnHit
-----
_ TSSCAN      3    6   50.0      5    10   50.0      5    10   50.0

Enter---PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12
      HELP  ----  END  ----  ----  ----  UP   DOWN  ----  >ZERO  ----  ----

```

PF10 Toggles between (1) Display only libraries with Greater than Zero hits; and (2) Display all libraries.

Field	Description
User ID (display-only)	User ID of the user who submitted the scan.
Environment (display-only)	N2O Environment on which the scan was executed.
Scan Parm Set (display-only)	Name of Scan Parm Set used as input for the scan.
Start Library (display-only)	Starting value for the range of libraries that were scanned. If End Library is blank, Start Library is the only library that was scanned.
Start Object (display-only)	Starting value for the range of objects that were scanned. If End Object is blank, Start Object is the only object that was scanned.
End Library (display-only)	Ending value for the range of libraries that were scanned. If blank, Start Library is the only library that was scanned.
End Object (display-only)	Ending value for the range of objects that were scanned. If blank, Start Object is the only object that was scanned.

(continued from previous page)

Field	Description
Start List at Library (modifiable)	Value with which to begin the selection list.
S (modifiable)	The function to be executed. Valid value is: R Output Standard Report – Provides a hardcopy of all statistics and detail of a scan. O Object Selection List - lists all objects scanned in this library.
Library (display-only)	Library scanned.
Objects Hit (display-only)	The number of objects scanned that contain at least one Scan Hit.
Objects Total (display-only)	The total number of objects scanned.
% Objs Hit (display-only)	Objects Hit, expressed as a percentage of Objects Total.
Lines Hit (display-only)	The number of lines scanned that contain at least one Scan Hit.
Lines Total (display-only)	The total number of lines scanned.
% Lns Hit (display-only)	Lines Hit expressed as a percentage of Lines Total.
NonComm Lns Hit (display-only)	The number of Non-Comment Lines scanned that contain at least one Scan Hit.
NonComm Lns Tot (display-only)	The total number of Non-Comment Lines scanned.
% NonC Ln Hit (display-only)	Non-Comment Lines Hit expressed as a percentage of Non-Comment Lines Total.

V.4.3.2.3.2.1 Select Object Scan Output Set Function

The Select Object Scan Output Set function displays statistical information about the objects that were scanned.

This screen is accessed by placing an 'O' in the 'S' (select) field on the Select Library Scan Output Set screen and pressing Enter.

```
Valid Values: L=Strings found, S=Source View, B=Batch Source Disp      TSI0373
01-12-31          N-2-O SELECT OBJECT SCAN OUTPUT SET                  TSI1
11:38:00

      User ID: TREE18      Environment: PROD
      Scan Parm Set: SCPRD1      Start Library: SCANONE      Start Object: PAYPGM1
                                End Library:                End Object: PAYPGM6
Start List at Object: _____

      S Object      Obj      Lines      Lines      % Lns      NonCom      NonCom      %NonC
      - - - - -      Type      Hit      Total      Hit      LnsHit      LnsTot      LnHit
      - - - - -      - - - - -      - - - - -      - - - - -      - - - - -      - - - - -      - - - - -
      _ PAYPGM1      P              3        600        0.5              5        500        1.0

Enter---PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12
      HELP  ----- END  ----- ----- UP      DOWN  ----- >ZERO -----
```

PF10 Toggles between (1) Display only objects with Greater than Zero hits; and (2) Display all objects.

Field	Description
User ID (display-only)	User ID of the user who submitted the scan.
Environment (display-only)	N2O Environment on which the scan was executed.
Scan Parm Set (display-only)	Name of Scan Parm Set used as input for the scan.
Start Library (display-only)	Starting value for the range of libraries that were scanned. If End Library is blank, Start Library is the only library that was scanned.
Start Object (display-only)	Starting value for the range of objects that were scanned. If End Object is blank, Start Object is the only object that was scanned.
End Library (display-only)	Ending value for the range of libraries that were scanned. If blank, Start Library is the only library that was scanned.
End Object (display-only)	Ending value for the range of objects that were scanned. If blank, Start Object is the only object that was scanned.

(continued from previous page)

Field	Description
Start List at Object (modifiable)	Value with which to begin the selection list.
S (modifiable)	The function to be executed. Valid values are: L List strings found Lists all strings found (i.e., all hits) in this Object. S Source display Displays source of Object with strings found (i.e., hits) highlighted. B Batch Source Display Provides a hardcopy of a specified object that was scanned.
Object (display-only)	Object scanned.
Obj Type (display-only)	Type of Object scanned. Valid values are: P Program S Subroutine N Subprogram M Map H Helproutine L Local Data Area A Parameter Data Area G Global Data Area C Copycode T Text O Macro R Report Y ExpertModel Z Recording 3 Dialog 4 Class 5 Processor K Server
Lines Hit (display-only)	The number of lines scanned that contain at least one Scan Hit.
Lines Total (display-only)	The total number of lines scanned.
% Lns Hit (display-only)	Lines Hit expressed as a percentage of Lines Total.

(continued from previous page)

Field	Description
NonCom LnsHit (display-only)	The number of Non-Comment Lines scanned that contain at least one Scan Hit.
NonCom LnsTot (display-only)	The total number of Non-Comment Lines scanned.
%NonC LnHit (display-only)	Non-Comment Lines Hit expressed as a percentage of Non-Comment Lines Total.

V.4.3.2.3.2.1.1 Scan Output Detail Function (List Strings Found)

The Scan Output Detail function displays strings found and the line numbers of the lines on which they were found in the object selected. (If the object selected is a data area, lines will be numbered sequentially)

This screen is accessed by placing an 'L' in the 'S' (select) field on the Select Object Scan Output Set screen and pressing Enter.

```

01-12-31          N-2-O SELECT OBJECT SCAN DETAIL          TSI0373
11:38:00                                     TSI1

      User ID: TREE18      Environment: PROD
      Scan Parm Set: SCPRD1  Start Library: SCANONE  Start Object: PAYPGM1
                          End Library:              End Object: PAYPGM6

      Library: PAY001
      Object: PAYCL01  Type: P

Line
Nbr C String Found
-----
0250 * #DATE-FIELD-1
0300 #DATE-STORED

Enter---PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12
      HELP  ----- END  ----- UP  DOWN -----

```

Field	Description
User ID (display-only)	User ID of the user who submitted the scan.
Environment (display-only)	N2O Environment on which the scan was executed.
Scan Parm Set (display-only)	Name of Scan Parm Set used as input for the scan.
Start Library (display-only)	Starting value for the range of libraries that were scanned. If End Library is blank, Start Library is the only library that was scanned.
Start Object (display-only)	Starting value for the range of objects that were scanned. If End Object is blank, Start Object is the only object that was scanned.
End Library (display-only)	Ending value for the range of libraries that were scanned. If blank, Start Library is the only library that was scanned.
End Object (display-only)	Ending value for the range of objects that were scanned. If blank, Start Object is the only object that was scanned.

(continued from previous page)

Field	Description
Library (display-only)	Library in which Object is stored.
Object (display-only)	Object scanned.
Type (display-only)	Type of Object scanned. Valid values are: P Program S Subroutine N Subprogram M Map H Helproutine L Local Data Area A Parameter Data Area G Global Data Area C Copycode T Text O Macro R Report Y ExpertModel Z Recording 3 Dialog 4 Class 5 Processor K Server
Line Nbr (display-only)	Number of the source line in which string was found. (Data areas are numbered sequentially.)
C (display-only)	Comment Line Indicator: An * will be displayed in this column if the source line in which the string was found is a comment line.
String Found (display-only)	The string found by the scan process.

V.4.3.2.3.2.1.2 Object Source View

The Object Source View function displays the source code of a scanned object with found strings (“hits”) highlighted.

This screen is accessed by placing an ‘S’ in the ‘S’ (select) field on the Select Object Scan Output Set screen and pressing Enter.

```

                                > + PROGRAM : PAY0130P           Lib:
PAYTEST
.....1.....2.....3.....4.....5.....Mode: STRUCT
0010 DEFINE DATA
0020 LOCAL USING PAYEMPL
0030 LOCAL
0040 01 #I (P3)
0050 01 #MAP
0060 02 #ID (A8/1:10)
0070 02 #NAME (A45/1:10)
0080 02 #DATE-EMPLOYED (A6/1:10)
0090 02 #STAT (A1:1:10)
0100 02 #BIRTH (N6/1:10)
0110 END-DEFINE
0120 SET KEY PF1 = PGM NAME 'HELP'
0130         PF1 = HELP
0140         PF2 = PGM NAMED ' '
0150         PF3 = PGM NAMED 'EXIT'
0160         PF4 = PGM NAMED ' '
0170         PF5 = PGM NAMED ' '
0180         PF6 = PGM NAMED ' '
0190         PF7 = PGM NAMED ' '
0200         PF8 = PGM NAMED ' + '
                                PF3-EXIT           PF4-UPDATE INFO

```

PF4 Pop-up window displays Date, Time, User-ID, Terminal, and NATURAL SM level for both source-code and object-code of the displayed NATURAL object.

V.4.3.2.3.2.1.3 Batch Source Display

The N2OSCAN Batch Source Display provides a hardcopy of a specific object that was scanned. Any hits are shown by bolding or underlining the found string. Input parameters specify the bolding or underlining method to be used in the run. Any character may be used for underlining.

This screen is accessed by placing a 'B' in the 'S' (select) field on the Select Object Scan Output Set screen and pressing Enter.

```
Valid Values: L=Strings found, S=Source View, B=Batch Source Disp
01-12-31      N-2-O SELECT OBJECT SCAN OUTPUT SET      TSI0373
11:38:00      TSI1

      Use +-----+
      Scan Parm | N2O Scan Batch Source Display Parameters | bject: PAY7000P
      Li | bject: PAY8000P
      Start List at O |
      S Ob | User: TSI0373
      - --- | Scan Parm Set: SCANPARM1 | NonC
      b N2O | Environment: PROD | nHit
      | Start Library: PAYPROD | ----
      | End Library: | 0.0
      | Start Object: PAY7000P |
      | End Object: PAY8000P |
      | Library: PAYPROD |
      | Object: PAY7110P |
      | Underline: N |
      | Underline Char: _ |
      +-----+

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      HELP ---- END ---- ---- ---- UP DOWN ---- >ZERO ----
```

Field	Description
User (display-only)	User ID of the user who submitted the selected Scan Output Set.
ScanParmSet (display-only)	Scan Parm Set ID of the selected Scan Output Set.
Environment (display-only)	N2O Environment of the selected Scan Output Set.
Start Library (display-only)	Starting library of the selected Scan Output Set.
End Library (display-only)	Ending library of the selected Scan Output Set.
Start Object (display-only)	Starting object of the selected Scan Output Set.
End Object (display-only)	Ending object of the selected Scan Output Set.
Library (display-only)	Library in which selected Object to be printed is stored.
Object (display-only)	Selected Object to be printed.
Underline (optional)	Valid values are "Y" or "N" (default is "N"): Y = Underline strings-found. N = Do not underline (show strings-found in bold).
Underline Char (optional)	Character used for underlining if UNDLN = "Y".

Pressing ENTER will submit the report to the internal reader.

Manual Submission of Batch Source Display

Note: LRECL for all CMPRINT and CMPRT01 datasets may be set to 133.

The following JCL is an example of OS/390 (MVS) JCL used to support the Batch Reporting process. JCL examples are shown only for OS/390 (MVS) in this section. VSE JCL, VM EXECs, and BS2000 JCL are located in **Appendix E VSE JCL**, **Appendix F VM EXECs**, and **Appendix G BS2000 JCL** respectively. JCL and EXECs should be tailored to accommodate site-specific needs. The N2O installation tape contains sample JCL in the library N2OBATCH for the program name specified.

The OS/390 (MVS) JCL to run this report is shown below.

MVSSCBSD

```
//N2OSCBSD EXEC PGM=NATBATCH
//* CMPRINT CONTAINS ANY MESSAGES/ERRORS PRODUCED DURING
//* EXECUTION OF N2OSCBSD
//CMPRINT DD SYSOUT=*
//* CMPRT01 CONTAINS SOURCE LISTING WITH HIGHLIGHTS OR
//* UNDERLINES
//CMPRT01 DD SYSOUT=*
//CMSYNIN DD *
LOGON N2OLIB
N2OSCBSD
FIN
//CMWKF01 DD *
*UID,*SPS,*ENV,*STARTLIB,*ENDLIB,*STARTOBJ,*ENDOBJ,*UNDLN,*CHAR
LIB,OBJ
/*
```

The layout for the record in CMWKF01 is as follows:
(Any value may be left blank by placing a “,” with no value)

Line 1:

*Userid, *Scan Parm Set, *Environment, *Start Library, *End Library, *Start Object,
*End Object, *Underline, *Underline Char

Line 2:

Multiple lines of the following may be specified, and “” wildcarding is acceptable.*

Library, Object

Note: * indicates the value should contain the same value as displayed on the Select Scan Output Set screen. This is the unique identifier of the scan.

The &INPUT parameter list by default is delimited by commas with no spaces following the commas. To override the default delimiter, modify the value of the jcl-delimiter field in User-Exit-22 (N2OUE22N).

V.4.3.2.3.2.2 Output Standard Report

The N2OSCAN Output Standard Report provides a hardcopy of all statistics and detail of a scan. Suppression of specific levels of detail or statistical information is possible using the *ZEROSUPPRESS* and/or *SUPPRESSLEVEL* input parameters. Statistical information is supplied at the complete Scan Output Set Level, the Library Level, and the Object Level. For each object, strings found and line numbers of lines on which they were found are listed.

This screen is accessed by placing an 'R' in the 'S' (select) field on the Select Library Scan Output Set screen and pressing Enter.

```

Valid values:  O=Object Selection List, R=Output Standard Report
01-12-31      N-2-O SELECT LIBRARY SCAN OUTPUT SET      TSI0373
11:38:00                                           TSI1

      Scan      +-----+
      Start List a | N2O Scan Output Standard Report Parameters | Object: PAY7000P
                  |-----+ | Object: PAY8000P
                  |
O      Report Start Library: PAYPROD      | m NonComm %NonC
S Library      | Report End Library: PAYPROD | t Lns Tot LnHit
- ----- - | Report Start Object:      | -- -----
r PAYPROD      | Report End Object:      | 0      377  0.0
                  | Zero Suppress:      |
                  | Suppression Level:  _ |
                  | Press <Enter> to submit, PF3 to Cancel |
                  +-----+

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
HELP  ----  END   ----  ----  ----  UP   DOWN  ----  >ZERO ----  ----

```

Field	Description
Report Start Library (optional)	Starting library of the report.
Report End Library (optional)	Ending library of the report.
Report Start Object (optional)	Starting object of the report.
Report End Object (optional)	Ending object of the report.
Zero Suppress (optional)	Zero Suppress - suppress objects with no hits. Valid value is: On-line Y Zero Suppress – Suppress objects with no hits. N Do not suppress objects with no hits. Batch ZS Zero Suppress - suppress objects with no hits.

(continued from previous page)

Field	Description
Suppression Level (optional)	Suppression Level - only one (or none) of the following may be specified. Valid values are: DS Detail Suppress - suppress all object line (detail) information. OS Object Suppress - suppress all object Summary and object line (detail) Information. LS Library Suppress - suppress all library Summary, object summary, and object line (detail) information.

Pressing ENTER will submit the report to the internal reader.

Manual Submission of Output Standard Report

Note: LRECL for all CMPRINT and CMPRT01 datasets may be set to 133.

The following JCL is an example of OS/390 (MVS) JCL used to support the Batch Reporting process. JCL examples are shown only for OS/390 (MVS) in this section. VSE JCL, VM EXECs, and BS2000 JCL are located in **Appendix E VSE JCL**, **Appendix F VM EXECs**, and **Appendix G BS2000 JCL** respectively. JCL and EXECs should be tailored to accommodate site-specific needs. The N2O installation tape contains sample JCL in the library N2OBATCH for the program name specified.

The OS/390 (MVS) JCL to run this report is shown below.

MVSSCB01

```
//N2OSCB01 EXEC PGM=NATBATCH
//*  CMPRINT CONTAINS ANY MESSAGES/ERRORS PRODUCED DURING
//*  EXECUTION OF N2OSCB01
//CMPRINT      DD SYSOUT=*
//*  CMPRT01 CONTAINS OUTPUT STANDARD REPORT
//CMPRT01      DD SYSOUT=*
//CMSYNIN      DD *
LOGON N2OLIB
N2OSCB01
FIN
//CMWKF01      DD *
*UID,*SPS,*ENV,*STARTLIB,*ENDLIB,*STARTOBJ,*ENDOBJ
RPTSTLIB,RPTENDLIB,RPTSTOBJ,RPTENDOBJ,ZEROSUPPRESS,SUPPRESSLEVEL
/*
```

The layout for the record in CMWKF01 is as follows:
(Any value may be left blank by placing a “,” with no value)

Line 1:

*Userid, *Scan Parm Set, *Environment, *Start Library, *End Library, *Start Object,
*End Object

Line 2:

Report Start Library, Report End Library, Report Start Object, Report End
Object, Zero Suppress, Suppression Level

Note: * indicates the value should contain the same value as displayed on the Select Scan Output Set screen. This is the unique identifier of the scan.

The &INPUT parameter list by default is delimited by commas with no spaces following the commas. To override the default delimiter, modify the value of the jcl-delimiter field in User-Exit-22 (N2OUE22N).

V.4.3.2.4 Delete Scan Output Set Function

The Delete Scan Output Set function provides a list of Scan Output Sets that were submitted by the user. The user may delete any output sets that are listed.

Entering a 'D' on the N2OSCAN Utility Menu accesses the Delete Scan Output Set function.

```
Valid Values: D=Online Del, B=Batch Del
01-12-31      N2O DELETE SCAN OUTPUT SET      TSI0373
11:08:43      TSI1

S      Scan      Start      End      Start      End      Date/Time
s t User ID Parm Set Env Library Library Object Object Executed
-----
b C TSI0373 PAYSC+-----+
|                                     |
|          *** Delete Scan Output Set ***          |
|                                     |
|          User ID: TSI0373      Start Library: PAYPROD      |
|          Scan Parm Set: PAYSCAN      End Library:          |
|          Environment: PROD          Start Object:          |
|                                     End Object:          |
|                                     |
|          Status: C Executed on: 2000/09/22 18:01:10      |
|                                     |
|          *** Press <ENTER> to delete, PF3 to cancel ***      |
|                                     |
+-----+
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
HELP  --- END  ---  ---  ---  ---  ---  ---  ---  ---  ---  ---  ---
                                UP    DOWN    ---  NOT-C  ---  ---
```

Pressing Enter will delete the Scan Output Set.

PF10 Toggles between (1) Display non-closed Scan Output Sets (those in status other than "closed"); and (2) Display all Scan Output Sets for scans submitted by the user.

Field	Description
S (modifiable)	The function to be executed. Valid value is as follows: D Delete the Scan Output Set On-line. B Delete the Scan Output Set in Batch.
St (display-only)	Status Indicator. Valid values are: C Closed, scan completed successfully. O Open, scan abended (captured abend). I In process (possibly uncaptured abend). D Deletion in progress.
User ID (display-only)	User ID of the user who submitted the scan.
Scan Parm Set (display-only)	Name of the Scan Parm Set that served as input to the scan.
Env (display-only)	N2O Environment on which the scan was executed.

(continued from previous page)

Field	Description
Start Library (display-only)	Starting value for the range of libraries that was scanned. If End Library is blank, Start Library is the only library that was scanned.
End Library (display-only)	Ending value for the range of libraries that was scanned. If blank, Start Library is the only library that was scanned.
Start Object (display-only)	Starting value for the range of objects that was scanned. If End Object is blank, Start Object is the only object that was scanned.
End Object (display-only)	Ending value for the range of objects that was scanned. If blank, Start Object is the only object that was scanned.
Date/Time Executed (display-only)	The date and time the scan was executed.

V.4.3.2.4.1 Batch Delete of Scan Output Set

The Batch Delete of a Scan Output Set allows the selected Scan Output Set to be deleted in batch.

Entering a 'B' on the Select Scan Output Set screen displays the Delete Scan Output Set confirmation pop-up window.

```

Valid Values: D=Online Del, B=Batch Del
01-12-31          N2O DELETE SCAN OUTPUT SET          TSI0373
11:08:43          TSI1

      S      Scan      Start      End      Start      End      Date/Time
      S t User ID  Parm Set Env  Library  Library  Object  Object  Executed
-----
b C TSI0373  PAYS+-----
      |
      |          *** Delete Scan
      |
      |          User ID: TSI0373
      |          Scan Parm Set: PAYS SCAN
      |          Environment: PROD
      |
      |          JCL Library: N2OJCL
      |          JCL Program: N2OSCBD1
      |          JCL Exit: N2OERJE
      |
      |          Status: C Executed o
      |
      |          *** Press <ENTER> to delete, PF3 to cancel ***
      |
      +-----
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      HELP  ---  END          ---  UP          DOWN          NOT-C          ---

```

Pressing Enter will submit a batch job to delete the Scan Output Set.

V.4.3.2.4.2 String Found Report

The N2OSCAN String Found Report provides a hardcopy of all strings found in the selected Scan Output Set. This report is sorted by string-found. The library, object, line number, and number of hits of each string on the line is displayed.

Entering an 'S' on the Select Scan Output Set screen accesses the String Found Report pop-up window.

Pressing ENTER will submit the report to the internal reader.

Manual Submission of String Found Report

The N2O installation tape contains sample JCL in the library N2OBATCH for the program name specified.

The OS/390 (MVS) JCL to run this report is shown below.

Note: LRECL for all CMPRINT and CMPRT01 datasets may be set to 133.

MVSSCB02

```
//N2OSCB02 EXEC PGM=NATBATCH
//*  CMPRINT CONTAINS ANY MESSAGES/ERRORS PRODUCED DURING
//*  EXECUTION OF N2OSCB02
//CMPRINT    DD SYSOUT=*
//*  CMPRT01 CONTAINS STRING FOUND REPORT
//CMPRT01    DD SYSOUT=*
//CMSYNIN    DD *
LOGON N2OLIB
N2OSCB02
FIN
//CMWKF01      DD *
UID,SPS,ENV,STARTLIB,ENDLIB,STARTOBJ,ENDOBJ
/*
```

The layout for the record in CMWKF01 is as follows:
(Any value may be left blank by placing a "," with no value)

Values	Description
* UID	User ID of the user who submitted the scan.
* SPS	Scan Parm Set that served as input to the scan.
* ENV	N2O Environment on which the scan was executed.
* STARTLIB	Starting value for the range of libraries that was scanned. If ENDLIB is blank, STARTLIB is the only library that was scanned.
* ENDLIB	Ending value for the range of libraries that was scanned. If blank, STARTLIB is the only library that was scanned.
* STARTOBJ	Starting value for the range of objects that was scanned. If ENDOBJ is blank, STARTOBJ is the only object that was scanned.
* ENDOBJ	Ending value for the range of objects that was scanned. If blank, STARTOBJ is the only object that was scanned.

Note: * indicates the value should contain the same value as displayed on the Select Scan Output Set screen. This is the unique identifier of the scan.

The &INPUT parameter list by default is delimited by commas with no spaces following the commas. To override the default delimiter, modify the value of the jcl-delimiter field in User-Exit-22 (N2OUE22N).

Manual Batch Delete for a Single Scan Output Set

The N2OSCAN Batch Delete for a Single Scan Output Set permits batch deletion of a single specified Scan Output Set. (See **N2OSCAN Batch Delete by Date and User-ID** for deletion of a range of Scan Output Sets)

The OS/390 (MVS) JCL to run this program is shown below.

```
//N2OSCBD1 EXEC PGM=NATBATCH
//*  CPRINT CONTAINS ANY MESSAGES/ERRORS PRODUCED DURING
//*  EXECUTION OF N2OSCBD1
//CPRINT      DD SYSOUT=*
//CMSYNIN     DD *
LOGON N2OLIB
N2OSCBD1
FIN
//CMWKF01      DD *
UID,SPS,ENV,STARTLIB,ENDLIB,STARTOBJ,ENDOBJ
/*
```

The layout for the record in CMWKF01 is as follows:
(Any start/end value may be left blank by placing a “,” with no value)

Line 1:

 Userid, Scan Parm Set, Environment, Start Library, End Library, Start
 Object, End Object

Note: These values should contain the same values as displayed on the Select Scan Output Set screen. This is the unique identifier of the scan.

Manual N2OSCAN Batch Delete by Date and User ID

The N2OSCAN Batch Delete by Date and User ID permits batch deletion of all Scan Output Sets executed on or before a specified date, either for all users or a specific user (denoted by User ID). (See **N2OSCAN Batch Delete for a Single Scan Output Set** for deletion of a specific Scan Output Set).

The N2O installation tape contains sample JCL in the library N2OBATCH for the program name specified.

The OS/390 (MVS) JCL to run this program is shown below.

MVSSCBD2

```
//N2OSCBD2 EXEC PGM=NATBATCH
//*  CMPRINT CONTAINS ANY MESSAGES/ERRORS PRODUCED DURING
//*  EXECUTION OF N2OSCBD2
//CMPRINT      DD SYSOUT=*
//CMSYNIN      DD *
LOGON N2OLIB
N2OSCBD2
FIN
//CMWKF01      DD *
DATE-EXECUTED,UID
/*
```

The layout for the record in CMWKF01 is as follows:

Values	Description
DATE-EXECUTED (required)	Date in the format YYYYMMDD. All Scan Output Sets for scans executed on or before this date will be deleted.
UID (optional)	User ID. If specified, limits deletion to Scan Parm Sets submitted by the user with this User ID.

The &INPUT parameter list by default is delimited by commas with no spaces following the commas. To override the default delimiter, modify the value of the jcl-delimiter field in User-Exit-22 (N2OUE22N).

V.4.3.2.5 Administrative Delete Scan Output Set Function

The Administrative Delete Scan Output Set function provides a list of ALL Scan Output Sets on the system. This screen will allow a user to delete any Scan Output Sets.

Entering an 'E' on the N2OSCAN Utility Menu accesses the Administrative Delete Scan Output Set function.

```

Valid value:  D=Online Delete,  B=Batch Delete
01-12-31      N-2-O Administrative Delete Scan Output Set      TSI0373
11:38:00                                           TSI1

Starting User ID: _____

  S      Scan      Start      End      Start      End      Date/Time
S t User ID Parm Set Env Library Library Object Object Executed
-----
- C TSI004 SCANDEV DEV PAY001 PAY001 CALC1 CALC2 01/12/01 11:43
- O TSI004 SCANPRD PRD TAX001 TAX002 PSTTAX PSTX99 01/12/01 12:45
- C TSI006 SCANTST TST TST001 TST999 * 01/09/18 20:23
- C TSI017 SCANTST PRD PAY001 PAY999 PGM001 PGM999 01/09/25 03:13

Enter---PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12
      HELP ----- END ----- UP DOWN ----- NOT-C -----

```

PF10 Toggles between (1) Display non-closed Scan Output Sets (those in status other than "closed"); and (2) Display all Scan Output Sets.

Field	Description
Starting User ID (modifiable)	Value with which to begin the selection list.
S (modifiable)	The function to be executed. Valid value is as follows: D Delete the Scan Output Set On-line. B Delete the Scan Output Set in Batch.
St (display-only)	Status Indicator. Valid values are: C Closed, scan completed successfully. O Open, scan abended (captured abend). I In process (possibly uncaptured abend). D Deletion in progress.
User ID (display-only)	User ID of the user who submitted the scan.
Scan Parm Set (display-only)	Name of the Scan Parm Set that served as input to the scan.
Env (display-only)	N2O Environment on which the scan was executed.

(continued from previous page)

Field	Description
Start Library (display-only)	Starting value for the range of libraries that was scanned. If End Library is blank, Start Library is the only library that was scanned.
End Library (display-only)	Ending value for the range of libraries that was scanned. If blank, Start Library is the only library that was scanned.
Start Object (display-only)	Starting value for the range of objects that was scanned. If End Object is blank, Start Object is the only object that was scanned.
End Object (display-only)	Ending value for the range of objects that was scanned. If blank, Start Object is the only object that was scanned.
Date/Time Executed (display-only)	The date and time the scan was executed.

V.5 Utility Tools

The N2O utility tools provide functions to aid in the diagnosis and resolution of exception situations.

To access the Utility Tools menu, enter 'U' on the Toolbox Subsystem menu or the direct command TOL UTIL on any menu.

```

13-12-31          N-2-O UTILITY TOOLS          TSI0373
11:38:00                                     TSI1

Code  Function
-----
A    Delete Checkout Records
B    Check for Duplicate Checkout Records
C    Change an Event Status
D    Display Header Record for an Event
E    Display Event detail records for an Object
F    Display All Records Related to an Event
G    Display all OXXXXXXX libraries
H    Display all OXXXXXXX programs in a library
I    Delete all OXXXXXXX libraries
J    Unlock a Master Event
K    Delete a User Canceling all their Checkouts
L    Delete 3GL Master Records
.    Terminate Trouble Shooting Tools
-    -----

Enter Code: _

Direct Command: TOL UTIL
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      HELP  ----  END  ENV  MIG  REP  TOL  ----  PRJ  ----  ----  EXIT

```

Field	Description
ENTER CODE (required)	The function to be executed. Valid values are as follows: <ul style="list-style-type: none"> A Delete Checkout Records Delete checkout records when the normal Migration Subsystem Checkout/Checkin Cancel option does not delete it. B Check for Duplicate Checkout Records Displays any possible orphaned checkout records. C Change an Event Status Modify the status of an Event to any other status. D Display Header Record for an Event Displays all the N2O-Migration fields used on the Event Header record. E Display Event Detail Records for an Object F Display All Records Related to an Event

(continued from previous page)

Field	Description
G	Display all 0XXXXXXX libraries Displays all pending autocompile library records.
H	Display all 0XXXXXXX programs in a library Display all pending autocompile records in a given library.
I	Delete all 0XXXXXXX libraries Deletes all pending autocompile library records.
J	Unlock a Master Event Unlocks an event's master record.
K	Delete a User Canceling all their Checkouts Cancels all checkouts for a user and deletes the user.
L	Delete 3GL Master Records Deletes 3GL master records.
.	Terminate Trouble Shooting Tools

V.5.1 Delete Checkout Records

The Delete Checkout Records function permits the cancellation of a checkout for any object.

This report will aid in resolving exception situations within N2O for specific objects. This function should only be used when all normal means have been ineffective.

To access the Delete Checkout Records function, enter "A" on the Utility Tools menu.

```

01-12-31          N-2-O UTILITY TOOLS          TSI0373
11:38:00                                     TSI1

      Code  Function
      ----  -
+-----+
|                                     |
| *****                          |
| Delete Checkout Records Utility    |
| *****                          |
| Object Type:  (NATURAL, SYSERR, PREDICT, OTHER) |
| Object Name:                                     |
| Node:                                               |
| DBID:          0                                 |
| FNR:           0                                 |
| Library:                                             |
| **                                                 |
| Ente | PF5 - LOOKUP INFO. (REQUIRES OBJECT TYPE/NAME) |
|      | ENTER '.' IN ANY FIELD OR PF3 TO CANCEL      |
+-----+

Direct Command: _____ TOL UTIL
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      HELP ---- END  ENV  MIG  REP  TOL  ---- PRJ  ---- ---- EXIT

```

Field	Type	Description
Object Type (required)	N,S,P,O	NATURAL, SYSERR, PREDICT, OTHER.
OBJECT Name (required)	N,S,P,O	Name of the checked out object to be cancelled.
Node (required)	N,S,P,O	The Node name assigned to the Checkout Environment. PF5 can be used to look up the value of this field.
Dbid (required)	N,S,P,O	The Database Id number assigned to the Checkout Environment. PF5 can be used to look up the value of this field.
FNR (required)	N,S,P,O	The FUSER File number assigned to the Checkout Environment. PF5 can be used to look up the value of this field.
Library (required)	N,S,P,O	The Library name assigned to the Checkout Environment. PF5 can be used to look up the value of this field.

V.5.2 Check for Duplicate Checkout Records

The Check for Duplicate Checkout Records function displays any objects that have multiple checkouts existing. This report will aid in resolving exception situations within N2O for specific objects. This function should only be used when all normal means have been ineffective.

To access the Check for Duplicate Checkout Records function, enter "B" on the Utility Tools menu. Processing will begin as soon as the option is selected. It may take several minutes, then a display of all duplicate checkouts will be appear.

01-12-31 11:38:00		DISPLAY DUPLICATE CHECKOUT RECORDS				PAGE: 1
TYPE	NODE	DBID	FNR	LIBRARY	OBJECT	
S	CPUL	00001	00231	TREE11C	1015	
S	CPUL	00001	00231	TREE11C	1015	
S	CPUL	00001	00231	TREE11C	1015	
S	CPUL	00001	00231	TREE26B	2030	
S	CPUL	00001	00231	TREE26B	2035	
S	CPUL	00001	00231	TREE26B	2035	
S	CPUL	00001	00231	TREE26B	2045	
S	CPUL	00001	00231	TREE26B	2045	
S	CPUL	00001	00231	TREE26B	2045	
S	CPUL	00001	00231	TREE26B	2045	
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---						EXIT

V.5.3 Change an Event Status

The Change an Event Status function permits an Event's status to be modified to any status. This report will aid in resolving exception situations within N2O for specific objects. This function should only be used when all normal means have been ineffective. An Event with a current status of 'C' (closed) cannot be modified.

To access the Change an Event Status function, enter "C" on the Utility Tools menu.

01-12-31
11:38:00

N-2-O Trouble-Shooting Tools
Update An Event Status

TSI0373
TSI1

Event Name:

Sequence Number:

New Event Status:

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---

HELP ---- END ----

Field	Description
Event Name (required)	Name of the Event.
Sequence Number (required)	Sequence Number of the Event.
New Event Status (required)	The new status of the Event. B Batch Ready I In Progress C Closed O Open H Hold

V.5.4 Display Header Record for an Event

The Display Header Record for an Event displays all of the Event Header fields on the N2O Migration File for a specific Event. This report will aid in resolving exception situations within N2O for specific objects.

To access the Display Header Record for an Event function, enter "D" on the Utility Tools menu.

01-12-31
11:38:00

N-2-O UTILITY TOOLS

Code

Function

DISPLAY EVENT HEADER RECORD

EVENT :

SEQUENCE:

ENTER '.' IN ANY FIELD OR PF3 TO CANCEL

Ente +-----

TSI0373

TSI1

Direct Command:

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---

HELP ---- END ENV MIG REP TOL ---- PRJ ---- ---- EXIT

TOL UTIL

Field	Description
Event Name (required)	Name of the Event.
Sequence Number (required)	Sequence Number of the Event.

V.5.5 Display Event Detail Records for an Object

The Display Event Detail Records for an object function shows all of the fields on the N2O Migration file that are related to a specific Event and object. This report will aid in diagnosing exception situations with in N2O for specific objects.

To access the Display Event Detail Records for an Object screen, enter "E" on the Utility Tools menu.

```

01-12-31                      N-2-O UTILITY TOOLS                      TSI0373
11:38:00

Code  Function
----  -
+-----+
|      |
|      | *****
|      | DISPLAY EVENT DETAIL RECORD
|      | *****
|      | EVENT :
|      | SEQUENCE:
|      | TYPE   :   (N,S,P,O)
|      | OBJECT :
|      |
|      | ** ENTER '.' IN EVENT OR PF3 TO CANCEL
|      | *****
Ente +-----+

Direct Command:
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
HELP  ----  END   ENV   MIG   REP   TOL   ----  PRJ   ----  EXIT

```

Field	Description
Event Name (required)	Name of the Event.
Sequence (required)	Sequence Number of the Event.
Type (required)	Type of object. N Indicates Natural S Indicates SYSERR P Indicates PREDICT O Indicates Other
Object (required)	Object name.

V.5.6 Display All Records Related to an Event

The Display All Records Related to an Event function Displays all records on the N2O Migration file related to a specific Event. This report will aid in resolving exception situations within N2O for specific objects. This function should only be used when all normal means have been ineffective.

To access the Change an Event Status function, enter "F" on the Utility Tools menu.

```

01-12-31          N-2-O UTILITY TOOLS          TSI0373
11:38:00                                     TSI1

      Code  Function
      ----  -
+-----+
|                                     |
| *****                               |
| DISPLAY ALL RECORDS FOR EVENT        |
| *****                               |
| EVENT      :                         |
| SEQUENCE:  :                         |
|                                     |
| ** ENTER '.' IN ANY FIELD OR PF3 TO CANCEL |
| *****                               |
|                                     |
Ente +-----+

Direct Command: _____ TOL UTIL
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      HELP ---- END  ENV  MIG  REP  TOL  ---- PRJ  ---- ---- EXIT

```

Field	Description
Event Name (required)	Name of the Event.
Sequence Number (required)	Sequence Number of the Event.

V.5.7 Display All OXXXXXXX Libraries

The Display all OXXXXXXX Libraries function displays all OXXXXXXX libraries in a specific Environment. OXXXXXXX libraries are created by N2O for use in the autocompile process. This report will aid in resolving exception situations within N2O for specific objects. This function should only be used when all normal means have been ineffective.

To access the Display all OXXXXXXX Libraries function, enter "G" on the Utility Tools menu.

V.5.8 Display All OXXXXXXX Programs in a Library

The Display all OXXXXXXX Programs function in a library displays all OXXXXXXX programs in a specific Natural Library. OXXXXXXX programs are created by N2O for use in the Autocompile process. This report will aid in resolving exception situations within N2O for specific objects. This function should only be used when all normal means have been ineffective.

To access the Display all OXXXXXXX programs function, enter "H" on the Utility Tools menu.

```

01-12-31          N-2-O UTILITY TOOLS          TSI0373
11:38:00                                     TSI1

      Code  Function
      ----  -
+-----+
| SEARCH FOR OXXXXXXX PROGRAMS IN LIBRARY: _____ |
| PF3 TO CANCEL                                           |
+-----+
      F    Display all Records related to an Event
      G    Display all OXXXXXXX libraries
      H    Display all OXXXXXXX programs in a library
      I    Delete all OXXXXXXX libraries
      J    Unlock a Master Event
      K    Delete a User Canceling all their Checkouts
      L    Delete 3GL Master Records
      .    Terminate Trouble Shooting Tools
      -    -----

Enter Code: h

Direct Command: _____ TOL UTIL
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
HELP ---- END  ENV  MIG  REP  TOL  ---- PRJ  ---- ---- EXIT

```

Field	Description
Library (required)	Library to search for OXXXXXXX records in.

V.5.9 Delete All OXXXXXXX Libraries

The Delete all OXXXXXXX Libraries function deletes all OXXXXXXX libraries in a specific Environment. OXXXXXXX libraries are created by N2O for use in the Autocompile process. This function will aid in resolving exception situations within N2O for specific objects. This function should only be used when all normal means have been ineffective.

To access the Delete all OXXXXXXX Libraries function, enter "I" on the Utility Tools menu.

V.5.10 Unlock a Master Event

The Unlock a Master Event function permits the unlocking of a master Event. This function should only be used when the customer encounters the error "Record is currently on hold - Please try later." when adding or modifying an event and no other user is currently defining an event. This problem may occur if an error occurred while defining an event.

To access the Unlock a Master Event function, enter "J" on the Utility Tools menu.

01-12-31 11:38:00	N-2-O UTILITY TOOLS	TSI0373 TSI1
Code	Function	
----	-----	
	<pre> +-----+ ***** UNLOCK EVENT MASTER RECORD ***** EVENT : ENTER '.' IN ANY FIELD OR PF3 TO CANCEL ***** +-----+ </pre>	
Enter	+	-----+
Direct Command: _____		TOL UTIL
Enter-PF1---	PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---	
HELP ----	END ENV MIG REP TOL ---- PRJ ---- ---- EXIT	

Field	Description
Event Name (required)	Name of the Master Event to be unlocked.

V.5.11 Delete a User Canceling all their Checkouts

The Delete a User Canceling all their Checkouts function cancels all checkouts for a User Definition and deletes the User Definition. This function should only be used when a User Definition cannot be deleted due to open checkouts for the User.

To access the Delete a User Canceling all their Checkouts function, enter "K" on the Utility Tools menu.

```
14-01-14          N-2-O UTILITY TOOLS          VLM1
14:37:04                                     SC0TCP11

      Code  Function
      ----  -
+-----+
!                               ! ckout Records
! User Definition: _____ !
!                               ! or an Event
! PF3, Enter END or . to exit ! cords for an Object
!                               ! ated to an Event
+-----+ braries
      H   Display all 0XXXXXXX programs in a library
      I   Delete all 0XXXXXXX libraries
      J   Unlock a Master Event
      K   Delete a User Canceling all their Checkouts
      L   Delete 3GL Master Records
      .   Terminate Trouble Shooting Tools
      -   -----

      Enter Code: k
Direct Command: _____ TOL UTIL

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      HELP  ----  END   ENV   MIG   REP   TOL   ----  PRJ   ----  ----  EXIT
```

Field	Description
User Definition (required)	User Definition to be deleted.

V.5.12 Delete 3GL Master Records

The Delete 3GL Master Records function deletes 3GL master records.

This report will aid in resolving exception situations within N2O for specific objects. This function should only be used when all normal means have been ineffective.

To access the Delete Checkout Records function, enter "L" on the Utility Tools menu.

```

14-01-08          N-2-O UTILITY TOOLS          VLM1
14:48:34                                     SC0TCP11

      Code  Function
      ----  -
+-----+
!          !
! ***** !
! Delete 3GL Objects from N2O Master Catalog !
! ***** !
! 3GL Base Env: !
!      Category: !
!      Object Name: !
! ** !
! PF1 - HELP !
! ENTER '.' IN ANY FIELD OR PF3 TO CANCEL !
! ***** !
+-----+
      -

Enter Code: 1
Direct Command: _____ TOL UTIL

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      HELP  ----  END   ENV   MIG   REP   TOL   ----  PRJ   ----  ----  EXIT

```

Field	Type	Description
3GL Base Env: (required)	O	Base Environment of the 3GL object of the Master Record to be deleted.
Category (required)	O	The 3GL/Other category of the 3GL object of the Master Record to be deleted. Valid values are as follows: ASMB Indicates all types of Assembler. COBOL Indicates all types of COBOL. FORT Indicates all types of FORTRAN. PL/I Indicates all PL/I types. RPG Indicates RPG. DATA Indicates DATA FILES. JCL Indicates JCL, CLIST, CNTL. OTHER, All other types.
OBJECT Name (required)	O	Name of the 3GL object of the Master Record to be deleted.

APPENDIX A

N2O Direct Commands

The following is a list of Direct Commands (screen names) and their descriptions.

SCREEN NAME	DESCRIPTION
MIG MENU	MIGRATION SUBSYSTEM MENU
MIG AUTH	• AUTHORIZE EVENTS MENU
MIG SUB	•BATCH JCL SUBMISSION MENU
MIG COCI	•CHECKOUT/CHECKIN UTILITIES MENU
MIG UTIL	• MIGRATION UTILITIES MENU
MIG REQ	• REQUEST EVENTS MENU
MIG SERV	• SERVICE EVENTS MENU
PRJ MENU	PROJECT TRACKING SUBSYSTEM MENU
PRJ PROJ	• PROJECT DEFINITION MENU
PRJ TASK	• TASK LIST MENU
PRJ SUGG	• SUGGESTION BOX MENU
PRJ TUTL	• TASK UTILITIES MENU
PRJ REP	•PROJECT TRACKING REPORTS MENU
REP MENU	REPORTING SUBSYSTEM MENU
REP ENV	• ENVIRONMENT REPORTING MENU
REP EVNT	• EVENT REPORTING MENU
REP OBJ	• OBJECT REPORTING MENU
REP STAT	• STATISTICAL REPORTING MENU
REP SEC	• SECURITY REPORTING MENU
TOL MENU	TOOLBOX SUBSYSTEM MENU
TOL DOC	• DOCUMENTATION TOOLS MENU
TOL MAIN	• MAINTENANCE TOOLS MENU
TOL PROG	• PROGRAMMER TOOLS MENU
TOL UTIL	•UTILITY TOOLS MENU
TOL SCAN	N2OSCAN UTILITY MENU
TOL SCEN	•N2OSCAN ENVIRONMENT FUNCTION MENU
TOL SCLI	•N2OSCAN LIBRARY FUNCTION MENU
TOL SCRP	•N2OSCAN SUBMIT BATCH REPORTS

This page intentionally left blank.

APPENDIX B

N2O EVENT STATUS

The following is a description of each Event status.

Status	Description
O	The Event is in an open status. An open Event can be an Event that still requires modifications, an Event that is pending migration, or an Event that requires authorization. Additionally, if the user does not complete the authorization process (presses PF3 before the migration occurs), the status of the Event will remain open and the Event will have to be authorized.
A	The Event has been authorized but still requires servicing.
B	The Event is a batch migration that is ready to be executed.
H	The Event is on hold by a user.
I	The Event is a batch migration that is in-progress.
C	The Event has completed and is closed.

This page intentionally left blank.

APPENDIX C

ERROR MESSAGES

N2O uses the following SYSERR messages. These messages are loaded into library N2OLIB when N2O is installed.

Error Number	Error Message
1010	Invalid function code
1015	Invalid PF KEY
1030	Value not found
1040	Value required
1050	Selection out of range
1060	Invalid selection
1070	Please choose one or press PF3 to quit
1080	No partial entries allowed in list
1090	At least one entry required in list
1100	Migration Profile not found
1110	Environment Definition not found
1120	Node Definition not found
1130	Select only one option
1135	Choose only one
1140	Date must be formatted YYYYMMDD
1145	Time must be formatted HH:MM:SS
1150	Valid values: A, B, C, H, I, O
1155	Invalid User-ID specified
1160	Invalid Environment Definition
1161	Environment Definition must contain FDIC information
1162	Environment Definition must contain FUSER information
1163	BASE Env does not define a NATURAL environment
1164	BASE Env does not define a 3GL environment
1165	Invalid 3GL Environment Definition
1169	Remote Environment Definition cannot be specified
1170	Please enter a Remote Environment Definition
1175	Please enter a BASE Environment Definition
1177	Cannot migrate an entire library with this function
1180	Object has already been selected
1185	Valid values: M, G, L, A, P, N, S, H, C, T, K, O, R, Y, Z, 3, 4, 5
1190	Valid values: ASMB, COBOL, FORT, PL/I, RPG, DATA, JCL, OTHER
1195	Not a valid PREDICT Type
1200	Top of available selection list displayed
1210	Last reviewed screen currently displayed
2010	Duplicate value
2015	Copycode/text cannot have object code
2017	DDM Generated only valid for ADABAS files

Error Number	Error Message
2020	Feature is not available
2025	Valid version numbers: -1 to -99
2030	Valid values: 1 - 255
2035	Valid values: Y or N
2040	Valid values: YES or NO
2042	Valid values: S, C
2045	Valid values: US, UL, U
2046	Valid values: 1, 2, 3, 4, 5, 6, 7, 8 or *
2050	Valid values: 0001 - 9999
2055	Valid values: O or B
2060	Environment must be a 3GL Environment
2070	Migration Profile within the same dataset is invalid
2075	Valid values: COPY or MOVE
2085	Profile contains inconsistent 3GL Environments
2086	From environments are inconsistent (NATURAL vs. 3GL)
2087	To environments are inconsistent (NATURAL vs. 3GL)
2090	Profile contains inconsistent environments
2130	No records found for search criteria
2150	Top of available data
2160	Bottom of available data
2170	Program does not exist
2180	Please select a valid type
2200	Please select an Environment Definition
2405	Please select a Category
3030	Invalid Library
3050	Event/Sequence not found
3060	Cannot delete non-selected object
3070	Cannot migrate programs within the same library
3075	Cannot migrate PREDICT objects within the same FDIC
3080	Valid values: A or D
3180	Type an X to select
3210	Cannot transfer to the same User-ID
3220	Current location cannot be a BASE Environment
3230	Archive Definition cannot be specified
3250	Cipher Code must be a number
3260	Days cannot be a negative number
4020	Program to be displayed could not be found
5000	Starting Error must be * or numeric
5030	Starting value outside Library range
6000	Invalid Scan Environment
6001	Invalid Start Library
6002	Start Library may not be greater than End Library
6003	Invalid Start Object
6004	Start Object may not be greater than End Object
7005	There are no Task Groups defined to this
7010	Project Definition not found
7015	Stage name reserved by N2O
7020	Valid Task Group required
9010	Type an X to view Source programs
9170	Type an X to submit the JCL

APPENDIX D

JCL samples

All JCL samples are included as part of the base N2O installation. The samples are loaded into the Natural library N2OBATCH.

D.1 – Base N2O batch functions

Archive Purge

```

Program      MVSARCHP Library N2OBATCH
0010 //ARCHPURG JOB (ACCOUNTING),'ARCHIVE PURGE',CLASS=A,NOTIFY=&USERID
0020 //*****
0030 //* THIS IS SAMPLE ARCHIVE PURGE JCL
0040 //* THIS JOB SHOULD BE RENAMED TO N2OPUARC
0050 //*****
0060 //* ARCHP1 RUNS WHERE N2O IS INSTALLED
0070 //*
0080 //ARCHP1 EXEC PGM=NATBATCH
0090 //CMWK02 DD DSN=LIST.PARMS,DISP=(NEW,PASS,DELETE),
0100 //          SPACE=(TRK,(1,1),RLSE),UNIT=SYSDA,
0110 //          DCB=(RECFM=FB,BLKSIZE=84,LRECL=80)
0120 //CMPRINT DD SYSOUT=*
0130 //CMPRT02 DD SYSOUT=*
0140 //CMSYNIN DD *
0150 LOGON N2OLIB
0160 N2OPARC1
0170 FIN
0180 /*
0190 //CMWK01 DD *
0200 &INPUT
0210 /*
0220 //****
0230 //* ARCHP2 RUNS ON AN FUSER THAT IS LOCAL TO THE ARCHIVE FILE
0240 //****
0250 /** N2OV5.2 CHANGE CMWK03 LRECL FROM 97 TO 99
0260 //****
0270 //ARCHP2 EXEC PGM=NATBATCH,COND=(9,LT)
0280 /*
0290 //CMWK01 DD DSN=LIST.PARMS,DISP=(OLD,PASS,CATLG)
0300 //CMWK03 DD DSN=ARCHIVE.LIST,DISP=(NEW,PASS,CATLG),
0310 //          SPACE=(TRK,(900,900),RLSE),UNIT=SYSDA,
0320 //          DCB=(RECFM=FB,BLKSIZE=101,LRECL=99)
0330 //CMPRINT DD SYSOUT=*
0340 //CMPRT02 DD SYSOUT=*
0350 //CMSYNIN DD *
0360 LOGON SYSTEM
0370 N2OPARC2
0380 FIN
0390 /*
0400 //****
0410 //* ARCHP3 RUNS ON AN FUSER THAT IS LOCAL TO THE ARCHIVE FILE
0420 //****
0430 /** N2OV5.2 CHANGE CMWK05 LRECL FROM 97 TO 99
0440 //****
0450 //ARCHP3 EXEC PGM=NATBATCH,COND=(9,LT)
0460 /*
0470 //CMWK01 DD DSN=LIST.PARMS,DISP=(OLD,DELETE,CATLG)
0480 //CMWK04 DD DSN=ARCHIVE.LIST,DISP=(OLD,PASS,CATLG)
0490 //CMWK05 DD DSN=ARCHIVE.PURGE,DISP=(NEW,CATLG,CATLG),
0500 //          SPACE=(TRK,(900,900),RLSE),UNIT=SYSDA,
0510 //          DCB=(RECFM=FB,BLKSIZE=101,LRECL=99)

```

```
0520 //CMWKF06 DD DSN=&BACKUP,DISP=(NEW,CATLG,CATLG),
0530 //          SPACE=(CYL,(15,15),RLSE),UNIT=SYSDA,
0540 //          DCB=(RECFM=VB,BLKSIZE=6108,LRECL=6104)
0550 //CMPRINT DD SYSOUT=*
0560 //CMPRT02 DD SYSOUT=*
0570 //CMPRT04 DD SYSOUT=*
0580 //CMPRT06 DD SYSOUT=*
0590 //CMSYNIN DD *
0600 LOGON SYSTEM
0610 N2OPARC3
0620 FIN
0630 /*
0640 //****
0650 //* ARCHP4 RUNS WHERE N2O IS INSTALLED
0660 //****
0670 //ARCHP4 EXEC PGM=NATBATCH,COND=(9,LT)
0680 /*
0690 //CMWKF05 DD DSN=ARCHIVE.PURGE,DISP=(OLD,DELETE,CATLG)
0700 /*
0710 //CMPRINT DD SYSOUT=*
0720 //CMPRT02 DD SYSOUT=*
0730 //CMSYNIN DD *
0740 LOGON N2OLIB
0750 N2OPARC4
0760 FIN
0770 /*
0780 //CMWKF03 DD *
0790 &BACKUP
0800 /*
0810 /*
***** End of list *****
```

```

Program      BSARCHP  Library N2OBATCH
0010 / .N2O LOGON
0020 /CALL-PROCEDURE NAME=$TSOSAVE.DO.JV.T
0030 /ASSIGN-SYSOUT TO-FILE=N2O.OUT.LOAD.&(JV.ZEIT.T)
0040 /MODIFY-JOB-OPTIONS LOGGING=PARAMETERS (LISTING=YES)
0050 /REMARK *** EXECUTE N2OPARC1 ***
0060 /SET-FILE-LINK LINK-NAME=W01, FILE-NAME=PURGE.PARMS
0070 /FILE LIST.PARMS, LINK=W02, RECFORM=FB, RECSIZE=80, BLKSIZE=84
0080 /FILE MASTER.LIST, LINK=P02
0090 /ASSIGN-SYSDTA TO-FILE=*SYSCMD
0100 /MODIFY-JOB-SWITCHES ON=(4,5)
0110 /START-PROGRAM FROM-FILE=$EDT
0120 LS=132, PS=60, MENU=OFF
0130 @WRITE 'N2O.PURGE.IPT.BATCH' OVERWRITE
0140 @HALT
0150 /MODIFY-JOB-SWITCHES OFF=(4,5)
0160 /ASSIGN-SYSIPT TO-FILE=N2O.PURGE.IPT.BATCH
0170 /MODIFY-JOB-SWITCHES ON=(2)
0180 /START-PROGRAM FROM-FRIL=$ADABAS.NATBATCH
0190 LOGON N2OLIB
0200 N2OPARC1
0210 FIN
0220 /REMARK *** EXECUTE N2OPARC2 ***
0230 /REMARK *****
0240 /REMARK N2OV5.2 CHANGE W03 LRECL FROM 97 TO 99 BLKSIZE 101 TO 103
0250 /REMARK *****
0260 /FILE LIST.PARMS, LINK=W01
0270 /FILE ARCHIVE.LIST, LINK=W03, RECFORM=FB, RECSIZE=99, BLKSIZE=103
0280 /FILE CONTROL.LIST, LINK=P02
0290 /SET-JOB-STEP
0300 /ASSIGN-SYSIPT TO-FILE=N2O.TRANSFER.IPT.BATCH
0310 /START-PROGRAM FROM-FILE=$ADABAS.NATBATCH
0320 LOGON SYSTEM
0330 N2OPARC2
0340 FIN
0350 /REMARK *** EXECUTE N2OPARC3 ***
0360 /REMARK *****
0370 /REMARK N2OV5.2 CHANGE W05 LRECL FROM 97 TO 99 BLKSIZE 101 TO 103
0380 /REMARK *****
0390 /FILE LIST.PARMS, LINK=W01
0400 /FILE ARCHIVE.LIST, LINK=W04
0410 /FILE ARCHIVE.PURGE, LINK=W05, RECFORM=FB, RECSIZE=99, BLKSIZE=103
0420 /FILE &BACKUP, LINK=W06, RECFORM=VB, RECSIZE=6104, BLKSIZE=6108
0430 /FILE CONTROL.LIST, LINK=P02
0440 /FILE SUMMARY.LIST, LINK=P04
0450 /FILE SOURCE.LIST, LINK=P06
0460 /SET-JOB-STEP
0470 /ASSIGN-SYSIPT TO-FILE=N2O.TRANSFER.IPT.BATCH
0480 /START-PROGRAM FROM-FILE=$ADABAS.NATBATCH
0490 LOGON SYSTEM
0500 N2OPARC3
0510 FIN
0520 /REMARK *** EXECUTE N2OPARC4 ***
0530 /SET-FILE-LINK LINK-NAME=W03, FILE-NAME=BACKUP.DSN
0540 /FILE ARCHIVE.PURGE, LINK=W05
0550 /FILE CONTROL.LIST, LINK=P02
0560 /SET-JOB-STEP
0570 /ASSIGN-SYSIPT TO-FILE=N2O.TRANSFER.IPT.BATCH
0580 /START-PROGRAM FROM-FILE=$ADABAS.NATBATCH
0590 LOGON N2OLIB
0600 N2OPARC4
0610 FIN
0620 /ASSIGN-SYSIPT TO-FILE=*PRIMARY
0630 /DELETE-FILE FILE-NAME=N2O.TRANSFER.IPT.BATCH,
0640 /OPTION=DESTROY-ALL
0650 /LOGOFF NOSPOOL
***** End of list *****

```

```
Program      VMARCHP  Library N2OBATCH
0010 /* Execute N2OPARC1 */
0020 ADDRESS 'COMMAND'
0030 'ERASE N2OPARC1 CMSYNIN A'
0040 'ERASE N2O CMWKF01 A'
0050 'EXECIO 1 DISKW N2OPARC1 CMWKF01 A 1 F 80 (STRING &INPUT'
0060 'EXECIO 1 DISKW N2OPARC1 CMSYNIN A 1 F 80 (STRING LOGON N2OLIB'
0070 'EXECIO 1 DISKW N2OPARC1 CMSYNIN A 2 F 80 (STRING N2OPARC1'
0080 'EXECIO 1 DISKW N2OPARC1 CMSYNIN A 3 F 80 (STRING FIN'
0090 'FILEDEF * CLEAR'
0100 'FILEDEF CMWKF01 DISK N2OPARC1 CMWKF01 A'
0110 'FILEDEF CMWKF02 DISK N2OPARC1 LISTPARM A',
0120 ' RECFM FB LRECL 80 BLKSIZE 84'
0130 'FILEDEF CMSYNIN DISK N2OPARC1 CMSYNIN A'
0140 'FILEDEF CMPRINT PRINTER'
0150 'FILEDEF CMPRT02 PRINTER'
0160 'EXEC NAT BATCH'
0170 /* Execute N2OPARC2 */
0180 /*
0190 /* N2OV5.2 CHANGE CMWKF03 LRECL FROM 97 TO 99 BLKSIZE FROM 101 TO 103
0200 /*
0210 'ERASE N2OPARC2 CMSYNIN A'
0220 'EXECIO 1 DISKW N2OPARC2 CMSYNIN A 1 F 80 (STRING LOGON SYSTEM'
0230 'EXECIO 1 DISKW N2OPARC2 CMSYNIN A 2 F 80 (STRING N2OPARC2'
0240 'EXECIO 1 DISKW N2OPARC2 CMSYNIN A 3 F 80 (STRING FIN'
0250 'FILEDEF * CLEAR'
0260 'FILEDEF CMWKF01 DISK N2OPARC1 LISTPARM A'
0270 'FILEDEF CMWKF03 DISK N2OPARC2 ARCHLIST A',
0280 ' RECFM FB LRECL 99 BLKSIZE 103'
0290 'FILEDEF CMSYNIN DISK N2OPARC2 CMSYNIN A'
0300 'FILEDEF CMPRINT PRINTER'
0310 'FILEDEF CMPRT02 PRINTER'
0320 'EXEC NAT BATCH'
0330 'ERASE N2OPARC2 CMSYNIN A'
0340 /* Execute N2OPARC3 */
0350 /*
0360 /* N2OV5.2 CHANGE CMWKF05 LRECL FROM 97 TO 99 BLKSIZE FROM 101 TO 103
0370 /*
0380 'ERASE N2OPARC3 CMSYNIN A'
0390 'EXECIO 1 DISKW N2OPARC3 CMSYNIN A 1 F 80 (STRING LOGON SYSTEM'
0400 'EXECIO 1 DISKW N2OPARC3 CMSYNIN A 2 F 80 (STRING N2OPARC3'
0410 'EXECIO 1 DISKW N2OPARC3 CMSYNIN A 3 F 80 (STRING FIN'
0420 'FILEDEF * CLEAR'
0430 'FILEDEF CMWKF01 DISK N2OPARC1 LISTPARM A'
0440 'FILEDEF CMWKF04 DISK N2OPARC2 ARCHLIST A'
0450 'FILEDEF CMWKF05 DISK N2OPARC3 ARCHPURG A',
0460 ' RECFM FB LRECL 99 BLKSIZE 103'
0470 'FILEDEF CMWKF06 DISK &BACKUP RECFM VB LRECL 6104 BLKSIZE 6108'
0480 'FILEDEF CMSYNIN DISK N2OPARC3 CMSYNIN A'
0490 'FILEDEF CMPRINT PRINTER'
0500 'FILEDEF CMPRT02 PRINTER'
0510 'FILEDEF CMPRT04 PRINTER'
0520 'FILEDEF CMPRT06 PRINTER'
0530 'EXEC NAT BATCH'
0540 'ERASE N2OPARC3 CMSYNIN A'
0550 /* Execute N2OPARC4 */
0560 'ERASE N2OPARC4 CMSYNIN A'
0570 'EXECIO 1 DISKW N2OPARC4 CMWKF03 A 1 F 80 (STRING &BACKUP'
0580 'EXECIO 1 DISKW N2OPARC4 CMSYNIN A 1 F 80 (STRING LOGON N2OLIB'
0590 'EXECIO 1 DISKW N2OPARC4 CMSYNIN A 2 F 80 (STRING N2OPARC4'
0600 'EXECIO 1 DISKW N2OPARC4 CMSYNIN A 3 F 80 (STRING FIN'
0610 'FILEDEF * CLEAR'
0620 'FILEDEF CMWKF03 DISK &BACKUP'
0630 'FILEDEF CMWKF05 DISK N2OPARC3 ARCHPURG A'
0640 'FILEDEF CMSYNIN DISK N2OPARC4 CMSYNIN A'
0650 'FILEDEF CMPRINT PRINTER'
0660 'FILEDEF CMPRT02 PRINTER'
0670 'EXEC NAT BATCH'
0680 'ERASE N2OPARC4 CMSYNIN A'
0690 exit
***** End of list *****
```

```

Program      VSEARCHP Library N2OBATCH
0010 * $$ JOB JNM=ARCHPURG,CLASS=A,USER=&USERID
0020 * $$ LST CLASS=A,LST=SYSLST
0030 * $$ LST CLASS=A,LST=02E,DISP=K,JSEP=0
0040 // JOB ARCHPURG
0050 // DLBL CMWKF01,'PURGE.INPUT.PARMS'
0060 // EXTENT SYS001,,,,nnnnn,nnnnn
0070 // EXEC IDCAMS,SIZE=AUTO
0080 REPRO INFILE(SYSIPT ENV(RECFM(FB) RECSZ(80))) -
0090      OUTFILE(CMWKF01 ENV(RECFM(FB) RECSZ(80) BLKSZ(84)))
0100 &INPUT
0110 /*
0120 * N2OPARC1 - FIND ARCHIVE PURGE PARAMETERS.
0130 // ASSGN SYSIPT,SYSRDR
0140 // ASSGN SYS001,DISK,SHR
0150 // ASSGN SYS002,DISK,SHR
0160 // ASSGN SYS009,SYSLIST
0170 // ASSGN SYS042,02E
0180 // DLBL CMWKF01,'PURGE.INPUT.PARMS'
0190 // EXTENT SYS001,,,,nnnnn,nnnnn
0200 // DLBL CMWKF02,'LIST.PARMS'
0210 // EXTENT SYS002,,,,nnnnn,nnnnn
0220 // EXEC NATBATCH
0230 BWORKD=(1,1,80,FB,2,2,80,FB)
0240 /*
0250 ADARUN DB=xxx,SVC=yyy,DEVICE=zzzz
0260 /*
0270 LOGON N2OLIB
0280 N2OPARC1
0290 FIN
0300 /*
0310 * N2OPARC2 - CREATE LIST OF OBJECTS TO BE PURGED
0320 *
0330 *      N2OV5.2 CHANGE CMWKF03 LRECL FROM 97 TO 99
0340 *
0350 // ASSGN SYS001,DISK,SHR
0360 // ASSGN SYS003,DISK,SHR
0370 // ASSGN SYS009,SYSLST
0380 // ASSGN SYS042,02E
0390 // DLBL CMWKF01,'LIST.PARMS'
0400 // EXTENT SYS001,,,,nnnnn,nnnnn
0410 // DLBL CMWKF03,'ARCHIVE.LIST'
0420 // EXTENT SYS003,,,,nnnnn,nnnnn
0430 // EXEC NATBATCH
0440 /BWORKD=(1,1,80,FB,3,3,99,FB)
0450 /*
0460 ADARUN DB=XXX,SVC=YYY,DEVICE=ZZZZ
0470 /*
0480 LOGON SYSTEM
0490 N2OPARC2
0500 FIN
0510 /*
0520 * $$ LST CLASS=A,LST=04E,DISP=K,JSEP=0
0530 * $$ LST CLASS=A,LST=06E,DISP=K,JSEP=0
0540 * N2OPARC3 - PURGE PROGRAMS FROM ARCHIVE FILE
0550 *
0560 *      N2OV5.2 CHANGE CMWKF05 LRECL FROM 97 TO 99
0570 *
0580 // ASSGN SYS001,DISK,SHR
0590 // ASSGN SYS004,DISK,SHR
0600 // ASSGN SYS005,DISK,SHR
0610 // ASSGN SYS006,DISK,SHR
0620 // ASSGN SYS009,SYSLST
0630 // ASSGN SYS042,02E
0640 // ASSGN SYS044,04E
0650 // ASSGN SYS046,06E
0660 // DLBL CMWKF01,'LIST.PARMS'
0670 // EXTENT SYS001,,,,nnnnn,nnnnn
0680 // DLBL CMWKF04,'ARCHIVE.LIST'

```

```
0690 // EXTENT SYS004,,,,nnnnn,nnnnn
0700 // DLBL CMWKF05,'ARCHIVE.PURGE'
0710 // EXTENT SYS005,,,,nnnnn,nnnnn
0720 // DLBL CMWKF06,'&BACKUP'
0730 // EXTENT SYS006,,,,nnnnn,nnnnn
0740 // EXEC NATBATCH
0750 BWORKD=(1,1,80,FB,4,4,97,FB,5,5,99,FB,6,6,6104,VB)
0760 /*
0770 ADARUN DB=xxx,SVC=yyy,DEVICE=zzzz
0780 /*
0790 LOGON SYSTEM
0800 N2OPARC3
0810 FIN
0820 /*
0830 * N2OPARC4 - UPDATE MIGRATION FILE
0840 // DLBL CMWKF03,'DSNAME.INPUT'
0850 // EXTENT SYS003,,,,nnnnn,nnnnn
0860 // EXEC IDCAMS,SIZE=AUTO
0870 REPRO INFILE(SYSIPT ENV(RECFM(FB) RECSZ(80))) -
0880 OUTFILE(CMWKF03 ENV(RECFM(FB) RECSZ(80) BLKSZ(80)))
0890 &BACKUP
0900 /*
0910 // ASSGN SYSIPT,SYSRDR
0920 // ASSGN SYS003,DISK,SHR
0930 // ASSGN SYS004,DISK,SHR
0940 // ASSGN SYS009,SYSLST
0950 // ASSGN SYS042,02E
0960 // DLBL CMWKF03,'DSNAME.INPUT'
0970 // EXTENT SYS003,,,,nnnnn,nnnnn
0980 // DLBL CMWKF05,'ARCHIVE.PURGE'
0990 // EXTENT SYS005,,,,nnnnn,nnnnn
1000 // EXEC NATBATCH
1010 BWORKD=(3,3,80,FB,5,5,97,FB)
1020 /*
1030 ADARUN DB=xxx,SVC=yyy,DEVICE=zzzz
1040 /*
1050 LOGON N2OLIB
1060 N2OPARC4
1070 FIN
1080 /*
1090 /&
1100 * $$ EOJ
***** End of list *****
```

Catalog Capture

```

Program      MVSCAPT  Library N2OBATCH
0010 //NATCAPT JOB (ACCOUNTING),'CATALOG CAPTURE',CLASS=A,NOTIFY=&USERID
0020 //*****
0030 /** THIS IS SAMPLE CATALOG CAPTURE JCL
0040 /** THIS JOB SHOULD BE RENAMED TO NATCAPT
0050 //*****
0060 /** THE FIRST STEP (CAPTURE1) SHOULD RUN ON THE FUSER THAT
0070 /** IS BEING CAPTURED
0080 //CAPTURE1 EXEC PGM=NATBATCH
0090 //CMWK02 DD DSN=N2O.CAPTURE.DATA,DISP=(,CATLG,DELETE),
0100 //          UNIT=SYSDA,SPACE=(CYL,(100,100),RLSE),
0110 //          DCB=(RECFM=VB,LRECL=127,BLKSIZE=131)
0120 /**
0130 //CMPRINT DD SYSOUT=*
0140 //CMPRT01 DD SYSOUT=*
0150 //CMSYNIN DD *
0160 LOGON SYSTEM
0170 N2OCAPT1
0180 FIN
0190 /*
0200 //CMWK01 DD *
0210 &INPUT
0220 /*
0230 /** THE CAPTURE2 STEP SHOULD BE RUN WHERE N2O IS INSTALLED
0240 //CAPTURE2 EXEC PGM=NATBATCH
0250 //CMWK02 DD DSN=N2O.CAPTURE.DATA,DISP=(OLD,DELETE,DELETE)
0260 //CMPRINT DD SYSOUT=*
0270 //CMSYNIN DD *
0280 LOGON N2OLIB
0290 N2OCAPT2
0300 FIN
0310 /*
0320 //CMWK01 DD *
0330 &INPUT
0340 /*
0350 /**
***** End of list *****

```

Program	BSCAPT	Library	N2OBATCH
0010	/.	N2O	LOGON
0020	/CALL-PROCEDURE	NAME=\$TSOSAVE.DO.JV.T	
0030	/ASSIGN-SYSOUT	TO-FILE=N2O.OUT.LOAD.&(JV.ZEIT.T)	
0040	/MODIFY-JOB-OPTIONS	LOGGING=PARAMETERS(LISTING=YES)	
0050	/REMARK	*** EXECUTE N2OCAPT1 ***	
0060	/FILE	CAPTURE.DATA, LINK=W02, RECFORM=VB, RECSIZE=127, BLKSIZE=131	
0070	/FILE	CAPT1.INPUT, LINK=W01	
0080	/ASSIGN-SYSDTA	TO-FILE=*SYSCMD	
0090	/MODIFY-JOB-SWITCHES	ON=(4,5)	
0100	/START-PROGRAM	FROM-FILE=\$EDT	
0110	LS=132, PS=60, MENU=OFF		
0120	@WRITE	'N2O.CAPTURE.IPT.BATCH' OVERWRITE	
0130	@HALT		
0140	/MODIFY-JOB-SWITCHES	OFF=(4,5)	
0150	/ASSIGN-SYSIPT	TO-FILE=N2O.CAPTURE.IPT.BATCH	
0160	/MODIFY-JOB-SWITCHES	ON=(2)	
0170	/START-PROGRAM	FROM-FRIL=\$ADABAS.NATBATCH	
0180	LOGON	SYSTEM	
0190	N2OCAPT1		
0200	FIN		
0210	/REMARK	*** EXECUTE N2OCAPT2 ***	
0220	/SET-FILE-LINK	LINK-NAME=W01, FILE-NAME=N2O.ENV.DEF	
0230	/FILE	CAPTURE.DATA, LINK=W02	
0240	/SET-JOB-STEP		
0250	/ASSIGN-SYSIPT	TO-FILE=N2O.CAPTURE.IPT.BATCH	
0260	/START-PROGRAM	FROM-FILE=\$ADABAS.NATBATCH	
0270	LOGON	N2OLIB	
0280	N2OCAPT2		
0290	FIN		
0300	/ASSIGN-SYSIPT	TO-FILE=*PRIMARY	
0310	/DELETE-FILE	FILE-NAME=N2O.CAPTURE.IPT.BATCH,	
0320	/OPTION=DESTROY-ALL		
0330	/LOGOFF	NOSPOOL	
*****	End of list	*****	

Program	VMCAPT	Library	N2OBATCH
0010	/*	Execute	N2OCAPT1 */
0020	address		'COMMAND'
0030	'ERASE	N2OCAPT1	CMSYNIN A'
0040	'ERASE	CAPTURE	DATA A'
0050	'ERASE	N2OCAPT1	CMWKF01 A'
0060	'EXECIO	1 DISKW	N2OCAPT1 CMSYNIN A 1 F 80 (STRING LOGON SYSTEM'
0070	'EXECIO	1 DISKW	N2OCAPT1 CMSYNIN A 2 F 80 (STRING N2OCAPT1'
0080	'EXECIO	1 DISKW	N2OCAPT1 CMSYNIN A 3 F 80 (STRING FIN'
0090	'EXECIO	1 DISKW	N2OCAPT1 CMWKF01 A 1 F 80 (STRING &INPUT'
0100	'FILEDEF	*	CLEAR'
0110	'FILEDEF	CMWKF02	DISK CAPTURE DATA A RECFM VB LRECL 127 BLKSIZE 131'
0120	'FILEDEF	CMSYNIN	DISK N2OCAPT1 CMSYNIN A'
0130	'FILEDEF	CMWKF01	DISK N2OCAPT1 CMWKF01 A'
0140	'FILEDEF	CMPRINT	PRINTER'
0150	'EXEC	NAT	BATCH'
0160	'ERASE	N2OCAPT1	CMSYNIN A'
0170	/*	Execute	N2OCAPT2 */
0180	'ERASE	N2OCAPT2	CMSYNIN A'
0190	'ERASE	N2O	CMWKF01 A'
0200	'EXECIO	1 DISKW	N2O CMWKF01 A 1 F 80 (STRING &INPUT'
0210	'EXECIO	1 DISKW	N2OCAPT2 CMSYNIN A 1 F 80 (STRING LOGON N2OLIB'
0220	'EXECIO	1 DISKW	N2OCAPT2 CMSYNIN A 2 F 80 (STRING N2OCAPT2'
0230	'EXECIO	1 DISKW	N2OCAPT2 CMSYNIN A 3 F 80 (STRING FIN'
0240	'FILEDEF	*	CLEAR'
0250	'FILEDEF	CMWKF01	DISK N2O CMWKF01 A'
0260	'FILEDEF	CMWKF02	DISK CAPTURE DATA A'
0270	'FILEDEF	CMSYNIN	DISK N2OCAPT2 CMSYNIN A'
0280	'FILEDEF	CMPRINT	PRINTER'
0290	'EXEC	NAT	BATCH'
0300	'ERASE	N2OCAPT2	CMSYNIN A'
0310	'ERASE	N2O	CMWKF01 A'
0320	'ERASE	CAPTURE	DATA A'
0330	exit		
*****	End of list	*****	

```
Program      VSECAPT  Library N2OBATCH
0010 * $$ JOB JNM=N2OCAPT1,CLASS=A,USER=&USERID
0020 * $$ LST CLASS=A,LST=SYSLST
0030 // JOB N2OCAPT1
0040 /*
0050 * N2OCAPT1 - CAPTURE FUSER AND FDIC
0060 // DLBL CMWKF01,'N2O.CAPT1.INPUT'
0070 // EXTENT SYS001,,,,nnnnn,nnnnn
0080 // EXEC IDCAMS,SIZE=AUTO
0090     REPRO INFILE(SYSIPT ENV(RECFM(FB) RECSZ(80))) -
0100         OUTFILE(CMWKF01 ENV(RECFM(FB) RECSZ(80) BLKSZ(80)))
0110 &INPUT
0120 /*
0130 // ASSGN SYSIPT,SYSRDR
0140 // ASSGN SYS001,DISK,SHR
0150 // ASSGN SYS002,DISK,SHR
0160 // ASSGN SYS000,SYSRDR
0170 // ASSGN SYS009,SYSLST
0180 // DLBL CMWKF02,'N2O.CAPTURE.DATA'
0190 // EXTENT SYS002,,,,NNNNN,NNNNN
0200 // DLBL CMWKF01,'N2O.CAPT1.INPUT'
0210 // EXTENT SYS001,,,,nnnnn,nnnnn
0220 // EXEC NATBATCH
0230 BWORKD=(1,1,80,FB,2,2,131,VB)
0240 /*
0250 ADARUN DB=xxx,SVC=yyy,DEVICE=zzzz
0260 /*
0270 LOGON SYSTEM
0280 N2OCAPT1
0290 FIN
0300 /*
0310 * N2OCAPT2 - UPDATE MIGRATION FILE
0320 // DLBL CMWKF01,'N2O.CAPT2.INPUT'
0330 // EXTENT SYS001,,,,nnnnn,nnnnn
0340 // EXEC IDCAMS,SIZE=AUTO
0350     REPRO INFILE(SYSIPT ENV(RECFM(FB) RECSZ(80))) -
0360         OUTFILE(CMWKF01 ENV(RECFM(FB) RECSZ(80) BLKSZ(80)))
0370 &INPUT
0380 /*
0390 // ASSGN SYSIPT,SYSRDR
0400 // ASSGN SYS001,DISK,SHR
0410 // ASSGN SYS002,DISK,SHR
0420 // ASSGN SYS009,SYSLST
0430 // DLBL CMWKF01,'N2O.CAPT2.INPUT'
0440 // EXTENT SYS001,,,,nnnnn,nnnnn
0450 // DLBL CMWKF02,'N2O.CAPTURE.DATA'
0460 // EXTENT SYS002,,,,nnnnn,nnnnn
0470 // EXEC NATBATCH
0480 BWORKD=(1,1,80,FB,2,2,131,VB)
0490 /*
0500 ADARUN DB=xxx,SVC=yyy,DEVICE=zzzz
0510 /*
0520 LOGON SYSTEM
0530 N2OCAPT2
0540 FIN
0550 /*
0560 /&
0570 * $$ EOJ
***** End of list *****
```

Object Compare**Program MVSCOMPO Library N2OBATCH**

```

0010 //N2OCOMPO JOB (ACCOUNTING),'COMP OBJECT',CLASS=A,TIME=40,NOTIFY=&USERID
0020 /***
0030 /* THIS IS SAMPLE JCL FOR THE TOOLBOX OPTION FOR OBJECT COMPARE
0040 /* THIS JOB SHOULD BE RENAMED N2OCOMPO
0050 /***
0060 /* N2OCOMPO RUNS WHERE N2O IS INSTALLED
0070 /***
0080 //N2OCOMPO EXEC PGM=NATBATCH
0090 /*
0100 //CMPRINT DD SYSOUT=*
0110 //CMPRT02 DD SYSOUT=*
0120 //CMSYNIN DD *
0130 LOGON N2OLIB
0140 N2O3120B
0150 &INPUT
0160 FIN
0170 /*
0180 /*
***** End of list *****

```

Program BSCOMPO Library N2OBATCH

```

0010 /.N2O LOGON
0020 /CALL-PROCEDURE NAME=$TSOSAVE.DO.JV.T
0030 /ASSIGN-SYSOUT TO-FILE=N2O.OUT.LOAD.&(JV.ZEIT.T)
0040 /MODIFY-JOB-OPTIONS LOGGING=PARAMETERS (LISTING=YES)
0050 /REMARK *** EXECUTE SOURCE COMPARE ***
0060 /FILE N2O.COMPARE, LINK=P01
0070 /ASSIGN-SYSDTA TO-FILE=*SYSCMD
0080 /MODIFY-JOB-SWITCHES ON=(4,5)
0090 /START-PROGRAM FROM-FILE=$EDT
0100 LS=132,PS=60,MENU=OFF
0110 @WRITE 'N2O.COMPARE.IPT.BATCH' OVERWRITE
0120 @HALT
0130 /MODIFY-JOB-SWITCHES OFF=(4,5)
0140 /ASSIGN-SYSIPT TO-FILE=N2O.COMPARE.IPT.BATCH
0150 /MODIFY-JOB-SWITCHES ON=(2)
0160 /START-PROGRAM FROM-FRIL=$ADABAS.NATBATCH
0170 LOGON N2OLIB
0180 N2O3110B
0190 &INPUT
0200 FIN
0210 /ASSIGN-SYSIPT TO-FILE=*PRIMARY
0220 /DELETE-FILE FILE-NAME=N2O.COMPARE.IPT.BATCH,
0230 /OPTION=DESTROY-ALL
0240 /LOGOFF NOSPOOL
***** End of list *****

```

Program VMCOMPO Library N2OBATCH

```

0010 /* Execute Object compare */
0020 address 'COMMAND'
0030 'ERASE COMPOBJ CMSYNIN A'
0040 'EXECIO 1 DISKW COMPOBJ CMSYNIN A 1 F 80 (STRING LOGON N2OLIB'
0050 'EXECIO 1 DISKW COMPOBJ CMSYNIN A 2 F 80 (STRING N2O3120B'
0060 'EXECIO 1 DISKW COMPOBJ CMSYNIN A 3 F 80 (STRING &INPUT'
0070 'EXECIO 1 DISKW COMPOBJ CMSYNIN A 4 F 80 (STRING FIN'
0080 'FILEDEF * CLEAR'
0090 'FILEDEF CMSYNIN DISK COMPOBJ CMSYNIN A'
0100 'FILEDEF CMPRINT PRINTER'
0110 'FILEDEF CMPRT01 PRINTER'
0120 'EXEC NAT BATCH'
0130 'ERASE COMPOBJ CMSYNIN A'
0140 exit
***** End of list *****

```

```
Program          VSECOMPO Library N2OBATCH
0010 * $$ JOB JNM=N2OCOMPO,CLASS=A,USER=&USERID
0020 * $$ LST CLASS=A,LST=SYSLST
0030 * $$ LST CLASS=A,LST=02E,DISP=K,JSEP=0
0040 // JOB N2OCOMPO
0050 * N2OCOMPO - COMPARE NATURAL OBJECT CODE
0060 // ASSGN SYSIPT,SYSRDR
0070 // ASSGN SYS001,01E
0080 // ASSGN SYS002,02E
0090 // EXEC NATBATCH
0100 /*
0110 ADARUN DB=xxx,SVC=yyy,DEVICE=zzzz
0120 /*
0130 LOGON N2OLIB
0140 N2O3120B
0150 &INPUT
0160 FIN
0170 /*
0180 /&
0190 * $$ EOJ
***** End of list *****
```

Source Compare - remote environments

```
Program          MVSCOMPR Library N2OBATCH
0010 //N2OCMPR JOB 'REMOTE SOURCE COMPARE' MSGLEVEL=1,
0020 //          CLASS=C,MSGCLASS=X,REGION=4M,NOTIFY=&SYSUID
0030 //*
0040 //***
0050 //* THIS IS SAMPLE JCL FOR N2O SOURCE COMPARE BETWEEN TWO REMOTE
0060 //* ENVIRONMENTS
0070 //* This step must be executed where N2O is installed
0080 //***
0090 //GCPARM EXEC PGM=NATBATCH
0100 //CMPRINT DD SYSOUT=*
0110 //CMPRT01 DD SYSOUT=*
0120 //CMPRT02 DD SYSOUT=*
0130 //CMWK01 DD DSN=N2O.SRCCR.PARMA1,DISP=(NEW,PASS,DELETE),
0140 //          DCB=(RECFM=FB,LRECL=80,BLKSIZE=80),
0150 //          UNIT=SYSDA,SPACE=(TRK,(1,1))
0160 //CMWK02 DD DSN=N2O.SRCCR.PARMA2,DISP=(NEW,PASS,DELETE),
0170 //          DCB=(RECFM=FB,LRECL=80,BLKSIZE=80),
0180 //          UNIT=SYSDA,SPACE=(TRK,(1,1))
0190 //CMSYNIN DD *
0200 LOGON N2OLIB
0210 N2O3110B
0220 &INPUT
0230 FIN
0240 /*
0250 //*
0260 //* This step must be executed on base environment
0270 //*
0280 //RRTM1 EXEC PGM=NATBATCH
0290 //CMPRINT DD SYSOUT=*
0300 //CMPRT01 DD SYSOUT=*
0310 //CMPRT02 DD SYSOUT=*
0320 //CMWK01 DD DSN=N2O.SRCCR.PARMA1,DISP=(OLD,DELETE,DELETE)
0330 //CMWK02 DD DSN=N2O.SRCCR.PARMB1,DISP=(NEW,PASS,DELETE),
0340 //          DCB=(RECFM=FB,LRECL=189,BLKSIZE=189),
0350 //          UNIT=SYSDA,SPACE=(TRK,(1,1))
0360 //CMWK03 DD DSN=N2O.SRCCR.OUTPUT1,DISP=(NEW,PASS,DELETE),
0370 //          DCB=(RECFM=FB,LRECL=133,BLKSIZE=133),
0380 //          UNIT=SYSDA,SPACE=(TRK,(1,1))
0390 //CMSYNIN DD *
0400 LOGON SYSTEM
0410 N2O3110C
0420 FIN
0430 /*
0440 //*
```

```

0450 /* This step must be executed on compare environment
0460 /*
0470 //RRTM2      EXEC PGM=NATBATCH
0480 //CMPRINT DD  SYSOUT=*
0490 //CMPRT01 DD  SYSOUT=*
0500 //CMPRT02 DD  SYSOUT=*
0510 //CMWKF01 DD  DSN=N2O.SRCCR.PARMA2,DISP=(OLD,DELETE,DELETE)
0520 //CMWKF02 DD  DSN=N2O.SRCCR.PARMB2,DISP=(NEW,PASS,DELETE),
0530 //          DCB=(RECFM=FB,LRECL=189,BLKSIZE=189),
0540 //          UNIT=SYSDA,SPACE=(TRK,(1,1))
0550 //CMWKF03 DD  DSN=N2O.SRCCR.OUTPT2,DISP=(NEW,PASS,DELETE),
0560 //          DCB=(RECFM=FB,LRECL=133,BLKSIZE=133),
0570 //          UNIT=SYSDA,SPACE=(TRK,(1,1))
0580 //CMSYNIN DD  *
0590 LOGON SYSTEM
0600 N2O3110C
0610 FIN
0620 /*
0630 /*
0640 /* This step must be executed where N2O is installed
0650 /*
0660 //COMPW      EXEC PGM=NATBATCH
0670 //CMPRINT DD  SYSOUT=*
0680 //CMPRT01 DD  SYSOUT=*
0690 //CMPRT02 DD  SYSOUT=*
0700 //CMWKF01 DD  DSN=N2O.SRCCR.PARMB1,DISP=(OLD,DELETE,DELETE)
0710 //CMWKF02 DD  DSN=N2O.SRCCR.OUTPT1,DISP=(OLD,DELETE,DELETE)
0720 //CMWKF03 DD  DSN=N2O.SRCCR.PARMB2,DISP=(OLD,DELETE,DELETE)
0730 //CMWKF04 DD  DSN=N2O.SRCCR.OUTPT2,DISP=(OLD,DELETE,DELETE)
0740 //CMSYNIN DD  *
0750 LOGON N2OLIB
0760 N2O3110D
0770 FIN
0780 /*
0790 //*****
***** End of list *****

```

Program BSCOMPR Library N2OBATCH

```

0010 /.N2O LOGON
0020 /CALL-PROCEDURE NAME= TSOSAVE.DO.JV.T
0030 /ASSIGN-SYSOUT TO-FILE=N2O.OUT.LOAD.&(JV.ZEIT.T)
0040 /MODIFY-JOB-OPTIONS LOGGING=PARAMETERS (LISTING=YES)
0050 /REMARK *** EXECUTE SOURCE COMPARE ***
0060 /FILE N2O.COMPARE,LINK=P01
0070 /FILE N2OCOMPA.PARM,LINK=W01,RECFORM=FB,RECSIZE=80,BLKSIZE=80
0080 /FILE N2OCOMPB.PARM,LINK=W02,RECFORM=FB,RECSIZE=80,BLKSIZE=80
0090 /ASSIGN-SYSDTA TO-FILE=*SYSCMD
0100 /MODIFY-JOB-SWITCHES ON=(4,5)
0110 /START-PROGRAM FROM-FILE=$EDT
0120 LS=132,PS=60,MENU=OFF
0130 @WRITE 'N2O.COMPARE.IPT.BATCH' OVERWRITE
0140 @HALT
0150 /MODIFY-JOB-SWITCHES OFF=(4,5)
0160 /ASSIGN-SYSIPT TO FILE=N2O.COMPARE.IPT.BATCH
0170 /MODIFY-JOB-SWITCHES ON=(2)
0180 /START-PROGRAM FROM-FRIL=$ADABAS.NATBATCH
0190 LOGON N2OLIB
0200 N2O3110B
0210 &INPUT
0220 FIN
0230 REMARK *** READ BASE ENVIRONMENT ***
0240 /FILE N2OCOMPA.PARM,LINK=W01
0250 /FILE N2OCOMPA.PARM2,LINK=W02,RECFROM=FB,RECSIZE=189,BLKSIZE=189
0260 /FILE N2OCOMPA.OUT,LINK=W03,RECFROM=FB,RECSIZE=133,BLKSIZE=133
0270 /SET-JOB-STEP
0280 /ASSIGN-SYSIPT TO-FILE=N2O.COMPARE.IPT.BATCH
0290 /START-PROGRAM FROM-FILE=$ADABAS.NATBATCH
0300 LOGON SYSTEM
0310 N2O3110C
0320 FIN

```

```
0330 REMARK *** READ COMPARE ENVIRONMENT ***
0340 /FILE N2OCOMPB.PARM, LINK=W01
0350 /FILE N2OCOMPB.PARM2, LINK=W02, RECFROM=FB, RECSIZE=189, BLKSIZE=189
0360 /FILE N2OCOMPB.OUT, LINK=W03, RECFROM=FB, RECSIZE=133, BLKSIZE=133
0370 /SET-JOB-STEP
0380 /ASSIGN-SYSIPT TO-FILE=N2O.COMPARE.IPT.BATCH
0390 /START-PROGRAM FROM-FILE=$ADABAS.NATBATCH
0400 LOGON SYSTEM
0410 N2O3110C
0420 FIN
0430 REMARK *** COMPARE BASE AND COMPARE ENVIRONMENTS ***
0440 /FILE N2OCOMPA.PARM2, LINK=W01
0450 /FILE N2OCOMPA.OUT, LINK=W02
0460 /FILE N2OCOMPB.PARM2, LINK=W03
0470 /FILE N2OCOMPB.OUT, LINK=W04
0480 /SET-JOB-STEP
0490 /ASSIGN-SYSIPT TO-FILE=N2O.COMPARE.IPT.BATCH
0500 /START-PROGRAM FROM-FILE=$ADABAS.NATBATCH
0510 LOGON N2OLIB
0520 N2O3110D
0530 FIN
0540 /ASSIGN-SYSIPT TO-FILE=*PRIMARY
0550 /DELETE-FILE FILE-NAME=N2O.COMPARE.IPT.BATCH,
0560 /OPTION=DESTROY-ALL
0570 /LOGOFF NOSPOOL
***** End of list *****
```

Program VMCOMPR Library N2OBATCH

```
0010 /* Execute Remote Source compare */
0020 address 'COMMAND'
0030 'ERASE COMPSRCA CMSYNIN A'
0040 'EXECIO 1 DISKW COMPSRC CMSYNIN A 1 F 80 (STRING LOGON N2OLIB'
0050 'EXECIO 1 DISKW COMPSRC CMSYNIN A 2 F 80 (STRING N2O3110B'
0060 'EXECIO 1 DISKW COMPSRC CMSYNIN A 3 F 80 (STRING &INPUT'
0070 'EXECIO 1 DISKW COMPSRC CMSYNIN A 4 F 80 (STRING FIN'
0080 'FILEDEF * CLEAR'
0090 'FILEDEF CMWKF01 COMP PARMA A RECFM VB LRECL 80 BLKSIZE 80'
0100 'FILEDEF CMWKF02 COMP PARMB A RECFM VB LRECL 80 BLKSIZE 80'
0110 'FILEDEF CMSYNIN DISK COMPSRCA CMSYNIN A'
0120 'FILEDEF CMPRINT PRINTER'
0130 'FILEDEF CMPRT01 PRINTER'
0140 'EXEC NAT BATCH'
0150 'ERASE COMPSRCA CMSYNIN A'
0160 /* Execute read BASE Environment */
0170 'ERASE COMPSRCB CMSYNIN A'
0180 'EXECIO 1 DISKW COMPSRCB CMSYNIN A 1 F 80 (STRING LOGON N2OLIB'
0190 'EXECIO 1 DISKW COMPSRCB CMSYNIN A 2 F 80 (STRING N2O3110C'
0200 'EXECIO 1 DISKW COMPSRCB CMSYNIN A 3 F 80 (STRING FIN'
0210 'FILEDEF * CLEAR'
0220 'FILEDEF CMWKF01 COMP PARMA A'
0230 'FILEDEF CMWKF02 COMP PARMA2 A RECFM VB LRECL 189 BLKSIZE 189'
0240 'FILEDEF CMWKF03 COMP OUTPUTA A RECFM VB LRECL 133 BLKSIZE 133'
0250 'FILEDEF CMSYNIN DISK COMPSRCB CMSYNIN A'
0260 'FILEDEF CMPRINT PRINTER'
0270 'FILEDEF CMPRT01 PRINTER'
0280 'EXEC NAT BATCH'
0290 'ERASE COMPSRCB CMSYNIN A'
0300 'ERASE COMP PARMA A'
0310 /* Execute read COMPARE Environment */
0320 'ERASE COMPSRCC CMSYNIN A'
0330 'EXECIO 1 DISKW COMPSRCC CMSYNIN A 1 F 80 (STRING LOGON N2OLIB'
0340 'EXECIO 1 DISKW COMPSRCC CMSYNIN A 2 F 80 (STRING N2O3110C'
0350 'EXECIO 1 DISKW COMPSRCC CMSYNIN A 3 F 80 (STRING FIN'
0360 'FILEDEF * CLEAR'
0370 'FILEDEF CMWKF01 COMP PARMB A'
0380 'FILEDEF CMWKF02 COMP PARMB2 A RECFM VB LRECL 189 BLKSIZE 189'
0390 'FILEDEF CMWKF03 COMP OUTPUTB A RECFM VB LRECL 133 BLKSIZE 133'
0400 'FILEDEF CMSYNIN DISK COMPSRCC CMSYNIN A'
0410 'FILEDEF CMPRINT PRINTER'
0420 'FILEDEF CMPRT01 PRINTER'
```

```

0430 'EXEC NAT BATCH'
0440 'ERASE COMPSRCC CMSYNIN A'
0450 'ERASE COMP PARMB A'
0460 /* Execute compare BASE and COMPARE Environment */
0470 'ERASE COMPSRCD CMSYNIN A'
0480 'EXECIO 1 DISKW COMPSRCD CMSYNIN A 1 F 80 (STRING LOGON N2OLIB'
0490 'EXECIO 1 DISKW COMPSRCD CMSYNIN A 2 F 80 (STRING N2O3110D'
0500 'EXECIO 1 DISKW COMPSRCD CMSYNIN A 3 F 80 (STRING FIN'
0510 'FILEDEF * CLEAR'
0520 'FILEDEF CMWKF01 COMP PARMA2 A'
0530 'FILEDEF CMWKF02 COMP OUTPUTA A'
0540 'FILEDEF CMWKF03 COMP PARMB2 A'
0550 'FILEDEF CMWKF04 COMP OUTPUTB A'
0560 'FILEDEF CMSYNIN DISK COMPSRCD CMSYNIN A'
0570 'FILEDEF CMPRINT PRINTER'
0580 'FILEDEF CMPRT01 PRINTER'
0590 'EXEC NAT BATCH'
0600 'ERASE COMPSRCD CMSYNIN A'
0610 'ERASE CMWKF01 COMP PARMA2 A'
0620 'ERASE CMWKF02 COMP OUTPUTA A'
0630 'ERASE CMWKF03 COMP PARMB2 A'
0640 'ERASE CMWKF04 COMP OUTPUTB A'
0650 exit
***** End of list *****

```

Program VSECOMPR Library N2OBATCH

```

0010 * JOB JNM=N2OCOMPR,CLASS=A,USER=&USERID
0020 * LST CLASS=A,LST=SYSLST
0030 // JOB N2OCOMPR
0040 * N2O3110B - VERIFY INPUT PARMS
0050 // ASSGN SYS001,DISK,SHR
0060 // ASSGN SYS002,DISK,SHR
0070 // ASSGN SYS009,SYSLST
0080 // DLBL CMWKF01,'N2OCOMPA.PARM'
0090 // EXTENT SYS001,, ,nnnnn,nnnnn
0100 // DLBL CMWKF02,'N2OCOMP.B.PARM'
0110 // EXTENT SYS002,, ,nnnnn,nnnnn
0120 // EXEC NATBATCH
0130 BWORKD=(1,1,80,FB,2,2,80,FB)
0140 /*
0150 ADARUN DB=XXX,SVC=YYY,DEVICE=ZZZZ
0160 /*
0170 N2OLIB,BATCH,BATCH
0180 N2O3110B
0190 &INPUT
0200 FIN
0210 /*
0220 * N2O3110C - READ BASE ENVIRONMENT
0230 // ASSGN SYS001,DISK,SHR
0240 // ASSGN SYS002,DISK,SHR
0250 // ASSGN SYS003,DISK,SHR
0260 // ASSGN SYS009,SYSLST
0270 // DLBL CMWKF01,'N2OCOMPA.PARM'
0280 // EXTENT SYS001,, ,nnnnn,nnnnn
0290 // DLBL CMWKF02,'N2OCOMPA.PARM2'
0300 // EXTENT SYS002,, ,nnnnn,nnnnn
0310 // DLBL CMWKF03,'N2OCOMPA.OUTPUT'
0320 // EXTENT SYS003,, ,nnnnn,nnnnn
0330 // EXEC NATBATCH
0340 BWORKD=(1,1,80,FB,2,2,189,FB,3,3,133,FB)
0350 /*
0360 ADARUN DB=xxx,SVC=yyy,DEVICE=zzzz
0370 /*
0380 SYSTEM,BATCH,BATCH
0390 N2O3110C
0400 FIN
0410 /*
0420 * N2O3110C - READ COMPARE ENVIRONMENT
0430 // ASSGN SYS001,DISK,SHR
0440 // ASSGN SYS002,DISK,SHR

```

```
0450 // ASSGN SYS003,DISK,SHR
0460 // ASSGN SYS009,SYSLST
0470 // DLBL CMWKF01,'N2OCOMP.B.PARM'
0480 // EXTENT SYS001,, ,nnnnn,nnnnn
0490 // DLBL CMWKF02,'N2OCOMP.B.PARM2'
0500 // EXTENT SYS002,, ,nnnnn,nnnnn
0510 // DLBL CMWKF03,'N2OCOMP.B.OUTP'
0520 // EXTENT SYS003,, ,nnnnn,nnnnn
0530 // EXEC NATBATCH
0540 BWORKD=(1,1,80,FB,2,2,189,FB,3,3,133,FB)
0550 /*
0560 ADARUN DB=xxx,SVC=yyy,DEVICE=zzzz
0570 /*
0580 SYSTEM,BATCH,BATCH
0590 N2O3110C
0600 FIN
0610 /*
0620 * N2O3110D - COMPARE BASE AND COMPARE ENVIRONMENT
0630 // ASSGN SYS001,DISK,SHR
0640 // ASSGN SYS002,DISK,SHR
0650 // ASSGN SYS003,DISK,SHR
0660 // ASSGN SYS004,DISK,SHR
0670 // ASSGN SYS009,SYSLST
0680 // DLBL CMWKF02,'N2OCOMP.A.PARM2'
0690 // EXTENT SYS002,, ,nnnnn,nnnnn
0700 // DLBL CMWKF03,'N2OCOMP.A.OUTP'
0710 // EXTENT SYS003,, ,nnnnn,nnnnn
0720 // DLBL CMWKF02,'N2OCOMP.B.PARM2'
0730 // EXTENT SYS002,, ,nnnnn,nnnnn
0740 // DLBL CMWKF03,'N2OCOMP.B.OUTP'
0750 // EXTENT SYS003,, ,nnnnn,nnnnn
0760 // EXEC NATBATCH
0770 BWORKD=(1,1,189,FB,2,2,133,FB,3,3,189,FB,4,4,133,FB)
0780 /*
0790 ADARUN DB=xxx,SVC=yyy,DEVICE=zzzz
0800 /*
0810 N2OLIB,BATCH,BATCH
0820 N2O3110D
0830 FIN
0840 /*
0850 /&
0860 * EOJ
***** End of list *****
```

Source Compare – local environments

Program MVSCOMPS Library N2OBATCH

```
0010 //N2OCOMPS JOB (ACCOUNTING),'COMP SOURCE',CLASS=A,TIME=40,NOTIFY=&USERID
0020 /***
0030 /* THIS IS SAMPLE JCL FOR THE TOOLBOX OPTION SOURCE COMPARE
0040 /* THIS JOB SHOULD BE RENAMED N2OCOMPS
0050 /***
0060 /* N2OCOMPS SHOULD BE RUN WHERE N2O IS INSTALLED
0070 //N2OCOMPS EXEC PGM=NATBATCH
0080 /*
0090 //CMPRINT DD SYSOUT=*
0100 //CMPRT01 DD SYSOUT=*
0110 //CMPRT02 DD SYSOUT=*
0120 //CMSYNIN DD *
0130 LOGON N2OLIB
0140 N2O3110B
0150 &INPUT
0160 FIN
0170 /*
0180 /***
***** End of list *****
```



```

Program      BSCOMPS  Library N2OBATCH
0010 /N2O LOGON
0020 /CALL-PROCEDURE NAME=$TSOSAVE.DO.JV.T
0030 /ASSIGN-SYSOUT TO-FILE=N2O.OUT.LOAD.&(JV.ZEIT.T)
0040 /MODIFY-JOB-OPTIONS LOGGING=PARAMETERS(LISTING=YES)
0050 /REMARK *** EXECUTE OBJECT COMPARE ***
0060 /FILE N2O.COMPOBJ, LINK=P01
0070 /FILE N2O.COMPARE, LINK=P02
0080 /ASSIGN-SYSDTA TO-FILE=*SYSCMD
0090 /MODIFY-JOB-SWITCHES ON=(4,5)
0100 /START-PROGRAM FROM-FILE=$EDT
0110 LS=132, PS=60, MENU=OFF
0120 @WRITE 'N2O.COMPARE.IPT.BATCH' OVERWRITE
0130 @HALT
0140 /MODIFY-JOB-SWITCHES OFF=(4,5)
0150 /ASSIGN-SYSIPT TO-FILE=N2O.COMPARE.IPT.BATCH
0160 /MODIFY-JOB-SWITCHES ON=(2)
0170 /START-PROGRAM FROM-FRIL=$ADABAS.NATBATCH
0180 LOGON N2OLIB
0190 N2O3110B
0200 &INPUT
0210 FIN
0220 /ASSIGN-SYSIPT TO-FILE=*PRIMARY
0230 /DELETE-FILE FILE-NAME=N2O.COMPARE.IPT.BATCH,
0240 /OPTION=DESTROY-ALL
0250 /LOGOFF NOSPOOL
***** End of list *****

```

```

Program      VMCOMPS  Library N2OBATCH
0010 /* Execute Source compare */
0020 address 'COMMAND'
0030 'ERASE COMPSRC CMSYNIN A'
0040 'EXECIO 1 DISKW COMPSRC CMSYNIN A 1 F 80 (STRING LOGON N2OLIB'
0050 'EXECIO 1 DISKW COMPSRC CMSYNIN A 2 F 80 (STRING N2O3110B'
0060 'EXECIO 1 DISKW COMPSRC CMSYNIN A 3 F 80 (STRING &INPUT'
0070 'EXECIO 1 DISKW COMPSRC CMSYNIN A 4 F 80 (STRING FIN'
0080 'FILEDEF * CLEAR'
0090 'FILEDEF CMSYNIN DISK COMPSRC CMSYNIN A'
0100 'FILEDEF CMPRINT PRINTER'
0110 'FILEDEF CMPRT01 PRINTER'
0120 'FILEDEF CMPRT02 PRINTER'
0130 'EXEC NAT BATCH'
0140 'ERASE COMPSRC CMSYNIN A'
0150 exit
***** End of list *****

```

```

Program      VSECOMPS Library N2OBATCH
0010 * $$ JOB JNM=N2OCOMPS, CLASS=A, USER=&USERID
0020 * $$ LST CLASS=A, LST=SYSLST
0030 * $$ LST CLASS=A, LST=02E, DISP=K, JSEP=0
0040 // JOB N2OCOMPS
0050 * N2OCOMPS - COMPARE NATURAL SOURCE
0060 // ASSGN SYSIPT, SYSRDR
0070 // ASSGN SYS001, 01E
0080 // ASSGN SYS002, 02E
0090 // ASSGN SYS009, SYSLST
0100 // EXEC NATBATCH
0110 /*
0120 ADARUN DB=xxx, SVC=yyy, DEVICE=zzzz
0130 /*
0140 LOGON N2OLIB
0150 N2O3110B
0160 &INPUT
0170 FIN
0180 /*
0190 /&
0200 * $$ EOJ
***** End of list *****

```

Deferred Moves

Program MVSDMOVE Library N2OBATCH

```
0010 //N2ODMOVE JOB (20000),'DEFERRED MOVE',CLASS=A,NOTIFY=&USERID
0020 /***
0030 /** THIS IS SAMPLE JCL FOR THE PROCESSING OF DEFERRED MOVES
0040 /***
0050 /** N2ODSEL RUNS WHERE N2O IS INSTALLED
0060 /***
0070 //N2ODSEL EXEC PGM=NATBATCH
0080 //CMWK02 DD DSN=N2O.DEFER,DISP=(NEW,PASS,DELETE),
0090 // DCB=(RECFM=VB,LRECL=3147,BLKSIZE=3151),
0100 // UNIT=SYSDA,SPACE=(TRK,(12,12))
0110 //CMPRINT DD SYSOUT=*
0120 //CMSYNIN DD *
0130 LOGON N2OLIB
0140 N2ODSEL
0150 FIN
0160 /*
0170 //CMWK01 DD *
0180 N2ODSEL ALL
0190 /*
0200 /***
0210 /** N2ODELT RUNS ON THE FROM (SOURCE) ENVIRONMENT FOR THE EVENT(S)
0220 /***
0230 //N2ODELT EXEC PGM=NATBATCH
0240 //CMWK01 DD DSN=N2O.DEFER,DISP=(OLD,DELETE,DELETE)
0250 //CMWK02 DD DSN=N2O.DACKN,DISP=(NEW,PASS,DELETE),
0260 // DCB=(RECFM=VB,LRECL=3147,BLKSIZE=3151),
0270 // UNIT=SYSDA,SPACE=(TRK,(12,12))
0280 //CMPRINT DD SYSOUT=*
0290 //CMSYNIN DD *
0300 LOGON SYSTEM
0310 N2ODELT
0320 FIN
0330 /*
0340 /***
0350 /** N2ODACKN RUNS WHERE N2O IS INSTALLED
0360 /***
0370 //N2ODACKN EXEC PGM=NATBATCH
0380 //CMWK01 DD DSN=N2O.DACKN,DISP=(OLD,DELETE,DELETE)
0390 //CMPRINT DD SYSOUT=*
0400 //CMSYNIN DD *
0410 LOGON N2OLIB
0420 N2ODACKN
0430 FIN
0440 /*
0450 /**
***** End of list *****
```

```

Program      BSDMOVE  Library N2OBATCH
0010 /N2O LOGON
0020 /CALL-PROCEDURE NAME=$TSOSAVE.DO.JV.T
0030 /ASSIGN-SYSOUT TO-FILE=N2O.OUT.LOAD.&(JV.ZEIT.T)
0040 /MODIFY-JOB-OPTIONS LOGGING=PARAMETERS(LISTING=YES)
0050 /REMARK *** EXECUTE N2ODSEL ***
0060 /SET-FILE-LINK LINK-NAME=W01,FILE-NAME=N2O.SELECT
0070 /FILE N2O.DEFER,LINK=W02,RECFORM=(VB),RECSIZE=(3147),BLKSIZE=(3151)
0080 /ASSIGN-SYSDTA TO-FILE=*SYSCMD
0090 /MODIFY-JOB-SWITCHES ON=(4,5)
0100 /START-PROGRAM FROM-FILE=$EDT
0110 LS=132,PS=60,MENU=OFF
0120 @WRITE 'N2O.DMOVE.IPT.BATCH' OVERWRITE
0130 @HALT
0140 /MODIFY-JOB-SWITCHES OFF=(4,5)
0150 /ASSIGN-SYSIPT TO-FILE=N2O.MOVE.IPT.BATCH
0160 /MODIFY-JOB-SWITCHES ON=(2)
0170 /START-PROGRAM FROM-FRIL=$ADABAS.NATBATCH
0180 LOGON N2OLIB
0190 N2ODSEL
0200 FIN
0210 /REMARK *** EXECUTE N2ODELT ***
0220 /FILE N2O.DEFER,LINK=W01,BLKSIZE=(STD,2)
0230 /FILE N2O.DACKN,LINK=W02,BLKSIZE=(STD,2)
0240 /SET-JOB-STEP
0250 /ASSIGN-SYSIPT TO-FILE=N2O.DMOVE.IPT.BATCH
0260 /START-PROGRAM FROM-FILE=$ADABAS.NATBATCH
0270 LOGON SYSTEM
0280 N2ODELT
0290 FIN
0300 /REMARK *** EXECUTE N2ODACKN ***
0310 /FILE N2O.DACKN,LINK=W01,RECFORM=VB,RECSIZE=3147,BLKSIZE=3151
0320 /SET-JOB-STEP
0330 /ASSIGN-SYSIPT TO-FILE=N2O.DMOVE.IPT.BATCH
0340 /START-PROGRAM FROM-FILE=$ADABAS.NATBATCH
0350 LOGON N2OLIB
0360 N2ODACKN
0370 FIN
0380 /ASSIGN-SYSIPT TO-FILE=*PRIMARY
0390 /DELETE-FILE FILE-NAME=N2O.DMOVE.IPT.BATCH,
0400 /OPTION=DESTROY-ALL
0410 /LOGOFF NOSPOOL
***** End of list *****

```

```
Program      VMDMOVE  Library N2OBATCH
0010 /* Execute N2ODSEL */
0020 address 'COMMAND'
0030 'ERASE N2ODSEL CMWKF01 A'
0040 'ERASE N2ODSEL CMSYNIN A'
0050 'EXECIO 1 DISKW N2O CMWKF01 A 1 F 80 (STRING N2ODSEL ALL'
0060 'EXECIO 1 DISKW N2ODSEL CMSYNIN A 1 F 80 (STRING LOGON N2OLIB'
0070 'EXECIO 1 DISKW N2ODSEL CMSYNIN A 2 F 80 (STRING N2ODSEL'
0080 'EXECIO 1 DISKW N2ODSEL CMSYNIN A 3 F 80 (STRING FIN'
0090 'FILEDEF * CLEAR'
0100 'FILEDEF CMWKF01 DISK N2ODSEL CMWKF01 A'
0110 'FILEDEF CMWKF02 DISK N2O DEFER A (RECFM VB LRECL 3147 BLKSIZE 3151'
0120 'FILEDEF CMSYNIN DISK N2ODSEL CMSYNIN A'
0130 'FILEDEF CPRINT PRINTER'
0140 'EXEC NAT BATCH'
0150 'ERASE N2ODSEL CMSYNIN A'
0160 /* Execute N2ODELT */
0170 'ERASE N2ODELT CMSYNIN A'
0180 'EXECIO 1 DISKW N2ODELT CMSYNIN A 1 F 80 (STRING LOGON SYSTEM'
0190 'EXECIO 1 DISKW N2ODELT CMSYNIN A 2 F 80 (STRING N2ODELT'
0200 'EXECIO 1 DISKW N2ODELT CMSYNIN A 3 F 80 (STRING FIN'
0210 'FILEDEF * CLEAR'
0220 'FILEDEF CMWKF01 DISK N2O DEFER A'
0230 'FILEDEF CMWKF02 DISK N2O DACKN A (RECFM VB LRECL 3147 BLKSIZE 3151'
0240 'FILEDEF CMSYNIN DISK N2ODELT CMSYNIN A'
0250 'FILEDEF CPRINT PRINTER'
0260 'EXEC NAT BATCH'
0270 'ERASE N2ODELT CMSYNIN A'
0280 'ERASE N2O DEFER A'
0290 /* Execute N2ODACKN */
0300 'ERASE N2ODACKN CMSYNIN A'
0310 'EXECIO 1 DISKW N2ODACKN CMSYNIN A 1 F 80 (STRING LOGON N2OLIB'
0320 'EXECIO 1 DISKW N2ODACKN CMSYNIN A 2 F 80 (STRING N2ODACKN'
0330 'EXECIO 1 DISKW N2ODACKN CMSYNIN A 3 F 80 (STRING FIN'
0340 'FILEDEF * CLEAR'
0350 'FILEDEF CMWKF01 N2O DACKN A'
0360 'FILEDEF CMSYNIN DISK N2ODACKN CMSYNIN A'
0370 'FILEDEF CPRINT PRINTER'
0380 'EXEC NAT BATCH'
0390 'ERASE N2ODACKN CMSYNIN A'
0400 'ERASE N2O DACKN A'
0410 exit
***** End of list *****
```

```

Program      VSEDMOVE Library N2OBATCH
0010 * $$ JOB JNM=NATMOVE,CLASS=A,USER=&USERID
0020 * $$ LST CLASS=A,LST=SYSLST
0030 // JOB NATMOVE
0040 // DLBL CMWKF01,'N2ODSEL.INPUT.CARDS'
0050 // EXTENT SYS001,,,,nnnnn,nnnnn
0060 // EXEC IDCAMS,SIZE=AUTO
0070 REPRO INFILE(SYSIPT ENV(RECFM(FB) RECSZ(80))) -
0080          OUTFILE(CMWKF01 ENV(RECFM(FB) RECSZ(80) BLKSZ(80)))
0090 N2ODSEL ALL
0100 /*
0110 * N2ODSEL - SELECT LIST OF PROGRAMS TO BE DELETED
0120 // ASSGN SYSIPT,SYSRDR
0130 // ASSGN SYS001,DISK,SHR
0140 // ASSGN SYS002,DISK,SHR
0150 // ASSGN SYS009,SYSLST
0160 // DLBL CMWKF01,'N2ODSEL.INPUT.CARDS'
0170 // EXTENT SYS001,...
0180 // DLBL CMWKF02,'N2O.DEFER'
0190 // EXTENT SYS002,...
0200 // EXEC NATBATCH
0210 BWORKD=(1,1,80,FB,2,2,3140,VB)
0220 /*
0230 ADARUN DB=xxx,SVC=yyy,DEVICE=zzzz
0240 /*
0250 LOGON N2OLIB
0260 N2ODSEL
0270 FIN
0280 /*
0290 * N2ODELT - DELETE PROGRAMS IN FROM ENV
0300 // ASSGN SYS001,DISK,SHR
0310 // ASSGN SYS002,DISK,SHR
0320 // ASSGN SYS009,SYSLST
0330 // DLBL CMWKF01,'N2O.DEFER'
0340 // EXTENT SYS001,...
0350 // DLBL CMWKF02,'N2O.DACKN'
0360 // EXTENT SYS002,...
0370 // EXEC NATBATCH
0380 BWORKD=(1,1,3151,VB,2,2,3151,VB)
0390 /*
0400 ADARUN DB=xxx,SVC=yyy,DEVICE=zzzz
0410 /*
0420 LOGON SYSTEM
0430 N2ODELT
0440 FIN
0450 /*
0460 * N2ODACKN - ACKNOWLEDGEMENT OF MOVE COMPLETION
0470 // ASSGN SYS001,DISK,SHR
0480 // ASSGN SYS009,SYSLST
0490 // DLBL CMWKF01,'N2O.DACKN'
0500 // EXTENT SYS001,...
0510 // EXEC NATBATCH
0520 BWORKD=(1,1,3151,VB)
0530 /*
0540 ADARUN DB=xxx,SVC=yyy,DEVICE=zzzz
0550 /*
0560 LOGON N2OLIB
0570 N2ODACKN
0580 FIN
0590 /*
0600 /&
0610 * $$ EOJ
***** End of list *****

```

Emergency Recovery in Batch

```
Program      MVSER      Library N2OBATCH
0010 //N2OER JOB (20100),'EXECUTE N2OER',CLASS=A,NOTIFY=&USERID
0020 /***
0030 /** THIS IS SAMPLE JCL FOR EMERGENCY RECOVERY IN BATCH
0040 /***
0050 /** RECOVERY RUNS
0060 /***
0070 //RECOVERY EXEC PGM=NATBATCH
0080 //CMWKF02 DD DSN=N2O.3GL.OBJECT,DISP=SHR
0090 //CMPRINT DD SYSOUT=*
0100 //CMSYNIN DD *
0110 LOGON SYSTEM
0120 N2OER
0130 &INPUT
0140 FIN
0150 /*
0160 /**
***** End of list *****
```

```
Program      BSER      Library N2OBATCH
0010 /.N2O LOGON
0020 /CALL-PROCEDURE NAME=$TSOSAVE.DO.JV.T
0030 /ASSIGN-SYSOUT TO-FILE=N2O.OUT.LOAD.&(JV.ZEIT.T)
0040 /MODIFY-JOB-OPTIONS LOGGING=PARAMETERS(LISTING=YES)
0050 /REMARK *** EXECUTE N2OER ***
0060 /ASSIGN-SYSDTA TO-FILE=*SYSCMD
0070 /MODIFY-JOB-SWITCHES ON=(4,5)
0080 /START-PROGRAM FROM-FILE=$EDT
0090 LS=132,PS=60,MENU=OFF
0100 @WRITE 'N2O.ER.IPT.BATCH' OVERWRITE
0110 @HALT
0120 /MODIFY-JOB-SWITCHES OFF=(4,5)
0130 /ASSIGN-SYSIPT TO-FILE=N2O.ER.IPT.BATCH
0140 /MODIFY-JOB-SWITCHES ON=(2)
0150 /START-PROGRAM FROM-FRIL=$ADABAS.NATBATCH
0160 LOGON SYSTEM
0170 N2OER
0180 &INPUT
0190 FIN
0200 /ASSIGN-SYSIPT TO-FILE=*PRIMARY
0210 /DELETE-FILE FILE-NAME=N2O.ER.IPT.BATCH,
0220 /OPTION=DESTROY-ALL
0230 /LOGOFF NOSPOOL
***** End of list *****
```

```
Program      VMER      Library N2OBATCH
0010 /* Execute N2OER */
0020 address 'COMMAND'
0030 'ERASE N2OER CMSYNIN A'
0040 'EXECIO 1 DISKW N2OER CMSYNIN A 1 F 80 (STRING LOGON SYSTEM'
0050 'EXECIO 1 DISKW N2OER CMSYNIN A 2 F 80 (STRING N2OER'
0060 'EXECIO 1 DISKW N2OER CMSYNIN A 3 F 80 (STRING &INPUT'
0070 'EXECIO 1 DISKW N2OER CMSYNIN A 4 F 80 (STRING FIN'
0080 'FILEDEF * CLEAR'
0090 'FILEDEF CMSYNIN DISK N2OER CMSYNIN A'
0100 'FILEDEF CMWKF02 DISK N2OER CMWKF02 A'
0110 'FILEDEF CMPRINT PRINTER'
0120 'EXEC NAT BATCH'
0130 'ERASE N2OREPT CMSYNIN A'
0140 exit
***** End of list *****
```

Program VSEER Library N2OBATCH

```

0010 * $$ JOB JNM=N2OER,CLASS=A,USER=&USERID
0020 * $$ LST CLASS=A,LST=SYSLST
0030 // JOB N2OER
0040 * N2ORECOVERY - N2O EMERGENCY RECOVERY
0050 // ASSGN SYSIPT,SYSRDR
0060 // ASSGN SYS009,SYSLST
0070 // EXEC NATBATCH
0080 /*
0090 ADARUN DB=xxx,SVC=yyy,DEVICE=zzzz
0100 /*
0110 LOGON SYSTEM
0120 N2OER
0130 &INPUT
0140 FIN
0150 /*
0160 /&
0170 * $$ EOJ
***** End of list *****

```

Emergency Recovery Acknowledgement

Program MVSERAKN Library N2OBATCH

```

0010 //NATERAKN JOB (ACCOUNTING),'EMERG REC ACKN',CLASS=A,NOTIFY=&USERID
0020 /**
0030 /** THIS JOB PERFORMS THE ACKNOWLEDGEMENT STEP FOR EMERGENCY RECOVERY
0040 /** WHICH UPDATES THE N2O MIGRATION FILE WITH ALL OBJECTS RECOVERED
0050 /** WITH THE N2O EMERGENCY RECOVERY UTILITY
0060 /**
0070 /** THIS STEP IS RAN AGAINST AN ENVIRONMENT THAT IS LOCAL TO THE
0080 /** ARCHIVE FILE USED IN EMERGENCY RECOVERY
0090 /**
0100 /** ARCHIVE-DBID MUST BE REPLACED WITH THE DBID OF THE
0110 /** ARCHIVE FILE USED IN EMERGENCY RECOVERY
0120 /**
0130 /** ARCHIVE-FNR MUST BE REPLACED WITH THE FILE NUMBER OF THE
0140 /** ARCHIVE FILE USED IN EMERGENCY RECOVERY
0150 /**
0160 //N2OERAK1 EXEC PGM=NATBATCH
0170 //CMWKF01 DD DSN=ARCHIVE.LIST.PARMS,DISP=(NEW,PASS,DELETE),
0180 // SPACE=(TRK,(1,1),RLSE),UNIT=SYSDA,
0190 // DCB=(RECFM=FB,BLKSIZE=152,LRECL=152)
0200 //CMPRINT DD SYSOUT=*
0210 //CMSYNIN DD *
0220 LOGON SYSTEM
0230 N2OERAK1
0240 ARCHIVE-DBID , ARCHIVE-FNR
0250 FIN
0260 /*
0270 /** THIS STEP IS RAN AGAINST AN ENVIRONMENT THAT IS LOCAL TO THE
0280 /** N2O MIGRATION FILE
0290 /**
0300 //N2OERAK2 EXEC PGM=NATBATCH
0310 /**
0320 //CMWKF01 DD DSN=ARCHIVE.LIST.PARMS,DISP=(OLD,PASS,CATLG)
0330 //CMPRINT DD SYSOUT=*
0340 //CMSYNIN DD *
0350 LOGON N2OLIB
0360 N2OERAK2
0370 FIN
0380 /*
0390 /**
***** End of list *****

```

```
Program      BSERAKN  Library N2OBATCH
0010 / .N2O LOGON
0020 /CALL-PROCEDURE NAME=$TSOSAVE.DO.JV.T
0030 /ASSIGN-SYSOUT TO-FILE=N2O.OUT.LOAD.&(JV.ZEIT.T)
0040 /MODIFY-JOB-OPTIONS LOGGING=PARAMETERS (LISTING=YES)
0050 /REMARK *** EXECUTE N2OERAK1 ***
0060 /FILE ARCHIVE.PARMS, LINK=W01, RECFORM=FB, RECSIZE=152, BLKSIZE=156
0070 /ASSIGN-SYSDTA TO-FILE=*SYSCMD
0080 /MODIFY-JOB-SWITCHES ON=(4,5)
0090 /START-PROGRAM FROM-FILE=$EDT
0100 LS=132, PS=60, MENU=OFF
0110 @WRITE 'N2O.ARCHIVE.IPT.BATCH' OVERWRITE
0120 @HALT
0130 /MODIFY-JOB-SWITCHES OFF=(4,5)
0140 /ASSIGN-SYSIPT TO-FILE=N2O.ARCHIVE.IPT.BATCH
0150 /MODIFY-JOB-SWITCHES ON=(2)
0160 /START-PROGRAM FROM-FRIL=$ADABAS.NATBATCH
0170 LOGON SYSTEM
0180 N2OERAK1
0190 ARCHIVE-DBID , ARCHIVE-FNR
0200 FIN
0210 /REMARK *** EXECUTE N2OERAK2 ***
0220 /FILE ARCHIVE.PARMS, LINK=W01
0230 /SET-JOB-STEP
0240 /ASSIGN-SYSIPT TO-FILE=N2O.ARCHIVE.IPT.BATCH
0250 /START-PROGRAM FROM-FILE=$ADABAS.NATBATCH
0260 LOGON N2OLIB
0270 N2OERAK2
0280 FIN
0290 /ASSIGN-SYSIPT TO-FILE=*PRIMARY
0300 /DELETE-FILE FILE-NAME=N2O.ARCHIVE.IPT.BATCH,
0310 /OPTION=DESTROY-ALL
0320 /LOGOFF NOSPOOL
***** End of list *****
```

```
Program      VMERAKN  Library N2OBATCH
0010 /*
0020 /* THIS JOB PERFORMS THE ACKNOWLEDGEMENT STEP FOR EMERGENCY RECOVERY
0030 /* WHICH UPDATES THE N2O MIGRATION FILE WITH ALL OBJECTS RECOVERED
0040 /* WITH THE N2O EMERGENCY RECOVERY UTILITY
0050 /*
0060 /* THIS STEP IS RAN AGAINST AN ENVIRONMENT THAT IS LOCAL TO THE
0070 /* ARCHIVE FILE USED IN EMERGENCY RECOVERY
0080 /*
0090 /* ARCH-DBID MUST BE REPLACED WITH THE DBID OF THE
0100 /* ARCHIVE FILE USED IN EMERGENCY RECOVERY
0110 /*
0120 /* ARCH-FNR MUST BE REPLACED WITH THE FILE NUMBER OF THE
0130 /* ARCHIVE FILE USED IN EMERGENCY RECOVERY
0140 /*
0150 /* EXECUTE N2OERAK1 */
0160 address 'COMMAND'
0170 'ERASE N2OERAK1 CMSYNIN A'
0180 'ERASE ARCHIVE PARMS A'
0190 'EXECIO 1 DISKW N2OERAK1 CMSYNIN A 1 F 80 (STRING LOGON SYSTEM'
0200 'EXECIO 1 DISKW N2OERAK1 CMSYNIN A 2 F 80 (STRING N2OERAK1'
0210 'EXECIO 1 DISKW N2OERAK1 CMSYNIN A 3 F 80 (STRING ARCH-DBID , ARCH-FNR'
0220 'EXECIO 1 DISKW N2OERAK1 CMSYNIN A 4 F 80 (STRING FIN'
0230 'FILEDEF * CLEAR'
0240 'FILEDEF CMWKF01 DISK ARCHIVE PARMS A RECFM FB LRECL 152 BLKSIZE 156'
0250 'FILEDEF CMSYNIN DISK N2OERAK1 CMSYNIN A'
0260 'FILEDEF CPRINT PRINTER'
0270 'EXEC NAT BATCH'
0280 'ERASE N2OERAK1 CMSYNIN A'
0290 /*
0300 /* THIS STEP IS RAN AGAINST AN ENVIRONMENT THAT IS LOCAL TO THE
0310 /* N2O MIGRATION FILE
0320 /*
0330 /* EXECUTE N2OERAK2 */
0340 'ERASE N2OERAK2 CMSYNIN A'
```



```

0350 'EXECIO 1 DISKW N2OERAK2 CMSYNIN A 1 F 80 (STRING LOGON N2OLIB'
0360 'EXECIO 1 DISKW N2OERAK2 CMSYNIN A 2 F 80 (STRING N2OERAK2'
0370 'EXECIO 1 DISKW N2OERAK2 CMSYNIN A 3 F 80 (STRING FIN'
0380 'FILEDEF * CLEAR'
0390 'FILEDEF CMWKF01 DISK ARCHIVE PARMS A'
0400 'FILEDEF CMSYNIN DISK N2OERAK2 CMSYNIN A'
0410 'FILEDEF CMPRINT PRINTER'
0420 'EXEC NAT BATCH'
0430 'ERASE N2OERAK2 CMSYNIN A'
0440 exit
***** End of list *****

```

Program VSEERAKN Library N2OBATCH

```

0010 * $$ JOB JNM=ERACKN,CLASS=A,USER=&USERID
0020 * $$ LST CLASS=A,LST=SYSLST
0030 // JOB ERACKN
0040 /*
0050 * EXECUTE N2OERAK1
0060 *
0070 * THIS JOB PERFORMS THE ACKNOWLEDGEMENT STEP FOR EMERGENCY RECOVERY
0080 * WHICH UPDATES THE N2O MIGRATION FILE WITH ALL OBJECTS RECOVERED
0090 * WITH THE N2O EMERGENCY RECOVERY UTILITY
0100 *
0110 * THIS STEP IS RAN AGAINST AN ENVIRONMENT THAT IS LOCAL TO THE
0120 * ARCHIVE FILE USED IN EMERGENCY RECOVERY
0130 *
0140 * ARCH-DBID MUST BE REPLACED WITH THE DBID OF THE
0150 * ARCHIVE FILE USED IN EMERGENCY RECOVERY
0160 *
0170 * ARCH-FNR MUST BE REPLACED WITH THE FILE NUMBER OF THE
0180 * ARCHIVE FILE USED IN EMERGENCY RECOVERY
0190 *
0200 // ASSGN SYSIPT,SYSRDR
0210 // ASSGN SYS001,DISK,SHR
0220 // ASSGN SYS009,SYSLST
0230 // DLBL CMWKF01,'ARCHIVE.PARM'
0240 // EXTENT SYS001,,,nnnnn,nnnnn
0250 // EXEC NATBATCH
0260 BWORKD=(1,1,152,FB)
0270 /*
0280 ADARUN DB=xxx,SVC=yyy,DEVICE=zzzz
0290 /*
0300 LOGON SYSTEM
0310 N2OERAK1
0320 ARCHIVE-DBID , ARCHIVE-FNR
0330 FIN
0340 /*
0350 * EXECUTE N2OERAK2
0360 *
0370 * THIS STEP IS RAN AGAINST AN ENVIRONMENT THAT IS LOCAL TO THE
0380 * N2O MIGRATION FILE
0390 *
0400 // ASSGN SYS009,SYSLST
0410 // DLBL CMWKF01,'ARCHIVE.PARM'
0420 // EXTENT SYS001,,,nnnnn,nnnnn
0430 // EXEC NATBATCH
0440 BWORKD=(1,1,152,FB)
0450 /*
0460 ADARUN DB=xxx,SVC=yyy,DEVICE=zzzz
0470 /*
0480 LOGON N2OLIB
0490 N2OERAK2
0500 FIN
0510 /*
0520 /&
0530 * $$ EOJ
***** End of list *****

```

Event Purge

Program MVSEVNTF Library N2OBATCH

```
0010 //EVNTPURG JOB (ACCOUNTING),'EVENT PURGE',CLASS=A,NOTIFY=&USERID
0020 /***
0030 /** THIS IS SAMPLE JCL FOR THE EVENT PURGE PROCESS
0040 /** THIS SHOULD BE RENAMED N2OPUEVT
0050 /***
0060 /** EVNTP1 RUNS WHERE N2O IS INSTALLED
0070 /***
0080 /** N2OV5.1 &INPUT FORMAT CHANGED - SEE MANUAL
0090 /***
0100 //EVNTP1 EXEC PGM=NATBATCH
0110 /*
0120 //CMWK01 DD DSN=EVENT.LIST,DISP=(NEW,PASS,DELETE),
0130 // SPACE=(TRK,(5,5),RLSE),UNIT=SYSDA,
0140 // DCB=(RECFM=FB,BLKSIZE=13,LRECL=13)
0150 //CMPRINT DD SYSOUT=*
0160 //CMPRT02 DD SYSOUT=*
0170 //CMSYNIN DD *
0180 LOGON N2OLIB
0190 N2OPEVT1
0200 &INPUT
0210 FIN
0220 /*
0230 /***
0240 /** EVNTP2 RUNS WHERE N2O IS INSTALLED
0250 /***
0260 /***
0270 /** N2OV5.1 CMWK03 NEW FILE
0280 /***
0290 //EVNTP2 EXEC PGM=NATBATCH
0300 /*
0310 //CMWK02 DD DSN=EVENT.LIST,DISP=(OLD,DELETE,CATLG)
0320 //CMWK03 DD DSN=&BACKUP,
0330 // DISP=(NEW,CATLG,CATLG),
0340 // DCB=(RECFM=FB,BLKSIZE=1998,LRECL=1998),
0350 // SPACE=(TRK,(5,5),RLSE),UNIT=SYSDA
0360 //CMPRINT DD SYSOUT=*
0370 //CMPRT02 DD SYSOUT=*
0380 //CMPRT04 DD SYSOUT=*
0390 //CMSYNIN DD *
0400 LOGON N2OLIB
0410 N2OPEVT2
0420 FIN
0430 /*
0440 /**
***** End of list *****
```

```

Program      BSEVNTP      Library N2OBATCH
0010 /N2O LOGON
0020 /CALL-PROCEDURE NAME=$TSOSAVE.DO.JV.T
0030 /ASSIGN-SYSOUT TO-FILE=N2O.OUT.LOAD.&(JV.ZEIT.T)
0040 /MODIFY-JOB-OPTIONS LOGGING=PARAMETERS(LISTING=YES)
0050 /REMARK *** EXECUTE N2OPEVT1 ***
0060 /FILE EVENT.LIST, LINK=W01, RECFORM=FB, RECSIZE=13, BLKSIZE=1300
0070 /FILE MASTER.LIST, LINK=P02
0080 /ASSIGN-SYSDTA TO-FILE=*SYSCMD
0090 /MODIFY-JOB-SWITCHES ON=(4,5)
0100 /START-PROGRAM FROM-FILE=$EDT
0110 LS=132, PS=60, MENU=OFF
0120 @WRITE 'N2O.PURGE.IPT.BATCH' OVERWRITE
0130 @HALT
0140 /MODIFY-JOB-SWITCHES OFF=(4,5)
0150 /ASSIGN-SYSIPT TO-FILE=N2O.PURGE.IPT.BATCH
0160 /MODIFY-JOB-SWITCHES ON=(2)
0170 /START-PROGRAM FROM-FRIL=$ADABAS.NATBATCH
0180 LOGON N2OLIB
0190 N2OPEVT1
0200 &INPUT
0210 FIN
0220 /REMARK *** EXECUTE N2OPEVT2 ***
0230 /FILE EVENT.LIST, LINK=W02
0240 /FILE &BACKUP, LINK=W03, RECFORM=FB, RECSIZE=1998, BLKSIZE=1998
0250 /FILE CONTROL.LIST, LINK=P02
0260 /FILE SUMMARY.LIST, LINK=P04
0270 /SET-JOB-STEP
0280 /ASSIGN-SYSIPT TO-FILE=N2O.TRANSFER.IPT.BATCH
0290 /START-PROGRAM FROM-FILE=$ADABAS.NATBATCH
0300 LOGON N2OLIB
0310 N2OPEVT2
0320 FIN
0330 /ASSIGN-SYSIPT TO-FILE=*PRIMARY
0340 /DELETE-FILE FILE-NAME=N2O.TRANSFER.IPT.BATCH,
0350 /OPTION=DESTROY-ALL
0360 /LOGOFF NOSPOOL
***** End of list *****

```

```

Program      VMEVNTP      Library N2OBATCH
0010 /* Execute N2OPEVT1 */
0020 address 'COMMAND'
0030 'ERASE N2OPEVT1 CMSYNIN A'
0040 'EXECIO 1 DISKW N2OPEVT1 CMSYNIN A 1 F 80 (STRING LOGON N2OLIB)'
0050 'EXECIO 1 DISKW N2OPEVT1 CMSYNIN A 2 F 80 (STRING N2OPEVT1)'
0060 'EXECIO 1 DISKW N2OPEVT2 CMSYNIN A 3 F 80 (STRING &INPUT)'
0070 'EXECIO 1 DISKW N2OPEVT1 CMSYNIN A 4 F 80 (STRING FIN)'
0080 'FILEDEF * CLEAR'
0090 'FILEDEF CMWKF01 DISK EVENT LIST A RECFM FB LRECL 13 BLKSIZE 1300'
0100 'FILEDEF CMSYNIN DISK N2OPEVT1 CMSYNIN A'
0110 'FILEDEF CMPRINT PRINTER'
0120 'FILEDEF CMPRT02 PRINTER'
0130 'EXEC NAT BATCH'
0140 'ERASE N2OPEVT1 CMSYNIN A'
0150 /* Execute N2OPEVT2 */
0160 'ERASE N2OPEVT2 CMSYNIN A'
0170 'EXECIO 1 DISKW N2OPEVT2 CMSYNIN A 1 F 80 (STRING LOGON N2OLIB)'
0180 'EXECIO 1 DISKW N2OPEVT2 CMSYNIN A 2 F 80 (STRING N2OPEVT2)'
0190 'EXECIO 1 DISKW N2OPEVT2 CMSYNIN A 3 F 80 (STRING FIN)'
0200 'FILEDEF * CLEAR'
0210 'FILEDEF CMWKF02 DISK EVENT LIST A'
0220 'FILEDEF CMWKF03 DISK &BACKUP RECFM FB LRECL 1998 BLKSIZE 1998'
0230 'FILEDEF CMSYNIN DISK N2OPEVT2 CMSYNIN A'
0240 'FILEDEF CMPRINT PRINTER'
0250 'FILEDEF CMPRT02 PRINTER'
0260 'FILEDEF CMPRT04 PRINTER'
0270 'EXEC NAT BATCH'
0280 'ERASE N2OPEVT2 CMSYNIN A'
0290 exit
***** End of list *****

```

```
Program          VSEEVNTP Library N2OBATCH
0010 * $$ JOB JNM=EVNTPURG,CLASS=A,USER=&USERID
0020 * $$ LST CLASS=A,LST=SYSLST
0030 * $$ LST CLASS=A,LST=02E,DISP=K,JSEP=0
0040 // JOB EVNTPURG
0050 /*
0060 * N2OPEVT1 - CREATE LIST OF EVENTS TO BE PURGED.
0070 // ASSGN SYSIPT,SYSRDR
0080 // ASSGN SYS001,DISK,SHR
0090 // ASSGN SYS002,02E
0100 // ASSGN SYS009,SYSLST
0110 // DLBL CMWKF01,'EVENT.LIST'
0120 // EXTENT SYS001,,,,nnnnn,nnnnn
0130 // EXEC NATBATCH
0140 BWORKD=(1,1,13,FB)
0150 /*
0160 ADARUN DB=xxx,SVC=yyy,DEVICE=zzzz
0170 /*
0180 LOGON N2OLIB
0190 N2OPEVT1
0200 &INPUT
0210 FIN
0220 /*
0230 * N2OPEVT2 - PURGE EVENTS FROM MIGRATION FILE
0240 * $$ LST CLASS=A,LST=04E,DISP=K,JSEP=0
0250 // ASSGN SYS002,DISK,SHR
0260 // ASSGN SYS003,DISK,SHR
0270 // ASSGN SYS004,04E
0280 // ASSGN SYS009,SYSLST
0290 // DLBL CMWKF02,'EVENT.LIST'
0300 // EXTENT SYS002,,,,nnnnn,nnnnn
0310 // DLBL CMWKF03,'&BACKUP'
0320 // EXTENT SYS003,,,,nnnnn,nnnnn
0330 // EXEC NATBATCH
0340 BWORKD=(2,2,13,FB,3,3,1998,1998)
0350 /*
0360 ADARUN DB=xxx,SVC=yyy,DEVICE=zzzz
0370 /*
0380 LOGON N2OLIB
0390 N2OPEVT2
0400 FIN
0410 /*
0420 /&
0430 * $$ EOJ
***** End of list *****
```

Batch Migration

```

Program      MVSMIG      Library N2OBATCH
0010 //NATMIGR JOB (20000),'NATURAL MIGRATION',CLASS=A,NOTIFY=&USERID
0020 //*****
0030 //* THIS IS SAMPLE JCL TO PERFORM  BATCH NATURAL, SYSERR,
0040 //* PREDICT 3.3 AND BELOW, PREDICT 3.4 AND 4.1 WITH
0050 //* BUILD EXTRACT SET TO FALSE MIGRATIONS(N2OUE14N)
0060 //* FOR PREDICT 3.4 AND ABOVE WITH BUILD EXTRACT (N2OUE14N)
0070 //* SEE THE MVSMIGP EXAMPLE.
0080 //* THIS JOB SHOULD BE RENAMED TO THE NAME SPECIFIED IN THE
0090 //* MIGRATION PROFILE JCL PROGRAM NAME
0100 //*****
0110 //* N2OSEL ALWAYS RUNS WHERE N2O IS INSTALLED
0120 //*****
0130 //****
0140 //* N2OV5.2 CHANGE CMWKF02 LRECL 3147 TO 3151, BLKSIZE 3151 TO 3155
0150 //****
0160 //N2OSEL      EXEC PGM=NATBATCH
0170 //CMWKF01 DD  *
0180 &INPUT
0190 /*
0200 //CMWKF02 DD  DSN=N2O.PARM,DISP=(NEW,PASS,DELETE),
0210 //          DCB=(RECFM=VB,LRECL=3151,BLKSIZE=3155),
0220 //          UNIT=SYSDA,SPACE=(TRK,(12,12))
0230 //CMWKF03 DD  DUMMY
0240 //CMWKF04 DD  DUMMY
0250 //CMPRINT DD  SYSOUT=*
0260 //CMSYNIN DD  *
0270 LOGON N2OLIB
0280 N2OSEL
0290 FIN
0300 /*
0310 /*
0320 //*****
0330 //* N2OSEND RUNS ON THE FROM FUSER (SOURCE FUSER)
0340 //*****
0350 //N2OSEND EXEC PGM=NATBATCH,COND=(9,LT)
0360 //CMWKF01 DD  DSN=N2O.PREDICT,DISP=(,CATLG,DELETE),
0370 //          DCB=(RECFM=VB,LRECL=1804,BLKSIZE=1808),
0380 //          UNIT=SYSDA,SPACE=(CYL,(1,1),RLSE)
0390 //CMWKF02 DD  DSN=N2O.SOURCE,DISP=(,CATLG,DELETE),
0400 //          DCB=(RECFM=VB,LRECL=9183,BLKSIZE=9187),
0410 //          UNIT=SYSDA,SPACE=(CYL,(1,1),RLSE)
0420 //CMWKF03 DD  DSN=N2O.PARM,DISP=(OLD,PASS,DELETE)
0430 //CMWKF05 DD  DUMMY
0440 //CMPRINT DD  SYSOUT=*
0450 //CMSYNIN DD  *
0460 LOGON SYSTEM
0470 N2OSEND
0480 FIN
0490 /*
0500 /*
0510 //*****
0520 //* N2ORECV RUNS ON THE TO FUSER (TARGET)
0530 //*****
0540 //****
0550 //* N2OV5.2 CHANGE CMWKF03 LRECL 3147 TO 3151, BLKSIZE 3151 TO 3155
0560 //****
0570 //N2ORECV EXEC PGM=NATBATCH,COND=(9,LT)
0580 //CMWKF01 DD  DSN=N2O.PREDICT,DISP=SHR
0590 //CMWKF02 DD  DSN=N2O.SOURCE,DISP=SHR
0600 //CMWKF03 DD  DSN=N2O.ACKN,DISP=(NEW,PASS,DELETE),
0610 //          DCB=(RECFM=VB,LRECL=3151,BLKSIZE=3155),
0620 //          UNIT=SYSDA,SPACE=(CYL,(1,1),RLSE)
0630 //CMWKF04 DD  DSN=N2O.ACACKN,DISP=(NEW,PASS,DELETE),
0640 //          DCB=(RECFM=VB,LRECL=100,BLKSIZE=104),
0650 //          UNIT=SYSDA,SPACE=(CYL,(1,1),RLSE)
0660 //CMWKF05 DD  DSN=N2O.RECOVER,DISP=(NEW,PASS,DELETE),
0670 //          DCB=(RECFM=VB,LRECL=160,BLKSIZE=164),

```

```

0680 //          UNIT=SYSDA,SPACE=(TRK,(12,12))
0690 //CMPRINT DD  SYSOUT=*
0700 //CMSYNIN DD  *
0710 LOGON SYSTEM
0720 N2ORECV
0730 LOGON SYSTEM
0740 N2OBCOMP
0750 FIN
0760 /*
0770 /*
0780 /** The following step is only necessary for sites using
0790 /** the MOVE option. If this step is removed for a COPY,
0800 /** then change the N2OACKN step so that CMWK01 references
0810 /** N2O.ACKN.
0820 /**
0830 /** N2ODELT RUNS ON THE FROM (SOURCE) FUSER
0840 /** (THE SAME AS N2OSEND STEP)
0850 /******
0860 /** N2OV5.2 CHANGE CMWK02 LRECL 3147 TO 3151, BLKSIZE 3151 TO 3155
0870 /******
0880 //N2ODELT EXEC PGM=NATBATCH,COND=(9,LT)
0890 //CMWK01 DD DSN=N2O.ACKN,DISP=(OLD,DELETE,DELETE)
0900 //CMWK02 DD DSN=N2O.DACKN,DISP=(NEW,PASS,DELETE),
0910 //          DCB=(RECFM=VB,LRECL=3151,BLKSIZE=3155),
0920 //          UNIT=SYSDA,SPACE=(CYL,(1,1),RLSE)
0930 //CMPRINT DD  SYSOUT=*
0940 //CMSYNIN DD  *
0950 LOGON SYSTEM
0960 N2ODELT
0970 FIN
0980 /*
0990 /**
1000 /*******
1010 /** N2OACKN ALWAYS RUNS WHERE N2O IS INSTALLED
1020 /** (THE SAME AS THE N2OSEL STEP)
1030 /*******
1040 //N2OACKN EXEC PGM=NATBATCH
1050 //CMWK01 DD DSN=N2O.DACKN,DISP=(OLD,DELETE,CATLG)
1060 //CMWK02 DD DSN=N2O.AACKN,DISP=(OLD,DELETE,CATLG)
1070 //CMWK03 DD DSN=N2O.RECOVER,DISP=(OLD,CATLG,DELETE)
1080 //CMPRINT DD  SYSOUT=*
1090 //CMSYNIN DD  *
1100 LOGON N2OLIB
1110 N2OACKN
1120 FIN
1130 /*
1140 /**
***** End of list *****

```

Program BSMIG Library N2OBATCH

```

0010 /.N2O LOGON
0020 /CALL-PROCEDURE NAME=$TSOSAVE.DO.JV.T
0030 /ASSIGN-SYSOUT TO-FILE=N2O.OUT.LOAD.&(JV.ZEIT.T)
0040 /MODIFY-JOB-OPTIONS LOGGING=PARAMETERS(LISTING=YES)
0050 /REMARK *** EXECUTE N2OSEL ***
0060 /remark ***
0070 /remark N2OV5.2 CHANGE CMWK02 LRECL 3147 TO 3151, BLKSIZE 3151 TO 3155
0080 /remark ***
0090 /SET-FILE-LINK LINK-NAME=W01,FILE-NAME=N2O.SELECT
0100 /FILE N2O.PARM,LINK=W02,RECFORM=VB,RECSIZE=3151,BLKSIZE=3155
0110 /ASSIGN-SYSDTA TO-FILE=*SYSCMD
0120 /MODIFY-JOB-SWITCHES ON=(4,5)
0130 /START-PROGRAM FROM-FILE=$EDT
0140 LS=132,PS=60,MENU=OFF
0150 @WRITE 'N2O.TRANSFER.IPT.BATCH' OVERWRITE
0160 @HALT
0170 /MODIFY-JOB-SWITCHES OFF=(4,5)
0180 /ASSIGN-SYSIPT TO-FILE=N2O.TRANSFER.IPT.BATCH
0190 /MODIFY-JOB-SWITCHES ON=(2)
0200 /START-PROGRAM FROM-FRIL=$ADABAS.NATBATCH

```

```

0210 LOGON N2OLIB
0220 N2OSEL
0230 FIN
0240 /REMARK *** EXECUTE N2OSEND ***
0250 /remark ***
0260 /remark N2OV5.2 CHANGE CMWKF03 LRECL 3147 TO 3151, BLKSIZE 3151 TO 3155
0270 /remark ***
0280 /FILE N2O.PREDICT, LINK=W01, RECFORM=VB, RECSIZE=1804, BLKSIZE=1808,
0290 /      SPACE=(6,6)
0300 /FILE N2O.SOURCE, LINK=W02, RECFORM=VB, RECSIZE=9183, BLKSIZE=9187,
0310 /      SPACE=(12,12)
0320 /FILE N2O.PARM, LINK=W03, RECFORM=VB, RECSIZE=3151, BLKSIZE=3155,
0330 /      SPACE=(12,12)
0340 /SET-JOB-STEP
0350 /ASSIGN-SYSIPT TO-FILE=N2O.TRANSFER.IPT.BATCH
0360 /START-PROGRAM FROM-FILE=$ADABAS.NATBATCH
0370 LOGON SYSTEM
0380 N2OSEND
0390 FIN
0400 /REMARK *** EXECUTE N2ORECV AND N2OBCOMP ***
0410 /remark ***
0420 /remark N2OV5.2 CHANGE CMWKF03 LRECL 3147 TO 3151, BLKSIZE 3151 TO 3155
0430 /remark ***
0440 /FILE N2O.PREDICT, LINK=W01
0450 /FILE N2O.SOURCE, LINK=W02, BLKSIZE=(STD,5)
0460 /FILE N2O.ACKN, LINK=W03, RECFORM=VB, RECSIZE=3151, BLKSIZE=3155,
0470 /      SPACE=(12,12)
0480 /FILE N2O.ACACKN, LINK=W04, RECFORM=VB, RECSIZE=100, BLKSIZE=104
0490 /FILE N2O.RECOVER, LINK=W05, RECFORM=VB, RECSIZE=160, BLKSIZE=164,
0500 /      SPACE=(12,12)
0510 /SET-JOB-STEP
0520 /ASSIGN-SYSIPT TO-FILE=N2O.TRANSFER.IPT.BATCH
0530 /START-PROGRAM FROM-FILE=$ADABAS.NATBATCH
0540 LOGON SYSTEM
0550 N2ORECV
0560 LOGON SYSTEM
0570 N2OBCOMP
0580 FIN
0590 /REMARK *** EXECUTE N2ODELT ***
0600 /remark ***
0610 /remark N2OV5.2 CHANGE CMWKF02 LRECL 3147 TO 3151, BLKSIZE 3151 TO 3155
0620 /remark ***
0630 /FILE N2O.ACKN, LINK=W01
0640 /FILE N2O.DACKN, LINK=W02, RECFORM=VB, RECSIZE=3151, BLKSIZE=3155
0650 /SET-JOB-STEP
0660 /ASSIGN-SYSIPT TO-FILE=N2O.TRANSFER.IPT.BATCH
0670 /START-PROGRAM FROM-FILE=$ADABAS.NATBATCH
0680 LOGON SYSTEM
0690 N2ODELT
0700 FIN
0710 /REMARK *** EXECUTE N2OACKN ***
0720 /FILE N2O.DACKN, LINK=W01
0730 /FILE N2O.ACACKN, LINK=W02
0740 /FILE N2O.RECOVER, LINK=W03
0750 /SET-JOB-STEP
0760 /ASSIGN-SYSIPT TO-FILE=N2O.TRANSFER.IPT.BATCH
0770 /START-PROGRAM FROM-FILE=$ADABAS.NATBATCH
0780 LOGON N2OLIB
0790 N2OACKN
0800 FIN
0810 /ASSIGN-SYSIPT TO-FILE=*PRIMARY
0820 /DELETE-FILE FILE-NAME=N2O.TRANSFER.IPT.BATCH,
0830 /OPTION=DESTROY-ALL
0840 /LOGOFF NOSPOOL
***** End of list *****

```

```
Program      VMMIG      Library N2OBATCH
0010 /* Execute N2OSEL */
0020 /*
0030 /* N2OV5.2 CHANGE CMWKF02 LRECL 3147 TO 3151, BLKSIZE 3151 TO 3155
0040 /*
0050 address 'COMMAND'
0060 'ERASE N2O CMWKF01 A'
0070 'ERASE N2OSEL CMWSYNIN A'
0080 'EXECIO 1 DISKW N2O CMWKF01 A 1 F 80(STRING &INPUT'
0090 'EXECIO 1 DISKW N2OSEL CMSYNIN A 1 F 80(STRING LOGON N2OLIB'
0100 'EXECIO 1 DISKW N2OSEL CMSYNIN A 2 F 80(STRING N2OSEL'
0110 'EXECIO 1 DISKW N2OSEL CMSYNIN A 3 F 80(STRING FIN'
0120 'FILEDEF * CLEAR'
0130 'FILEDEF CMWKF01 DISK N2O CMWKF01 A'
0140 'FILEDEF CMWKF02 DISK N2O PARM A RECFM VB LRECL 3151 BLKSIZE 3155'
0150 'FILEDEF CMSYNIN DISK N2OSEL CMSYNIN A'
0160 'FILEDEF CMPRINT PRINTER'
0170 'EXEC NAT BATCH'
0180 'ERASE N2O CMWKF01 A'
0190 'ERASE N2OSEL CMWSYNIN A'
0200 /* Execute N2OSEND */
0210 'ERASE N2OSEND CMSYNIN A'
0220 'ERASE N2O PREDICT A'
0230 'ERASE N2O PARM A'
0240 'EXECIO 1 DISKW N2OSEND CMSYNIN A 1 F 80(STRING LOGON SYSTEM'
0250 'EXECIO 1 DISKW N2OSEND CMSYNIN A 2 F 80(STRING N2OSEND'
0260 'EXECIO 1 DISKW N2OSEND CMSYNIN A 3 F 80(STRING FIN'
0270 'FILEDEF * CLEAR'
0280 'FILEDEF CMWKF01 DISK N2O PREDICT A RECFM VB LRECL 1804 BLKSIZE 1808'
0290 'FILEDEF CMWKF02 DISK N2O SOURCE A RECFM VB LRECL 9183 BLKSIZE 9187'
0300 'FILEDEF CMWKF03 DISK N2O PARM A'
0310 'FILEDEF CMSYNIN DISK N2OSEND CMSYNIN A'
0320 'FILEDEF CMPRINT PRINTER'
0330 'EXEC NAT BATCH NATPARMS FUSER=(&FROMFUSER) FDIC=(&FROMFDIC) '
0340 'ERASE N2OSEND CMSYNIN A'
0350 /* Execute N2ORECV */
0360 /*
0370 /* N2OV5.2 CHANGE CMWKF03 LRECL 3147 TO 3151, BLKSIZE 3151 TO 3155
0380 /*
0390 'ERASE N2ORECV CMSYNIN A'
0400 'EXECIO 1 DISKW N2ORECV CMSYNIN A 1 F 80(STRING LOGON SYSTEM'
0410 'EXECIO 1 DISKW N2ORECV CMSYNIN A 2 F 80(STRING N2ORECV'
0420 'EXECIO 1 DISKW N2ORECV CMSYNIN A 3 F 80(STRING LOGON SYSTEM'
0430 'EXECIO 1 DISKW N2ORECV CMSYNIN A 4 F 80(STRING N2OBCOMP'
0440 'EXECIO 1 DISKW N2ORECV CMSYNIN A 5 F 80(STRING FIN'
0450 'FILEDEF * CLEAR'
0460 'FILEDEF CMWKF01 DISK N2O PREDICT A'
0470 'FILEDEF CMWKF02 DISK N2O SOURCE A'
0480 'FILEDEF CMWKF03 DISK N2O ACKN A RECFM VB LRECL 3151 BLKSIZE 3155'
0490 'FILEDEF CMWKF04 DISK N2O ACACKN A RECFM VB LRECL 100 BLKSIZE 104'
0500 'FILEDEF CMWKF05 DISK N2O RECOVER A RECFM VB LRECL 160 BLKSIZE 164'
0510 'FILEDEF CMSYNIN DISK N2ORECV CMSYNIN A'
0520 'FILEDEF CMPRINT DISK N2ORECV OUTPUT A'
0530 'EXEC NAT BATCH NATPARMS FUSER=(&TOFUSER1) FDIC=(&TOFDIC1) '
0540 'ERASE N2O PREDICT A'
0550 'ERASE N2O SOURCE A'
0560 'ERASE N2ORECV CMSYNIN A'
0570 /* Execute N2ODELT */
0580 /*
0590 /* N2OV5.2 CHANGE CMWKF02 LRECL 3147 TO 3151, BLKSIZE 3151 TO 3155
0600 /*
0610 'ERASE N2ODELT CMSYNIN A'
0620 'EXECIO 1 DISKW N2ODELT CMSYNIN A 1 F 80(STRING LOGON SYSTEM'
0630 'EXECIO 1 DISKW N2ODELT CMSYNIN A 2 F 80(STRING N2ODELT'
0640 'EXECIO 1 DISKW N2ODELT CMSYNIN A 3 F 80(STRING FIN'
0650 'FILEDEF * CLEAR'
0660 'FILEDEF CMWKF01 DISK N2O ACKN A'
0670 'FILEDEF CMWKF02 DISK N2O DACKN A RECFM VB LRECL 3151 BLKSIZE 3155'
0680 'FILEDEF CMSYNIN DISK N2ODELT CMSYNIN A'
0690 'FILEDEF CMPRINT PRINTER'
0700 'EXEC NAT BATCH NATPARMS FUSER=(&FROMFUSER) FDIC=(&FROMFDIC) '
```



```

0710 'ERASE N2ODELT CMSYNIN A'
0720 'ERASE N2O ACKN A'
0730 /* Execute N2OACKN /*
0740 'ERASE N2OACKN CMSYNIN A'
0750 'EXECIO 1 DISKW N2OACKN CMSYNIN A 1 F 80 (STRING LOGON N2OLIB'
0760 'EXECIO 1 DISKW N2OACKN CMSYNIN A 2 F 80 (STRING N2OACKN'
0770 'EXECIO 1 DISKW N2OACKN CMSYNIN A 3 F 80 (STRING FIN'
0780 'FILEDEF * CLEAR'
0790 'FILEDEF CMWKF01 DISK N2O DACKN A'
0800 'FILEDEF CMWKF02 DISK N2O ACACKN A'
0810 'FILEDEF CMWKF03 DISK N2O RECOVER A'
0820 'FILEDEF CMSYNIN DISK N2OACKN CMSYNIN A'
0830 'FILEDEF CMPRINT PRINTER'
0840 'EXEC NAT BATCH'
0850 'ERASE N2OACKN CMSYNIN A'
0860 'ERASE N2O DACKN A'
0870 'ERASE N2O ACACKN A'
0880 'ERASE N2O AUTOREC A'
0890 exit
***** End of list *****

```

Program VSEMIG Library N2OBATCH

```

0010 * $$ JOB JNM=NATMIGR,CLASS=A,USER=&USERID
0020 * $$ LST CLASS=A,LST=SYSLST
0030 // JOB NATMIGR
0040 // DLBL CMWKF01,'N2OSEL.INPUT.CARDS'
0050 // EXTENT SYS001,, ,nnnnn,nnnnn
0060 // EXEC IDCAMS,SIZE=AUTO
0070 REPRO INFILE(SYSIPT ENV(RECFM(FB) RECSZ(80))) -
0080        OUTFILE(CMWKF01 ENV(RECFM(FB) RECSZ(80) BLKSZ(80)))
0090 &INPUT
0100 /*
0110 * N2OSEL - SELECT LIST OF PROGRAMS/OBJECTS TO BE MIGRATED
0120 *
0130 * N2OV5.2 CHANGE CMWKF02 3151 TO 3155
0140 *
0150 // ASSGN SYSIPT,SYSRDR
0160 // ASSGN SYS001,DISK,SHR
0170 // ASSGN SYS002,DISK,SHR
0180 // ASSGN SYS009,SYSLST
0190 // DLBL CMWKF01,'N2OSEL.INPUT.CARDS'
0200 // EXTENT SYS001,...
0210 // DLBL CMWKF02,'N2O.PARM'
0220 // EXTENT SYS002,...
0230 // EXEC NATBATCH
0240 BWORKD=(1,1,80,FB,2,2,3155,VB)
0250 /*
0260 ADARUN DB=xxx,SVC=yyy,DEVICE=zzzz
0270 /*
0280 LOGON N2OLIB
0290 N2OSEL
0300 FIN
0310 /*
0320 * N2OSEND - UNLOAD THE PROGRAMS TO BE MIGRATED
0330 *
0340 * N2OV5.2 CHANGE CMWKF02 3151 TO 3155
0350 *
0360 // ASSGN SYS001,DISK,SHR
0370 // ASSGN SYS002,DISK,SHR
0380 // ASSGN SYS003,DISK,SHR
0390 // ASSGN SYS009,SYSLST
0400 // DLBL CMWKF01,'N2O.PREDICT'
0410 // EXTENT SYS001,...
0420 // DLBL CMWKF02,'N2O.SOURCE'
0430 // EXTENT SYS002,...
0440 // DLBL CMWKF03,'N2O.PARM'
0450 // EXTENT SYS003,...
0460 // EXEC NATBATCH
0470 BWORKD=(1,1,1808,VB,2,2,9187,VB,3,3,3155,VB)
0480 /*

```

```
0490 ADARUN DB=xxx,SVC=yyy,DEVICE=zzzz
0500 /*
0510 LOGON SYSTEM
0520 N2OSEND
0530 FIN
0540 /*
0550 * N2ORECV - LOAD THE PROGRAMS TO THE TARGET FUSER/FDIC.
0560 *
0570 * N2OV5.2 CHANGE CMWKF03 3151 TO 3155
0580 *
0590 // ASSGN SYS001,DISK,SHR
0600 // ASSGN SYS002,DISK,SHR
0610 // ASSGN SYS003,DISK,SHR
0620 // ASSGN SYS004,DISK,SHR
0630 // ASSGN SYS005,DISK,SHR
0640 // ASSGN SYS009,SYSLST
0650 // DLBL CMWKF01,'N2O.PREDICT'
0660 // EXTENT SYS001,...
0670 // DLBL CMWKF02,'N2O.SOURCE'
0680 // EXTENT SYS002,...
0690 // DLBL CMWKF03,'N2O.ACKN'
0700 // EXTENT SYS003,...
0710 // DLBL CMWKF04,'N2O.ACACKN'
0720 // EXTENT SYS004,...
0730 // DLBL CMWKF05,'N2O.RECOVER'
0740 // EXTENT SYS005,...
0750 // EXEC NATBATCH
0760 BWORKD=(1,1,1808,VB,2,2,9187,VB,3,3,3155,VB,4,4,104,VB,5,5,164,VB)
0770 /*
0780 ADARUN DB=xxx,SVC=yyy,DEVICE=zzzz
0790 /*
0800 LOGON SYSTEM
0810 N2ORECV
0820 LOGON SYSTEM
0830 N2OBCOMP
0840 FIN
0850 /*
0860 * N2ODELT - DELETE PROGRAMS IN FROM ENV FOR MOVES.
0870 *
0880 * N2OV5.2 CHANGE CMWKF02 3151 TO 3155
0890 *
0900 // ASSGN SYS001,DISK,SHR
0910 // ASSGN SYS002,DISK,SHR
0920 // ASSGN SYS009,SYSLST
0930 // DLBL CMWKF01,'N2O.ACKN'
0940 // EXTENT SYS001,...
0950 // DLBL CMWKF02,'N2O.DACKN'
0960 // EXTENT SYS002,...
0970 // EXEC NATBATCH
0980 BWORKD=(1,1,3151,VB,2,2,3155,VB)
0990 /*
1000 ADARUN DB=xxx,SVC=yyy,DEVICE=zzzz
1010 /*
1020 LOGON SYSTEM
1030 N2ODELT
1040 FIN
1050 /*
1060 * N2OACKN - ACKNOWLEDGEMENT OF EVENT COMPLETION
1070 // ASSGN SYS001,DISK,SHR
1080 // ASSGN SYS002,DISK,SHR
1090 // ASSGN SYS003,DISK,SHR
1100 // ASSGN SYS009,SYSLST
1110 // DLBL CMWKF01,'N2O.DACKN'
1120 // EXTENT SYS001,...
1130 // DLBL CMWKF02,'N2O.ACACKN'
1140 // EXTENT SYS002,...
1150 // DLBL CMWKF03,'N2O.RECOVER'
1160 // EXTENT SYS003,...
1170 // EXEC NATBATCH
1180 BWORKD=(1,1,3151,VB,2,2,104,VB,3,3,164,VB)
1190 /*
```

```

1200 ADARUN DB=xxx,SVC=yyy,DEVICE=zzzz
1210 /*
1220 LOGON N2OLIB
1230 N2OACKN
1240 FIN
1250 /*
1260 /&
1270 * $$ EOJ
***** End of list *****

```

N2OPURGE

Program MVSPURGE Library N2OBATCH

```

0010 //N2OPURGE JOB (20000),'N2OPURGE UTILITY',CLASS=A,NOTIFY=&USERID
0020 /***
0030 /** THIS IS SAMPLE JCL FOR THE N2OPURGE UTILITY
0040 /** THIS SHOULD BE RENAMED N2OPURGE
0050 /***
0060 /** N2OPURGE RUNS ON FUSER WHERE OBJECTS ARE TO BE PURGED FROM
0070 /***
0080 /***
0090 /** N2OV5.2 CHANGE CMWKF01 LRECL FROM 123 TO 150, BLKSIZE 127 TO 154
0100 /***
0110 //N2OPURGE EXEC PGM=NATBATCH
0120 //CMWKF01 DD DSN=N2OPURGE.LIST,DISP=(,CATLG),
0130 //          DCB=(RECFM=VB,LRECL=150,BLKSIZE=154),
0140 //          UNIT=SYSDA,SPACE=(TRK,(12,12))
0150 //CMPRINT DD SYSOUT=*
0160 //CMSYNIN DD *
0170 LOGON N2OLIB
0180 N2OPURGE
0190 &INPUT
0200 FIN
0210 /*
0220 /**
0230 /***
0240 /** N2OV5.2 CHANGE CMWKF02 LRECL FROM 290 TO 317, BLKSIZE 294 TO 321
0250 /***
0260 /**
0270 //N2OPURG1 EXEC PGM=NATBATCH
0280 //CMWKF01 DD DSN=N2OPURGE.LIST,DISP=SHR
0290 //CMWKF02 DD DSN=N2OPURGE.ACKN,DISP=(,CATLG),
0300 //          DCB=(RECFM=VB,LRECL=317,BLKSIZE=321),
0310 //          UNIT=SYSDA,SPACE=(TRK,(12,12))
0320 //CMPRINT DD SYSOUT=*
0330 //CMSYNIN DD *
0340 LOGON SYSTEM
0350 N2OPURG1
0360 FIN
0370 /*
0380 /***
0390 /** N2OPURG2 RUNS WHERE N2O IS INSTALLED
0400 /***
0410 //N2OPURG2 EXEC PGM=NATBATCH
0420 //CMWKF02 DD DSN=N2OPURGE.ACKN,DISP=SHR
0430 //CMPRINT DD SYSOUT=*
0440 //CMSYNIN DD *
0450 LOGON N2OLIB
0460 N2OPURG2
0470 FIN
0480 /*
0490 /**
***** End of list *****

```

```
Program      BSPURGE   Library N2OBATCH
0010 /N2O LOGON
0020 /CALL-PROCEDURE NAME=$TSOSAVE.DO.JV.T
0030 /ASSIGN-SYSOUT TO-FILE=N2O.OUT.LOAD.&(JV.ZEIT.T)
0040 /MODIFY-JOB-OPTIONS LOGGING=PARAMETERS (LISTING=YES)
0050 /REMARK *** EXECUTE N2OPURGE ***
0060 /remark **
0070 /remark N2OV5.2 CHANGE CMWKF01 LRECL FROM 123 - 150, BLKSIZE 127 - 154
0080 /remark **
0090 /FILE N2OPURGE.LIST, LINK=W01, RECFORM=VB, RECSIZE=150, BLKSIZE=154
0100 /ASSIGN-SYSDTA TO-FILE=*SYSCMD
0110 /MODIFY-JOB-SWITCHES ON=(4,5)
0120 /START-PROGRAM FROM-FILE=$EDT
0130 LS=132, PS=60, MENU=OFF
0140 @WRITE 'N2O.PURGE.IPT.BATCH' OVERWRITE
0150 @HALT
0160 /MODIFY-JOB-SWITCHES OFF=(4,5)
0170 /ASSIGN-SYSIPT TO-FILE=N2O.PURGE.IPT.BATCH
0180 /MODIFY-JOB-SWITCHES ON=(2)
0190 /START-PROGRAM FROM-FRIL=$ADABAS.NATBATCH
0200 LOGON N2OLIB
0210 N2OPURGE
0220 &INPUT
0230 FIN
0240 /REMARK *** EXECUTE N2OPURG1 ***
0250 /remark **
0260 /remark N2OV5.2 CHANGE CMWKF02 LRECL FROM 290 - 317, BLKSIZE 294 - 321
0270 /remark **
0280 /FILE N2OPURGE.LIST, LINK=W01
0290 /FILE N2OPURGE.ACKN, LINK=W02, RECFORM=VB, RECSIZE=317, BLKSIZE=321
0300 /SET-JOB-STEP
0310 /ASSIGN-SYSIPT TO-FILE=N2O.PURGE.IPT.BATCH
0320 /START-PROGRAM FROM-FILE=$ADABAS.NATBATCH
0330 LOGON SYSTEM
0340 N2OPURG1
0350 FIN
0360 /REMARK *** EXECUTE N2OPURG2 ***
0370 /FILE N2OPURGE.ACKN, LINK=W02
0380 /SET-JOB-STEP
0390 /ASSIGN-SYSIPT TO-FILE=N2O.PURGE.IPT.BATCH
0400 /START-PROGRAM FROM-FILE=$ADABAS.NATBATCH
0410 LOGON N2OLIB
0420 N2OPURG2
0430 FIN
0440 /ASSIGN-SYSIPT TO-FILE=*PRIMARY
0450 /DELETE-FILE FILE-NAME=N2O.PURGE.IPT.BATCH,
0460 /OPTION=DESTROY-ALL
0470 /LOGOFF NOSPOOL
***** End of list *****
```

```

Program      VMPURGE  Library N2OBATCH
0010 /* Execute N2OPURGE */
0020 /*
0030 /*      N2OV5.2 CHANGE CMWKF01 LRECL FROM 123 TO 150, BLKSIZE 127 TO 154
0040 /*
0050 address 'COMMAND'
0060 'ERASE N2OPURGE CMSYNIN A'
0070 'EXECIO 1 DISKW N2OPURGE CMSYNIN A 1 F 80 (STRING LOGON N2OLIB'
0080 'EXECIO 1 DISKW N2OPURGE CMSYNIN A 2 F 80 (STRING N2OPURGE'
0090 'EXECIO 1 DISKW N2OPURGE CMSYNIN A 3 F 80 (STRING &INPUT'
0100 'EXECIO 1 DISKW N2OPURGE CMSYNIN A 4 F 80 (STRING FIN'
0110 'FILEDEF * CLEAR'
0120 'FILEDEF CMWKF01 N2OPURGE LIST A RECFM VB LRECL 150 BLKSIZE 154'
0130 'FILEDEF CMSYNIN DISK N2OPURGE CMSYNIN A'
0140 'FILEDEF CMPRINT PRINTER'
0150 'EXEC NAT BATCH'
0160 'ERASE N2OPURGE CMSYNIN A'
0170 /* Execute N2OPURG1 */
0180 /*
0190 /*      N2OV5.2 CHANGE CMWKF01 LRECL FROM 290 TO 317, BLKSIZE 294 TO 321
0200 /*
0210 'ERASE N2OPURG1 CMSYNIN A'
0220 'EXECIO 1 DISKW N2OPURG1 CMSYNIN A 1 F 80 (STRING LOGON SYSTEM'
0230 'EXECIO 1 DISKW N2OPURG1 CMSYNIN A 2 F 80 (STRING N2OPURG1'
0240 'EXECIO 1 DISKW N2OPURG1 CMSYNIN A 3 F 80 (STRING FIN'
0250 'FILEDEF * CLEAR'
0260 'FILEDEF CMWKF01 N2OPURGE LIST A'
0270 'FILEDEF CMWKF02 N2OPURGE ACKN A RECFM VB LRECL 317 BLKSIZE 321'
0280 'FILEDEF CMSYNIN DISK N2OPURG1 CMSYNIN A'
0290 'FILEDEF CMPRINT PRINTER'
0300 'EXEC NAT BATCH'
0310 'ERASE N2OPURGE LIST A'
0320 'ERASE N2OPURG1 CMSYNIN A'
0330 /* Execute N2OPURG2 */
0340 'ERASE N2OPURG2 CMSYNIN A'
0350 'EXECIO 1 DISKW N2OPURG2 CMSYNIN A 1 F 80 (STRING LOGON N2OLIB'
0360 'EXECIO 1 DISKW N2OPURG2 CMSYNIN A 2 F 80 (STRING N2OPURG2'
0370 'EXECIO 1 DISKW N2OPURG2 CMSYNIN A 3 F 80 (STRING FIN'
0380 'FILEDEF * CLEAR'
0390 'FILEDEF CMWKF02 N2OPURGE ACKN A'
0400 'FILEDEF CMSYNIN DISK N2OPURG2 CMSYNIN A'
0410 'FILEDEF CMPRINT PRINTER'
0420 'EXEC NAT BATCH'
0430 'ERASE N2OPURGE ACKN A'
0440 'ERASE N2OPURG2 CMSYNIN A'
0450 exit
***** End of list *****

```

```
Program      VSEPURGE Library N2OBATCH
0010 * $$ JOB JNM=N2OPURGE,CLASS=A,USER=&USERID
0020 * $$ LST CLASS=A,LST=SYSLST
0030 // JOB N2OPURGE
0040 * N2OPURGE - VERIFY INPUT PARMS
0050 *
0060 *      N2OV5.2 CHANGE CMWKF01 127 TO 154
0070 *
0080 // ASSGN SYSIPT,SYSRDR
0090 // ASSGN SYS001,DISK,SHR
0100 // ASSGN SYS009,SYSLST
0110 // DLBL CMWKF01,'N2OPURGE.LIST'
0120 // EXTENT SYS001,, ,nnnnn,nnnnn
0130 // EXEC NATBATCH
0140 BWORKD=(1,1,154,VB)
0150 /*
0160 ADARUN DB=xxx,SVC=yyy,DEVICE=zzzz
0170 /*
0180 LOGON N2OLIB
0190 N2OPURGE
0200 &INPUT
0210 FIN
0220 /*
0230 * N2OPURG1 - BATCH DELETE OF PROGRAMS
0240 *
0250 *      N2OV5.2 CHANGE CMWKF02 294 TO 321
0260 *
0270 // ASSGN SYS001,DISK,SHR
0280 // ASSGN SYS002,DISK,SHR
0290 // ASSGN SYS009,SYSLST
0300 // DLBL CMWKF01,'N2OPURGE.LIST'
0310 // EXTENT SYS001,, ,nnnnn,nnnnn
0320 // DLBL CMWKF02,'N2OPURGE.ACKN'
0330 // EXTENT SYS002,, ,nnnnn,nnnnn
0340 // EXEC NATBATCH
0350 BWORKD=(1,1,127,VB,2,2,321,VB)
0360 /*
0370 ADARUN DB=xxx,SVC=yyy,DEVICE=zzzz
0380 /*
0390 LOGON SYSTEM
0400 N2OPURG1
0410 FIN
0420 /*
0430 * N2OPURG2 - ACKNOWLEDGE DELETE
0440 *
0450 *      N2OV5.2 CHANGE CMWKF01 294 TO 321
0460 *
0470 *
0480 // ASSGN SYS002,DISK,SHR
0490 // ASSGN SYS009,SYSLST
0500 // DLBL CMWKF02,'N2OPURGE.ACKN'
0510 // EXTENT SYS002,, ,nnnnn,nnnnn
0520 // EXEC NATBATCH
0530 BWORKD=(1,1,321,VB)
0540 /*
0550 ADARUN DB=xxx,SVC=yyy,DEVICE=zzzz
0560 /*
0570 LOGON N2OLIB
0580 N2OPURG2
0590 FIN
0600 /*
0610 /&
0620 * $$ EOJ
***** End of list *****
```

3GL N2OPURGE

```

Program      MVS3PRGE Library N2OBATCH
0010 //PDSPURG  JOB (ACCOUNTING),'PDS N2OPURGE',CLASS=A,NOTIFY=&SYSUID
0020 /*
0030 //*****
0040 /**
0050 /*  THIS IS SAMPLE JCL FOR THE 3GL N2OPURGE UTILITY
0060 /*  THIS SHOULD BE RENAMED TO PDSPURGE
0070 /**
0080 /**
0090 //*****
0100 /*
0110 /* &INCLUDE PRTPCH will be automatically replaced with the IEBTPCH
0120 /* commands necessary to punch the members to a workfile.
0130 /*
0140 //NPPUNCH      EXEC PGM=IEBTPCH
0150 //SYSPRINT DD   SYSOUT=*
0160 //SYSUT1 DD     DSN=&PDS,DISP=(SHR,KEEP),UNIT=SYSDA
0170 //SYSUT2 DD     DSN=&&TEMP,DISP=(NEW,PASS,DELETE),
0180 //              UNIT=SYSDA,SPACE=(TRK,(15,15))
0190 //SYSIN DD      *
0200 &INCLUDE PRTPCH
0210 /*
0220 //*****
0230 /*
0240 /* &INCLUDE DELETE will be replaced automatically by N2O with
0250 /* IDCAMS cards to delete each member that were migrated
0260 /* if MOVE is specified for the Migration Profile.
0270 /*
0280 //NPDELETE     EXEC PGM=IDCAMS,COND=(8,LT)
0290 //SYSPRINT DD   DSN=&&DELOUT,
0300 //              DCB=(RECFM=VB,LRECL=125,BLKSIZE=129),
0310 //              DISP=(NEW,PASS,DELETE),
0320 //              UNIT=SYSDA,SPACE=(TRK,(5,5))
0330 //DD1 DD        DISP=SHR,DSN=&PDS
0340 //SYSIN DD      *
0350 &INCLUDE DELETE
0360 /*
0370 //*****
0380 /*  N2OPURG3 RUNS ON THE FUSER WHERE N2O IS INSTALLED.
0390 /*  IT REQUIRES A NATURAL NUC WITH ACCESS TO THE N2O-ADMINISTRATION
0400 /*  N2O-MIGRATION FILES AND ANY N2O-ARCHIVE FILE DEFINED TO THE 3GL
0410 /*  ENVIRONMENT WHERE THE 3GL N2OPURGE OCCURS.
0420 //*****
0430 //NPACKN      EXEC NATBATCH
0440 //CMWKF01 DD    *
0450 &N2OPURGE
0460 /*
0470 //CMWKF02 DD    DSN=&&TEMP,DISP=(OLD,PASS,DELETE)
0480 //CMWKF03 DD    DSN=&&DELOUT,DISP=(OLD,PASS,DELETE)
0490 //CMPRINT DD    SYSOUT=*
0500 //CMSYNIN DD    *
0510 LOGON N2OLIB
0520 N2OPURG3
0530 FIN
0540 /*

```

Recover from Archive backup (Natural objects)

```
Program      MVSRA B      Library N2OBATCH
0010 //N2ORAB JOB (ACCT),'RECOVER ARCH BACKUP',CLASS=A,NOTIFY=&USERID
0020 /***
0030 /***      THIS IS SAMPLE JCL FOR A RECOVER FROM ARCHIVE BACKUP
0040 /***      THIS SHOULD BE RENAMED TO N2ORAB
0050 /***
0060 /** N2ORAB1 RUNS WHERE N2O IS INSTALLED
0070 /***
0080 //N2ORAB1 EXEC PGM=NATBATCH
0090 //CMWK F02 DD DSN=REC.PARMS,DISP=(NEW,PASS,DELETE),
0100 //          SPACE=(TRK,(5,5),RLSE),UNIT=SYSDA,
0110 //          DCB=(RECFM=VB,BLKSIZE=193,LRECL=189)
0120 //CMPRINT DD SYSOUT=*
0130 //CMSYNIN DD *
0140 LOGON N2OLIB
0150 N2ORAB1
0160 FIN
0170 /*
0180 //CMWK F01 DD *
0190 &INPUT
0200 /*
0210 /***
0220 /** N2ORAB2 RUNS ON THE TARGET FUSER
0230 /***
0240 //N2ORAB2 EXEC PGM=NATBATCH
0250 //CMWK F01 DD DSN=REC.PARMS,DISP=(OLD,DELETE,CATLG)
0260 //CMWK F02 DD DSN=&BACKUP,DISP=(OLD,KEEP,KEEP)
0270 //CMWK F03 DD DSN=REC.ACKN,DISP=(NEW,PASS,DELETE),
0280 //          SPACE=(TRK,(5,5),RLSE),UNIT=SYSDA,
0290 //          DCB=(RECFM=VB,BLKSIZE=193,LRECL=189)
0300 //CMPRINT DD SYSOUT=*
0310 //CMSYNIN DD *
0320 LOGON SYSTEM
0330 N2ORAB2
0340 FIN
0350 /*
0360 /***
0370 /** N2ORAB3 RUNS WHERE N2O IS INSTALLED
0380 /***
0390 //N2ORAB3 EXEC PGM=NATBATCH
0400 //CMWK F01 DD DSN=REC.ACKN,DISP=(OLD,DELETE,CATLG)
0410 //CMPRINT DD SYSOUT=*
0420 //CMSYNIN DD *
0430 LOGON N2OLIB
0440 N2ORAB3
0450 FIN
0460 /*
0470 /**
***** End of list *****
```


Program	BSRAB	Library	N2OBATCH
0010			/N2O LOGON
0020			/CALL-PROCEDURE NAME=\$TSOSAVE.DO.JV.T
0030			/ASSIGN-SYSOUT TO-FILE=N2O.OUT.LOAD.&(JV.ZEIT.T)
0040			/MODIFY-JOB-OPTIONS LOGGING=PARAMETERS(LISTING=YES)
0050			/REMARK *** EXECUTE N2ORAB1 ***
0060			/SET-FILE-LINK LINK-NAME=W01,FILE-NAME=N2O.RAB.INFO
0070			/FILE REC.PARMS, LINK=W02, RECFORM=VB, RECSIZE=189, BLKSIZE=193
0080			/ASSIGN-SYSDTA TO-FILE=*SYSCMD
0090			/MODIFY-JOB-SWITCHES ON=(4,5)
0100			/START-PROGRAM FROM-FILE=\$EDT
0110			LS=132, PS=60, MENU=OFF
0120			@WRITE 'N2O.RAB.IPT.BATCH' OVERWRITE
0130			@HALT
0140			/MODIFY-JOB-SWITCHES OFF=(4,5)
0150			/ASSIGN-SYSIPT TO-FILE=N2O.RAB.IPT.BATCH
0160			/MODIFY-JOB-SWITCHES ON=(2)
0170			/START-PROGRAM FROM-FRIL=\$ADABAS.NATBATCH
0180			LOGON N2OLIB
0190			N2ORAB1
0200			FIN
0210			/REMARK *** EXECUTE N2ORAB2 ***
0220			/FILE REC.PARMS, LINK=W01
0230			/FILE &BACKUP, LINK=W02
0240			/FILE REC.ACKN, LINK=W03, RECFORM=VB, RECSIZE=189, BLKSIZE=193
0250			/SET-JOB-STEP
0260			/ASSIGN-SYSIPT TO-FILE=N2O.RAB.IPT.BATCH
0270			/START-PROGRAM FROM-FILE=\$ADABAS.NATBATCH
0280			LOGON SYSTEM
0290			N2ORAB2
0300			FIN
0310			/REMARK *** EXECUTE N2ORAB3 ***
0320			/FILE REC.ACKN, LINK=W01
0330			/SET-JOB-STEP
0340			/ASSIGN-SYSIPT TO-FILE=N2O.RAB.IPT.BATCH
0350			/START-PROGRAM FROM-FILE=\$ADABAS.NATBATCH
0360			LOGON N2OLIB
0370			N2ORAB3
0380			FIN
0390			/ASSIGN-SYSIPT TO-FILE=*PRIMARY
0400			/DELETE-FILE FILE-NAME=N2O.RAB.IPT.BATCH,
0410			/OPTION=DESTROY-ALL
0420			/LOGOFF NOSPOOL
*****			End of list *****

```

Program      VMRAB      Library N2OBATCH
0010 /* Execute N2ORAB1 */
0020 address 'COMMAND'
0030 'ERASE N2ORAB1 CMSYNIN A'
0040 'EXECIO 1 DISKW N2ORAB1 CMWKF01 A 1 F 80 (STRING &INPUT'
0050 'EXECIO 1 DISKW N2ORAB1 CMSYNIN A 1 F 80 (STRING LOGON N2OLIB'
0060 'EXECIO 1 DISKW N2ORAB1 CMSYNIN A 2 F 80 (STRING N2ORAB1'
0070 'EXECIO 1 DISKW N2ORAB1 CMSYNIN A 3 F 80 (STRING FIN'
0080 'FILEDEF * CLEAR'
0090 'FILEDEF CMWKF01 N2ORAB1 CMWKF01 A'
0100 'FILEDEF CMWKF02 REC PARMS A RECFM VB LRECL 189 BLKSIZE 193'
0110 'FILEDEF CMSYNIN DISK N2ORAB1 CMSYNIN A'
0120 'FILEDEF CMPRINT PRINTER'
0130 'EXEC NAT BATCH'
0140 'ERASE N2ORAB1 CMSYNIN A'
0150 /*
0160 /* Execute N2ORAB2 */
0170 'ERASE N2ORAB2 CMSYNIN A'
0180 'EXECIO 1 DISKW N2ORAB2 CMSYNIN A 1 F 80 (STRING LOGON SYSTEM'
0190 'EXECIO 1 DISKW N2ORAB2 CMSYNIN A 2 F 80 (STRING N2ORAB2'
0200 'EXECIO 1 DISKW N2ORAB2 CMSYNIN A 3 F 80 (STRING FIN'
0210 'FILEDEF * CLEAR'
0220 'FILEDEF CMWKF01 REC PARMS A'
0230 'FILEDEF CMWKF02 &BACKUP'
0240 'FILEDEF CMWKF03 REC ACKN RECFM VB LRECL 189 BLKSIZE 193'
0250 'FILEDEF CMSYNIN DISK N2ORAB2 CMSYNIN A'
0260 'FILEDEF CMPRINT PRINTER'
0270 'EXEC NAT BATCH'
0280 'ERASE N2ORAB2 CMSYNIN A'
0290 'ERASE REC PARMS A'
0300 /* Execute N2ORAB3 */
0310 'ERASE N2ORAB3 CMSYNIN A'
0320 'EXECIO 1 DISKW N2ORAB3 CMSYNIN A 1 F 80 (STRING LOGON N2OLIB'
0330 'EXECIO 1 DISKW N2ORAB3 CMSYNIN A 2 F 80 (STRING N2ORAB3'
0340 'EXECIO 1 DISKW N2ORAB3 CMSYNIN A 3 F 80 (STRING FIN'
0350 'FILEDEF * CLEAR'
0360 'FILEDEF CMWKF01 REC ACKN a'
0370 'FILEDEF CMSYNIN DISK N2ORAB3 CMSYNIN A'
0380 'FILEDEF CMPRINT PRINTER'
0390 'EXEC NAT BATCH'
0400 'ERASE N2ORAB3 CMSYNIN A'
0410 'ERASE REC ACKN A'
0420 exit
***** End of list *****

```

```

Program      VSERAB      Library N2OBATCH
0010 * $$ JOB JNM=N2ORAB,CLASS=A,USER=&USERID
0020 * $$ LST CLASS=A,LST=SYSLST
0030 // JOB N2ORAB
0040 // DLBL CMWKF01,'RAB.INPUT.PARMS'
0050 // EXTENT SYS001,, ,nnnnn,nnnnn
0060 // EXEC IDCAMS,SIZE=AUTO
0070 REPRO INFILE(SYSIPT ENV(RECFM(FB) RECSZ(80))) -
0080 OUTFILE(CMWKF01 ENV(RECFM(FB) RECSZ(80) BLKSZ(80)))
0090 &INPUT
0100 /*
0110 * N2ORAB1 - VERIFY INPUT PARMS
0120 // ASSGN SYSIPT,SYSRDR
0130 // ASSGN SYS001,DISK,SHR
0140 // ASSGN SYS002,DISK,SHR
0150 // ASSGN SYS009,SYSLST
0160 // DLBL CMWKF01,'RAB.INPUT.PARMS'
0170 // EXTENT SYS001,, ,nnnnn,nnnnn
0180 // DLBL CMWKF02,'REC.PARMS'
0190 // EXTENT SYS002,, ,nnnnn,nnnnn
0200 // EXEC NATBATCH
0210 BWORKD=(1,1,80,FB,2,2,193,VB)
0220 /*
0230 ADARUN DB=xxx,SVC=yyy,DEVICE=zzzz
0240 /*

```

```

0250 LOGON N2OLIB
0260 N2ORAB1
0270 FIN
0280 /*
0290 * N2ORAB2 - RECOVER OBJECT TO TARGET
0300 // ASSGN SYS001,DISK,SHR
0310 // ASSGN SYS002,DISK,SHR
0320 // ASSGN SYS003,DISK,SHR
0330 // ASSGN SYS009,SYSLST
0340 // DLBL CMWKF01,'REC.PARMS'
0350 // EXTENT SYS001,, ,nnnnn,nnnnn
0360 // DLBL CMWKF02,'&BACKUP'
0370 // EXTENT SYS002,, ,nnnnn,nnnnn
0380 // DLBL CMWKF03,'REC.ACKN'
0390 // EXTENT SYS003,, ,nnnnn,nnnnn
0400 // EXEC NATBATCH
0410 BWORKD=(1,1,193,VB,2,2,5500,VB,3,3,193)
0420 /*
0430 ADARUN DB=xxx,SVC=yyy,DEVICE=zzzz
0440 /*
0450 LOGON SYSTEM
0460 N2ORAB2
0470 FIN
0480 /*
0490 * N2ORAB3 - ACKNOWLEDGE RECOVERY
0500 // ASSGN SYS001,DISK,SHR
0510 // ASSGN SYS009,SYSLST
0520 // DLBL CMWKF01,'REC.ACKN'
0530 // EXTENT SYS001,, ,nnnnn,nnnnn
0540 // EXEC NATBATCH
0550 BWORKD=(1,1,193,VB)
0560 /*
0570 ADARUN DB=xxx,SVC=yyy,DEVICE=zzzz
0580 /*
0590 LOGON N2OLIB
0600 N2ORAB3
0610 FIN
0620 /*
0630 /&
0640 * $$ EOJ
***** End of list *****

```

Recover from archive backup (3GL PDS Objects)

Program MVSRA3 Library N2OBATCH

```

0010 //N2ORAB3 JOB (ACCT),'RECOVER PDS ARCH BACKUP',CLASS=A,NOTIFY=&USERID
0020 /***
0030 /* THIS IS SAMPLE JCL FOR A PDS RECOVER FROM ARCHIVE BACKUP
0040 /***
0050 /* N2ORAB1 RUNS WHERE N2O IS INSTALLED
0060 /***
0070 //N2ORAB1 EXEC PGM=NATBATCH
0080 //CMWKF02 DD DSN=REC.PARMS,DISP=(NEW,PASS,DELETE),
0090 // SPACE=(TRK,(5,5),RLSE),UNIT=SYSDA,
0100 // DCB=(RECFM=VB,BLKSIZE=193,LRECL=189)
0110 //CMPRINT DD SYSOUT=*
0120 //CMSYNIN DD *
0130 LOGON N2OLIB
0140 N2ORAB1
0150 FIN
0160 /*
0170 //CMWKF01 DD *
0180 &INPUT
0190 /*
0200 /***
0210 /* N2ORAB2T RUNS ON THE TARGET RECOVERY ENVIRONMENT
0220 /***
0230 //N2ORAB2T EXEC PGM=NATBATCH
0240 //CMWKF01 DD DSN=REC.PARMS,DISP=(OLD,DELETE,CATLG)
0250 //CMWKF02 DD DSN=&BACKUP,DISP=(OLD,KEEP,KEEP)

```

```
0260 //CMWK03 DD DSN=REC.ACKN,DISP=(NEW,PASS,DELETE),
0270 //          SPACE=(TRK,(5,5),RLSE),UNIT=SYSDA,
0280 //          DCB=(RECFM=VB,BLKSIZE=193,LRECL=189)
0290 //CMWK05 DD DSN=&PDS(&MEMBER),DISP=SHR
0300 //CMPRINT DD SYSOUT=*
0310 //CMSYNIN DD *
0320 LOGON SYSTEM
0330 N2ORAB2T
0340 FIN
0350 /*
0360 /***
0370 /* N2ORAB3 RUNS WHERE N2O IS INSTALLED
0380 /***
0390 //N2ORAB3 EXEC PGM=NATBATCH
0400 //CMWK01 DD DSN=REC.ACKN,DISP=(OLD,DELETE,CATLG)
0410 //CMPRINT DD SYSOUT=*
0420 //CMSYNIN DD *
0430 LOGON N2OLIB
0440 N2ORAB3
0450 FIN
0460 /*
0470 /***
***** End of list *****
```

Recover Purged Events

```
Program      MVSREB      Library N2OBATCH
0010 //N2OREB JOB (ACCT),'RECOVER EVENT BACKUP',CLASS=A,NOTIFY=&USERID
0020 /***
0030 //N2OREB1 EXEC PGM=NATBATCH
0040 //CMWK01 DD DSN=&BACKUP,DISP=SHR
0050 //CMPRINT DD SYSOUT=*
0060 //CMPRT01 DD SYSOUT=*
0070 //CMPRT01 DD SYSOUT=*
0080 //CMPRT02 DD SYSOUT=*
0090 //CMPRT03 DD SYSOUT=*
0100 //CMPRT04 DD SYSOUT=*
0110 //CMSYNIN DD *
0120 LOGON N2OLIB
0130 N2OREB
0140 FIN
0150 /*
0160 /***
***** End of list *****
```

```
Program      BSREB      Library N2OBATCH
0010 /.N2O LOGON
0020 /CALL=PROCEDURE NAME=$TSOSAVE.DO.JV.T
0030 /ASSIGN-SYSOUT TO-FILE=N2O.OUT.LOAD.&(JV.ZEIT.T)
0040 /MODIFY-JOB-OPTIONS LOGGING=PARAMETERS(LISTING=YES)
0050 /REMARK *** EXECUTE N2O EVENT RECOVERY ***
0060 /FILE N2O.REPORT,LINK=P01
0070 /ASSIGN-SYSDTA TO-FILE=*SYSCMD
0080 /MODIFY-JOB-SWITCHES ON=(4,5)
0090 /START-PROGRAM FROM-FILE=$EDT
0100 LS=132,PS=60,MENU=OFF
0110 @WRITE 'N2O.REPT.IPT.BATCH' OVERWRITE
0120 @HALT
0130 /MODIFY-JOB-SWITCHES OFF=(4,5)
0140 /ASSIGN-SYSIPT TO-FILE=N2O.REPT.IPT.BATCH
0150 /MODIFY-JOB-SWITCHES ON=(2)
0160 /START-PROGRAM FROM-FRIL=$ADABAS.NATBATCH
0170 LOGON N2OLIB
0180 N2OREB
0190 FIN
0200 /FILE &BACKUP,LINK=W01
0210 /ASSIGN-SYSIPT TO-FILE=*PRIMARY
0220 /DELETE-FILE FILE-NAME=N2O.REPT.IPT.BATCH,
0230 /OPTION=DESTROY-ALL
```

```
0240 /LOGOFF NOSPOOL
***** End of list *****
```

```
Program      VMREB      Library N2OBATCH
0010 /* EXECUTE A EVENT RECOVERY */
0020 ADDRESS 'COMMAND'
0030 'ERASE N2OREB CMSYNIN A'
0040 'EXECIO 1 DISKW N2OREB CMSYNIN A 1 F 80 (STRING LOGON N2OLIB'
0050 'EXECIO 1 DISKW N2OREB CMSYNIN A 2 F 80 (STRING N2OREB'
0060 'EXECIO 1 DISKW N2OREB CMSYNIN A 3 F 80 (STRING FIN'
0070 'FILEDEF * CLEAR'
0080 'FILEDEF CMWKF01 DISK N2OREB &BACKUP A'
0090 'FILEDEF CMSYNIN DISK N2OREB CMSYNIN A'
0100 'FILEDEF CMPRINT PRINTER'
0110 'FILEDEF CMPRT01 PRINTER'
0120 'EXEC NAT BATCH'
0130 'ERASE N2OREB CMSYNIN A'
0140 exit
***** End of list *****
```

```
Program      VSEREB      Library N2OBATCH
0010 * $$ JOB JNM=N2OREPT,CLASS=A,USER=&USERID
0020 * $$ LST CLASS=A,LST=SYSLST
0030 // JOB N2OREPT
0040 * N2OREB - N2O EVENT RECOVERY JCL
0050 // ASSGN SYS001,DISK,SHR
0060 // ASSGN SYS009,SYSLST
0070 // DLBL CMWKF01,'&BACKUP'
0080 // EXTENT SYS001,,,,NNNNN,NNNNN
0090 // EXEC NATBATCH
0100 /BWORKD=(1,1,80,FB)
0110 /*
0120 ADARUN DB=XXX,SVC=YYY,DEVICE=ZZZZ
0130 /*
0140 LOGON N2OLIB
0150 N2OREB
0160 FIN
0170 /*
0180 /&
0190 * $$ EOJ
***** End of list *****
```

Reporting

```
Program      MVSREPT      Library N2OBATCH
0010 //N2OREPT JOB (20100),'EXECUTE REPORT',CLASS=A,NOTIFY=&USERID
0020 //***
0030 //* THIS IS SAMPLE JCL FOR ALL OF N2O REPORTS AND FOR THE
0040 //* DOCUMENTATION TOOLS SUBSYSTEM
0050 //*
0060 //* THIS JCL SHOULD BE RENAMED AS N2OREPT
0070 //***
0080 //* N2OREPT RUNS WHERE N2O IS INSTALLED
0090 //***
0100 //N2OREPT EXEC PGM=NATBATCH
0110 //CMPRINT DD SYSOUT=*
0120 //CMPRT01 DD SYSOUT=*
0130 //CMSYNIN DD *
0140 LOGON N2OLIB
0150 &REPORT
0160 &INPUT
0170 FIN
0180 /*
0190 //*
***** End of list *****
```

```

Program      BSREPT      Library N2OBATCH
0010 / .N2O LOGON
0020 /CALL-PROCEDURE NAME=$TSOSAVE.DO.JV.T
0030 /ASSIGN-SYSOUT TO-FILE=N2O.OUT.LOAD.&(JV.ZEIT.T)
0040 /MODIFY-JOB-OPTIONS LOGGING=PARAMETERS (LISTING=YES)
0050 /REMARK *** EXECUTE N2OREPORT ***
0060 /FILE N2O.REPORT, LINK=P01
0070 /ASSIGN-SYSDTA TO-FILE=*SYSCMD
0080 /MODIFY-JOB-SWITCHES ON=(4,5)
0090 /START-PROGRAM FROM-FILE=$EDT
0100 LS=132, PS=60, MENU=OFF
0110 @WRITE 'N2O.REPT.IPT.BATCH' OVERWRITE
0120 @HALT
0130 /MODIFY-JOB-SWITCHES OFF=(4,5)
0140 /ASSIGN-SYSIPT TO-FILE=N2O.REPT.IPT.BATCH
0150 /MODIFY-JOB-SWITCHES ON=(2)
0160 /START-PROGRAM FROM-FRIL=$ADABAS.NATBATCH
0170 LOGON N2OLIB
0180 &REPORT
0190 &INPUT
0200 FIN
0210 /ASSIGN-SYSIPT TO-FILE=*PRIMARY
0220 /DELETE-FILE FILE-NAME=N2O.REPT.IPT.BATCH,
0230 /OPTION=DESTROY-ALL
0240 /LOGOFF NOSPOOL
***** End of list *****

```

```

Program      VMREPT      Library N2OBATCH
0010 /* Execute a report */
0020 address 'COMMAND'
0030 'ERASE N2OREPT CMSYNIN A'
0040 'EXECIO 1 DISKW N2OREPT CMSYNIN A 1 F 80 (STRING LOGON N2OLIB'
0050 'EXECIO 1 DISKW N2OREPT CMSYNIN A 2 F 80 (STRING &REPORT'
0060 'EXECIO 1 DISKW N2OREPT CMSYNIN A 3 F 80 (STRING &INPUT'
0070 'EXECIO 1 DISKW N2OREPT CMSYNIN A 4 F 80 (STRING FIN'
0080 'FILEDEF * CLEAR'
0090 'FILEDEF CMSYNIN DISK N2OREPT CMSYNIN A'
0100 'FILEDEF CMPRINT PRINTER'
0110 'FILEDEF CMPRT01 PRINTER'
0120 'EXEC NAT BATCH'
0130 'ERASE N2OREPT CMSYNIN A'
0140 exit
***** End of list *****

```

```

Program      VSEREPT      Library N2OBATCH
0010 * $$ JOB JNM=N2OREPT, CLASS=A, USER=&USERID
0020 * $$ LST CLASS=A, LST=SYSLST
0030 // JOB N2OREPT
0040 * N2OREPT - N2O REPORTING
0050 // ASSGN SYSIPT, SYSRDR
0060 // ASSGN SYS009, SYSLST
0070 // EXEC NATBATCH
0080 /*
0090 ADARUN DB=xxx, SVC=yyy, DEVICE=zzzz
0100 /*
0110 LOGON N2OLIB
0120 &REPORT
0130 &INPUT
0140 FIN
0150 /*
0160 /&
0170 * $$ EOJ
***** End of list *****

```

N2OSCAN**Program MVSSCAN Library N2OBATCH**

```
0010 //N2OSCAN JOB (ACCOUNTING),'N2OSCAN ',CLASS=A,TIME=40,NOTIFY=&USERID
0020 /***
0030 /** THIS IS SAMPLE JCL FOR THE TOOLBOX OPTION FOR THE N2OSCAN UTILITY
0040 /** THIS JOB SHOULD BE RENAMED N2OSCAN
0050 /***
0060 /** N2OSCAN RUNS WHERE N2O IS INSTALLED
0070 /***
0080 //N2OSCAN EXEC PGM=NATBATCH
0090 /**
0100 //CMPRINT DD SYSOUT=*
0110 //CMPRT02 DD SYSOUT=*
0120 //CMSYNIN DD *
0130 LOGON N2OLIB
0140 N2OSCANX
0150 &INPUT
0160 FIN
0170 /*
0180 /**
***** End of list *****
```

Program VMSCAN Library N2OBATCH

```
0010 /* Execute N2OSCAN Utility */
0020 address 'COMMAND'
0030 'ERASE N2OSCAN CMSYNIN A'
0040 'EXECIO 1 DISKW N2OSCAN CMSYNIN A 1 F 80 (STRING LOGON N2OLIB'
0050 'EXECIO 1 DISKW N2OSCAN CMSYNIN A 2 F 80 (STRING N2OSCANX'
0060 'EXECIO 1 DISKW N2OSCAN CMSYNIN A 3 F 80 (STRING &INPUT'
0070 'EXECIO 1 DISKW N2OSCAN CMSYNIN A 4 F 80 (STRING FIN'
0080 'FILEDEF * CLEAR'
0090 'FILEDEF CMSYNIN DISK N2OSCAN CMSYNIN A'
0100 'FILEDEF CMPRINT PRINTER'
0110 'FILEDEF CMPRT01 PRINTER'
0120 'EXEC NAT BATCH'
0130 'ERASE N2OSCAN CMSYNIN A'
0140 exit
***** End of list *****
```

Program VESCAN Library N2OBATCH

```
0010 * $$ JOB JNM=N2OSCAN,CLASS=A,USER=&USERID
0020 * $$ LST CLASS=A,LST=SYSLST
0030 * $$ LST CLASS=A,LST=02E,DISP=K,JSEP=0
0040 // JOB N2OSCAN
0050 * N2OSCAN - N2OSCAN UTILITY
0060 // ASSGN SYSIPT,YSRDR
0070 // ASSGN SYS002,02E
0080 // EXEC NATBATCH
0090 /*
0100 ADARUN DB=xxx,SVC=yyy,DEVICE=zzzz
0110 /*
0120 LOGON N2OLIB
0130 N2OSCANX
0140 &INPUT
0150 FIN
0160 /*
0170 /&
0180 * $$ EOJ
***** End of list *****
```


N2OSCAN delete specific scan output set

Program MVSSCBD1 Library N2OBATCH

```

0010 //N2OSCBD1 JOB (ACCOUNTING),'N2OSCAN DELETE',CLASS=A,NOTIFY=&USERID
0020 //*****
0030 //* THIS IS SAMPLE N2OSCAN DELETE JCL (FOR N2OSCBD1)
0040 //* THIS JOB SHOULD BE RENAMED TO N2OSCBD1
0050 //*****
0060 //* N2OSCBD1 RUNS WHERE N2O IS INSTALLED
0070 //*
0080 //N2OSCBD1 EXEC PGM=NATBATCH
0090 //CMPRINT DD SYSOUT=*
0100 //CMPRT01 DD SYSOUT=*
0110 //CMPRT02 DD SYSOUT=*
0120 //CMSYNIN DD *
0130 LOGON N2OLIB
0140 N2OSCBD1
0150 FIN
0160 /*
0170 //CMWKF01 DD *
0180 &INPUT
0190 /*
0200 /*
***** End of list *****

```

Program VMSCBD1 Library N2OBATCH

```

0010 /* Execute N2OSCBD1 */
0020 address 'COMMAND'
0030 'ERASE N2OSCBD1 CMSYNIN A'
0040 'ERASE N2O CMWKF01 A'
0050 'EXECIO 1 DISKW N2OSCBD1 CMWKF01 A 1 F 80 (STRING &INPUT'
0060 'EXECIO 1 DISKW N2OSCBD1 CMSYNIN A 1 F 80 (STRING LOGON N2OLIB'
0070 'EXECIO 1 DISKW N2OSCBD1 CMSYNIN A 2 F 80 (STRING N2OSCBD1'
0080 'EXECIO 1 DISKW N2OSCBD1 CMSYNIN A 3 F 80 (STRING FIN'
0090 'FILEDEF * CLEAR'
0100 'FILEDEF CMWKF01 DISK N2OSCBD1 CMWKF01 A'
0110 'FILEDEF CMSYNIN DISK N2OSCBD1 CMSYNIN A'
0120 'FILEDEF CMPRINT PRINTER'
0130 'FILEDEF CMPRT01 PRINTER'
0140 'FILEDEF CMPRT02 PRINTER'
0150 'EXEC NAT BATCH'
0160 exit
***** End of list *****

```

```
Program      VSESCBD1 Library N2OBATCH
0010 * N2OSCBD1 - N2OSCAN DELETE 1
0020 * $$ JOB JNM=N2OSCBD1,CLASS=A,USER=&USERID
0030 * $$ LST CLASS=A,LST=SYSLST
0040 // JOB N2OSCBD1
0050 /*
0060 * N2OSCBD1 -
0070 // DLBL CMWKF01,'N2O.SCBD1.INPUT'
0080 // EXTENT SYS001,,,,nnnnn,nnnnn
0090 // EXEC IDCAMS,SIZE=AUTO
0100     REPRO INFILE(SYSIPT ENV(RECFM(FB) RECSZ(80))) -
0110           OUTFILE(CMWKF01 ENV(RECFM(FB) RECSZ(80) BLKSZ(80)))
0120 &INPUT
0130 /*
0140 // ASSGN SYSIPT,SYSRDR
0150 // ASSGN SYS000,SYSRDR
0160 // ASSGN SYS001,DISK,SHR
0170 // ASSGN SYS009,SYSLST
0180 // DLBL CMWKF01,'N2O.SCBD1.INPUT'
0190 // EXTENT SYS001,,,,nnnnn,nnnnn
0200 // EXEC NATBATCH
0210 BWORKD=(1,1,80,FB)
0220 /*
0230 ADARUN DB=xxx,SVC=yyy,DEVICE=zzzz
0240 /*
0250 LOGON N2OLIB
0260 N2OSCBD1
0270 FIN
0280 /*
0290 /&
0300 * $$ EOJ
***** End of list *****
```

N2OSCAN Batch Delete by Date and User ID

```
Program      MVSSCBD2 Library N2OBATCH
0010 //N2OSCBD2 JOB (ACCOUNTING),'N2OSCAN DELETE',CLASS=A,NOTIFY=&USERID
0020 //*****
0030 /* THIS IS SAMPLE N2OSCAN DELETE JCL (FOR N2OSCBD2)
0040 /* THIS JOB SHOULD BE RENAMED TO N2OSCBD2
0050 //*****
0060 /* N2OSCBD2 RUNS WHERE N2O IS INSTALLED
0070 /*
0080 //N2OSCBD2 EXEC PGM=NATBATCH
0090 //CMPRINT DD SYSOUT=*
0100 //CMPRT01 DD SYSOUT=*
0110 //CMPRT02 DD SYSOUT=*
0120 //CMSYNIN DD *
0130 LOGON N2OLIB
0140 N2OSCBD2
0150 FIN
0160 /*
0170 //CMWKF01 DD *
0180 &INPUT
0190 /*
0200 /*
***** End of list *****
```

Program VMSCBD2 Library N2OBATCH

```

0010 /* Execute N2OSCBD2 */
0020 address 'COMMAND'
0030 'ERASE N2OSCBD2 CMSYNIN A'
0040 'ERASE N2O CMWKF01 A'
0050 'EXECIO 1 DISKW N2OSCBD2 CMWKF01 A 1 F 80 (STRING &INPUT'
0060 'EXECIO 1 DISKW N2OSCBD2 CMSYNIN A 1 F 80 (STRING LOGON N2OLIB'
0070 'EXECIO 1 DISKW N2OSCBD2 CMSYNIN A 2 F 80 (STRING N2OSCBD2'
0080 'EXECIO 1 DISKW N2OSCBD2 CMSYNIN A 3 F 80 (STRING FIN'
0090 'FILEDEF * CLEAR'
0100 'FILEDEF CMWKF01 DISK N2OSCBD2 CMWKF01 A'
0110 'FILEDEF CMSYNIN DISK N2OSCBD2 CMSYNIN A'
0120 'FILEDEF CMPRINT PRINTER'
0130 'FILEDEF CMPRT01 PRINTER'
0140 'FILEDEF CMPRT02 PRINTER'
0150 'EXEC NAT BATCH'
0160 exit
***** End of list *****

```

Program VSESCBD2 Library N2OBATCH

```

0010 * N2OSCBD2 - N2OSCAN DELETE 1
0020 * $$ JOB JNM=N2OSCBD2,CLASS=A,USER=&USERID
0030 * $$ LST CLASS=A,LST=SYSLST
0040 // JOB N2OSCBD2
0050 /*
0060 * N2OSCBD2 -
0070 // DLBL CMWKF01,'N2O.SCBD2.INPUT'
0080 // EXTENT SYS001,, ,nnnnn,nnnnn
0090 // EXEC IDCAMS,SIZE=AUTO
0100 REPRO INFILE(SYSIPT ENV(RECFM(FB) RECSZ(80))) -
0110 OUTFILE(CMWKF01 ENV(RECFM(FB) RECSZ(80) BLKSZ(80)))
0120 &INPUT
0130 /*
0140 // ASSGN SYSIPT,SYSRDR
0150 // ASSGN SYS001,DISK,SHR
0160 // ASSGN SYS000,SYSRDR
0170 // ASSGN SYS009,SYSLST
0180 // DLBL CMWKF01,'N2O.SCBD2.INPUT'
0190 // EXTENT SYS001,, ,nnnnn,nnnnn
0200 // EXEC NATBATCH
0210 BWORKD=(1,1,80,FB)
0220 /*
0230 ADARUN DB=xxx,SVC=yyy,DEVICE=zzzz
0240 /*
0250 LOGON N2OLIB
0260 N2OSCBD2
0270 FIN
0280 /*
0290 /&
0300 * $$ EOJ
***** End of list *****

```

N2OSCAN Batch source display**Program MVSSCBSD Library N2OBATCH**

```
0010 //N2OSCBSD JOB (ACCOUNTING),'N2OSCAN BSD',CLASS=A,NOTIFY=&USERID
0020 //*****
0030 /* THIS IS SAMPLE N2OSCAN BATCH SOURCE DISPLAY
0040 /* THIS JOB SHOULD BE RENAMED TO N2OSCBSD
0050 //*****
0060 /* N2OSCBSD RUNS WHERE N2O IS INSTALLED
0070 /*
0080 //N2OSCBSD EXEC PGM=NATBATCH
0090 //CMPRINT DD SYSOUT=*
0100 //CMPRT01 DD SYSOUT=*
0110 //CMPRT02 DD SYSOUT=*
0120 //CMSYNIN DD *
0130 LOGON N2OLIB
0140 N2OSCBSD
0150 FIN
0160 /*
0170 //CMWKF01 DD *
0180 &INPUT
0190 /*
0200 /*
***** End of list *****
```

Program VMSCBSD Library N2OBATCH

```
0010 /* Execute N2OSCBSD */
0020 address 'COMMAND'
0030 'ERASE N2OSCBSD CMSYNIN A'
0040 'ERASE N2O CMWKF01 A'
0050 'EXECIO 1 DISKW N2OSCBSD CMWKF01 A 1 F 80 (STRING &INPUT'
0060 'EXECIO 1 DISKW N2OSCBSD CMSYNIN A 1 F 80 (STRING LOGON N2OLIB'
0070 'EXECIO 1 DISKW N2OSCBSD CMSYNIN A 2 F 80 (STRING N2OSCBSD'
0080 'EXECIO 1 DISKW N2OSCBSD CMSYNIN A 3 F 80 (STRING FIN'
0090 'FILEDEF * CLEAR'
0100 'FILEDEF CMWKF01 DISK N2OSCBSD CMWKF01 A'
0110 'FILEDEF CMSYNIN DISK N2OSCBSD CMSYNIN A'
0120 'FILEDEF CMPRINT PRINTER'
0130 'FILEDEF CMPRT01 PRINTER'
0140 'FILEDEF CMPRT02 PRINTER'
0150 'EXEC NAT BATCH'
0160 exit
***** End of list *****
```

```
Program      VSESCBSD Library N2OBATCH
0010 * N2OSCBSD - N2OSCAN BATCH SOURCE DISPLAY
0020 * $$ JOB JNM=N2OSCBSD,CLASS=A,USER=&USERID
0030 * $$ LST CLASS=A,LST=SYSLST
0040 // JOB N2OSCBSD
0050 /*
0060 * N2OSCBSD -
0070 // DLBL CMWKF01,'N2O.SCBSD.INPUT'
0080 // EXTENT SYS001,,,,nnnnn,nnnnn
0090 // EXEC IDCAMS,SIZE=AUTO
0100     REPRO INFILE(SYSIPT ENV(RECFM(FB) RECSZ(80))) -
0110           OUTFILE(CMWKF01 ENV(RECFM(FB) RECSZ(80) BLKSZ(80)))
0120 &INPUT
0130 /*
0140 // ASSGN SYS001,DISK,SHR
0150 // ASSGN SYSIPT,SYSRDR
0160 // ASSGN SYS000,SYSRDR
0170 // ASSGN SYS009,SYSLST
0180 // DLBL CMWKF01,'N2O.SCBSD.INPUT'
0190 // EXTENT SYS001,,,,nnnnn,nnnnn
0200 // EXEC NATBATCH
0210 BWORKD=(1,1,80,FB)
0220 /*
0230 ADARUN DB=xxx,SVC=yyy,DEVICE=zzzz
0240 /*
0250 LOGON N2OLIB
0260 N2OSCBSD
0270 FIN
0280 /*
0290 /&
0300 * $$ EOJ
***** End of list *****
```

N2OSCAN**Program MVSSCBX Library N2OBATCH**

```
0010 //N2OSCBX JOB (ACCOUNTING),'N2OSCAN',CLASS=A,NOTIFY=&USERID
0020 //*****
0030 /* THIS IS SAMPLE N2OSCAN JCL
0040 /* THIS JOB SHOULD BE RENAMED TO N2OSCBX
0050 //*****
0060 /* N2OSCBX RUNS WHERE N2O IS INSTALLED
0070 /*
0080 //N2OSCBX EXEC PGM=NATBATCH
0090 //CMPRINT DD SYSOUT=*
0100 //CMPRT01 DD SYSOUT=*
0110 //CMPRT02 DD SYSOUT=*
0120 //CMSYNIN DD *
0130 LOGON N2OLIB
0140 N2OSCBX
0150 FIN
0160 /*
0170 //CMWKF01 DD *
0180 &INPUT
0190 /*
0200 /*
***** End of list *****
```

Program VMSCBX Library N2OBATCH

```
0010 /* Execute N2OSCBX */
0020 address 'COMMAND'
0030 'ERASE N2OSCBX CMSYNIN A'
0040 'ERASE N2O CMWKF01 A'
0050 'EXECIO 1 DISKW N2OSCBX CMWKF01 A 1 F 80 (STRING &INPUT'
0060 'EXECIO 1 DISKW N2OSCBX CMSYNIN A 1 F 80 (STRING LOGON N2OLIB'
0070 'EXECIO 1 DISKW N2OSCBX CMSYNIN A 2 F 80 (STRING N2OSCBX'
0080 'EXECIO 1 DISKW N2OSCBX CMSYNIN A 3 F 80 (STRING FIN'
0090 'FILEDEF * CLEAR'
0100 'FILEDEF CMWKF01 DISK N2OSCBX CMWKF01 A'
0110 'FILEDEF CMSYNIN DISK N2OSCBX CMSYNIN A'
0120 'FILEDEF CMPRINT PRINTER'
0130 'FILEDEF CMPRT01 PRINTER'
0140 'FILEDEF CMPRT02 PRINTER'
0150 'EXEC NAT BATCH'
0160 exit
***** End of list *****
```

```

Program      VSESCBX  Library N2OBATCH
0010 * N2OSCBX - N2OSCAN
0020 * $$ JOB JNM=N2OSCBX,CLASS=A,USER=&USERID
0030 * $$ LST CLASS=A,LST=SYSLST
0040 // JOB N2OSCBX
0050 /*
0060 * N2OSCBX -
0070 // DLBL CMWKF01,'N2O.SCBX.INPUT'
0080 // EXTENT SYS001,, ,nnnnn,nnnnn
0090 // EXEC IDCAMS,SIZE=AUTO
0100     REPRO INFILE(SYSIPT ENV(RECFM(FB) RECSZ(80))) -
0110           OUTFILE(CMWKF01 ENV(RECFM(FB) RECSZ(80) BLKSZ(80)))
0120 &INPUT
0130 /*
0140 // ASSGN SYSIPT,SYSRDR
0150 // ASSGN SYS001,DISK,SHR
0160 // ASSGN SYS000,SYSRDR
0170 // ASSGN SYS009,SYSLST
0180 // DLBL CMWKF01,'N2O.SCBX.INPUT'
0190 // EXTENT SYS001,, ,nnnnn,nnnnn
0200 // EXEC NATBATCH
0210 BWORKD=(1,1,80,FB)
0220 /*
0230 ADARUN DB=xxx,SVC=yyy,DEVICE=zzzz
0240 /*
0250 LOGON N2OLIB
0260 N2OSCBX
0270 FIN
0280 /*
0290 /&
0300 * $$ EOJ
***** End of list *****

```

N2OSCAN Standard report**Program MVSSCB01 Library N2OBATCH**

```
0010 //N2OSCB01 JOB (ACCOUNTING),'N2OSCAN B01',CLASS=A,NOTIFY=&USERID
0020 //*****
0030 /* THIS IS SAMPLE N2OSCAN OUTPUT STANDARD REPORT
0040 /* THIS JOB SHOULD BE RENAMED TO N2OSCB01
0050 //*****
0060 /* N2OSCB01 RUNS WHERE N2O IS INSTALLED
0070 /*
0080 //N2OSCB01 EXEC PGM=NATBATCH
0090 //CMPRINT DD SYSOUT=*
0100 //CMPRT01 DD SYSOUT=*
0110 //CMPRT02 DD SYSOUT=*
0120 //CMSYNIN DD *
0130 LOGON N2OLIB
0140 N2OSCB01
0150 FIN
0160 /*
0170 //CMWKF01 DD *
0180 &INPUT
0190 /*
0200 /*
***** End of list *****
```

Program VMSCB01 Library N2OBATCH

```
0010 /* Execute N2OSCB01 */
0020 address 'COMMAND'
0030 'ERASE N2OSCB01 CMSYNIN A'
0040 'ERASE N2O CMWKF01 A'
0050 'EXECIO 1 DISKW N2OSCB01 CMWKF01 A 1 F 80 (STRING &INPUT'
0060 'EXECIO 1 DISKW N2OSCB01 CMSYNIN A 1 F 80 (STRING LOGON N2OLIB'
0070 'EXECIO 1 DISKW N2OSCB01 CMSYNIN A 2 F 80 (STRING N2OSCB01'
0080 'EXECIO 1 DISKW N2OSCB01 CMSYNIN A 3 F 80 (STRING FIN'
0090 'FILEDEF * CLEAR'
0100 'FILEDEF CMWKF01 DISK N2OSCB01 CMWKF01 A'
0110 'FILEDEF CMSYNIN DISK N2OSCB01 CMSYNIN A'
0120 'FILEDEF CMPRINT PRINTER'
0130 'FILEDEF CMPRT01 PRINTER'
0140 'FILEDEF CMPRT02 PRINTER'
0150 'EXEC NAT BATCH'
0160 exit
***** End of list *****
```


Program VSESCB01 Library N2OBATCH

```

0010 * N2OSCB01 - N2OSCAN OUTPUT STD REPORT
0020 * $$ JOB JNM=N2OSCB01,CLASS=A,USER=&USERID
0030 * $$ LST CLASS=A,LST=SYSLST
0040 // JOB N2OSCB01
0050 /*
0060 * N2OSCB01 -
0070 // DLBL CMWKF01,'N2O.SCB01.INPUT'
0080 // EXTENT SYS001,,,,nnnnn,nnnnn
0090 // EXEC IDCAMS,SIZE=AUTO
0100 REPRO INFILE(SYSIPT ENV(RECFM(FB) RECSZ(80))) -
0110 OUTFILE(CMWKF01 ENV(RECFM(FB) RECSZ(80) BLKSZ(80)))
0120 &INPUT
0130 /*
0140 // ASSGN SYSIPT,SYSRDR
0150 // ASSGN SYS001,DISK,SHR
0160 // ASSGN SYS000,SYSRDR
0170 // ASSGN SYS009,SYSLST
0180 // DLBL CMWKF01,'N2O.SCB01.INPUT'
0190 // EXTENT SYS001,,,,nnnnn,nnnnn
0200 // EXEC NATBATCH
0210 BWORKD=(1,1,80,FB)
0220 /*
0230 ADARUN DB=xxx,SVC=yyy,DEVICE=zzzz
0240 /*
0250 LOGON N2OLIB
0260 N2OSCB01
0270 FIN
0280 /*
0290 /&
0300 * $$ EOJ
***** End of list *****

```

N2OSCAN String found report

Program MVSSCB02 Library N2OBATCH

```

0010 //N2OSCB02 JOB (ACCOUNTING),'N2OSCAN B02',CLASS=A,NOTIFY=&USERID
0020 //*****
0030 /* THIS IS SAMPLE N2OSCAN STRING FOUND REPORT
0040 /* THIS JOB SHOULD BE RENAMED TO N2OSCB02
0050 //*****
0060 /* N2OSCB02 RUNS WHERE N2O IS INSTALLED
0070 /*
0080 //N2OSCB02 EXEC PGM=NATBATCH
0090 //SYSOUT DD SYSOUT=*
0100 //CMPRINT DD SYSOUT=*
0110 //CMPRT01 DD SYSOUT=*
0120 //CMPRT02 DD SYSOUT=*
0130 //CMSYNIN DD *
0140 LOGON N2OLIB
0150 N2OSCB02
0160 FIN
0170 /*
0180 //CMWKF01 DD *
0190 &INPUT
0200 /*
0210 /*
***** End of list *****

```

Program VMSCB02 Library N2OBATCH

```

0010 /* Execute N2OSCB02 */
0020 address 'COMMAND'
0030 'ERASE N2OSCB02 CMSYNIN A'
0040 'ERASE N2O CMWKF01 A'
0050 'EXECIO 1 DISKW N2OSCB02 CMWKF01 A 1 F 80 (STRING &INPUT'
0060 'EXECIO 1 DISKW N2OSCB02 CMSYNIN A 1 F 80 (STRING LOGON N2OLIB'
0070 'EXECIO 1 DISKW N2OSCB02 CMSYNIN A 2 F 80 (STRING N2OSCB02'
0080 'EXECIO 1 DISKW N2OSCB02 CMSYNIN A 3 F 80 (STRING FIN'
0090 'FILEDEF * CLEAR'

```

```
0100 'FILEDEF CMWKF01 DISK N2OSCB02 CMWKF01 A'
0110 'FILEDEF CMSYNIN DISK N2OSCB02 CMSYNIN A'
0120 'FILEDEF CMPRINT PRINTER'
0130 'FILEDEF CMPRT01 PRINTER'
0140 'FILEDEF CMPRT02 PRINTER'
0150 'EXEC NAT BATCH'
0160 exit
***** End of list *****
```

Program VESCB02 Library N2OBATCH

```
0010 * N2OSCB02 - N2OSCAN STRING FOUND REPORT
0020 * $$ JOB JNM=N2OSCB02,CLASS=A,USER=&USERID
0030 * $$ LST CLASS=A,LST=SYSLST
0040 // JOB N2OSCB02
0050 /*
0060 * N2OSCB02 -
0070 // DLBL CMWKF01,'N2O.SCB02.INPUT'
0080 // EXTENT SYS001,,,,nnnnn,nnnnn
0090 // EXEC IDCAMS,SIZE=AUTO
0100 REPRO INFILE(SYSIPT ENV(RECFM(FB) RECSZ(80))) -
0110 OUTFILE(CMWKF01 ENV(RECFM(FB) RECSZ(80) BLKSZ(80)))
0120 &INPUT
0130 /*
0140 // ASSGN SYSIPT,SYSRDR
0150 // ASSGN SYS001,DISK,SHR
0160 // ASSGN SYS000,SYSRDR
0170 // ASSGN SYS009,SYSLST
0180 // DLBL CMWKF01,'N2O.SCB02.INPUT'
0190 // EXTENT SYS001,,,,nnnnn,nnnnn
0200 // EXEC NATBATCH
0210 BWORKD=(1,1,80,FB)
0220 /*
0230 ADARUN DB=xxx,SVC=yyy,DEVICE=zzzz
0240 /*
0250 LOGON N2OLIB
0260 N2OSCB02
0270 FIN
0280 /*
0290 /&
0300 * $$ EOJ
***** End of list *****
```

Batch Update of Environment FUSER/FDIC Information**Program MVSUML Library N2OBATCH**

```
0010 //N2OBATCH JOB 'UPDATE ENVIRONMENT',MSGLEVEL=1,
0020 // CLASS=C,MSGCLASS=X,REGION=4M,NOTIFY=&USERID
0030 /*
0040 /* UPDATE THE FUSER/FDIC INFORMATION FOR AN EXISTING ENVIRONMENT
0050 /* THIS MEMBER SHOULD BE RENAMED NATUML
0060 /* THIS STEP RUNS WHERE N2O IS INSTALLED
0070 /*
0080 //STEP1 EXEC PGM=NATBATCH,
0090 // TIME=1400,COND=(9,LT)
0100 /*
0110 //CMPRINT DD SYSOUT=*
0120 //CMPRT01 DD SYSOUT=*
0130 //CMSYNIN DD *
0140 LOGON N2OLIB
0150 N2O5210P
0160 FIN
0170 /*
0180 //CMWKF01 DD *
0190 &INPUT
0200 /*
0210 /*
***** End of list *****
```

```

Program      BSUML      Library N2OBATCH
0010 /REMARK *** RENAME NATUML ***
0020 /.N2O LOGON
0030 /CALL-PROCEDURE NAME=$TSOSAVE.DO.JV.T
0040 /ASSIGN-SYSOUT TO-FILE=N2O.OUT.LOAD.&(JV.ZEIT.T)
0050 /MODIFY-JOB-OPTIONS LOGGING=PARAMETERS (LISTING=YES)
0060 /REMARK *** EXECUTE N2OUML ***
0070 /FILE CAPT1.INPUT, LINK=W01
0080 /ASSIGN-SYSDTA TO-FILE=*SYSCMD
0090 /MODIFY-JOB-SWITCHES ON=(4,5)
0100 /START-PROGRAM FROM-FILE=$EDT
0110 LS=132, PS=60, MENU=OFF
0120 @WRITE 'N2O.CAPTURE.IPT.BATCH' OVERWRITE
0130 @HALT
0140 /MODIFY-JOB-SWITCHES OFF=(4,5)
0150 /ASSIGN-SYSIPT TO-FILE=N2O.CAPTURE.IPT.BATCH
0160 /MODIFY-JOB-SWITCHES ON=(2)
0170 /START-PROGRAM FROM-FRIL=$ADABAS.NATBATCH
0180 LOGON N2OLIB
0190 N2OUML
0200 FIN
0210 /ASSIGN-SYSIPT TO-FILE=*PRIMARY
0220 /DELETE-FILE FILE-NAME=N2O.CAPTURE.IPT.BATCH,
0230 /OPTION=DESTROY-ALL
0240 /LOGOFF NOSPOOL
***** End of list *****

```

```

Program      VMUML      Library N2OBATCH
0010 /* EXECUTE N2OUML RENAME THIS TO NATUML */
0020 address 'COMMAND'
0030 'ERASE N2OUML1 CMSYNIN A'
0040 'ERASE CAPTURE DATA A'
0050 'ERASE N2OUML1 CMWKF01 A'
0060 'EXECIO 1 DISKW N2OUML1 CMSYNIN A 1 F 80 (STRING LOGON N2OLIB'
0070 'EXECIO 1 DISKW N2OUML1 CMSYNIN A 2 F 80 (STRING N2OUML1'
0080 'EXECIO 1 DISKW N2OUML1 CMSYNIN A 3 F 80 (STRING FIN'
0090 'EXECIO 1 DISKW N2OUML1 CMWKF01 A 1 F 80 (STRING &INPUT'
0100 'FILEDEF * CLEAR'
0110 'FILEDEF CMSYNIN DISK N2OUML1 CMSYNIN A'
0120 'FILEDEF CMWKF01 DISK N2OUML1 CMWKF01 A'
0130 'FILEDEF CMPRINT PRINTER'
0140 'EXEC NAT BATCH'
0150 'ERASE N2OUML1 CMSYNIN A'
0160 exit
***** End of list *****

```

```
Program      VSEUML      Library N2OBATCH
0010 * N2OUML - MODIFY ENVIRONMENT  RENAME NATUML
0020 * $$ JOB JNM=N2OUML1,CLASS=A,USER=&USERID
0030 * $$ LST CLASS=A,LST=SYSLST
0040 // JOB N2OUML1
0050 /*
0060 * N2OUML1 -
0070 // DLBL CMWKF01,'N2O.UML.INPUT'
0080 // EXTENT SYS001,,,,nnnnn,nnnnn
0090 // EXEC IDCAMS,SIZE=AUTO
0100     REPRO INFILE(SYSIPT ENV(RECFM(FB) RECSZ(80))) -
0110           OUTFILE(CMWKF01 ENV(RECFM(FB) RECSZ(80) BLKSZ(80)))
0120 &INPUT
0130 /*
0140 // ASSGN SYSIPT,SYSRDR
0150 // ASSGN SYS001,DISK,SHR
0160 // ASSGN SYS000,SYSRDR
0170 // ASSGN SYS009,SYSLST
0180 // DLBL CMWKF01,'N2O.UML.INPUT'
0190 // EXTENT SYS001,,,,nnnnn,nnnnn
0200 // EXEC NATBATCH
0210 BWORKD=(1,1,80,FB)
0220 /*
0230 ADARUN DB=xxx,SVC=yyy,DEVICE=zzzz
0240 /*
0250 LOGON SYSTEM
0260 N2OUML
0270 FIN
0280 /*
0290 /&
0300 * $$ EOJ
***** End of list *****
```

Archive Backup Reporting

```
Program      MVSWKRP      Library N2OBATCH
0010 //N2OREPT JOB (20100),'EXECUTE REPORT',CLASS=A,NOTIFY=&USERID
0020 //***
0030 /* THIS IS SAMPLE JCL FOR THE N2O ARCHIVE BACKUP REPORT
0040 //***
0050 /* N2OREPT RUNS WHERE N2O IS INSTALLED
0060 //***
0070 //N2OREPT EXEC PGM=NATBATCH
0080 //CMPRINT DD SYSOUT=*
0090 //CMPRT01 DD SYSOUT=*
0100 //CMSYNIN DD *
0110 LOGON N2OLIB
0120 N2OTOLC
0130 &INPUT
0140 FIN
0150 //CMWKF01 DD DSN=&BACKUP,DISP=SHR
0160 /*
0170 /*
***** End of list *****
```

```
Program      BSWKRP      Library N2OBATCH
0010 /.N2O LOGON
0020 /CALL-PROCEDURE NAME=$TSOSAVE.DO.JV.T
0030 /ASSIGN-SYSOUT TO-FILE=N2O.OUT.LOAD.&(JV.ZEIT.T)
0040 /MODIFY-JOB-OPTIONS LOGGING=PARAMETERS(LISTING=YES)
0050 /REMARK *** EXECUTE N2OREPORT ***
0060 /FILE N2O.REPORT,LINK=P01
0070 /ASSIGN-SYSDTA TO-FILE=*SYSCMD
0080 /MODIFY-JOB-SWITCHES ON=(4,5)
0090 /START-PROGRAM FROM-FILE=$EDT
0100 LS=132,PS=60,MENU=OFF
0110 @WRITE 'N2O.REPT.IPT.BATCH' OVERWRITE
0120 @HALT
0130 /MODIFY-JOB-SWITCHES OFF=(4,5)
```

```

0140 /ASSIGN-SYSIPT TO-FILE=N2O.REPT.IPT.BATCH
0150 /MODIFY-JOB-SWITCHES ON=(2)
0160 /START-PROGRAM FROM-FRIL=$ADABAS.NATBATCH
0170 LOGON N2OLIB
0180 N2OTOLC
0190 &INPUT
0200 FIN
0210 /FILE &BACKUP, LINK=W01
0220 /ASSIGN-SYSIPT TO-FILE=*PRIMARY
0230 /DELETE-FILE FILE-NAME=N2O.REPT.IPT.BATCH,
0240 /OPTION=DESTROY-ALL
0250 /LOGOFF NOSPOOL
***** End of list *****

```

Program VMWKR Library N2OBATCH

```

0010 /* EXECUTE A REPORT WITH A WORKFILE */
0020 ADDRESS 'COMMAND'
0030 'ERASE N2OREPT CMSYNIN A'
0040 'EXECIO 1 DISKW N2OREPT CMSYNIN A 1 F 80 (STRING LOGON N2OLIB'
0050 'EXECIO 1 DISKW N2OREPT CMSYNIN A 2 F 80 (STRING N2OTOLC'
0060 'EXECIO 1 DISKW N2OREPT CMSYNIN A 3 F 80 (STRING &INPUT'
0070 'EXECIO 1 DISKW N2OREPT CMSYNIN A 4 F 80 (STRING FIN'
0080 'FILEDEF * CLEAR'
0090 'FILEDEF CMWKF01 DISK N2OREPT &BACKUP A'
0100 'FILEDEF CMSYNIN DISK N2OREPT CMSYNIN A'
0110 'FILEDEF CMPRINT PRINTER'
0120 'FILEDEF CMPRT01 PRINTER'
0130 'EXEC NAT BATCH'
0140 'ERASE N2OREPT CMSYNIN A'
0150 EXIT
***** End of list *****

```

Program VSEWKR Library N2OBATCH

```

0010 * $$ JOB JNM=N2OREPT, CLASS=A, USER=&USERID
0020 * $$ LST CLASS=A, LST=SYSLST
0030 // JOB N2OREPT
0040 * N2OREPT - N2O REPORTING WITH INPUT WORK FILE
0050 // ASSGN SYS001, DISK, SHR
0060 // ASSGN SYS009, SYSLST
0070 // DLBL CMWKF01, '&BACKUP'
0080 // EXTENT SYS001, , , , NNNNN, NNNNN
0090 // EXEC NATBATCH
0100 /BWORKD=(1,1,80,FB)
0110 /*
0120 ADARUN DB=XXX, SVC=YYY, DEVICE=ZZZZ
0130 /*
0140 LOGON N2OLIB
0150 N2OTOLC
0160 &INPUT
0170 FIN
0180 /*
0190 /&
0200 * $$ EOJ
***** End of list *****

```

3GL compile

Program MVS3GLAC Library N2OBATCH

```
0010 //COMPILE JOB (ACCOUNTING),'COMPILE MEMBERS',CLASS=A,NOTIFY=&USERID
0020 /*
0030 &INCLUDE COMPILE
0040 /*
***** End of list *****
```

3GL batch submit

Program N2O3GL Library N2OBATCH

```
0010 //N2O3GL JOB (ACCT),'SUBMIT 3GL',CLASS=A,NOTIFY=&USERID
0020 /*
0030 //N2O3GL1 EXEC PGM=NATBATCH
0040 //CMWKF01 DD *
0050 &INPUT
0060 /*
0070 //CMWKF02 DD DSN=&&TEMP,DISP=(NEW,PASS,DELETE),
0080 //          DCB=(RECFM=FB,LRECL=80,BLKSIZE=80),
0090 //          UNIT=SYSDA,SPACE=(TRK,(12,12))
0100 //CMPRINT DD SYSOUT=*
0110 //CMSYNIN DD *
0120 LOGON N2OLIB
0130 N2OSELT
0140 FIN
0150 /*
0160 /*
0170 //N2O3GL2 EXEC PGM=IEBGENER,COND=(4,LT)
0180 //SYSUT1 DD DSN=&&TEMP,
0190 //          DISP=(OLD,DELETE)
0200 //SYSUT2 DD SYSOUT=(A,INTRDR)
0210 //SYSPRINT DD SYSOUT=*
0220 //SYSIN DD DUMMY
0230 /*
0240 /*
***** End of list *****
```

D.2 – 3GL PDS JCL

PDS archive

```

Program      PDSARCH  Library N2OBATCH
0010  /* &INCLUDE PRTPCH will be automatically replaced with the IEBTPCH
0020  /* commands necessary to punch the members to a workfile.
0030  /*
0040  /*&STEP1      EXEC PGM=IEBTPCH
0050  /*
0060  //SYSPRINT DD  SYSOUT=A
0070  //SYSUT1   DD  DSNNAME=&PDS,DISP=(SHR,KEEP),UNIT=SYSDA
0080  //SYSUT2   DD  DSNNAME=&&TEMP,DISP=(NEW,PASS,DELETE),
0090  //          UNIT=SYSDA,VOL=SER=XXXXXX,SPACE=(TRK,(12,12))
0100  //SYSIN    DD  *
0110  &INCLUDE PRTPCH
0120  /*
0130  /*
0140  /*&STEP2      EXEC PGM=NATBATCH
0150  //CMWKF01   DD  *
0160  &EVENT
0170  /*
0180  //CMWKF02   DD  DSN=&&TEMP,DISP=(OLD,DELETE,DELETE)
0190  //CMPRINT   DD  SYSOUT=*
0200  /*
0210  //CMSYNIN   DD  *
0220  LOGON N2OLIB
0230  N2OARCP
0240  FIN
0250  /*
0260  /*
***** End of list *****

```

PDS Catalog Capture

```
Program      PDSCAPT  Library N2OBATCH
0010 //PDSCAPT  JOB  (ACCOUNTING),'CATALOG CAPTURE',CLASS=A,NOTIFY=&USERID
0020 //*
0030 //PDSLIST  EXEC  PGM=IEHLIST
0040 //*
0050 //*****
0060 //*      CUSTOMIZATION NOTES
0070 //*****
0080 //*      THE CORRECT "VOLSER" MUST BE IDENTIFIED.
0090 //*      DCB INFORMATION LISTED IS MANDATORY.
0100 //*      THE LISTPDS STATEMENTS CANNOT BEGIN IN COLUMN ONE
0110 //*      UP TO TEN LISTPDS STATEMENTS MAY BE ISSUED.
0120 //*****
0130 //DD1      DD  UNIT=SYSDA,DISP=OLD,VOL=SER=volser
0140 //SYSPRINT DD  UNIT=SYSDA,DSN=N2O.PDS.CAPTURE.DATA,
0150 //          DCB=(RECFM=FBA,LRECL=121,BLKSIZE=1210),
0160 //          DISP=(,CATLG,DELETE),SPACE=(CYL,(1,1),RLSE)
0170 //SYSIN    DD  *
0180          LISTPDS DSN=dsname1,VOL=SYSDA=volser
0190          LISTPDS DSN=dsname2,VOL=SYSDA=volser
0200          LISTPDS DSN=dsname3,VOL=SYSDA=volser
0210          ...
0220 /*
0230 //*
0240 //CAPTURE  EXEC  PGM=NATBATCH
0250 //CMWKF01 DD  *
0260 &INPUT
0270 /*
0280 //CMWKF02 DD  DSN=N2O.PDS.CAPTURE.DATA,DISP=(OLD,DELETE,KEEP)
0290 //CMPRINT DD  SYSOUT=*
0300 //CMSYNIN DD  *
0310 LOGON N2OLIB
0320 N2OCAPT3
0330 FIN
0340 /*
0350 //*
***** End of list *****
```

PDS Compile

```
Program      PDSCMPL  Library N2OBATCH
0010 //PDSCMPL JOB  (ACCOUNTING),'PDS COMPILE',CLASS=A,NOTIFY=&USERID
0020 //*
0030 &INCLUDE COMPILE
0040 //*
***** End of list *****
```


PDS Move

Program PDSDMOVE Library N2OBATCH

```

0010 /** Steps below required only for 3GL MOVE events.
0020 /**
0030 /** &INCLUDE DELETE will be replaced automatically by N2O with
0040 /** IDCAMS cards to delete each member that were migrated
0050 /** if MOVE is specified for the Migration Profile.
0060 /**
0070 //PDSDEL EXEC PGM=IDCAMS,COND=(8,LT)
0080 //SYSPRINT DD DSN=N2O.DELOUT,
0090 // DCB=(RECFM=VB,LRECL=125,BLKSIZE=129),
0100 // DISP=(NEW,PASS,DELETE)
0110 //SYSIN DD *
0120 &INCLUDE DELETE
0130 /*
0140 /**
0150 //PDSACKN2 EXEC NATBATCH
0160 //CMWK01 DD DSN=N2O.DELOUT,DISP=OLD
0170 //CMWK02 DD *
0180 &EVENT
0190 /*
0200 //CMPRINT DD SYSOUT=*
0210 //CMSYNIN DD *
0220 LOGON N2OLIB
0230 N2OACKND
0240 FIN
0250 /*
0260 /**
***** End of list *****

```

PDS Migration

Program PDSMIGR Library N2OBATCH

```

0010 //PDSMIGR JOB (ACCOUNTING),'PDS MIGRATION',CLASS=A,NOTIFY=&USERID
0020 /**
0030 /** The Archive JCL exists in program PDSARCH in library N2OBATCH.
0040 /** Archiving will be performed if specified on the TO-ENV Definition
0050 /**
0060 &INCLUDE ARCHIVE
0070 /**
0080 /** &INCLUDE PDS will automatically be replaced with the names of
0090 /** the FROM and TO PDS identified on the Environment Definitions.
0100 /** This information will be formulated into the INDD and OUTDD cards.
0110 /**
0120 //PDSCOPY EXEC PGM=IEBCOPY
0130 //SYSPRINT DD DSN=N2O.COPYOUT,
0140 // DISP=(NEW,PASS,DELETE),LRECL=120,SPACE=(TRK,(1))
0150 /**
0160 &INCLUDE PDS
0170 /*
0180 //SYSUT3 DD UNIT=SYSDA,SPACE=(TRK,(1))
0190 //SYSUT4 DD UNIT=SYSDA,SPACE=(TRK,(1))
0200 /**
0210 /** &INCLUDE COPY will be replaced automatically by N2O with the
0220 /** COPY and SELECT control statements necessary to migrate the
0230 /** selected members.
0240 /**
0250 //SYSIN DD *
0260 &INCLUDE COPY
0270 /*
0280 /**
0290 //PDSACKN EXEC PGM=NATBATCH
0300 //CMWK01 DD DSN=N2O.COPYOUT,DISP=OLD
0310 //CMWK02 DD *
0320 &EVENT
0330 /*
0340 //CMPRINT DD SYSOUT=*
0350 //CMSYNIN DD *

```

```
0360 LOGON N2OLIB
0370 N2OACKNP
0380 FIN
0390 /*
0400 /*
0410 /* &INCLUDE COMPILE will be replaced automatically by N2O
0420 /*      with compile JCL for each member migrated
0430 /*      if Autocompile is specified for the Migration Profile.
0440 /*
0450 &INCLUDE COMPILE
***** End of list *****
```

PDS archive recovery

```
Program      PDSRJOB  Library N2OBATCH
0010 //PDSRMIGR JOB (ACCOUNTING),'PDS RECOVERY',CLASS=A,NOTIFY=&USERID
0020 /*
0030 /* &INCLUDE RECOVERY will be replaced by the JCL step (PDSRMIGR)
0040 /*      for each member to be recovered.
0050 /*
0060 &INCLUDE RECOVERY
0070 /*
0080 /* &INCLUDE COMPILE will be replaced automatically by N2O with
0090 /*      compile JCL for each member migrated if Autocompile is
0100 /*      for the Migration Profile.
0110 /*
0120 &INCLUDE COMPILE
0130 /*
***** End of list *****
```

PDS Archive recovery

```
Program      PDSRMIGR Library N2OBATCH
0010 //&STEPNUM EXEC PGM=NATBATCH
0020 //CMWK01 DD *
0030 &MEMBER
0040 &EVENT
0050 /*
0060 /*
0070 //CMPRINT DD SYSOUT=*
0080 //CMWK02 DD DSN=&PDS,DISP=SHR
0090 /*
0100 //SYSIN DD *
0110 //CMSYNIN DD *
0120 LOGON N2OLIB
0130 N2ORECP
0140 FIN
0150 /*
***** End of list *****
```

3GL member submit to PREDICT pre-processor

```

Program          PREPROCS Library N2OBATCH
0010 /** JCL to submit 3GL members to the PREDICT Pre-processor.
0020 /** The pre-processor will store XREF information for
0030 /** a 3GL member in PREDICT.
0040 /**
0050 /** &STEPNUM will be replaced automatically by N2O with the next
0060 /** available step name.
0070 /**
0080 /** &SLIB will be replaced automatically by N2O with the target
0090 /** PDS name of the Event.
0100 /**
0110 /** &MEMBER will be replaced automatically by N2O with the name of
0120 /** the migrated member.
0130 /**
0140 /**&STEPNUM EXEC PGM=NATBATCH
0150 /**
0160 /** The COBOL source code is input to the pre-processor
0170 /**
0180 /**CMWK01 DD DSN=&SLIB(&MEMBER),DISP=SHR
0190 /**
0200 /** The output of the pre-processor can be passed to the compiler,
0210 /** but the SYSIN statement of compile JCL must have the DSN below.
0220 /**
0230 /**CMWK02 DD DSN=&TEMPPPDS(&MEMBER),DISP=(NEW,PASS),
0240 /**          UNIT=SYSDA,DCB=(RECFM=FB,LRECL=80,BLKSIZE=800)
0250 /**
0260 /** Temporary work file for the pre-processor.
0270 /**
0280 /**CMWK03 DD DSN=&WORK,DISP=(NEW,DELETE),
0290 /**          UNIT=SYSDA,DCB=(RECFM=FB,LRECL=91,BLKSIZE=9100)
0300 /**CMPRINT DD SYSOUT=*,DCB=BLKSIZE=1330
0310 /**CMPRT01 DD SYSOUT=*,DCB=BLKSIZE=1330 /* Success of run
0320 /**CMPRT02 DD SYSOUT=*,DCB=BLKSIZE=1330 /* List of Pre-proc cmds
0330 /**CMPRT03 DD SYSOUT=*,DCB=BLKSIZE=1330 /* List of errors
0340 /**CMSYSIN DD *
0350 LOGON SYSDIC
0360 MENU
0370 PREPROCESS,COBOL,&MEMBER
0380 FIN
0390 /*
0400 /**
***** End of list *****

```

D.3 – Panvalet JCL

Panvalet Catalog Capture

```
Program          PANVCAPT Library N2OBATCH
0010 //PANVCAPT JOB (ACCOUNTING),'CATALOG CAPTURE',CLASS=A,NOTIFY=&USERID
0020 /*
0030 //PANPRT      EXEC PGM=PAN#2
0040 /*
0050 //PANDD1      DD DSN=&PANDD1,DISP=SHR
0060 //SYSPUNCH    DD DSN=N2O.CAPTURE.DATA,LRECL=121,
0070 //              DISP=(,CATLG,DELETE),
0080 //              UNIT=SYSDA,SPACE=(CYL,(1,1),RLSE)
0090 //SYSPRINT    DD SYSOUT=*
0100 //SYSIN       DD *
0110 ++PRINT 0-UP
0120 /*
0130 /*
0140 //CAPTURE      EXEC PGM=NATBATCH
0150 /*
0160 //CMWKF01      DD *
0170 &INPUT
0180 /*
0190 //CMWKF02      DD DSN=N2O.CAPTURE.DATA,DISP=SHR
0200 //CMPRINT      DD SYSOUT=*
0210 //CMSYNIN      DD *
0220 LOGON N2OLIB
0230 N2OCAPT3
0240 FIN
0250 /*
0260 /*
***** End of list *****
```

Panvalet Compile

```
Program          PANVCMPL Library N2OBATCH
0010 //PANVCMPL JOB (ACCOUNTING),'PANVALET COMPILE',CLASS=A,NOTIFY=&USERID
0020 /*
0030 &INCLUDE COMPILE
0040 /*
***** End of list *****
```

Panvalet Migration

```

Panvalet Migration Program      PANVMIGR Library N2OBATCH
0010 //PANVMIGR JOB (ACCOUNTING),'PANVALET MIGRATION',CLASS=A,NOTIFY=&USERID
0020 /**
0030 /**      &PANDD1 and &PANDD2 will be replaced automatically by N2O when
0040 /**      the batch migration is submitted to an internal reader.
0050 /**
0060 //PANTRAN EXEC PGM=PAN#2,PARM='OPEN=INP'
0070 /**
0080 //PANDD1 DD DSN=&PANDD1,DISP=SHR
0090 //PANDD2 DD DSN=&PANDD2,DISP=SHR
0100 //SYSPRINT DD DSN=N2O.PANV.MIGR,
0110 //      DISP=(NEW,PASS,CATLG)
0120 //SYSIN DD *
0130 &INCLUDE TRANSFER
0140 /*
0150 /**
0160 //PANACKN EXEC PGM=NATBATCH
0170 /**
0180 //CMWKF01 DD DSN=N2O.PANV.MIGR,DISP=(OLD,DELETE,CATLG)
0190 //CMWKF02 DD *
0200 &EVENT
0210 /*
0220 //CMSYNIN DD *
0230 LOGON N2OLIB
0240 N2OACKNP
0250 FIN
0260 /*
0270 /**
0280 /**      &INCLUDE COMPILE will be replaced automatically by N2O with
0290 /**      the JCL to compile each migrated member if Autocompile
0300 /**      is specified for the Migration Profile.
0310 /**
0320 &INCLUDE COMPILE
0330 /**
0340 //PANMOVE EXEC PGM=PAN#2,PARM='OPEN=INP'
0350 //PANDD1 DD DSN=&PANDD1,DISP=SHR
0360 //PANDD2 DD DUMMY
0370 //SYSPRINT DD SYSOUT=N2O.PANV.MOVELIST,
0380 //      DISP=(NEW,PASS,CATLG)
0390 //SYSIN DD *
0400 &INCLUDE DELETE
0410 /*
0420 /**
0430 //PANACKN2 EXEC PGM=NATBATCH
0440 /**
0450 //CMWKF01 DD DSN=N2O.PANV.MOVELIST,DISP=(OLD,DELETE,CATLG)
0460 //CMWKF02 DD *
0470 &EVENT
0480 /*
0490 //CMSYNIN DD *
0500 LOGON N2OLIB
0510 N2ODAKNP
0520 FIN
0530 /*
***** End of list *****

```

D.4 - Endeavor JCL

Endeavor Catalog capture

```
Program      ENDVCAPT Library N2OBATCH
0010 //ENDVCAPT JOB (ACCOUNTING),'CATALOG CAPTURE',CLASS=A,NOTIFY=&USERID
0020 /**
0030 //CAPTURE1 EXEC PGM=NDVRC1,PARM='C1BR1000',REGION4096K
0040 //CONLIB DD DSN=PREND.PERM.CONLIB,DISP=SHR
0050 //SYSOUT DD DSN=N2O.CAPTURE.DATA,DISP=SHR
0060 //BSTINP DD *
0070 REPORT 03 .
0080 ENVIRONMENT PROD .
0090 SYSTEM * .
0100 SUBSYSTEM * .
0110 TYPE * .
0120 STAGE P .
0130 DAYS 7 .
0140 //BSTPDS DD DUMMY
0150 //SMFDATA DD DUMMY
0160 //UNLINPT DD DUMMY
0170 //BSTPCH DD DSN=&TEMP,DISP=(NEW,DELETE,DELETE),
0180 // UNIT=SYSDA,SPACE=(CYL,(1,2)),
0190 // DCB=(RECFM=FB,LRECL=416,BLKSIZE=4160)
0200 //BSTLST DD SYSOUT=*
0210 //SORTIN DD UNIT=SYSDA,SPACE=(CYL(5,5))
0220 //SORTOUT DD UNIT=SYSDA,SPACE=(CYL(5,5))
0230 //SORTWK01 DD UNIT=SYSDA,SPACE=(CYL(5,5))
0240 //SORTWK02 DD UNIT=SYSDA,SPACE=(CYL(5,5))
0250 //SORTWK03 DD UNIT=SYSDA,SPACE=(CYL(5,5))
0260 //C1MSG1 DD SYSOUT=*
0270 //SYSOUT DD SYSOUT=*
0280 //SYSPRINT DD SYSOUT=*
0290 /*
0300 //CAPTURE2 EXEC PGM=NATBATCH
0310 /**
0320 //CMWKF01 DD *
0330 &INPUT
0340 /*
0350 //CMWKF02 DD DSN=N2O.CAPTURE.DATA,DISP=SHR
0360 /**
0370 //CMPRINT DD SYSOUT=*
0380 //CMSYSIN DD *
0390 LOGON SYSTEM
0400 N2OCAPT3
0410 FIN
0420 /*
0430 /**
***** End of list *****
```

Endevor migration

Program **ENDVMIGR Library N2OBATCH**

```

0010 //ENDVMIGR JOB (ACCOUNTING),'ENDEVOR MIGRATION',CLASS=A,NOTIFY=&USERID
0020 /**
0030 //ENDV001 EXEC PGM=NDVRC1,DYNAMNBR=1500,PARM='C1BM3000',REGION=4096K
0040 //CONLIB DD DSN=IPRFX.IQUAL.CONLIB,DISP=SHR
0050 //SYSPRINT DD DSN=N2O.ENDVOUT,DISP=SHR
0060 /**
0070 /** &INCLUDE COPY will be replaced automatically by N2O with the
0080 /** ADD, MOVE, OR RETRIEVE statements necessary to migrate the
0090 /** selected members.
0100 /**
0110 //BSTIPT01 DD *
0120 &INCLUDE COPY
0130 /*
0140 //C1MSGSL DD SYSOUT=*
0150 //C1PRINT DD SYSOUT=*
0160 //SYSOUT DD SYSOUT=*
0170 /**
0180 /** &INCLUDE COMPILE will be replaced automatically by N2O with the
0190 /** compile JCL for each member migrated if Autocompile is set to YES.
0200 /**
0210 &INCLUDE COMPILE
0220 /**
0230 /** &EVENT will be replaced automatically by N2O with the Event that
0240 /** is being migrated when the batch migration is submitted to an
0250 /** internal reader.
0260 /**
0270 //ENDVACKN EXEC PGM=NATBATCH
0280 //CMWKF01 DD DSN=N2O.ENDVOUT,DISP=OLD
0290 //CMWKF02 DD *
0300 &EVENT
0310 /*
0320 //CMPRINT DD SYSOUT=*
0330 //CMSYNIN DD *
0340 LOGON N2OLIB
0350 N2OACKNE
0360 FIN
0370 /*
***** End of list *****

```

D.5 - Librarian JCL

Librarian catalog capture

```
Program      LIBRCAPT Library N2OBATCH
0010 //LIBRCAPT JOB (LIST),'CATALOG CAPTURE',CLASS=A,NOTIFY=&USERID
0020 /*
0030 //LIBPRT   EXEC PGM=LIBRPROG
0040 /*
0050 /*  &MASTER1 will be replaced automatically by N2O with
0060 /*  the Librarian Master file name to be captured.
0070 /*
0080 //OSJOB     DD DSN=&&TEMP,UNIT=SYSDA,
0090 //           SPACE=(TRK,(3,1)),DISP=NEW
0100 //MASTER   DD DSN=&MASTER1,DISP=SHR
0110 //INDEX     DD DSN=N2O.CAPTURE.DATA,LRECL=121,
0120 //           DISP=(,CATLG,DELETE),
0130 //           UNIT=SYSDA,SPACE=(CYL,(1,1),RLSE)
0140 //SYSPRINT  DD SYSOUT=*
0150 //SYSIN     DD *
0160 -OPT INDEX
0170 -END
0180 /*
0190 /*
0200 //CAPTURE EXEC PGM=NATBATCH
0210 /*
0220 //CMWK01    DD *
0230 &INPUT
0240 /*
0250 //CMWK02    DD DSN=N2O.CAPTURE.DATA,DISP=SHR
0260 //CMPRINT   DD SYSOUT=*
0270 //CMSYNIN   DD *
0280 LOGON N2OLIB
0290 N2OCAPT3
0300 FIN
0310 /*
0320 /*
***** End of list *****
```

Librarian Compile

```
Program      LIBRCMPL Library N2OBATCH
0010 //LIBRCMPL JOB (ACCOUNTING),'LIBRARIAN COMPILE',CLASS=A,NOTIFY=&USERID
0020 /*
0030 &INCLUDE COMPILE
0040 /*
***** End of list *****
```


Librarian migration

Program LIBRMIGR Library N2OBATCH

```

0010 //LIBRMIGR JOB (ACCOUNTING),'LIBRARIAN MIGRATION',CLASS=A,NOTIFY=&USERID
0020 /**
0030 /** &MASTER1 will be replaced automatically by N2O with the
0040 /** LIBRARIAN Master File representing the source of the migration,
0050 /** when the batch migration is submitted to an Internal Reader.
0060 /**
0070 /** &MASTER2 will be replaced automatically by N2O with the
0080 /** LIBRARIAN Master File representing the target of the migration,
0090 /** when the batch migration is submitted to an Internal Reader.
0100 /**
0110 /** &INCLUDE COPY will be replaced automatically by N2O with
0120 /** the LIBRARIAN commands necessary to perform the migration.
0130 /**
0140 //LIBCOPY1 EXEC PGM=LIBRCOPY,PARM='NOSEQ,NOHIST'
0150 /**
0160 //OSJOB DD DSN=&TEMP,DISP=(NEW,PASS),
0170 // UNIT=DISK,SPACE=(CYL,(5,1)),
0180 // DCB=(RECFM=FB,LRECL=80,BLKSIZE=80)
0190 //MASTER DD DSN=&MASTER1,DISP=SHR
0200 //DESTMAS DD DSN=&MASTER2,DISP=SHR
0210 //SYSPRINT DD DSN=N2O.LIBR.COPY,SPACE=(CYL,(2,1)),
0220 // DISP=(NEW,PASS,CATLG),
0230 // DCB=(RECFM=FB,LRECL=121,BLKSIZE=1210)
0240 //SYSIN DD *
0250 &INCLUDE COPY
0260 /**
0270 /**
0280 //LIBCOPY2 EXEC PGM=LIBRPROG,PARM='NRJS,NJTS'
0290 /**
0300 //OSJOB DD DUMMY
0310 //LIST DD SYSOUT=*
0320 //INDEX DD SYSOUT=*
0330 //MASTER DD DSN=&MASTER2,DISP=SHR
0340 //SYSPRINT DD DSN=N2O.LIBR.PROGLIST,
0350 // SPACE=(CYL,(2,1)),
0360 // DISP=(NEW,PASS,CATLG),
0370 // DCB=(RECFM=FB,LRECL=121,BLKSIZE=1210)
0380 //SYSIN DD &&TEMP,DISP=(OLD,DELETE)
0390 /**
0400 /** &EVENT will be replaced automatically by N2O with the Event
0410 /** that is being migrated when the batch migration is submitted.
0420 /**
0430 //LIBACKN1 EXEC PGM=NATBATCH
0440 /**
0450 //CMWKF01 DD DSN=N2O.LIBR.COPY,
0460 // DISP=(OLD,DELETE,CATLG)
0470 //CMWKF02 DD *
0480 &EVENT
0490 /**
0500 //CMWKF03 DD DSN=N2O.LIBR.PROGLIST,
0510 // DISP=(OLD,DELETE,CATLG)
0520 //CMPRINT DD SYSOUT=*
0530 //CMSYNIN DD *
0540 LOGON N2OLIB
0550 N2OACKNL
0560 FIN
0570 /**
0580 /** &INCLUDE COMPILE will be replaced automatically by N2O with
0590 /** the JCL to compile each migrated member if Autocompile
0600 /** is specified on the Migration Profile.
0610 /**
0620 &INCLUDE COMPILE
0630 /**
0640 /** The following steps are for Librarian MOVES only.
0650 /**
0660 //LIBMOVE EXEC PGM=LIBRPROG,COND=(4,LT)
0670 /**

```

```
0680 //MASTER DD DSN=&MASTER1,DISP=SHR
0690 //SYSAF01 DD UNIT=SYSDA,SPACE=(TRK,(30,30),RLSE)
0700 //SYSAF02 DD UNIT=SYSDA,SPACE=(TRK,(30,30),RLSE)
0710 //OSJOB DD DUMMY
0720 //LIST DD SYSOUT=*
0730 //SYSPRINT DD DSN=N2O.LIBR.MOVELIST,SPACE=(CYL,(2,1)),
0740 // DISP=(NEW,PASS,CATLG)
0750 //SYSIN DD *
0760 &INCLUDE DELETE
0770 //*
0780 //LIBACKN2 EXEC PGM=NATBATCH
0790 //*
0800 //CMWKF01 DD DSN=N2O.LIBR.MOVELIST,DISP=(OLD,DELETE,CATLG)
0810 //CMWKF02 DD *
0820 &EVENT
0830 //*
0840 //CMPRINT DD SYSOUT=*
0850 //CMSYNIN DD *
0860 LOGON N2OLIB
0870 N2OACKNL
0880 FIN
0890 /*
***** End of list *****
```

D.6 - DB2 related JCL

```

Program      DB2ASM      Library N2OBATCH
0010 /*      &ASMNUM will generate the next available step name for the
0020 /*      Assemble step (e.g. ASM1, ASM2).
0030 /*
0040 /*&ASMNUM EXEC PGM=IEV90,REGION=1M,PARM='NODECK,OBJECT'
0050 /*
0060 //SYSLIB DD DISP=SHR,DSN=NDB21X.SRCE
0070 // DD DISP=SHR,DSN=NAT21X.SRCE
0080 // DD DISP=SHR,DSN=DSNXXX.DSNMACS
0090 // DD DISP=SHR,DSN=SYS1.MACLIB
0100 //SYSIN DD DSN=&DSNHOUT,
0110 // DISP=(OLD,DELETE)
0120 //SYSLIN DD DSN=&LOADSET,
0130 // DISP=(NEW,PASS),UNIT=SYSDA,SPACE=(800,(500,500))
0140 // DCB=(RECFM=FBS,LRECL=80,BLKSIZE=800,BUFNO=1)
0150 //SYSTEM DD SYSOUT=*
0160 //SYSPRINT DD SYSOUT=*
0170 //SYSUDUMP DD SYSOUT=*
0180 //SYSUT1 DD SPACE=(TRK,(50,5)),UNIT=SYSDA,DISP=(,DELETE)
0190 //SYSUT2 DD SPACE=(TRK,(36,5)),UNIT=SYSDA,DISP=(,DELETE)
0200 //SYSUT3 DD SPACE=(TRK,(36,5)),UNIT=SYSDA,DISP=(,DELETE)
0210 /*
***** End of list *****

```

```

Program      DB2BIND      Library N2OBATCH
0010 //N2OBIND JOB (ACCT),'SUBMIT BIND',CLASS=A,NOTIFY=&USERID
0020 /*
0030 //JOB LIB DD DSN=NATURAL.NAT21X.LOADLIB,
0040 // DISP=(SHR,KEEP,KEEP)
0050 // DD DSN=ADABAS.ADA52X.LOADLIB,
0060 // DISP=(SHR,KEEP,KEEP)
0070 /*
0080 //N2OBIND1 EXEC PGM=NATBATCH
0090 /*
0100 //DDCARD DD *
0110 ADARUN DBID=xxx,SVC=yyy,DEVICE=zzzz,MODE=MULTI,PROGRAM=USER
0120 /*
0130 //CMPRINT DD SYSOUT=*
0140 //CMSYNIN DD *
0150 LOGON N2OLIB
0160 N2OBIND
0170 FIN
0180 /*
0190 //CMWKF01 DD *
0200 &INPUT
0210 /*
0220 //CMWKF02 DD DSN=SYSTSIN.INPUT.N2O
0230 //CMWKF03 DD DSN=&&TEMP,DISP=(NEW,PASS,DELETE),
0240 // UNIT=WORK,SPACE=(TRK,(1,1),RLSE),
0250 // DCB=(RECFM=FB,LRECL=80,BLKSIZE=80)
0260 /*
0270 /*
0280 /* COPY JCL TO BIND DB2 PLAN TO INTERNAL READER
0290 /*
0300 //N2OBIND2 EXEC PGM=IEBGENER,COND=(4,LT,N2OBIND)
0310 //SYSUT1 DD DSN=&&TEMP,
0320 // DISP=(OLD,DELETE)
0330 //SYSUT2 DD SYSOUT=(A,INTRDR)
0340 //SYSIN DD DUMMY
0350 /*
0360 /*
***** End of list *****

```

```
Program      DB2BINDP Library N2OBATCH
0010 //BINDPLAN JOB (ACCT),'BIND DB2 PLAN',CLASS=A,NOTIFY=&USERID
0020 /**
0030 /** If each DBRM was bound separately as a package, see DB2PKLST.
0040 /**
0050 /** &PLAN will be replaced automatically by N2O with the name
0060 /** of the Plan to be bound (set in User Exit 9).
0070 /**
0080 /** &SUBSYS will be replaced automatically by N2O with the name
0090 /** of the DB2 Subsystem (set in User Exit 9).
0100 /**
0110 /** &DBRM will be replaced automatically by N2O with the name(s)
0120 /** of the DBRM(s) to be bound. The list of DBRM(s) is written
0130 /** to work file 2 in N2OUE10N, and then copied to work file 3
0140 /** with the remainder of the JCL.
0150 /**
0160 //BIND      EXEC PGM=IKJEFT01,DYNAMNBR=20,REGION=4096K,TIME=200
0170 /**
0180 //STEPLIB DD DISP=SHR,DSN=DSNxxx.DSNLOAD
0190 //DBRMLIB DD DISP=SHR,DSN=NDB21x.DBRMLIB
0200 //SYSTSPRT DD SYSOUT=*
0210 //SYSPRINT DD SYSOUT=*
0220 //SYSUDUMP DD SYSOUT=*
0230 //SYSTSIN DD *
0240     &INPUT
0250     OR
0260     DSN SYSTEM(&SUBSYS)
0270     BIND PLAN(&PLAN) -
0280     MEM( -
0290         &DBRM
0300     ) -
0310     ISOLATION(CS) -
0320     RELEASE(COMMIT) -
0330     ACTION(REPLACE) -
0340     END
0350 /*
***** End of list *****
```

```

Program      DB2DBRM  Library N2OBATCH
0010 //N2ODBRM JOB  (ACCT),'CREATE DBRM',CLASS=A,NOTIFY=&USERID
0020 /**
0030 //JOB LIB      DD DSN=NATURAL.NAT21X.LOADLIB,
0040 //              DISP=(SHR,KEEP,KEEP)
0050 //              DD DSN=ADABAS.ADA52X.LOADLIB,
0060 //              DISP=(SHR,KEEP,KEEP)
0070 /**
0080 //N2ODBRM1 EXEC PGM=NATBATCH
0090 /**
0100 //DDCARD      DD *
0110 ADARUN DBID=xxx,SVC=yyy,DEVICE=zzzz,MODE=MULTI,PROGRAM=USER
0120 /**
0130 //CMPRINT      DD SYSOUT=*
0140 //CMSYNIN      DD *
0150 LOGON N2OLIB
0160 N2ODBRM
0170 FIN
0180 /**
0190 //CMWKF01      DD *
0200 &INPUT
0210 /**
0220 //CMWKF03      DD DSN=&&TEMP,DISP=(NEW,PASS,DELETE),
0230 //              UNIT=WORK,SPACE=(TRK,(1,1),RLSE),
0240 //              DCB=(RECFM=FB,LRECL=80,BLKSIZE=80)
0250 /**
0260 //N2ODBRM2 EXEC PGM=IEBGENER,COND=(4,LT,N2ODBRM)
0270 //SYSUT1      DD DSN=&&TEMP,
0280 //              DISP=(OLD,DELETE)
0290 //SYSUT2      DD SYSOUT=(A,INTRDR)
0300 //SYSIN       DD DUMMY
0310 /**
0320 /**
***** End of list *****

```

```

Program      DB2DBRMA Library N2OBATCH
0010 /** The NATURAL DB/2 Batch Nucleus must be used for this job.
0020 /**
0030 /** &DBRM will be replaced automatically by N2O with the name
0040 /** of the DBRM to be created.
0050 /**
0060 /** &LIBRARY will be replaced automatically by N2O with the name
0070 /** of the library containing the programs included in the DBRM.
0080 /**
0090 /** &PROGRAM will be replaced automatically by N2O with the name
0100 /** of the program(s) to be included in the DBRM.
0110 /**
0120 //&DBRM      EXEC PGM=NATDEMO,REGION=2000K,TIME=1400
0130 /**
0140 //STEPLIB    DD DSN=NDB21X.LOAD,DISP=SHR
0150 //           DD DSN=ADA51X.LOAD,DISP=SHR
0160 //           DD DSN=NAT21X.LOAD,DISP=SHR
0170 //DDKARTE    DD DUMMY
0180 //DDDRUCK    DD SYSOUT=*
0190 //DDPRINT    DD SYSOUT=*
0200 //DDCARD     DD *
0210 ADARUN DBID=xxx,SVC=yyy,DEVICE=zzzz,MODE=MULTI,PROGRAM=USER
0220 /**
0230 //***** OUTPUT DECKS
0240 //CMWKF01    DD DSN=&&TMP1,
0250 //           DISP=(,PASS),UNIT=SYSDA,SPACE=(TRK,(5,5)),
0260 //           DCB=(DSORG=PS,RECFM=FB,LRECL=80,BLKSIZE=3120)
0270 //CMWKF02    DD DSN=&&TMP2,
0280 //           DISP=(,PASS),UNIT=SYSDA,SPACE=(TRK,(5,5)),
0290 //           DCB=(DSORG=PS,RECFM=FB,LRECL=80,BLKSIZE=3120)
0300 //CMWKF03    DD DSN=&&TMP3,
0310 //           DISP=(,PASS),UNIT=SYSDA,SPACE=(TRK,(5,5)),
0320 //           DCB=(DSORG=PS,RECFM=FB,LRECL=80,BLKSIZE=3120)
0330 //CMWKF04    DD DSN=&&TMP4,
0340 //           DISP=(,PASS),UNIT=SYSDA,SPACE=(TRK,(5,5)),

```

```

0350 //          DCB=(DSORG=PS,RECFM=FB,LRECL=80,BLKSIZE=3120)
0360 //CMWK05  DD DSN=&&TMP5,
0370 //          DISP=(,PASS),UNIT=SYSDA,SPACE=(TRK,(5,5)),
0380 //          DCB=(DSORG=PS,RECFM=FB,LRECL=80,BLKSIZE=3120)
0390 //CMWK06  DD DSN=&&TMP,
0400 //          DISP=(,PASS),UNIT=SYSDA,SPACE=(TRK,(5,5)),
0410 //          DCB=(DSORG=PS,RECFM=FB,LRECL=80,BLKSIZE=3120)
0420 //CMWK07  DD DSN=&&TMP7,
0430 //          DISP=(,PASS),UNIT=SYSDA,SPACE=(TRK,(5,5)),
0440 //          DCB=(DSORG=PS,RECFM=FB,LRECL=80,BLKSIZE=3120)
0450 // *
0460 //CMPRINT  DD SYSOUT=*
0470 //CMSYNIN  DD *
0480 LOGON SYSD2
0490 CMD CREATE DBRM &DBRM USING INPUT DATA WITH XREF NO
0500 &LIBRARY,&PROGRAM
0510 .
0520 FIN
0530 /*
***** End of list *****

```

Program DB2JOB Library N2OBATCH

```

0010 //NSTATIC JOB (ACCT),'GENERATE DBRM',CLASS=A,
0020 // MSGCLASS=X,NOTIFY=&USERID
0030 /*
0040 /* The following JOBLIB statements can be used instead of specifying
0050 /* LOADLIBS in each step.
0060 /*
0070 /*JOBPARM S=CPU1
0080 /*ROUTE PRINT SYSPRT
0090 /*
0100 //JOBLIB DD DSN=NATURAL.NAT21X.LOADLIB,
0110 //        DISP=(SHR,KEEP,KEEP)
0120 //        DD DSN=NATURAL.NDB21X.LOADLIB,
0130 //        DISP=(SHR,KEEP,KEEP)
0140 //        DD DSN=ADABAS.ADA51X.LOADLIB,
0150 //        DISP=(SHR,KEEP,KEEP)
0160 //        DD DSN=DB2.DSNLOAD.LOADLIB,
0170 //        DISP=(SHR,KEEP,KEEP)
***** End of list *****

```

Program DB2LINK Library N2OBATCH

```

0010 /* &LKONUM will generate the next available step name for the
0020 /* Online Link step (e.g. LK01, LK02).
0030 /*
0040 /* &LKBNUM will generate the next available step name for the
0050 /* Batch Link step (e.g. LKB1, LKB2).
0060 /*
0070 /* Note: Online Link Skeleton shown below.
0080 /*
0090 /* &DBRM will be replaced automatically by N2O with the name
0100 /* of the DBRM specified in the generate step above.
0110 /*
0120 //&LKONUM EXEC PGM=IEWL,PARM='REUS,XREF',
0130 //          COND=((4,LT,&ASNUM),(4,LT,&PCNUM))
0140 /*
0150 //SYSLIB DD DISP=SHR,DSN=NDB21X.LOAD,DCB=BLKSIZE=20000
0160 //        DD DISP=SHR,DSN=DSNXXX.DSNLOAD
0170 /*        DD DISP=SHR,DSN=IMSVS.RESLIB >--- IMS
0180 /*        DD DISP=SHR,DSN=CICS.LOADLIB >--- CICS
0190 //SYSLIN DD DSN=&&LOADSET,
0200 //          DISP=(OLD,DELETE)
0210 //        DD DDNAME=SYSIN
0220 /*
0230 /* Include the appropriate language interface
0240 /*
0250 //SYSIN DD *
0260 INCLUDE SYSLIB(DSNCLI) <--- CICS
0270 NAME &DBRM(R)

```

```

0280 /* INCLUDE SYSLIB(DSNELI)                <--- TSO
0290 /* INCLUDE SYSLIB(DSNALI)                <--- CAF
0300 /* INCLUDE SYSLIB(DFSLLI000)             <--- IMS/DC
0310 /*
0320 //SYSUT1 DD UNIT=SYSDA,SPACE=(1024,(50,50))
0330 //SYSLMOD DD DISP=SHR,DSN=NDB21X.LOAD(&DBRM)
0340 //SYSPRINT DD SYSOUT=*
0350 //SYSUDUMP DD SYSOUT=*
0360 /*
***** End of list *****

```

```

Program      DB2PC      Library N2OBATCH
0010 /*      &PCNUM will generate the next available step name for the
0020 /*      Precompile step (e.g. PC1, PC22).
0030 /*
0040 /*      &DBRM will be replaced automatically by N2O with the name
0050 /*      of the DBRM specified in the generate step above.
0060 /*
0070 //&PCNUM EXEC PGM=DSNHPC,REGION=2048K,PARM='HOST(ASM) ',
0080 //      COND=(4,LT,&DBRM)
0090 /*
0100 //DBRMLIB DD DSN=NDB21X.DBRMLIB(&DBRM),
0110 //      DISP=SHR
0120 //SYSIN DD DSN=&&TMP,
0130 //      DISP=(OLD,DELETE)
0140 //SYSUT1 DD UNIT=SYSDA,SPACE=(800,(500,500),,,ROUND)
0150 //SYSCIN DD DSN=&&DSNHOUT,
0160 //      DISP=(NEW,PASS),UNIT=SYSDA,SPACE=(800,(500,500))
0170 //SYSPRINT DD SYSOUT=*
0180 //SYSTEM DD SYSOUT=*
0190 /*
0200 /* * * * * *
0210 /*      OUTPUT PRE-COMPILE
0220 /* * * * * *
0230 /*
0240 //PRINT1 EXEC PGM=IEBGENER
0250 //SYSUT1 DD DSN=&&DSNHOUT,DISP=(OLD,PASS)
0260 //SYSUT2 DD SYSOUT=*
0270 //SYSIN DD DUMMY
0280 //SYSPRINT DD SYSOUT=*
0290 /*
***** End of list *****

```

```
Program      DB2PKG      Library N2OBATCH
0010 /*      &PKANUM will generate the next available step name for the
0020 /*      Bind Package Add step (e.g. PKA1, PKA2).
0030 /*
0040 /*      &PKRNUM will generate the next available step name for the
0050 /*      Bind Package Replace step (e.g. PKA1, PKA2).
0060 /*
0070 /*      &DBRM will be replaced automatically by N2O with the name
0080 /*      of the DBRM specified in the generate step above.
0090 /*
0100 /*&PKRNUM EXEC PGM=IKJEFT01,DYNAMNBR=20,
0110 /*          COND=((4,LT,&ASMNUM),(4,LT,&PCNUM))
0120 /*
0130 /*STEPLIB DD DISP=SHR,DSN=NDB23X.LOADLIB
0140 /*SYSTSPRT DD SYSOUT=*
0150 /*SYSPPRINT DD SYSOUT=*
0160 /*SYSUDUMP DD SYSOUT=*
0170 /*SYSTSIN DD *
0180 DSN
0190 BIND PACKAGE (Location-name.Collection-id) -
0200 QUALIFIER(qualifier-name) -
0210 MEMBER(&DBRM) -
0220 LIBRARY(dbrm-pds-name) -
0230 SQLERROR(NOPACKAGE) -
0240 VALIDATE(RUN) -
0250 FLAG(I) -
0260 ISOLATION(CS) -
0270 RELEASE(COMMIT) -
0280 EXPLAIN(NO) -
0290 CURRENTDATA(NO) -
0300 ACTION(REPLACE) -
0310 ENABLE (*)
0320 END
***** End of list *****
```

```
Program      DB2PKLST Library N2OBATCH
0010 //BINDPLAN JOB (ACCT),'BIND DB2 PLAN',CLASS=A,NOTIFY=&USERID
0020 /*
0030 /*      To bind DBRMs directly to a plan, see DB2BIND.
0040 /*
0050 /*      &PLAN will be replaced automatically by N2O with the name
0060 /*      of the Plan to be bound (set in User Exit 9).
0070 /*
0080 /*      &SUBSYS will be replaced automatically by N2O with the name
0090 /*      of the DB2 Subsystem (set in User Exit 9).
0100 /*
0110 /*      &INPUT will be replaced automatically by N2O with the SYSTSIN
0120 /*      statements necessary to perform the bind. These statements
0130 /*      are written to work file 2 in N2OUE10N, and then copied to
0140 /*      work file 3 with the remainder of the JCL.
0150 /*
0160 //BIND EXEC PGM=IKJEFT01,DYNAMNBR=20,REGION=4096K,TIME=200
0170 /*
0180 //STEPLIB DD DISP=SHR,DSN=DSNXXX.DSNLOAD
0190 //DBRMLIB DD DISP=SHR,DSN=NDB21X.DBRMLIB
0200 //SYSTSPRT DD SYSOUT=*
0210 //SYSPPRINT DD SYSOUT=*
0220 //SYSUDUMP DD SYSOUT=*
0230 //SYSTSIN DD *
0240 DSN SYSTEM(&SUBSYS)
0250 BIND PLAN(&PLAN) -
0260 &INPUT
0270 ISOLATION(CS) -
0280 RELEASE(COMMIT) -
0290 ACTION(REPLACE) -
0300 END
0310 /*
***** End of list *****
```


D.7 - Network Data Mover sample JCL

```

Program      NDMTRANF Library N2OBATCH
0010 /*      USED BY SITES THAT HAVE NOT MODIFIED N2OUE14N,
0020 /*      VARIABLE BUILD-EXTRACT SET TO FALSE (DEFAULT)
0030 /*      *****
0040 /*      &PFUSERNETID will be replaced automatically by N2O with the
0050 /*      Network Id for the primary FUSER node (FROM FUSER Node).
0060 /*
0070 /*      &SFUSER NETID1 - &SFUSERNETID10 will be replaced by N2O with
0080 /*      the Network Id for the secondary FUSER nodes (TO FUSER Nodes)
0090 /*
0100 /*      &PFDICNETID will be replaced automatically by N2O with the
0110 /*      Network Id for the primary FDIC node (FROM FDIC Node).
0120 /*
0130 /*      &SFDIC NETID1 - &SFDICNETID10 will be replaced by N2O with
0140 /*      the Network Id for the secondary FDIC nodes (TO FDIC Nodes)
0150 /*
0160 /*      &DATE will be replaced automatically by N2O with a value
0170 /*      derived from &DATN in order to uniquely identify the dataset.
0180 /*
0190 /*      &TIME will be replaced automatically by N2O with a value
0200 /*      derived from &TIMN in order to uniquely identify the dataset.
0210 /*
0220 //NDMBATCH EXEC PGM=DMBATCH
0230 //          REGION=4M,
0240 //          PARM=(YYSLYNN)
0250 //DMPUBLIB DD DSN=PRNDM.PERM.PROCESS.LIB,DISP=SHR
0260 //          DD DSN=PSOPE.PERM.NDM.PROCESS,DISP=SHR
0270 //DMSGFIL DD DSN=PRNDM.PERM.MSG,DISP=SHR
0280 //DMPRINT DD SYSOUT=*
0290 //NDMCMDs DD SYSOUT=*
0300 //SYSIN   DD *
0310     SIGNON NETMAP=PSNDM.PERM.NETMAP
0320           ESF=YES
0330     SUBMIT PROC=D4903NEW
0340     &&PNODE=&PFUSERNETID
0350     &&SNODE=&SFUSERNETID1
0360     &&FROMDSN=N2O.SOURCE
0370     &&TODSN=N2O.SOURCE.&DATE.&TIME
0380     &&UNIT=SYSDA
0390 /*
0400 //NDMBATCH EXEC PGM=DMBATCH
0410 //          REGION=4M,
0420 //          PARM=(YYSLYNN)
0430 //DMPUBLIB DD DSN=PRNDM.PERM.PROCESS.LIB,DISP=SHR
0440 //          DD DSN=PSOPE.PERM.NDM.PROCESS,DISP=SHR
0450 //DMSGFIL DD DSN=PRNDM.PERM.MSG,DISP=SHR
0460 //DMPRINT DD SYSOUT=*
0470 //NDMCMDs DD SYSOUT=*
0480 //SYSIN   DD *
0490     SIGNON NETMAP=PSNDM.PERM.NETMAP
0500           ESF=YES
0510     SUBMIT PROC=D4903NEW
0520     &&PNODE=&PFUSERNETID
0530     &&SNODE=&SFUSERNETID1
0540     &&FROMDSN=N2O.PREDICT
0550     &&TODSN=N2O.PREDICT.&DATE.&TIME
0560     &&UNIT=SYSDA
0570 /*
***** End of list *****

```

```

Program      NDMTRANT Library N2OBATCH
0010 /* USED BY SITES THAT HAVE MODIFIED N2OUE14N, SETTING THE
0020 /* VARIABLE BUILD-EXTRACT TO TRUE
0030 /******
0040 /* &PFUSERNETID WILL BE REPLACED AUTOMATICALLY BY N2O WITH THE NETWORK
0050 /* ID FOR THE PRIMARY FUSER NODE (FROM FUSER NODE).
0060 /**
0070 /* &SFUSER NETID1 - &SFUSERNETID10 WILL BE REPLACED BY N2O WITH THE
0080 /* NETWORK ID FOR THE SECONDARY FUSER NODES (TO FUSER NODES).
0090 /**
0100 /* &PFDICNETID WILL BE REPLACED AUTOMATICALLY BY N2O WITH THE NETWORK
0110 /* ID FOR THE PRIMARY FDIC NODE (FROM FDIC NODE).
0120 /* &SFDICNETID1 - &SFDICNETID10 WILL BE REPLACED BY N2O WITH THE
0130 /* NETWORK ID FOR THE SECONDARY FDIC NODES (TO FDIC NODES).
0140 /**
0150 /* &DATE WILL BE REPLACED AUTOMATICALLY BY N2O WITH A VALUE DERIVED
0160 /* FROM *DATN IN ORDER TO UNIQUELY IDENTIFY THE DATASET.
0170 /* &TIME WILL BE REPLACE AUTOMATICALLY BY N2O WITH A VALUE DERIVED FROM
0180 /* *TIMN IN ORDER TO UNIQUELY IDENTIFY THE DATASET.
0190 //N2OSEND      EXEC NATBAT,SOUT=X
0200 //CMWK01        DD      DSN=N2OPRD,DISP=(NEW,CATLG),
0210 //              SPACE=(CYL,(4,4)),
0220 //              DCB=(RECFM=VB,LRECL=1804,BLKSIZE=1808)
0230 //CMWK02        DD      DSN=N2OSRC,DISP=(NEW,CATLG),
0240 //              DCB=(RECFM=VB,LRECL=9183,BLKSIZE=9187),
0250 //              SPACE=(CYL,(1,1),RLSE)
0260 //CMWK03        DD      DSN=N2OPARM,DISP=SHR
0270 //CMWK05        DD      DSN=CMWK05,DISP=(NEW,CATLG),
0280 //              DCB=(RECFM=VB,LRECL=254,BLKSIZE=2540),
0290 //              SPACE=(CYL,(4,4))
0300 //CMPRT01      DD      SYSOUT=X
0310 //SYSIN         DD      DSN=N2OCOMM,DISP=SHR
0320 /**
0330 //NDMBATCH EXEC PGM=DMBATCH,
0340 //              REGION=4M,
0350 //              PARM=(YYSLYNN)
0360 //DMPUBLIB      DD      DSN=PRNDM.PERM.PROCESS.LIB,DISP=SHR
0370 //              DD      DSN=PSOPE.PERM.NDM.PROCESS,DISP=SHR
0380 //DMMSGFIL      DD      DSN=PSNDM.PERM.MSG,DISP=SHR
0390 //DMPRINT       DD      SYSOUT=*
0400 //NDMCMD5      DD      SYSOUT=*
0410 //SYSIN         DD*
0420 SIGNON NETMAP=PSNDM.PERM.NETMAP,
0430 ESF=YES
0440 SUBMIT PROC=D4903NEW
0450 &&PNODE=&PFUSERNETID
0460 &&SNODE=&SFUSERNETID1
0470 &&FROMDSN=N2O.SOURCE
0480 &&TODSN=N2O.SOURCE.&DATE.&TIME
0490 &&UNIT=SYSDA
0500 //NDMBATCH      EXEC      PGM=DMBATCH,
0510 //              REGION=4M,
0520 //              PARM=(YYSLYNN)
0530 //DMPUBLIB      DD      DSN=PRNDM.PERM.PROCESS.LIB,DISP=SHR
0540 //              DD      DSN=PSOPE.PERM.NDM.PROCESS,DISP=SHR
0550 //DMMSGFIL      DD      DSN=PSNDM.PERM.MSG,DISP=SHR
0560 //DMPRINT       DD      SYSOUT=*
0570 //NDMCMD5      DD      SYSOUT=*
0580 //SYSIN         DD*
0590 SIGNON NETMAP=PSNDM.PERM.NETMAP,
0600 ESF=YES
0610 SUBMIT PROC=D4903NEW
0620 &&PNODE=&PFUSERNETID
0630 &&SNODE=&SFUSERNETID1
0640 &&FROMDSN=N2O.PREDICT
0650 &&TODSN=N2O.PREDICT.&DATE.&TIME
0660 &&UNIT=SYSDA
0670 //NDMBATCH EXEC PGM=DMBATCH,
0680 //              REGION=4M
0690 //              PARM=(YYSLYNN)
0700 //DMPUBLIB      DD      DSN=PRNDM.PERM.PROCESS.LIB,DISP=SHR

```

```
0710 //          DD      DSN=PSOPE.PERM.NDM.PROCESS,DISP=SHR
0720 //DMSGFIL    DD      DSN=PSNDM.PERM.MSG,DISP=SHR
0730 //DMPRINT    DD      SYSOUT=*
0740 //NDMCMDSDS  DD      SYSOUT=*
0750 //          SYSIN    DD*
0760          SIGNON    NETMAP=PSNDM.PERM.NETMAP,
0770          ESF=YES
0780          SUBMIT    PROC=D4903NEW
0790          &&PNODE=&PFUSERNETID
0800          &&SNODE=&SFUSERNETID1
0810          &&FROMDSN=N2OCOMM
0820          &&TODSN=N2OCOMM.&DATE.&TIME
0830          &&UNIT=SYSDA
***** End of list *****
```

Section D.8 – COBOL sample JCL

```

Program      N2OCMPL  Library N2OBATCH
0010 //CBLOAD    PROC MEMBER=TEMPNAME,
0020 //          SLIB=,LLIB=DEVL,OBJNAME=TEMPNAME,
0030 //          CLIB1=CB,CLIB2=CB,CLIB3=CB,
0040 //          LLIB1=DEVL,LLIB2=PROD,FLAG=W,
0050 //          CALL=,CLIST=,DMAP=,DYNAM=,PMAP=NO,
0060 //          STATE=NO,FLOW=,RES=,COPT=,LOPT=,
0070 //          SYMDMP=NO,SYSOUT=A
0080 //COB        EXEC PGM=IKFCBL00,PARM=(&CLIST.CLIST,
0090 //          &DMAP.DMAP,&DYNAM.DYNAM,FLAG&FLAG,
0100 //          &PMAP.PMAP,&RES.RESIDENT,&STATE.STATE,
0110 //          &SYMDMP.SYMDMP,'&FLOW',
0120 //          TERM,LIB,'SIZE=384K',&COPT)
0130 //STEPLIB    DD DSN=SYS1.VSCOLIB,DISP=SHR
0140 //SYSLIB      DD DSN=ADMU.B014.&CLIB1..SOURCE,DISP=SHR
0150 //            DD DSN=ADMU.B014.&CLIB2..SOURCE,DISP=SHR
0160 //            DD DSN=ADMU.B014.&CLIB3..SOURCE,DISP=SHR
0170 //            DD DSN=ADMU.B014.CB.SOURCE,DISP=SHR
0180 //            DD DSN=ADMU.B014.MP.SOURCE,DISP=SHR
0190 //            DD DSN=SYS2.MACCOB,DISP=SHR
0200 //            DD DSN=SYSC.B022.PROD.SOURCE,DISP=SHR
0210 //SYSPRINT   DD SYSOUT=&SYSOUT
0220 //SYSTEM      DD SYSOUT=&SYSOUT
0230 //SYSPUNCH   DD SYSOUT=B
0240 //SYSUT1      DD UNIT=SYSDA,SPACE=(460,(700,100)),DSN=&&SYSUT1
0250 //SYSUT2      DD UNIT=SYSDA,SPACE=(460,(700,100)),DSN=&&SYSUT2
0260 //SYSUT3      DD UNIT=SYSDA,SPACE=(460,(700,100)),DSN=&&SYSUT3
0270 //SYSUT4      DD UNIT=SYSDA,SPACE=(460,(700,100)),DSN=&&SYSUT4
0280 //SYSUT5      DD UNIT=SYSDA,SPACE=(460,(700,100)),DSN=&&SYMDMP,
0290 //            DISP=(,PASS)
0300 //SYSLIN      DD DSN=&&LOADSET,DISP=(MOD,PASS),UNIT=SYSDA,
0310 //            SPACE=(80,(500,100))
0320 //SYSIN       DD DSN=&SLIB(&MEMBER),DISP=SHR
***** End of list *****

```

```

Program      MVSCOBAC Library N2OBATCH
0010 /** COBOL COMPILE JCL
0020 /**
0030 /** &STEPNUM will be replaced automatically by N2O with the next
0040 /** available step name.
0050 /**
0060 /** &SLIB will be replaced automatically by N2O with the target
0070 /** PDS name of the Event.
0080 /**
0090 /** &MEMBER will be replaced automatically by N2O with the name of
0100 /** the migrated member.
0110 /**
0120 /** &UXXXXXX will be replaced with the corresponding value specified
0130 /** in User-Exit-11.
0140 /**
0150 /**&STEPNUM EXEC PGM=IKFCBL00,PARM=(&UCLIST.CLIST,
0160 /**          &UDMAP.DMAP,&UDYNAM.DYNAM,FLAG&UFLAG,
0170 /**          &UPMAP.PMAP,&URES.RESIDENT,&USTATE.STATE,
0180 /**          &USYMDMP.SYMDMP,'&UFLOW',
0190 /**          TERM,LIB,'SIZE=384K',&COPT)
0200 //STEPLIB    DD DSN=SYS1.VSCOLIB,DISP=SHR
0210 //SYSLIB      DD DSN=&UCLIB1,DISP=SHR
0220 //            DD DSN=&UCLIB2,DISP=SHR
0230 //            DD DSN=&UCLIB3,DISP=SHR
0240 //            DD DSN=TREE.CB.SOURCE,DISP=SHR
0250 //            DD DSN=TREE.MP.SOURCE,DISP=SHR
0260 //            DD DSN=SYS2.MACCOB,DISP=SHR
0270 //            DD DSN=TREE.PROD.SOURCE,DISP=SHR
0280 //SYSPRINT   DD SYSOUT=&USYSOUT
0290 //SYSTEM      DD SYSOUT=&USYSOUT
0300 //SYSPUNCH   DD SYSOUT=B
0310 //SYSUT1      DD UNIT=SYSDA,SPACE=(460,(700,100))
0320 //SYSUT2      DD UNIT=SYSDA,SPACE=(460,(700,100))

```

```

0330 //SYSUT3 DD UNIT=SYSDA,SPACE=(460,(700,100))
0340 //SYSUT4 DD UNIT=SYSDA,SPACE=(460,(700,100))
0350 //SYSUT5 DD UNIT=SYSDA,SPACE=(460,(700,100))
0360 //SYSLIN DD DSN=&&LOADSET,DISP=(MOD,PASS),UNIT=SYSDA,
0370 //          SPACE=(80,(500,100))
0380 //SYSIN DD DSN=&SLIB(&MEMBER),DISP=SHR
0390 /**
***** End of list *****

```

Program MVSCOBK Library N2OBATCH

```

0010 /** LINK EDIT JCL
0020 /**
0030 /** &STEPNUM will be replaced automatically by N2O with the next
0040 /** available step name.
0050 /**
0060 /** &MEMBER will be replaced automatically by N2O with the name of
0070 /** the migrated member.
0080 /**
0090 /** &UXXXXXX will be replaced with the corresponding value specified
0100 /** in User-Exit-11.
0110 /**
0120 /**&STEPNUM EXEC PGM=IEWL,PARM=(&LUOPT),
0130 /**          COND=(5,LT,COB)
0140 //SYSLIN DD DSNNAME=&&LOADSET,DISP=(OLD,DELETE)
0150 //          DDNAME=SYSIN
0160 //STEPLIB DD DSN=SYS1.VSCOLIB,DISP=SHR
0170 //SYSMOD DD DSNNAME=&ULLIB(&MEMBER),DISP=SHR
0180 //SYSLIB DD DSN=TREE.VSCLLIB,DISP=SHR
0190 //          DD DSN=TREE.NTSUBRTN.LOAD,DISP=SHR
0200 //          DD DSN=&ULLIB1,DISP=SHR
0210 //          DD DSN=&ULLIB2,DISP=SHR
0220 //          DD DSN=TREE.PROD.ADALOAD,DISP=SHR
0230 //          DD DSN=TREE.PROD.LOAD,DISP=SHR
0240 //          DD DSN=TREE.PROD.COBLOAD,DISP=SHR
0250 //SYSUT1 DD UNIT=SYSDA,SPACE=(1024,(50,20))
0260 //SYSPRINT DD SYSOUT=&USYSOUT
0270 /**
***** End of list *****

```

Program MVSCOBUS Library N2OBATCH

```

0010 /**
0020 /** This JCL could be used to compile a COBOL program by calling a
0030 /** PROC.
0040 /**
0050 /** &STEPNUM will be replaced automatically by N2O with the next
0060 /** available step name.
0070 /**
0080 /** &SLIB will be replaced automatically by N2O with the target
0090 /** PDS name of the Event.
0100 /**
0110 /** &MEMBER will be replaced automatically by N2O with the name of
0120 /** the migrated member.
0130 /**
0140 /** &UXXXXXX will be replaced with the corresponding value specified
0150 /** in User-Exit-11.
0160 /**
0170 /**&STEPNUM EXEC COBCMPL,
0180 //          SLIB=&SLIB,
0190 //          MEMBER=&MEMBER,
0200 //          SYSOUT=*,
0210 //          OBJNAME=&UOBJ,
0220 //          LOPT=&ULOPT
0230 /**
***** End of list *****

```

This page intentionally left blank.

APPENDIX E

Frequently Asked Questions

Where does N2O place the output of my batch job?

N2O writes the output to CMPRT01.

How can I delete an Event with a status of 'H'?

A status of 'H' indicates that the Event is on hold. The status of the Event can be modified using the Utility Tools in the Toolbox Subsystem.

Why is my Event marked "Override"?

N2O allows self-authorization and emergency migrations without authority or approval. In both cases the Events are marked as override. An override Event is always copied regardless of the migration profile. Therefore, users will see a move changed to a copy. Override Events do not delete objects.

What is an Extract Event and how is it used?

An Extract Event migrates an object without causing a checkout to occur. It is used for migrating objects to a development library. The objects would be copies of existing code to be used as the basis for new programs. An Extract Event also allows the object to be renamed on the target environment.

How do I use an existing program as a base for creating a new program?

An Extract Event migrates an object to a library without performing a checkout. It also allows an object to be renamed at the target.

How do I allow a supervisor to authorize an Event if the programmer is not available?

When defining a migration profile with authorization, the user also defines the authorization level and authorization ID. Entering "*" allows any user with the appropriate approval profile to authorize the Event. The Supervisor's approval profile should contain the migration paths necessary to authorize Events as needed. Up to 40 migration paths can be defined in the approval profile.

How is Project Tracking used with N2O?

Every time an Event is requested, the user can relate that Event to a specific task defined in the N2O Project Tracking Subsystem. This allows the user to track the relationships of Events and projects. Refer to **Section III Project Tracking Subsystem**.

How does N2O handle multiple versions of the same program?

Multiple versions of programs are handled using the checkout/checkin features of N2O. The Checkout/Checkin field on the N2O install parms screen specifies the levels of checkout permitted. Every time an object is checked out, N2O verifies the current number of checkouts. If more than one checkout exists the user receives a warning message on the screen. A user will receive this warning every time the object is migrated if more than one checkout exists.

Does N2O have a move option so that the object's source and compiled code is deleted from the location from which you are migrating?

Yes, there is a move option. It is set in the Migration Profile method parameter. Refer to the ***N2O Administrator Manual***.

For PDSs, the JCL must be changed from an IEBCOPY to an IEBMOVE. For PANVALET, ENDEVOR, or Librarian, it would depend on their capabilities.

What does the Change Control Number do?

The Change Control Number provides a way to relate several Events. If the user has ten Events to complete a specific enhancement/bug fix, the user can assign them all the same Change Control Number. A report by Change Control Number is available to show all Events related to a selected number. This allows a history of all modules changed to be related to an enhancement/bug fix.

Installation/Product Upgrade Questions

What do I have to do to N2O when upgrading Natural versions?

When upgrading NATURAL, the N2OUCPY program must be executed to ensure that the correct USR* modules are in the SYSTEM and SYSLIB libraries. If you are using N2O's autocompile and/or N2OEDIT components, they must be re-installed.

Does upgrading PREDICT versions require any changes to N2O?

Yes, the PREDICT version in User-Exit 14 must be changed and the member stowed as described in the ***N2O Administrator Manual***.

Can I install N2O on the FNAT?

No. N2O cannot be installed on the FNAT.

APPENDIX F

N2OSCAN GLOSSARY

[illegible]

TERM	DEFINITION
Hit	See <i>Scan Hit</i> .
Include/Exclude Indicator	Valid values are I (for “include”) or E (for “exclude”). If value is I , then the associated <i>Scan String</i> becomes an <i>Inclusion String</i> used in <i>Inclusion Processing</i> . If value is N , then the associated <i>Scan String</i> becomes an <i>Exclusion String</i> used in <i>Exclusion Processing</i> .
Inclusion Process	A target source line is examined for all <i>Inclusion Strings</i> defined in the <i>Scan Parm Set</i> . If an <i>Inclusion String</i> is found, then a <i>Hit</i> is registered and the complete space-delimited string identified in the target source line is designated as a <i>Found String</i> . A <i>Found String</i> is passed on to the <i>Exclusion Process</i> .
Inclusion String	A <i>Scan String</i> (denoted by <i>Include/exclude Indicator</i> = I) used as input to the <i>Inclusion Process</i> . (Refer to “ <i>Include/exclude Indicator</i> ”.)
Label of Scan Parm Set	Used by N2OSCAN to differentiate <i>Scan Parm Set</i> objects from other NATURAL text objects. A valid <i>Label</i> value consists of the characters ENV= or ENVIRONMENT= found at the beginning of the first non-comment line. The presence or absence of this <i>Label</i> distinguishes <i>Scan Parm Set</i> objects (which have this <i>Label</i>) from other NATURAL text objects (which do not have this <i>Label</i>).
Optional Header Parms	Any of the following, upper- or lower- case, separated by a comma delimiter, may appear following the Required Header Parm (see above). A comma at the end of a line indicates continuation to next line. <i>Optional Header Parms</i> may be in any order. START-LIB=xxxxxxx or START-LIBRARY=xxxxxxx END-LIB=xxxxxxx or END-LIBRARY=xxxxxxx START-OBJ=xxxxxxx or START-OBJECT=xxxxxxx END-OBJ=xxxxxxx or END-OBJECT=xxxxxxx DELIM=<xxxxxxx> or DELIMITER=<xxxxxxx> or DELIMITERS=<xxxxxxx> (may have up to 32 Delimiters) Additional note: Each Header Parm above may appear only once in the Header. If any Header Parm appears more than once, the first occurrence will be used in processing and subsequent occurrences will be ignored.
Required Header Parm	The following, upper- or lower-case, must appear at the beginning of the first non-comment line of the <i>Scan Parm Set</i> . To be valid, it must be set equal to an existing N2O Environment on a local node. ENV=xxxx or ENVIRONMENT=xxxx
Scan Hit	An event identifying a target source Environment, Library, Object, Line Number, and <i>Found String</i> value output by the Scan Process.

TERM	DEFINITION
Scan Output Set	<p>A set of records stored on the N2O-MIGRATION file, which constitute the output of a scan.</p> <p>A <i>Scan Output Set</i> consists of (1) detail records of all <i>Scan Hits</i> and (2) summary records outlining scan statistics at the object, library, and full <i>Scan Output Set</i> level.</p> <p>A <i>Scan Output Set</i> is uniquely identified by: (1) the User ID of the user who submitted the scan, (2) the Scan Parm Set ID of the <i>Scan Parm Set</i> selected as input to the scan, (3) the starting value for the range of libraries scanned, (4) the ending value for the range of libraries scanned, (5) the starting value for the range of objects scanned, and (6) the ending value for the range of objects scanned.</p>
Scan Parm Set	<p>A NATURAL text object that has a valid <i>Scan Parm Set Label</i>.</p> <p>To be valid for scan processing, a <i>Scan Parm Set</i> must have a valid <i>Scan Parm Set Label</i>, a valid <i>Scan Parm Set Header</i>, and at least one valid <i>Detail Line</i> with an <i>Inclusion String</i>.</p>
Scan Process	<p><i>Scan Process</i> examines target source code one line at a time, performing the <i>Inclusion Process</i> followed by the <i>Exclusion Process</i>.</p>
Scan String	<p>A case-sensitive string (up to 32 characters in length) used as input to <i>Scan Processing</i>.</p>

This page intentionally left blank

INDEX

3

3GL
 Batch Submit JCL D-61
 PDS archive JCL D-62
 PDS Archive Recovery JCL D-65
 PDS Catalog Capture JCL D-63
 PDS Compile sample JCL D-63
 PDS Migration JCL D-64
 PDS sample MOVE JCL D-64
 Predict Pre-processor JCL D-66
 Sample Compile JCL D-61
 3GL Objects 2
 3GL/Other Autocompile 125
 3GL/Other PDS Member
 Type Update 85, 92–93

A

Add
 Event 19
 Project Definition 141, 142–46
 Suggestion 157, 158–60
 Task 152–53
 Application Life Cycle 2
 Archive
 Backup Reporting
 BS2000 JCL D-59
 BSE JCL D-60
 VM JCL D-60
 z/OS JCL D-59
 Purge
 BS2000 JCL D-3
 VM JCL D-4
 VSE JCL D-5
 z/OS JCL D-1
 Archive Definition Usage 200–201
 Archive Version Summary 249, 284–86
 Archiving/Recovery 5
 Audit Trail 5
 Authorized Users
 to an Environment 195, 196–97
 Autocompile 5, 16, 85, 86, 87, 89,
 92, 125, 134, 136
 Libraries Pending Autocompile 86–89
 N2OCAT 87
 Autocompile Summary for
 Events 208, 241–46

B

Batch Documentation Process 362
 Batch JCL Submission
 3GL/Other Autocompile 125
 All Pending Events 125

Event 125, 126–27, 128
 Master Event 125
 Migration Profiles 125, 128–30
 View JCL for a Profile 125, 132–33
 Batch Migration
 BS2000 JCL D-30
 VM JCL D-32
 VSE JCL D-33
 z/OS JCL D-29
 Batch N2OPURGE Utility JCL 371
 Batch Reporting 362, 379, 424, 427
 Batch Source Compare Utility 393

C

Cancel a Task 163, 166–67
 Cancel Utility 96, 97–100, 97–100, 97–100
 Catalog Capture
 BS2000 JCL D-8
 VM JCL D-9
 VSE JCL D-10
 z/OS JCL D-7
 Checked-out Objects 249
 Checkout Utility 96, 112–17
 Checkout/Checkin 5, 17, 18
 Checkout/Checkin Utilities 94–122, 94–122
 Cancel Utility 96, 97–100,
 97–100, 97–100
 Checkout Utility 96, 97, 112–17
 Enrollment Facility 96, 97, 119–22,
 119–22
 Reject Utility 96, 97, 118
 Transfer by Event Utility 96, 97,
 110–11, 110–11
 Transfer Utility 96, 97, 107–8
 Chronology of Events 207
 COBOL
 Sample JCL D-83
 Compare Utilities 5
 Copy
 Event 19, 47
 Project Definition 141, 147
 Suggestion 157, 160
 Task 154
 Cross-Reference 5, 269–70
 Cross-Reference Selection Process 27

D

Data Area Listing 333, 362, 436
 Data Entry Screens 7, 9
 DB2
 Sample JCL D-74
 DBW Plan Bind 136–38
 Deferred MOVE 46, 85, 90–91

Deferred Moves	
BS2000 JCL	D-19
VM JCL	D-20
VSE JCL	D-21
z/OS JCL	D-18
Delete	
Event	19, 48, 63, 69, 76
Project Definition	141, 148
Suggestion	157, 160
DENIED	62
Descriptor X-Ref Information	333
Report Type	350
Direct Command line	8
Directory Compare	264–68
Directory List	249, 258–61
Documentation Tools	331, 332, 333–63
Data Area Listing	333, 362, 436
Descriptor X-Ref Information	333
Report Type	350
File Layouts	333, 362
Data Repository	348
Detail Level	348
With Keyword	347
Force Uppercase	337
Map Listing	333, 339–44, 362
Automatic	343
Free	343
Inline	343, 344
PREDICT Automatic	343
PREDICT Free	343
Sample	341
Show Fields and Rules	340, 341
Values	344
Ver Type	344
Mode	337
Natural Object Listing	333, 334, 362, 436
Exclude Object Types	336
Explode Copycode	336
Explode Data Areas	336
Format Data Areas	337
Format Maps	337
Object X-Ref	337
Object Flow Analysis	333
Sample	353
Object X-Ref	334
Sample	355
Route Output	337

E

Emergency Recovery	
Acknowledgement	
BS2000 JCL	D-24
VM JCL	D-24
VSE JCL	D-25
z/OS JCL	D-23
Batch Execution	

BS2000 JCL	D-22
VM JCL	D-22
VSE JCL	D-23
z/OS JCL	D-22
ENDEVOR	35, 52, 99, 107, 115, 118, 121
Catalog Capture JCL	D-69
Migration JCL	D-70
Enrollment Facility	96, 119–22, 119–22
Environment	
Batch update of FUSER/FDIC	
BS2000 JCL	D-58
VM JCL	D-58
VSE JCL	D-59
z/OS JCL	D-57
Environment Definition Usage	202–3
Environment Reporting	195–206
Archive Definition Usage	200–201
Authorized Users	
to an Environment	195, 196–97
Node Definition Usage	195, 198–99
Users Related to a Group-ID	204–5
Environment Reporting in Batch	206
Error Message Screens	7, 13
Event	
Add	19, 20–23
Authorize	64–68
Autocompile Summary	208, 241–46
Batch JCL Submission	131
Cancel Deferred Move	85, 91
Chronology	207
Copy	47
Copy	19
Delete	19, 48, 63, 69, 76
Deleting In-progress	48, 69, 76
Details	207, 216–28
Extract	38
Inquire on	19, 49–50, 63, 70, 73, 70–72, 75, 77–79
Migration Subsystem	63–74, 75–84
Migration Utilities	90, 91
Modify	19, 51
Multiple Target	17, 23
Objects Migrated	293, 302–3, 302–3
Pending Autocompile	208, 238–40
Pending Autocompile for a	
Library	294–95
Pending for an Environment	293, 296
Pending for an Object	249, 287–89
Pending Move	207, 236–37
Process Deferred Move	85, 90
Processed by Date	207, 229–31
Recovery from Archive	52–55
Related by Change Control	207, 213–15
Reporting	194, 207–47
Reporting in Batch	247, 306
Request	20–35, 48, 49–50, 55

Requiring Further	
Authorization	207, 208–10
Select Events for	
Processing	19, 59, 63, 74, 75, 84
Service	80–83
Submit	125, 126–27
Submit a Master Event	125
Submit All Pending Events	125, 131
Transfer by Event	
Utility	96, 110–11, 110–11
Viewing NATURAL Programs	49
With Warning Messages	207, 232–35
Event Purge	
BS2000 JCL	D-27
VM JCL	D-27
VSE JCL	D-28
z/OS JCL	D-26
Exclusion Process	398, F-1, F-2, F-3

F

FAILED	61
Field-Level Help	10
File Layouts	333, 362
Data Repository	348
Detail Level	348
With Keyword	347

G

Group-ID	204
----------------	-----

H

Help Screens	7, 10
History of a Task	181–82
History of an Environment	249, 250–53
History of an Object	249, 254–57

I

Include/Exclude Indicator	398, F-1, F-2
Inclusion Process	398, F-1, F-2, F-3
Inquire on	
Event	19, 49–50, 63, 70–72, 75, 77–79
Project Definition	141, 149
Suggestion	157, 161
Task	155

L

Librarian	
Catalog Capture	D-71
Compile Sample JCL	D-71
Migration JCL	D-72
Libraries Pending Autocompile	86–89
Link Objects to a Task	163, 170–72
Link Suggestions to a Task	163, 174–75
Link Tasks to a Task	163, 177–78

M

Maintenance Tools	331, 332
N2OPURGE Utility	364, 365–71
Map Listing	333, 339–44, 362
Automatic	343
Free	343
Inline	343, 344
PREDICT Automatic	343
PREDICT Free	343
Sample	341
Show Fields and Rules	340, 341
Values	344
Ver Type	344
Menu Screens	7
Migration Process	44–46
Migration Subsystem	15–138
Authorize Events	16
Batch JCL Submission	16
Checkout/Checkin Utilities	16
Migration Utilities	16
Request Events	16
Service Events	16
Migration Utilities	85–93
3GL/Other PDS Member Type Update	85
Cancel Deferred Move Events	85
Libraries Pending Autocompile	85, 86–89
Process Deferred Move Events	85
Modify	
Event	19, 51
Project Definition	141, 149
Suggestion	157, 161
Task	155
MOVE	46
Deferred	85, 91
MULTIPLE	62

N

N2O Subsystems	4
N2O User Interface	6–13
N2O3110B	392
N2OCATI	86
N2OPURGE	
BS2000 JCL	D-36
VM JCL	D-37
VSE JCL	D-38
z/OS JCL	D-35
N2OPURGE Utility	364, 365–72
N2OSCAN	
Batch Execution	
VM JCL	D-47
VSE JCL	D-47
Batch Execution	
z/OS JCL	D-47
Batch Source Display	
VM JCL	D-51

VSE JCL	D-52
z/OS JCL	D-51
Delete by date and userid	
VM JCL	D-50
VSE JCL	D-50
z/OS JCL	D-49
Delete scan output set	
VM JCL	D-48
VSE JCL	D-49
z/OS JCL	D-48
Standard Report	
VM JCL	D-55
VSE JCL	D-56
z/OS JCL	D-55
String found Report	
VM JCL	D-56
VSE JCL	D-57
z/OS JCL	D-56
VM JCL	D-53
VSE JCL	D-54
z/OS JCL	D-53
N2OSCAN Utility	395
Natural Object Listing	333, 334, 362, 436
Exclude Object Types	336
Explode Copycode	336
Explode Data Areas	336
Format Data Areas	337
Format Maps	337
Object X-Ref	337
NATURAL Objects	1
Network Data Mover	
JCL	D-80
NO DOC	61
NO OBJ	62
NO SRC	62
NO XREF	61
Node Definition Usage	195, 198–99

O

OBJ FAIL	61
Object Compare	382
BS2000 JCL	D-11
VM JCL	D-11
VSE JCL	D-12
z/OS JCL	D-11
Object Details	226–28
Object Flow Analysis	333
Sample	353
Object Reporting	250–92
Archive Version Summary	284–86
Cross-Reference	269–70
Directory Compare	264–68
Directory List	258–61
Events Pending for an Object	287–89
History of an Environment	249, 250–53
History of an Object	249

Objects Archived by	
N2OPURGE	281–83
Object Selection Process	
3GL/Other Members	35–43
N2OPURGE Recovery	57–58
NATURAL Objects	26–27
PREDICT Objects	30–34
Scrolling	24, 127
SYSERR Messages	28–29
Object Selection Screen Messages	
DENIED	62
FAILED	61
MULTIPLE	62
NO DOC	61
NO OBJ	62
NO SRC	62
NO XREF	61
OBJ FAIL	61
WARNING	61
Object X-Ref	334
Sample	355
Objects Archived by	
N2OPURGE	249, 281–83
Objects Migrated	293, 298–99
Objects Migrated by a User	293, 300–301, 300–301
On-line Authorization	5
On-line Processing	45–46
On-line/Batch Migration	5

P

Panvalet	
Catalog Capture JCL	D-67
Compile Sample JCL	D-67
Migration JCL	D-68
PF-keys	8
PREDICT Objects	1
Programmer Tools	331, 332
Object Compare	382
Source Compare	382
View Archived Objects	382
View Program Source	382
Project Definition	140, 141–50
Add	141, 142–46
Copy	141, 147
Delete	141, 148
Inquire on	141, 149
Modify	141, 149
Select	141, 150
Project Status	185–86
Project Tracking Reports	140
History of a Task	181–82
Project Status	185–86
Task Details	183–84
User Status	187–88
Project Tracking Subsystem	6

Project Definition	140, 141–50
Project Tracking Reports	140
Suggestion Box	140, 157–62
Task List	140, 151–56
Task Utilities	140, 163–79
PURGE and ARCHIVE	370

R

Recover From an Archive Backup	364
Recover from Archive Backup	
BS2000 JCL	D-40
VM JCL	D-41
VSE JCL	D-41
z/OS JCL	D-39
Recover from Archive Backup PDS	
z/OS JCL	D-42
Recover Purged Events	
BS2000 JCL	D-43
VM JCL	D-44
VSE JCL	D-45
z/OS JCL	D-43
Recovery from Archive	52–55
N2OPURGE	53
Reject a Task	163, 168–69
Reject Utility	96, 118
Rename an object	38
Reporting	
BS2000 JCL	D-46
VM JCL	D-46
VSE JCL	D-46
z/OS JCL	D-45
Reporting Subsystem	6
Environment	194, 195–206
Event	194, 207–47
Object	194, 250–92
Statistical	194

S

Scan Output Set	395, 398, 399, 408, 410–18, 419, 421, 422, 424, 425, 427, 422–35, 431, 432, 433, F-1, F-3
Scan Parm Set	395–98, 399, 400, 401, 402–3, 404–5, 406, 409, 410, 412, 414, 416, 419, 423, 428, 431, 433, 434, F-1, F-2, F-3
DELIM Header Parm	F-1
Detail Line	395, 396, 397–98, 400, 401, 403, 405, F-1, F-3
Header Parm	395, 396–97, 400, 401, 402, 403, 404, F-1, F-2
Scan String	398, F-1, F-2, F-3
Screens	6–13
Data Entry	7, 9
Error Message	7, 13
Help	7, 10

Menu	7
Selection	7, 9
Startup	7
SECURITRE	196
Security	6
Select	19
Event	19, 74, 75, 84
Project Definition	141, 150
Suggestion	157, 162
Task	156
Selection Screens	7, 9
Service Events	
Inquire on an Event	77–79
Source Compare	382
Local Environment	
BS2000 JCL	D-17
VM JCL	D-17
VSE JCL	D-17
z/OS JCL	D-16
Remote Environment	
BS2000 JCL	D-13
VM JCL	D-14
VSE JCL	D-15
z/OS JCL	D-12
Startup Screens	7
Statistical Reporting	
Events Pending Autocompile	
for a Library	293, 294–95
Events Pending for an Environment ...	296
Events Pending Migration for an	
Environment	293
Objects Migrated	293, 298–99
Objects Migrated	
by a User	293, 300–301, 300–301
Objects Migrated	
for an Event	293, 302–3, 302–3
Statistical Reporting in Batch	330
Status of Event	B-1
Submit Migration Profiles	125, 128–30
Suggestion Box	140, 157–62
Add	157, 158–59
Copy	157, 160
Delete	157, 160
Inquire on	157, 161
Modify	157, 161
Select	157, 162
SYSERR Messages	1

T

Task Details	183–84
Task List	140, 151–56
Add	152–53
Copy	154
Inquire on	155
Modify	155
Select	156

Task Utilities	140, 163–79
Cancel a Task	163, 166–67
Link Objects to a Task.....	163, 170–73
Link Suggestions to a Task ...	163, 174–75
Link Tasks to a Task	163, 177–79
Reject a Task	163, 168–69
Update Stage for a Task	163, 164–65
Toolbox Subsystem	
Documentation Tools	332
Maintenance Tools	332
Programmer Tools	332
Recover from an Archive Backup	364
Transfer by Event Utility	96
Transfer Utility	96

U

Update Stage for a Task	163, 164–65
User Status.....	187–88
User-Exit-12	90
User-Exit-15	22

User-Exit-2	62
User-Exit-5	95, 98, 102, 104, 107
User-Exit-7	89
User-exits	6
Users Related to a Group-ID.....	204–5
Utility Tools.....	332, 436–44

V

View Archived Objects	382
View JCL for a Profile.....	125, 132–33
View Program Source	382

W

WARNING	61
---------------	----

X

XREF.....	1, 269–70
XREF Selection Process	27