READ THIS FIRST SEDIT 4.70 S/REXX 2.70

Important Copyright Notice

Benaroya et Compagnie owns the copyright to the SEDIT computer program with all rights reserved. Under the copyright laws, the Program may not be copied, in whole or part, without the written consent of Benaroya et Compagnie, except to install it onto a licensed computer system.

Benaroya et Compagnie reserves the right to make changes in specifications and other information contained in this publication without prior notice, and the reader should in all cases consult Benaroya et Compagnie to determine whether any such changes have been made. This manual may not be reproduced and is intended for the exclusive use of Benaroya et Compagnie's customers.

The terms and conditions governing the sale of the SEDIT licence software consist solely of those set forth in the licence agreement included with this package. No statement contained in this publication shall be considered a warranty by Benaroya et Compagnie for any purpose or give rise to any liability of Benaroya et Compagnie.

SEDIT and S/REXX are registered trademarks of Benaroya et Compagnie. UNIX is a trademark of X/OPEN Company LTD. IBM is a registered trademark of International Business Machines. OpenLook is a trademark of Novell.

Table of Contents

	1
Loading on SUN Solaris Systems with the SUN Volume Management	1
Loading on SUN Solaris Systems without the SUN Volume Management	1
Loading on SunOS 4.1.3+ Systems	2
Loading on HPUX 9.05 Systems	2
Loading on HPUX 10.xx and 11+ Systems	2
Loading on IBM Systems	3
Loading on DEC Digital Unix Systems	3
Loading on SiliconGraphics Systems	3
Loading on LINUX Systems	4
Installing System Shared Libraries	4
Loading on SCO Systems	4
Loading on SINIX Systems	5
Loading on UNIXWARE Systems	5
Session Example Running on Solaris	6
Note for Previous Release Users	7
Note for Windows Users	8
Using SEDIT on Sun Workstations with SOLARIS 2.4+	9
Using the MOTIF Version	9
Using SEDIT on Sun Workstations with Sun OS	10
Using the OPENWINDOWS version	10
Using the MOTIF Version	10
Using SEDIT on PCs with SOLARIS 2.5+	11
Using SEDIT on IBM Workstations	12
IBM-850 Font Versus ISO8859-1 Font	13
IDM-650 Font Versus ISO6657-1 Font	15
Using SEDIT on HP Workstations	14
Using SEDIT on HP Workstations Using SEDIT on Silicon Graphics Workstations	14 15
Using SEDIT on HP Workstations Using SEDIT on Silicon Graphics Workstations Using SEDIT on PCs with LINUX	14 15 16
Using SEDIT on HP Workstations Using SEDIT on Silicon Graphics Workstations Using SEDIT on PCs with LINUX	14 15 16
Using SEDIT on HP Workstations Using SEDIT on Silicon Graphics Workstations Using SEDIT on PCs with LINUX Checking your SEDITID Using the Character Mode Version	14 15 16 16
Using SEDIT on HP Workstations Using SEDIT on Silicon Graphics Workstations Using SEDIT on PCs with LINUX Checking your SEDITID Using the Character Mode Version Installing System Shared Libraries	14 15 16 16 17 17
Using SEDIT on HP Workstations Using SEDIT on Silicon Graphics Workstations Using SEDIT on PCs with LINUX Checking your SEDITID Using the Character Mode Version Installing System Shared Libraries Using SEDIT on an a.out Linux Kernel	14 15 16 16 17 17 17
Using SEDIT on HP Workstations Using SEDIT on Silicon Graphics Workstations Using SEDIT on PCs with LINUX Checking your SEDITID Using the Character Mode Version Installing System Shared Libraries Using SEDIT on an a.out Linux Kernel	14 15 16 16 17 17 17
Using SEDIT on HP Workstations Using SEDIT on Silicon Graphics Workstations Using SEDIT on PCs with LINUX Checking your SEDITID Using the Character Mode Version Installing System Shared Libraries Using SEDIT on an a.out Linux Kernel Using SEDIT on PCs with SCO	14 15 16 16 17 17 17 17

Using SEDIT on PCs with UNIXWARE	19
Checking the SEDITID	19
Using the MOTIF Version	19
Using SEDIT on DEC/COMPAQ/HP TRUE64 OSF1 Stations	20
Checking the SEDITID	20
Setting the Keyboard Mapping	20
Checking the CPU ID	
Using SEDIT on Siemens SINIX Systems	22
Using ASCII Terminals	23
Using Dialog Boxes with MOTIF or CDE	24

Loading from a CDROM

We assume that the cdrom mounting point is /cdrom. If this directory does not exist, create it with the following command:

mkdir /cdrom

Loading on SUN Solaris Systems with the SUN Volume Management

When the SUN Volume Management is active, the cdrom will be automatically mounted on the /cdrom directory.

Type the following statements to start the install script:

```
# ls -Ftla /cdrom
drwxr-xr-x 5 root 512 Feb 10 15:12 ./
lrwxrwxrwx 1 root 25 Feb 10 15:12 cdrom0 -> ./sedit_420c1_srexx_220c1
drwxr-xr-x 70 root 2048 Feb 7 11:28 ../
drwxr-xr-x 2 root 512 May 14 1997 sunsolve_3_0/
drwxr-xr-x 2 root 512 May 2 1997 cdrom#1/
dr-xr-xr- 2 root 2048 Jan 1 1970 sedit_420c1_srexx_220c1/
# /cdom/cdrom0/unix/install
```

The ls commands shows the actual mounting point. In this example, it is assumed to be /cdrom/cdrom0.

install will ask you if you want to load the **SEDIT** version corresponding to the operating system you are using. An example of a session is displayed on page 6.

<u>Loading on SUN Solaris Systems without the SUN Volume Management</u>

Issue the following commands:

```
# mount -r -F hsfs -o ro /dev/sr0 /cdrom
# /cdrom/unix/install
```

The cdrom device /dev/sr0 is only an example. Therefore, the device number may be different on your system.

install will ask you if you want to load the **SEDIT** version corresponding to the operating system you are using. An example of a session is displayed on page 6.

Loading on SunOS 4.1.3+ Systems

Issue the following commands:

```
# mount mount -r -F hsfs -o ro /dev/sr1 /cdrom
# /cdrom/unix/install
```

The cdrom device /dev/sr1 is only an example. Therefore, the device number may be different on your system.

install will ask you if you want to load the **SEDIT** version corresponding to the operating system you are using. An example of a session is displayed on page 6.

Loading on HPUX 9.05 Systems

Issue the following commands:

mount -r -t cdfs /dev/dsk/c201d1s0 /cdrom

'/cdrom/UNIX/INSTALL;1'

The cdrom device /dev/dsk/c0t1d0 is only an example. Therefore, the device number may be different on your system.

'INSTALL; 1' will ask you if you want to load the **SEDIT** version corresponding to the operating system you are using. An example of a session is displayed on page 6.

Notes: The quotes in the '/cdrom/UNIX/INSTALL;1' expression are mandatory.

SEDIT 4.20 and S/REXX 2.20 are the last releases to support HPUX 9.05.

Loading on HPUX 10.xx and 11+ Systems

Issue the following commands:

mount -r -F cdfs -ocdcase /dev/dsk/c0tld0 /cdrom
/cdrom/unix/install

The cdrom device /dev/dsk/c0t1d0 is only an example. Therefore, the device number may be different on your system.

install will ask you if you want to load the **SEDIT** version corresponding to the operating system you are using. An example of a session is displayed on page 6.

Notes: **SEDIT** 4.60A and **S/REXX** 2.60A are the last releases to support HPUX 10.xx.

Loading on IBM Systems

Issue the following commands:

```
# mount -r -v'cdrfs' /dev/cd1 /cdrom
# /cdrom/unix/install.ibm /cdrom
```

The cdrom device /dev/cd0 is only an example. Therefore, the device number may be different on your system.

install.ibm will ask you if you want to load the **SEDIT** version corresponding to the operating system you are using. An example of a session is displayed on page 6.

Note: **SEDIT** 4.40 and **S/REXX** 2.40 are the last releases to support AIX 3.2.5.

Loading on DEC Digital Unix Systems

Issue the following commands:

```
# mount -t cdfs -o noversion -r /dev/rz4c /cdrom
# /cdrom/unix/install
```

The cdrom device /dev/rz4c is only an example. Therefore, the device number may be different on your system.

install will ask you if you want to load the **SEDIT** version corresponding to the operating system you are using. An example of a session is displayed on page 6.

Loading on SiliconGraphics Systems

Usually, the cdrom is automatically mounted on / CDROM when inserted in the cdrom drive.

Issue the following command:

```
# /CDROM/unix/install
```

The cdrom directory /CDROM is only an example. Therefore, the cdrom directory may be different on your system.

install will ask you if you want to load the **SEDIT** version corresponding to the operating system you are using. An example of a session is displayed on page 6.

Loading on LINUX Systems

Issue the following commands:

```
# mount -r /dev/scd0 /cdrom
```

```
# /cdrom/unix/install
```

The cdrom device /dev/scd0 is only an example. Therefore, the device number may be different on your system.

install will ask you if you want to load the **SEDIT** version corresponding to the operating system you are using. An example of a session is displayed on page 6.

Installing System Shared Libraries

If install indicates an error while loading shared libraries, you may try to install the supplied shared libraries by typing:

/cdrom/unix/linux/libs/install

Note: you must be ROOT to use /cdrom/unix/linux/libs/install.

Loading on SCO Systems

Issue the following commands:

mount -r -f HS,lower /dev/cd0 /cdrom
/cdrom/unix/install /cdrom

The cdrom device /dev/scd0 is only an example. Therefore, the device number may be different on your system.

Notes: The UNIX kernel must support High Sierra / ISO9660 filesystem. The /usr/lib/mkdev/cdrom utility may be used to configure the kernel. The SCO tar utility may display various error messages, such as:

tar: ./ - cannot create
tar: ./bin/ - cannot create
tar: ./bin/sco/ - cannot create

These messages can be ignored.

install will ask you if you want to load the **SEDIT** version corresponding to the operating system you are using. An example of a session is displayed on page 6.

Notes: **SEDIT** 4.60A and **S/REXX** 2.60A are the last releases to support SCO systems.

Loading on SINIX Systems

Issue the following commands:

```
# mount -F hs -oro,dos /dev/ios0/sdisk005s0 /cdrom
# cp /cdrom/unix/install .
# chdir a+x install
# ./install /cdrom
```

The cdrom device /dev/ios0/sdisk005s0 is only an example. Therefore, the device number may be different on your system.

install will ask you if you want to load the **SEDIT** version corresponding to the operating system you are using. An example of a session is displayed on page 6.

Note: **SEDIT** 4.30 and **S/REXX** 2.30 are the last releases to support SINIX.

Loading on UNIXWARE Systems

Issue the following commands:

```
% mount -F cdfs -r -ofperm=0555 /dev/cdrom/c0b0t510 /cdrom
% /cdrom/unix/install
```

The cdrom device /dev/cdrom/c0b0t510 is only an example. Therefore, the device number may be different on your system.

install will ask you if you want to load the **SEDIT** version corresponding to the operating system you are using. An example of a session is displayed on page 6.

Note: **SEDIT** 4.30 and **S/REXX** 2.30 are the last releases to support UNIXWARE.

Session Example Running on Solaris

```
C{home}% /cdrom/cdrom0/unix/install
This cd-rom contains SEDIT-S/REXX and Adobe Acrobat Reader.
Do you want to install SEDIT-S/REXX (Yes/No)? y
This cd-rom contains the following SEDIT-S/REXX versions:
)1 "SEDIT 4.6 S/REXX 2.6" for: Solaris Sparc 2.5+
)2 "SEDIT 4.6 S/REXX 2.6" for: SunOS 4.1.3+
)3 "SEDIT 4.6 S/REXX 2.6" for: Solaris Intel 2.5+
)4 "SEDIT 4.6 S/REXX 2.6" for: AIX 3.2.5+
   "SEDIT 4.6 S/REXX 2.6" for: IRIX 5.3+
) 5
)6 "SEDIT 4.6 S/REXX 2.6" for: HP-UX 11.00+
)7 "SEDIT 4.6 S/REXX 2.6" for: HP-UX 10.10
)8 "SEDIT 4.6 S/REXX 2.6" for: DEC-OSF1 4.0+
)9 "SEDIT 4.6 S/REXX 2.6" for: Linux 2.0.32+
)10 "SEDIT 4.6 S/REXX 2.6" for: Unixware 2.01+
)11 "SEDIT 4.6 S/REXX 2.6" for: SCO 3.0+
)12 "SEDIT 4.3 S/REXX 2.3" for: Sinix 5.42+
)13 "SEDIT 4.2 S/REXX 2.2" for: HP-UX 9.05
)14 "SEDIT 4.2 S/REXX 2.2" for: Linux 1.2.8+
Do you want to install the Solaris Sparc 2.5+ version (Yes/No)? y
The default installation directory is: /home/xed
Do you want to install SEDIT and S/REXX in /home/xed (Yes/No)? y
install is about to install:
          SEDIT 4.6 S/REXX 2.6
for:
          Solaris Sparc 2.5+
in:
          /home/xed
Do you want to continue (Yes/No/Retry)? \boldsymbol{y}
cd /home/xed
/cdrom/sedit_440a_srexx_240a/unix/sparc/zcat
    /cdrom/sedit_440a_srexx_240a/unix/sparc/tarfile.gz | tar -xf -
"SEDIT 4.6 S/REXX 2.6" files for "Solaris Sparc 2.5+"
have been installed in "/home/xed".
You may use the following commands to install your passwords:
   cd /home/xed
   ./install
C{home}%
```

Note for Previous Release Users

We suggest you carefully read the RELEASE NOTES at the end of the manual.

We recommend not using a release of the profile.sedit initialization file previous to **SEDIT** 4.20. If you have an older customized version of profile.sedit in usage, we recommend that you customize the **SEDIT** 4.40 profile.

Important notices:

- Since the release of **SEDIT** 4.20, **S/REXX** macros are enabled without an **S/REXX** license.
- Since the release of S/REXX 2.50, the S/REXX Debugger does no longer need a separate license.

Note for Windows Users

SEDIT and S/REXX support Windows NT 4.0+ and Windows 95+.

The installation process is described in the **SEDIT-S/REXX** manual.

Note: When an ethernet card is installed, **SEDIT** 4.40B+ and **S/REXX** 2.40B+ use the physical internet address to determine the cpuid number. The cpuid for **SEDIT** 4.40B+ and **S/REXX** 2.40B+ will be different from the cpuid returned by previous releases, but will no longer change when re-installing the WINDOWS operating system.

Using SEDIT on Sun Workstations with SOLARIS 2.4+

SEDIT needs approximately 27 MB of disk space.

When a type 4 keyboard is in use, the set_sun_t5 statement in the profile.sedit file must be replaced with set_sun_t4.

Using the MOTIF Version

To start **SEDIT** in MOTIF mode, the user must have a DISPLAY environment variable, but not an OPENWINHOME variable.

Alternatively, the user may call the MOTIF version directly by typing mxed or msedit.

The MOTIF version requires the SUN MOTIF dynamic libraries to be installed. They are generally located on /usr/dt/lib.

When using the C-Shell, you must include in your ~/.cshrc file the following line:

setenv LD_LIBRARY_PATH /usr/openwin/lib:/usr/dt/lib

When using the Bourne or Korn Shell, include the following lines in your ~/.profile file:

```
LD_LIBRARY_PATH=/usr/openwin/lib:/usr/dt/lib
export LD_LIBRARY_PATH
```

Using SEDIT on Sun Workstations with Sun OS

SEDIT needs approximately 36 MB of disk space.

For performance consideration, the SunOS **SEDIT** version is provided statically linked. If you wish to save memory usage, at the possible expense of slower scrolling, you may use the dynamically linked **SEDIT** version by typing the following commands:

```
% cd install-dir
% ./mkln d
```

To restore the static version, type:

% ./mkln s

When a type 4 keyboard is in use, the set_sun_t5 statement in the profile.sedit file must be replaced with set_sun_t4.

Using the OPENWINDOWS version

In order to use the F1 key, **remove** the following line in the ~/ .xinitrc file:

```
xmodmap -e 'keysym F1 = Help'
```

Using the MOTIF Version

To start **SEDIT** in MOTIF mode, the user must have a DISPLAY environment variable, but not an OPENWINHOME variable.

Alternatively, the user may call the MOTIF version directly by typing mxed or msedit. If MOTIF is not installed on your workstation, please issue the following commands:

```
% cd install-dir/motif
% ./install
```

Note: SunView is no longer supported.

Using SEDIT on PCs with SOLARIS 2.5+

SEDIT needs approximately 16 MB of disk space. The default **SEDIT** version is the MOTIF version. To start **SEDIT** in OpenLook mode, use the following command:

% xsedit

The OpenLook version is provided "as is" without support, and does not fully support PC keyboards.

Using SEDIT on IBM Workstations

SEDIT needs AIX 3.2.5 (or higher) and MOTIF 1.2 (or higher) and approximately 14 MB of disk space.

The C-SHELL must be installed.

SEDIT uses the alt-key combinations in a manner that conflicts with the usual MWM motif window manager binding. For example, if the user wants to be able to use the alt-mouse keys within **SEDIT**, the user must modify his ~/.mwmrc file by typing:

```
% cd {install-dir-sedit}  # typically /home/xed
% ./install mwmrc
```

install looks for lines like:

Meta <btn1down></btn1down>	icon window	f.lower
Meta <btn2down></btn2down>	icon window	f.lower

and changes them into:

Meta <btn1down></btn1down>	icon	frame	f.lower
Meta <btn2down></btn2down>	icon	frame	f.lower

MWM does not allow the use of the Shift-Escape key. To enter the "Erase All field" command, the user must use Control-Escape instead.

MWM does not allow the use of the Alt-Escape key. To enter the "Print Screen" command, the user must use Shift-Control-Escape instead.

When using a local keyboard, meta characters such as { } [] are entered by holding the meta key down. By default, within **SEDIT**, the meta key is located at the left of the space bar.

If the user wants the key located to the right of the space bar to be the meta key, uncomment the following bold-faced statement in the profile.sedit file:

```
when arch = 'ibm' | arch = 'esa' then do
    'setenv SEDIT_META_ON_RIGHT'
```

IBM-850 Font Versus ISO8859-1 Font

When the system is set up with an ISO8859-1 environment, the LANG environment variable starts with a lower case letter. To determine this, the user may type the following command:

```
% printenv LANG
fr_FR
%
```

In this case, or if the LANG variable is generic C, SEDIT uses the rom17.isol ISO8859-1 font.

When the system is set up with an IBM-850 environment, the LANG environment variable starts with an upper case letter:

```
% printenv LANG
Fr_FR
%
```

In this case, SEDIT uses the IBM-850 rom17 font.

Note that local keyboards always send ISO8859-1 characters to **SEDIT**. When **SEDIT** is in IBM-850 mode, **SEDIT** translates all ISO8859-1 characters into IBM-850 characters

This translation cannot be achieved automatically when starting **SEDIT** from another architecture, such as SUN or HP, and displaying it on an IBM terminal.

If the user wants to enter IBM-850 characters, the user will have to build a specific translation table by using the mktrans utility, and load it by using the keyboard command.

The table \$xhome/keyboard/IBM_FRENCH_ROM17.TRANS is an example of such a table designed for French AZERTY keyboards.

Using SEDIT on HP Workstations

SEDIT needs approximately 16 MB of disk space.

The **UNIX** file system must be configured to use long filenames.

If the user is using a PC style keyboard, the user must replace the set_hp statement in the profile.sedit file with the set_hppc statement.

The HPUX 9.05 and 10.10 character mode **SEDIT** versions do not support reverse video display. In particular, selections are not highlighted.

When using a PC-like local keyboard, meta characters such as $\{ \}$ [] are entered by holding the meta key down. By default, within **SEDIT**, the meta key is located at the left of the space bar.

If the user wants the key located to the right of the space bar to be the meta key, uncomment the following bold-faced statement in the profile.sedit file:

```
when arch = 'hp' then do
    'setenv SEDIT_META_ON_RIGHT'
```

When running with HPUX, local keyboards always send ISO8859-1 characters to **SEDIT**. Since **SEDIT** starts with the HP Roman8 courb18 font by default, **SEDIT** translates all ISO8859-1 characters into HP Roman8 characters.

This translation may be disabled by inserting the following command in the profile.sedit initialization file:

'isoconv off'

Note that this translation cannot be achieved automatically when starting **SEDIT** from another architecture, such as SUN or IBM, and displaying it on an HP terminal.

If the user wants to enter HP Roman8 characters, the user will have to build a specific translation table by using the mktrans utility, and load it by using the keyboard command.

The table \$xhome/keyboard/HPA.TRANS is an example of such a table designed for French AZERTY keyboards.

Note that the ISOCONV ON command disables any previously loaded translation table.

Using SEDIT on Silicon Graphics Workstations

SEDIT needs approximately 17 MB of disk space.

Using SEDIT on PCs with LINUX

SEDIT needs approximately 22 MB of disk space. The C-SHELL must be installed.

Checking your SEDITID

To check the seditid, install **SEDIT** and type:

```
% cd xed
% ./seditid
259756
%
```

Once your seditid established, you will have to request a corresponding **SEDIT** and/or **S/REXX** password to enable your software.

Note: When an ethernet card is installed, **SEDIT** 4.40B+ and **S/REXX** 2.40B+ use the physical internet address to determine the seditid number. The seditid for **SEDIT** 4.40B+ and **S/REXX** 2.40B+ will be different from the seditid returned by previous releases, but will no longer change when reinstalling the LINUX operating system.

Using the Character Mode Version

The **SEDIT** character mode version uses the ncurses package. ncurses supports 8 colors on the PC console, which are mapped to the **SEDIT** 15 colors in the following way:

SEDIT COLOR	DISPLAYED COLOR
WHITE	BLACK
BLUE	BLUE
RED	RED
ORANGE	RED
GREEN	GREEN
INDIGO	BLUE
YELLOW	YELLOW
PINK	BLUE
MAGENTA	MAGENTA
CYAN	CYAN
MAGENTA2	MAGENTA
MAROON	RED
MAROON2	RED
PURPLE	RED
BLACK	WHITE

The r g b values cannot be changed and are hardware dependent.

With some kernels, colors are not supported.

Installing System Shared Libraries

If **SEDIT** or **S/REXX** indicates an error while loading shared libraries, you may try to install the supplied shared libraries from the **SEDIT** cdrom as described page 4.

Using SEDIT on an a.out Linux Kernel

The cdrom contains the **SEDIT** 4.20E1 a.out Linux version located in the 'unix/linux1' subdirectory.

SEDIT 4.20E1 is the last version supporting a . out kernels.

Using SEDIT on PCs with SCO

SEDIT needs approximately 14 MB of disk space.

Checking the SEDITID

To check the seditid, install **SEDIT** and type:

```
% cd xed
% ./seditid
259756
%
```

Once your seditid is established, you will have to request a corresponding **SEDIT** and/or **S/REXX** password to enable your software.

Using SEDIT on PCs with UNIXWARE

SEDIT needs approximately 14 MB of disk space.

SEDIT 4.30A and S/REXX 2.30A are the last releases to support UNIXWARE.

Checking the SEDITID

To check the seditid, install **SEDIT** and type:

```
% cd xed
% ./seditid
259756
%
```

Once your seditid is established, you will have to request a corresponding **SEDIT** and/or **S/REXX** password to enable your software.

Using the MOTIF Version

The Unixware Desktop does not allow the use of the R3 (Pause) key. Therefore, the SAVE function normally assigned to this key on PC keyboards is assigned to the R2 (Scroll Lock) key.

Using SEDIT on DEC/COMPAQ/HP TRUE64 OSF1 Stations

SEDIT needs approximately 19 MB of disk space.

Checking the SEDITID

To check the seditid, install **SEDIT** and type:

```
% cd xed
% ./seditid
259756
%
```

Once your seditid is established, you will have to request a corresponding **SEDIT** and/or **S/REXX** password to enable your software.

Setting the Keyboard Mapping

Depending on the command used to start it, **SEDIT** uses one of the following *.sedit initialization macros:

Unix COMMAND	Initialization macro
xed	profile.sedit
sedit	profile.sedit
pxed	profile.sedit
psedit	profile.sedit
xedit	prof_xedit.sedit
pdf	prof_pdf.sedit

To simplify the keyboard mapping, the various **SEDIT** *.sedit initialization macros automatically call the set_alphapc macro, as follows:

```
when arch = 'alpha' then do
   'set_alphapc'
   /* 'set_alpha' */
```

When a native DEC keyboard is in use, the set_alphapc statement in the *.sedit files in use must be replaced with the set_alpha statement.

Checking the CPU ID

SEDIT and/or **S/REXX** use the cpu ethernet address as the cpu id. To display this address, type the following:

```
% /usr/sbin/uerf -R -r 300 | more
---- EVENT INFORMATION -----
EVENT CLASS
                                OPERATIONAL EVENT
OS EVENT TYPE
                         300.
                                SYSTEM STARTUP
SEQUENCE NUMBER
                         Ο.
OPERATING SYSTEM
                                DEC OSF/1
                          tu0: DEC TULIP Ethernet Interface,
                         _hardware address: 08-00-2B-E4-F3-0B
                            tu0: console mode: selecting AUI
Ŷ
```

The cpu id is the last four ethernet address bytes. In this example, it would be 2BE4F30B.

Alternately, you may install **SEDIT** and type the following:

```
% cd xed
/home/xed
% ./seditid
2BE4F30B
%
```

Once your seditid is established, you will have to request a corresponding **SEDIT** and/or **S/REXX** password to enable your software.

Using SEDIT on Siemens SINIX Systems

SEDIT needs approximately 18 MB of disk space.

SEDIT 4.30 and S/REXX 2.30 are the last releases to support SINIX.

Using ASCII Terminals

Some ASCII terminals do not display reverse video characters properly. In such a case, review the "{install-dir}/profile.sedit" macro to execute the "highlight off" command when running that terminal.

Example:

If the user is running a "wyse50" terminal, uncomment and modify the following bold-faced line:

```
'* If your terminal does not handle reverse video characters,
* uncomment and update the following lines
*/
/* if $TERM = 'wyse50' then "highlight off" */
```

IBM ASCII terminals use XON/XOFF flow control. This means that typing "^s" (the XOFF character) will freeze the screen. The user must type "^q" (the XON character) to restart.

Depending on the ASCII terminal in use, the BackSpace key may send either the ^h or the ^? character.

By default, **SEDIT** recognizes the ^h character as the BackSpace character, and ^? as the Delete character.

Issuing the "BACKSPACE ^?" command reverts its behavior.

If a terminal such as this is in use, edit the "/home/xed/profile.sedit" macro, and add the following bold-faced line:

```
if version = 'curses' then
do
    if $TERM = 'MyTerminal' then 'set backspace ^?'
```

Using Dialog Boxes with MOTIF or CDE

When the MOTIF or CDE window manager is in click-to-type mode, it is necessary to add the following resources in the user's \sim /.Xdefaults file:

```
Mwm*dialog*focusAutoRaise: false
Mwm*sedit*focusAutoRaise: false
Dtwm*dialog*focusAutoRaise: false
Dtwm*sedit*focusAutoRaise: false
```

The user must then restart the window manager.

SEDIT and S/REXX User's Guide and Reference Manual

SEDIT Release 4.70

S/REXX Release 2.70

Important Copyright Notice

Benaroya S.A.R.L. owns the copyright to the SEDIT, S/REXX and S/REXX Debugger computer programs with all rights reserved. Under the copyright laws, these programs may not be copied, in whole or part, without the written consent of Benaroya S.A.R.L., except to install them onto a licensed computer system.

Benaroya S.A.R.L. reserves the right to make changes in specifications and other information contained in this publication without prior notice, and the reader should in all cases consult Benaroya S.A.R.L. to determine whether any such changes have been made. This manual may not be reproduced and is intended for the exclusive use of Benaroya's customers.

The terms and conditions governing the sale of the programs licence software consist solely of those set forth in the licence agreement included with this package. No statement contained in this publication shall be considered a warranty by Benaroya S.A.R.L. for any purpose or give rise to any liability of Benaroya S.A.R.L.

SEDIT, S/REXX and S/REXX Debugger are registered trademarks of Benaroya S.A.R.L.

UNIX is a trademark of X/OPEN Company LTD.

IBM is a registered trademark of International Business Machines.

OpenLook is a trademark of Novell.

KEDIT is a registered trademark of the Mansfield Software Group, Inc.

Table of Contents

Installing SEDIT on UNIX Systems	
Using a Grey Scale Monitor	2
Setting the Background Color	2
Setting the Path	2
Setting the Password for CPU Bound Licenses	3
Setting the Keyboard Mapping	6
Setting the MOTIF Resources	7
Setting the Keyboard Translations for an ASCII Terminal	8
Using MKESC	8
Installing SEDIT on WINDOWS Systems	
Installing S/REXX on UNIX Systems	
Setting the Password in Fixed License Mode	16
Installing S/REXX on WINDOWS Systems	
Using the License Server	
Installing xserv on UNIX systems	21
Installing xserv on WINDOWS NT systems	24
Using an Alternate Server	
Reserving Licenses on UNIX Systems	
Reserving Licenses on WINDOWS systems	26
Configuring a UNIX Heterogeneous Network	26
Setting the SEDIT Idle Time	26
Setting the S/REXX Linger Time	27
Logging Activity on UNIX systems	27
Usage Notes	27
Using XINFO	29
Stopping the Server on UNIX Systems	29
Stopping the Server on WINDOWS Systems	29
SEDIT Compatibility issues	
XEDIT Compatibility Issues	31
SEDIT Differences	
ISPF/PDF Compatibility Issues	36
Customizing SEDIT (UNIX)	
Using XED, SEDIT, PXED, PSEDIT or KEDIT	39
Using XEDIT or PDF	
Customizing SEDIT (WINDOWS)	40
Using the XEDIT-MODE, PDF-MODE and KEDIT-MODE Icons	40
Using the XEDIT-EXACTLY or PDF-EXACTLY Icons	40

EDIT User's Guide	41
The 3270 Screen Interface	41
Getting Started (UNIX)	44
Starting SEDIT Within DYALOG APL	44
Starting SEDIT Under UNIX	44
The UNIX Command Line Options	46
Getting Started (WINDOWS)	47
Starting SEDIT	47
SEDIT - XEDIT Mode	47
SEDIT - PDF Mode	47
SEDIT - XEDIT Exactly	47
SEDIT - PDF Exactly	47
SEDIT - KEDIT Mode	48
The WINDOWS Command Line Options	49
Using a UNIX Keyboard Layout	50
Exploring the SEDIT SCREEN	51
Moving Through a File	53
Editing Multiple Files	54
Using Function Keys on SUN Keyboards	56
Using Function Keys on IBM, SiliconGraphics and PCs Keyboards	62
Using Function Keys on DEC/COMPAO/HP TRUE64 station Keyboards	
Using Function Keys on HP Keyboards	74
Using Function Keys on WINDOWS	80
Using Function Keys in KEDIT Mode	
Using Function Keys on ASCII Terminal Keyboards	94
Using the Keyboard	97
Using the Default Buttons (UNIX)	98
Using the Default MenuBar (WINDOWS)	98
Using the DEFAULT Menu	104
Prefix Commands	105
Single Prefix Commands	106
Double Prefix Commands	114
Overlaying Lines	118
Writing Prefix Macros	119
Using the Mouse on UNIX systems	
Making a Linear Selection	123
The Sun Selection Related Keys	123
The Other Workstations Selection Related Keys	
Deleting the Selected Characters	123
Copying the Selected Characters	124
Moving the Selected Characters	124
Searching for Selected Characters	
Making a Rectangular Selection	
Selecting Whole Lines	
Moving Data to Other Windows	
Using the Mouse in MOTIF Mode	
Using the Mouse on WINDOWS Systems	
Making a Linear Selection	
The Selection Related Keys	
J	

Deleting the Selected Characters	
Copying the Selected Characters	
Searching for Selected Characters	
Making a Rectangular Selection	
Selecting Whole Lines	
Undoing	
Using MAKE	
Using ASCII Terminals	
Using INTERNAL Macro Commands	
Variable Substitution	
Using EXTERNAL Macro Commands (UNIX Only)	
Using an Interpreted Language	
Using the C Language (UNIX Only)	
Using S/REXX Macro Commands	
Using EXTRACT	
Using the BATCH Option	
UNIX Examples	
WINDOWS Examples	
	1 47
SEDII Command Reference Guide	
Variable Substitution	
Avoiding Variable Substitution	
ACCess - Add Directory To the Path	
Add - Add Lines	
ALI - Global Selective Line Editing	
ALT - Change The Number of Alterations	
APL - Pass a Command to APL	
ARBchar - Set Arbitrary Character	
AUTOBin - Auto-Binary Feature	
AUTOExp - Auto-Expand Feature	
AUTOI - Auto-Indent Feature	
AUtosave - Auto-Save Feature	
BACKUP - Set Backup Mode	
BAckward - Scroll Backward	
BEEP - Set Beep Mode	
BInary - Set Binary Mode	
Bottom - Bottom of File	
BOUNDS - Set the Edit Boundaries	
BUILTIN - Process a Built-in Command	
BUtton - Create Button	
CANcel (XEDIT MODE)- Abandon Files	
CANcel (ISPF MODE)- Cancel Edit Changes	
CAppend - Append Text	
CAPS - Control Automatic Character Conversion	
CASE - Case Respect	
CD - Change Directory	
CDElete - Delete Characters	
CENTER F L F LC	
CENTER_End - End Connection with Codecenter	

CENTER_Init - Initialize Connection with CodeCenter	168
CENTER_Send - Send Command to CodeCenter	169
CFirst - Move Column Pointer	170
Change (XEDIT MODE) - Change String	171
Change (ISPF MODE)- Change String	173
CInsert - Insert Characters	176
CLAst - Move Column Pointer	177
CLEARErrors - Clear Compiling Errors	177
CLocate - Locate Characters	178
CLOSEConsole - Close the Console	179
CMDline - Set the Command Line Position	179
CN - Change Name String	180
COLor - Set Color	182
COMmand - Execute a Command	189
COMPIle - Compile a Program	190
COMPLete - File Name Completion	194
COMPRess - Compress Data	195
COpy (XEDIT MODE) - Copy File Lines	196
COpy (ISPF MODE) - Copy Data	197
COUnt - Count String Occurrences	198
COVerlay - Selectively Replace Characters	200
CREAte - Create a New File	201
CReplace - Replace Characters	202
CTags - Use a Tags File	203
CTLCHAR - Define Control Character	205
CURLine - Change Current Physical Line	207
CURsor - Move Cursor	208
C_APLStop - Reverse APL Stop Setting	209
C_APLTrace - Reverse APL Trace Setting	209
C_Dup - Duplicate Cursor Line	210
C_ENDCurl - Goto End of Current Line	210
C_ENDLine - Goto End of Cursor Line	210
C_ENDS - End Selection	210
C_ENDSAll - End Selection at End of Line	211
C_ENDSR - End Rectangular Selection	211
C_EXT - Extend Field	211
C_LINEAdd - Add Line	212
C_LINEDel - Delete Line	212
C_SCRH - Split Screen Horizontally	212
C_SCRJ - Unsplit Screen	212
C_SCRV - Split Screen Vertically	213
C_SPlit - Split/Join Lines	213
C_STARTLine - Goto Start of Cursor Line	213
C_STARTS - Start Selection	214
DACCess- Add Directory to the CDPATH	215
DELete (XEDIT MODE) - Delete Line	216
DELete (ISPF MODE) - Delete Line	217
DELAY - Display a String	218
DFlist - Call Directory Editor	218

DISPlay - Set Display Range	219
Down/Next - Scroll Down	220
DUPlicat - Current Line Duplication	221
DRELEase - Removes a Directory from the CDPATH	222
DY_All - Start the ALL Dialog Box	223
DY_Exclude - Start the EXCLUDE Dialog Box	224
DY FInd - Start the FIND Dialog box	225
DY FILL - Start the FILL dialog box	226
DY FOnt - Set the Dialog Font	226
DY LASTFILES - Display Last Edited Files	226
DY OPEN (UNIX) - Start the OPEN Dialog Box	227
DY OPEN (WINDOWS) - Start the OPEN Dialog Box	230
DY SAVE (UNIX) - Start the SAVE Dialog Box	231
DY SAVE (WINDOWS) - Start the SAVE Dialog Box	234
DY SHow - Start the SHOW Dialog Box	235
FDIT	235
EMSG - Display Text	236
END - End the Edit Session	236
ESCAPEdelay - Set Escape Sequence Time-out	236
ESCAI Editing - Set Escape Sequence Time-out	230
EXClude (ISPE MODE) - Global Selective Line Editing	237
EXCLUDE (ISFT MODE) - EXCLUDE LINES HOIL DISPLAY	237
EXII / EEAII - EXIL	240
EA Hact - Keuleve Information	241
FDUII011 - Set Directory Editor Buttons	230
FD - Change File Directory	250
FIIe / FFIIe / KFIIe / DOSFIIe - Save and Leave FIIe	257
FILECONV - File Conversion	258
FILTER - Filter the Selection Contents	260
FINd (XEDIT MODE) - Find a Starting String	261
FINd (ISPF MODE) - Find a Data String	262
FINDUP - Find a Starting String	265
FLAth - Directory Editor Permissions Display	266
FLDATE - Directory Editor Date Format	267
FLFile - File + FLIST	267
FFList - Call Directory Editor	267
Flist - Call Directory Editor	268
FMACRO - Execute FLIST Macro	268
FLOW - Reformats Text	269
Using the CURSOR Operand	.270
Using the CURSOR_STRICT Operand	.270
FLPP - Directory Editor Parent Directory Display	271
FLQuit - AQUIT + F	271
FN - Change Filename	271
FOLLOW - Follow Links	272
FONt - Change Font	272
FORMAT - Set Formatting Parameters	273
FORward - Scroll Forward	274
FT - Change Filetype	275
GET - Insert Data	276

GET_Panel - Fullscreen User Interface	277
GLOBALCase - Global File Case Handling	281
HAsh - Scan Directories	281
Help - Fullscreen Help	282
HEX - Hexadecimal Target	284
HEXType - Hexadecimal Display	285
HIghlight - Disable Highlight	287
HIStory - Set the History Length Buffer	287
HOme - Switch Cursor Position	288
IMPcmscp - Implicit UNIX or WINDOWS Execution	288
Input- Add a Text Line	289
ISOConv - Set ISO Conversion	289
ISwitch - Switch Between files	289
KEEPBLanks - Trailing Blanks Removal	290
KEYboard - Redefine Keyboard	291
Using MKTRANS	.292
LASTFiles - Set the LASTFILES Parameters	294
LASTLorc - Set LASTLORC Buffer	294
LEft - Scroll Left	295
LEFTAdjust - Left-Adjusting Text	296
LIMIT - Set File Size Limit	297
Large Files support	.297
LINECol	297
LINENd - Separator Change	298
LIsten - Listen for External Commands	299
Locate (XEDIT MODE) - Locate a Target	300
Locate (ISPF MODE) - Locate a Line	303
LOWercas - Translate Into Lowercase	304
LRecl - Set Record Length	305
MACRO - Execute a Macro	306
MAN - Display UNIX Reference Manual Pages	306
MARgins - Set Text Margins	307
MAtch - Match Delimiters	308
MBUtton - Create a Menu Button	309
MENu - Create a Menu	310
MENUBar - Create a Menubar	312
MErge - Merge Two Set of Lines	314
MESsagesdir	316
METAKey - Set the Meta Key	316
MODE - Set Various Modes	318
MOUSEMode - Set Mouse Buttons	322
MOve - Move File Lines	323
MSG - Display Text	324
N - Goto Nth Line	324
NEXTError - Error Scanning	325
NEXTWord - Cursor Moving to Next Word	325
NFind - Find a Missing Starting String	326
NFINDUp - Find a Missing Starting String	326
NIS - Use NIS Users Database	327
NISG - Use NIS Groups Database	327
--	-----
NUMber / NUMBER_Screen - Display File Line Numbers	328
PENDing - Update the Pending List	329
PGDown - Scroll Down	330
PGUp - Scroll up	330
POINT - Assign a Symbolic Name	331
POWerinput - Set Power Input Mode	332
PREfix/ PREFIX_Screen - Change Prefix Mode	335
PREServe - Settings Preservation	336
PREVWord - Cursor Moving to Previous Word	337
PRINTFile (UNIX) - Print a File Hardcopy	338
PRINTFile (WINDOWS) - Print a File Hardcopy	339
PRINTScreen (UNIX) - Print a Screen Hardcopy	340
PRINTScreen (WINDOWS) - Print a Screen Hardcopy	341
PRompt - Prompt user	341
PUT - Save Data	342
PUTD - Save Data	343
PURge - Clear Macros	344
PWD/W - Display Current Directory	344
Query - Query About Editing Options	344
QUIT / AQUIT / PQUIT / QQuit - Abandon File	345
RChange (XEDIT MODE) - Regular Expression Change	346
RChange (ISPF MODE) - Repeat Last Change	347
READ - Place Terminal Information in the STACK	348
READScreen - Read User Action	351
RECYCLE - Use the Recycle Bin	352
REDo - Cancel Last Undo	352
REFRESH - Screen Update	352
RELEase - Removes a Directory From the PATH	353
RELoad - Automatic Reload Feature	354
REPEat - Repeat a Command	355
REPEATDelay - Set Auto-repeat Time-out	356
Replace (XEDIT MODE) - Replace Current Line	356
Replace (ISPF MODE)- Replace Data	357
RESERved - Reserve a Specified Line on the Screen	358
RESet - Reset the Data Display	360
RESTore - Settings Retrieval	360
RFlist - Call Directory Editor	361
RFINd - Repeat Last Find	361
RIght - Scroll Right	361
RIGHTAdjust - Right-adjusting Text	362
RW - Enable Read/Write Mode	363
R/ - Regular Expression Search	363
R-/ - Regular Expression Search	366
SABER_End - End Connection with Saber-C	366
SABER_Init - Initialize Connection with Saber-C	367
SABER_Send - Send Command to Saber-C	368
SAve / SSave / KSAve/ DOSSave - Save File	370
SAVECLEARUNDO - Set Clear Undo Status	370

SCALe / SCALE_Screen - Set Scale Line	371
SChange - Selective String Change	372
SCKeys - Selective Change Confirmation Keys	374
SCN - Selective Name String Change	375
SCOpe - Set Selective Editing Scope	377
SCReen - Split Screen	378
SCROllbar - Set Scrollbar	380
SELect - Set Selection Level	381
SELECTall - Set Selection Level on All Lines	382
SEP - Separator Change	383
SEt - Set Function Keys	384
SETEnv - Set Environment Variable	393
SETP - Set Display String	393
SHAdow - Set Selective Editing Display Mode	394
SHBlank - Show Last Trailing Blank	394
SHEIL - Execute a Shell Command	395
SHift - Shift I ines	396
SHOw - Global Selective Line Editing	397
SHOWCdnath - Displays the Accessed Directories	397
SHOWHistory - Show History	397
SHOWPath - Displays the Accessed Directories	308
SOrt - Sort a File	300
SOPTPing Sort the Ding	300
SOK I King - Soft the King	<i>4</i> 00
SDAN Multiple Lines Search	400
SDELL Spalling Chacker	403
SPELL - Spennig Checker	404
SDELL_Add - Opdate I fivate Dictionary	404
SPELL_Next - Search for Next Wisspened word	405
SPChange Selective Degular Expression Change	405
STAck Stock Lines	400
STACK - Stack Lines	400
STATUS (Moore) Disclepancy Keloau Settings	409
STATUS (Macro) - Displays All Settings	410
STAT - Current Line Move	410
STOP - Set APL stop	411
STReam - Set Stream Status	411
Switch - Switch Between Files	412
SYNonym - Set a Synonym	413
SYNTax - Set Syntax Coloring	414
S_COpy - Copy a Selection	41/
S_CUt - Cut a Selection	41/
S_Find - Find a Selection	417
S_Heip - Shows Heip About a Selected Item	418
S_Lower - Translate Into Lowercase	418
S_LShift - Shift Left from Selection	419
S_MAN - Display Selected UNIX Reference Manual Pages	419
S_Paste - Retrieve a Selection	420
S_RShift - Shift Right from Selection	421
S_Set - Set Selection	422

S_Xed - Edit a Selected File 423 TABExp Expand Tabulations 424 TABExtp - Expand Tabulations 424 TABExtp - Set Tabline 425 TABSet - Set Tabulations 426 TOP Top Top of File 427 TTOP - Top of File 428 428 TRAce - Set APL Trace 429 TREEScanlevel - Set TREE Scanning Level 429 TRUnc - Set Truncation Column 430 UNButton - Remove Button 431 UNSetenv - Remove Environment Variable 431 UP Scroil Up 432 UPPercas - Translate Into Uppercase 433 Verify / VERIFY Screen - Set Columns 435 Verify / VERIFY Screen - Set Columns 438 Windows - Execute a WINDOWS Command 438 WRap - Wrap Around Feature 439 XBin - Edit Binary Files 440 XF - Edit an APL Object. 441 XCSHell - Execute a Shell Command 443 XKB - Edit Files with Trailing Blanks 442 XKSHell - Execute a Shell Command 443 XSHELLMax - Set Dis		S Upper - Translate into Uppercase	423
TABExp - Expand Tabulations 424 TABLine / TABLINE_Screen - Set Tabline 425 TABSet - Set Tabulations 426 TOolbar - Set Toolba 427 TO - Top of File 428 TRAce - Set APL Trace 428 Tree - Start the TREE Editor 429 TREEScanlevel - Set TREE Scanning Level 429 TRUC - Set Trunce into Column 430 UNButton - Remove Button 431 UND - Cancel Last File Modification 431 UP - Scroll Up 432 UP - Scroll Up 432 UP ranslate Into Uppercase 433 VARIDAR - Ignore Stuccessive Blanks 434 Verify / VERIFY_Screen - Set Columns 435 VERIFY_Save / VERIFY Save / VERIFY KSave 437 VIsible - Count Visible Lines 438 Windows - Execute a WINDOWS Command 438 WRap - Wrap Around Feature 439 XEDit - Edit New Files 440 XCSHell - Execute a Shell Command 443 XSHELL HAx - Set Displayed XSHELL Files Limit 444 XSHELL Nax - Set Displayed XSHELL Files Limit 444 XSHELL Nax - Set D		S Xed - Edit a Selected File	423
TABLine / TÅBLINE_Screen - Set Tabline		TABExp - Expand Tabulations	424
TABSet - Set Tabulations 426 TOOlbar - Set Toolbar 427 TOP - Top of File 428 TRAce - Set APL Trace 428 Tree - Start the TREE Editor 429 TRUnc - Set Truncation Column 430 UNButton - Remove Button 431 UND - Cancel Last File Modification 431 UP - Scroll Up 432 UP - Scroll Up 433 VARblank - Ignore Successive Blanks 434 Verify / VERIFY_Saree - Set Columns 435 VIsible - Count Visible Lines 438 Windows - Execute a WINDOWS Command 438 WRap - Wrap Around Feature 439 XSB - Edit Bin APL Object. 441 XCSHell - Execute a Shell Command 443 XSHell - Execute a Shell Command 443 XSHELLMax - Set Displayed XSHELL Files Limit 444 XSHELLMax - Set Displayed XSHELL File		TABLine / TABLINE Screen - Set Tabline	425
TOolbar - Set Toolbar427TOP - Top of File428TRAcce - Set APL Trace428Tree - Start the TREE Editor429TREEScanlevel - Set TREE Scanning Level429TRUnc - Set Truncation Column430UNButton - Remove Button431UNDo - Cancel Last File Modification431UND - Cancel Last File Modification431UN Setenv - Remove Environment Variable432UPPercas - Translate Into Uppercase433VARblank - Ignore Successive Blanks434Verify / VERIFY_Screen - Set Columns435VERIFY_Save / VERIFY_SSave / VERIFY_KSave437Visible - Count Visible Lines438Windows - Execute a WINDOWS Command438WRap - Wrap Around Feature439XEDit - Edit New Files440XF - Edit an APL Object441XCSHell - Execute a Shell Command442XKB - Edit Files with Trailing Blanks442XKB - Edit Files with Trailing Blanks443XSHell - Execute a Shell Command443XSHell - Execute a Shell Command443XSHell - Execute a Shell Command444XTESTChars - Set the Font Testing Mode444XTESTChars - Set the Font Testing Mode445Zone / ZONE_Screen - Set Zone446V - Locate a Name String447- Locate a Name String448? - Display Last Command449# - Display Last Command449# - Display Last Command449# - Display Last Command449<		TABSet - Set Tabulations	426
TOP - Top of File428TRAce - Set APL Trace428Tree - Start the TREE Editor429TRUnc - Set TREE Scanning Level429TRUnc - Set Truncation Column430UNButton - Remove Button431UNDo - Cancel Last File Modification431UP- Scroll Up432UPPercas - Translate Into Uppercase433VARblank - Ignore Successive Blanks434Verify / VERIFY_Screen - Set Columns435VERIFY_Save / VERIFY_Save / VERIFY_KSave437VIsible - Count Visible Lines438Windows - Execute a WINDOWS Command438WRap - Wrap Around Feature439XEDit - Edit Biary Files440XF - Edit an APL Object441XCSHell - Execute a Shell Command443XKSHell - Execute a Shell Command443XKSHell - Execute a Shell Command443XKSHell - Execute a Shell Command444XTESTChars - Set the Font Testing Mode444XTESTChars - Set the Font Testing Mode449* - Locate a Name String446· Locate a Name String448* Display Last Command448* Display Last Command449# - Comments449# - Comments449# - Comments449# - Comments451		TOolbar - Set Toolbar	427
TRAce - Set APL Trace428Tree - Start the TREE Editor429TREEScanlevel - Set TREE Scanning Level.429TRUnc - Set Truncation Column430UNButton - Remove Button.431UNDo - Cancel Last File Modification431UNSetenv - Remove Environment Variable.431UP-Scroll Up432UPPercas - Translate Into Uppercase.433VARblank - Ignore Successive Blanks434Verify / VERIFY_Screen - Set Columns435VERIFY_Save / VERIFY_Save / VERIFY_KSave437Visible Count Visible Lines.438Windows - Execute a WINDOWS Command.438WRap - Wrap Around Feature439XEDit - Edit Riers with Trailing Blanks.440XF - Edit Riers with Trailing Blanks.442XKB - Edit Files with Trailing Blanks.442XKBHell - Execute a Shell Command.443XSHEIL-Max - Set Displayed XSHELL Files Limit.444XTESTChars - Set the Font Testing Mode.444XTESTChars - Set the Font Testing Mode.446YTESTChars - Set the Font Testing Mode.447- Locate a Name String448- Display Last Command.449# - Comments449# - Comments449# - Display Last Command.443XSHEIT Text Formatting Facilities451Margins451Margins451Margins451Margins451Vortorl-F"453What Is It For?453What Is It For?<		TOP - Top of File	428
Tree - Start the TREE Editor.429TREEScanlevel - Set TREE Scanning Level.429TR Unc - Set Truncation Column430UNButton - Remove Button.431UNDo - Cancel Last File Modification431UNSetenv - Remove Environment Variable.431UP Scroll Up432UPPercas - Translate Into Uppercase.433VARblank - Ignore Successive Blanks434Verify / VERIFY_Screen - Set Columns435VERIFY_Save / VERIFY_KSave / VERIFY_KSave.437VIsible - Count Visible Lines.438WIndows - Execute a WINDOWS Command.438Wandows - Execute a WINDOWS Command.439XEDit - Edit New Files.440XF - Edit an APL Object.441XCSHell - Execute a Shell Command.443XSHell - Execute a Shell Command.443XSHEll - Execute a Shell Command.443XSHELLMax - Set Displayed XSHELL Files Limit.444XSHOwhistory - Show History In Fullscreen Mode.444XTESTChars - Set the Font Testing Mode.446\treestream - Zone.446\- Locate a Name String.448? - Display Last Command.449# - Comments.449# - Comments.449# - Command.443XSHOIT Text Formatting Facilities441XSHOUN withory - Show History In Fullscreen Mode.444XSHOUN withory - Show History In Fullscreen Mode.444XSHOUN withory - Show History In Fullscreen Mode.444XSHOUN withory - Show History In Fullscreen		TRAce - Set APL Trace	428
TREEScanlevel - Set TREE Scanning Level. 429 TRUnc - Set Truncation Column 430 UNButton - Remove Button. 431 UNDo - Cancel Last File Modification 431 UP-Scroll Up 432 UPPercas - Translate Into Uppercase. 433 VARblank - Ignore Successive Blanks 434 Verify / VERIFY_Screen - Set Columns 435 VERIFY_Save / VERIFY_SSave / VERIFY_KSave 437 Visible Lines. 438 Windows - Execute a WINDOWS Command. 438 WRap - Wrap Around Feature 439 XED it - Edit New Files. 440 XF - Edit an APL Object. 441 XCSHell - Execute a Shell Command 442 XKB - Edit Files with Trailing Blanks. 442 XKB + Edit Files with Trailing Blanks. 443 XSHELLMax - Set Displayed XSHELL Files Limit. 444 XSHELLMax - Set Displayed XSHELL Files Limit. 444		Tree - Start the TREE Editor	429
TRUnc - Set Truncation Column 430 UNButton - Remove Button. 431 UNDo - Cancel Last File Modification. 431 UNDo - Cancel Last File Modification. 431 UNSetenv - Remove Environment Variable. 431 UP-Scroll Up. 432 UPPercas - Translate Into Uppercase. 433 VARblank - Ignore Successive Blanks. 434 Verify / VERIFY_Sare / VERIFY Save / VERIFY_KSave. 437 Visible - Count Visible Lines. 438 Windows - Execute a WINDOWS Command. 438 WRap - Wrap Around Feature 439 XBin - Edit Binary Files. 439 XBin - Edit New Files. 440 XCSHell - Execute a Shell Command. 441 XCSHell - Execute a Shell Command 443 XSHell - Execute a Shell Command 443 XSHell - Execute a Shell Command 443 XSHell - Execute a Shell Command 443 XSHELLMax - Set Displayed XSHELL Files Limit. 444 XSHELLMax - Set Displayed XSHELL Files Limit. 444 XSHEWI - Execute a Shell Command 443 XSHEWI - Secute a Name String 444 YESTORar - Set Kof		TREEScanlevel - Set TREE Scanning Level	429
UNButton - Remove Button		TRUnc - Set Truncation Column	430
UNDo - Cancel Last File Modification431UNSetenv - Remove Environment Variable431UP- Scroll Up432UPPercas - Translate Into Uppercase433VARblank - Ignore Successive Blanks434Verify / VERIFY_Screen - Set Columns435VERIFY_Save / VERIFY_SSave / VERIFY_KSave437Visible - Count Visible Lines438Windows - Execute a WINDOWS Command438WRap - Wrap Around Feature439XBin - Edit Binary Files439XEDit - Edit New Files440XF - Edit an APL Object441XCSHell - Execute a Shell Command443XSHell - Execute a Shell Command443XSHell - Execute a Shell Command443XSHell - Execute a Shell Command443XSHELLMax - Set Displayed XSHELL Files Limit.444XSHOwhistory - Show History In Fullscreen Mode444XTESTChars - Set the Font Testing Mode444XTESTChars - Set Zone446\- Locate a Name String447\- Locate a Name String448? 1- Display Last Command449# 1- Display Last Command449# 2- Comments4451Wordwrap Feature451Margins451Formatting Text451Wordwrap Feature451Margins451Formatting Text453What Is It For?453Using "Control-F"455Laree Files support455		UNButton - Remove Button	431
UNSetenv - Remove Environment Variable431UP- Scroll Up432UPPercas - Translate Into Uppercase433VARblank - Igore Successive Blanks433VARblank - Upore Successive Blanks435VERIFY_Save / VERIFY_SSave / VERIFY_KSave437Visible - Count Visible Lines438WIndows - Execute a WINDOWS Command438WRap - Wrap Around Feature439XBin - Edit Binary Files439XEDit - Edit New Files440XF - Edit an APL Object441XCSHell - Execute a Shell Command443XSHell - Execute a Shell Command443XSHell - Execute a Shell Command443XSHell - Execute a Shell Command444XTESTChars - Set Displayed XSHELL Files Limit444XTESTChars - Set Displayed XSHELL Files Limit444XTESTChars - Set Displayed XSHELL Files Limit446\ - Locate a Name String447\ - Locate a Name String447\ - Locate a Name String449# - Omments449# - Comments449# - Comments445Margins451Formatting Text451Wordwrap Feature451Wordwrap Feature453What Is It For?453Using "Control-F"455Larce Files support455Larce Files support455		UNDo - Cancel Last File Modification	431
UP- Scroll Up432UPPercas - Translate Into Uppercase.433VARblank - Ignore Successive Blanks434Verify / VERIFY_Screen - Set Columns435VERIFY_Save / VERIFY_SSave / VERIFY_KSave437VIsible - Count Visible Lines.438WIndows - Execute a WINDOWS Command438WRap - Wrap Around Feature439XBin - Edit Binary Files.439XEDit - Edit New Files440XF - Edit an APL Object.441XCSHell - Execute a Shell Command442XKB - Edit Files with Trailing Blanks.442XKB - Edit Files with Trailing Blanks.443XSHell - Execute a Shell Command443XSHELLMax - Set Displayed XSHELL Files Limit.444XSHOwhistory - Show History In Fullscreen Mode444XTESTChars - Set the Font Testing Mode.444X - Locate a Name String.447-\ - Locate a Name String.449# - Display Last Command.449# - Comments.449# - Comments.449# - Comments.449# - Comments.449# - Comments.4451Wordwrap Feature451Margins		UNSetenv - Remove Environment Variable	431
UPPercas - Translate Into Uppercase433VARblank - Ignore Successive Blanks434Verify / VERIFY_Screen - Set Columns435Verify / VERIFY_Save / VERIFY_KSave437Visible - Count Visible Lines438WIndows - Execute a WINDOWS Command438WRap - Wrap Around Feature439XBin - Edit Binary Files439XEDit - Edit New Files440XF - Edit an APL Object441XCSHell - Execute a Shell Command442XKB - Edit Files with Trailing Blanks442XKB - Edit Files with Trailing Blanks443XSHell - Execute a Shell Command443XSHell - Execute a Shell Command444XSHCLMax - Set Displayed XSHELL Files Limit.444XSHOW history - Show History In Fullscreen Mode444XTESTChars - Set the Font Testing Mode446\- Locate a Name String447\- Locate a Name String448? - Display Last Command449# - Comments449# Commen		UP- Scroll Up	432
VARblank - Ignore Successive Blanks434Verify / VERIFY_Screen - Set Columns435VERIFY_Save / VERIFY_SSave / VERIFY_KSave437VIsible - Count Visible Lines.438WIndows - Execute a WINDOWS Command438WRap - Wrap Around Feature439XBin - Edit Binary Files.439XEDit - Edit New Files440XF - Edit an APL Object.441XCSHell - Execute a Shell Command442XKB - Edit Files with Trailing Blanks.442XKSHell - Execute a Shell Command443XSHell - Execute a Shell Command443XSHell - Execute a Shell Command443XSHell - Execute a Shell Command444XSHOwhistory - Show History In Fullscreen Mode444XTESTChars - Set the Font Testing Mode446\ - Locate a Name String447\- Locate a Name String447\- Locate a Name String449= - Repeat Last Command449# - Comments449# - Comments449# - Comments449# - Comments4451Margins451Margins451Margins451What Is It For?453What Is It For?453Using "Control-F"455Large Files support455		UPPercas - Translate Into Uppercase	433
Verify / VERIFY_Screen - Set Columns435VERIFY_Save / VERIFY_SSave / VERIFY_KSave437VIsible - Count Visible Lines438WIndows - Execute a WINDOWS Command438WRap - Wrap Around Feature439XEDit - Edit Binary Files439XEDit - Edit New Files440XF - Edit an APL Object441XCSHell - Execute a Shell Command442XKB - Edit Files with Trailing Blanks442XKSHell - Execute a Shell Command443XSHell - Execute a Shell Command443XSHell - Execute a Shell Command443XSHell - Execute a Shell Command444XSHow History In Fullscreen Mode444XTESTChars - Set the Font Testing Mode446\u03c4 TESTChars - Set the Font Testing Mode447-\ - Locate a Name String447-\ - Locate a Name String448? - Display Last Command449# - Repeat Last Command449# - Comments449# - Comments445Margins451Formatting Text451Wordwrap Feature451Wordwrap Feature451What Is It For?453Using "Control-F"455Large Files support455		VARblank - Ignore Successive Blanks	434
VERIFY_Save / VERIFY_SSave / VERIFY_KSave437VIsible - Count Visible Lines		Verify / VERIFY Screen - Set Columns	435
VIsible - Count Visible Lines.438WIndows - Execute a WINDOWS Command.438WRap - Wrap Around Feature439XBin - Edit Binary Files.439XEDit - Edit New Files.440XF - Edit an APL Object.441XCSHell - Execute a Shell Command442XKB - Edit Files with Trailing Blanks.442XKSHell - Execute a Shell Command443XSHell - Execute a Shell Command443XSHell - Execute a Shell Command444XSHell - Execute a Shell Command443XSHell - Secute a Shell Command444XSHowhistory - Show History In Fullscreen Mode444XSHOwhistory - Show History In Fullscreen Mode446\ - Locate a Name String447-\ - Locate a Name String448? - Display Last Command449SEDIT Text Formatting Facilities451Margins451Formatting Text453What Is It For?453Using "Control-F"455Large Files support455		VERIFY Save / VERIFY SSave / VERIFY KSave	437
WIndows - Execute a WINDOWS Command.438WRap - Wrap Around Feature439XBin - Edit Binary Files.439XEDit - Edit New Files440XF - Edit an APL Object.441XCSHell - Execute a Shell Command442XKB - Edit Files with Trailing Blanks.442XKSHell - Execute a Shell Command443XSHell - Execute a Shell Command443XSHell - Execute a Shell Command443XSHell - Execute a Shell Command444XSHowhistory - Show History In Fullscreen Mode444XTESTChars - Set the Font Testing Mode444XTESTChars - Set the Font Testing Mode446\ - Locate a Name String447-\ - Locate a Name String448? - Display Last Command449#1 - Display Last Command449#49#44SEDIT Text Formatting Facilities451Margins451Formatting Text453What Is It For?453Using "Control-F"455Large Files support455		VIsible - Count Visible Lines	438
WRap - Wrap Around Feature439XBin - Edit Binary Files439XEDit - Edit New Files440XF - Edit an APL Object441XCSHell - Execute a Shell Command442XKB - Edit Files with Trailing Blanks442XKSHell - Execute a Shell Command443XSHell - Execute a Shell Command444XSHowhistory - Show History In Fullscreen Mode444XTESTChars - Set the Font Testing Mode445Zone / ZONE_Screen - Set Zone446\- Locate a Name String447YI - Display Last Command449# - Comments449# - Comments449# - Comments449Wordwrap Feature451Margins451Wordwrap Feature453What Is It For?453Using "Control-F"453Large Files support455		WIndows - Execute a WINDOWS Command	438
XBin - Edit Binary Files.439XEDit - Edit New Files440XF - Edit an APL Object.441XCSHell - Execute a Shell Command442XKB - Edit Files with Trailing Blanks.442XKSHell - Execute a Shell Command443XSHell - Execute a Shell Command443XSHell - Execute a Shell Command443XSHELLMax - Set Displayed XSHELL Files Limit.444XSHOwhistory - Show History In Fullscreen Mode444XTESTChars - Set the Font Testing Mode445Zone / ZONE_Screen - Set Zone446\ - Locate a Name String447-\ - Locate a Name String448? - Display Last Command449# - Repeat Last Command449# - Comments449Wordwrap Feature451Margins451Wordwrap Feature453What Is It For?453Using "Control-F"455Large Files support455		WRap - Wrap Around Feature	439
XEDit - Edit New Files440XF - Edit an APL Object441XCSHell - Execute a Shell Command442XKB - Edit Files with Trailing Blanks442XKSHell - Execute a Shell Command443XSHell - Set Displayed XSHELL Files Limit444XSHOwhistory - Show History In Fullscreen Mode444XTESTChars - Set the Font Testing Mode445Zone / ZONE_Screen - Set Zone446\ - Locate a Name String447-\ - Locate a Name String448? - Display Last Command449# - Repeat Last Command449# - Comments449# - Comments451Margins451Margins451What Is It For?453Using "Control-F"455Large Files support455		XBin - Edit Binary Files	439
XF - Edit an APL Object		XEDit - Edit New Files	440
XCSHell - Execute a Shell Command442XKB - Edit Files with Trailing Blanks442XKSHell - Execute a Shell Command443XSHell - Execute a Shell Command443XSHell - Execute a Shell Command443XSHELLMax - Set Displayed XSHELL Files Limit.444XTESTChars - Set the Font Testing Mode444XTESTChars - Set the Font Testing Mode445Zone / ZONE_Screen - Set Zone446\ - Locate a Name String447-\ - Locate a Name String448? - Display Last Command449# - Repeat Last Command449# - Comments449# - Comments445Margins451Margins451Mordwrap Feature451Wordwrap Feature453What Is It For?453Using "Control-F"455Laree Files support455		XF - Edit an APL Object	441
XKB - Edit Files with Trailing Blanks.442XKSHell - Execute a Shell Command443XSHell - Execute a Shell Command443XSHELLMax - Set Displayed XSHELL Files Limit.444XSHOwhistory - Show History In Fullscreen Mode444XTESTChars - Set the Font Testing Mode445Zone / ZONE_Screen - Set Zone446\ - Locate a Name String447-\ - Locate a Name String448? - Display Last Command449# - Oisplay Last Command449# - Comments449# - Comments449# - Comments451Margins451Formatting Text451Wordwrap Feature453What Is It For?453Using "Control-F"455Large Files support455		XCSHell - Execute a Shell Command	442
XKSHell - Execute a Shell Command443XSHell - Execute a Shell Command443XSHELLMax - Set Displayed XSHELL Files Limit444XSHOwhistory - Show History In Fullscreen Mode444XTESTChars - Set the Font Testing Mode445Zone / ZONE_Screen - Set Zone446\ - Locate a Name String447-\ - Locate a Name String448? - Display Last Command448? I - Display Last Command449= - Repeat Last Command449# - Comments449# - Comments451Margins451Formatting Text451Wordwrap Feature451What Is It For?453Using "Control-F"455Large Files support455		XKB - Edit Files with Trailing Blanks	442
XSHell - Execute a Shell Command443XSHELLMax - Set Displayed XSHELL Files Limit.444XSHOwhistory - Show History In Fullscreen Mode444XTESTChars - Set the Font Testing Mode445Zone / ZONE_Screen - Set Zone446\ - Locate a Name String447-\ - Locate a Name String448? - Display Last Command448? I - Display Last Command449# - Comments449# - Comments449SEDIT Text Formatting Facilities451Margins451Wordwrap Feature451Wordwrap Feature453What Is It For?453Using "Control-F"455Large Files support455		XKSHell - Execute a Shell Command	443
XSHELLMax - Set Displayed XSHELL Files Limit		XSHell - Execute a Shell Command	443
XSHOwhistory - Show History In Fullscreen Mode 444 XTESTChars - Set the Font Testing Mode 445 Zone / ZONE_Screen - Set Zone 446 \ - Locate a Name String 447 -\ - Locate a Name String 447 -\ - Locate a Name String 448 ? - Display Last Command 448 ? I - Display Last Command 449 = - Repeat Last Command 449 # - Comments 449 # - Comments 449 SEDIT Text Formatting Facilities 451 Margins 451 Wordwrap Feature 451 What Is It For? 453 What Is It For? 453 Using "Control-F" 455 Large Files support 455		XSHELLMax - Set Displayed XSHELL Files Limit	444
XTESTChars - Set the Font Testing Mode445Zone / ZONE_Screen - Set Zone446\ - Locate a Name String447-\ - Locate a Name String448? - Display Last Command448? I - Display Last Command449= - Repeat Last Command449# - Comments449# - Comments449# SEDIT Text Formatting Facilities451Margins451Formatting Text451Wordwrap Feature451Wordwrap Feature451What Is It For?453Using "Control-F"455Large Files support455		XSHOwhistory - Show History In Fullscreen Mode	444
Zone / ZONE_Screen - Set Zone446\ - Locate a Name String447-\ - Locate a Name String448? - Display Last Command448?I - Display Last Command449= - Repeat Last Command449# - Comments449# - Comments449SEDIT Text Formatting Facilities451Margins451Formatting Text451Wordwrap Feature451The Directory Editor FLIST453Using "Control-F"453Large Files support455		XTESTChars - Set the Font Testing Mode	445
\ - Locate a Name String447-\ - Locate a Name String448? - Display Last Command448?I - Display Last Command449= - Repeat Last Command449# - Comments449# - Comments449SEDIT Text Formatting Facilities451Margins451Formatting Text451Wordwrap Feature451The Directory Editor FLIST453What Is It For?453Using "Control-F"455Large Files support455		Zone / ZONE_Screen - Set Zone	446
-\ - Locate a Name String 448 ? - Display Last Command 448 ?I - Display Last Command 449 = - Repeat Last Command 449 # - Comments 449 SEDIT Text Formatting Facilities 451 Margins 451 Formatting Text 451 Wordwrap Feature 451 What Is It For? 453 Using "Control-F" 455 Large Files support 455		\ - Locate a Name String	447
 ? - Display Last Command		-\ - Locate a Name String	448
?I - Display Last Command449= - Repeat Last Command449# - Comments449SEDIT Text Formatting Facilities451Margins451Formatting Text451Wordwrap Feature451The Directory Editor FLIST453What Is It For?453Using "Control-F"455Large Files support455		? - Display Last Command	448
 = - Repeat Last Command		?I - Display Last Command	449
# - Comments 449 SEDIT Text Formatting Facilities 451 Margins 451 Formatting Text 451 Wordwrap Feature 451 The Directory Editor FLIST 453 What Is It For? 453 Using "Control-F" 455 Large Files support 455		= - Repeat Last Command	449
SEDIT Text Formatting Facilities 451 Margins 451 Formatting Text 451 Wordwrap Feature 451 The Directory Editor FLIST 453 What Is It For? 453 Using "Control-F" 455 Large Files support 455		# - Comments	449
SEDIT Text Formatting Facilities 451 Margins	CT		451
Margins	51	DIT Text Formatting Facilities	451
Formatting Text		Margins	451
Wordwrap Feature		Formatting Text	451
The Directory Editor FLIST 453 What Is It For? 453 Using "Control-F" 455 Large Files support 455		Wordwrap Feature	451
What Is It For?	Tł	ne Directory Editor FLIST	453
Using "Control-F"		What Is It For?	453
Large Files support		Using "Control-F"	
		Large Files support	

Getting Started	455
Displaying Owner/Group/Timestamp	457
Using the Function Keys	458
Using the Buttons	461
Mouse Editing a File	462
Switching Permissions Display	
Passing Commands	465
The Built-in Commands	465
The Non-built-in Commands	471
Overriding a Built-in Command	471
Using S/REXX Macros Within FLIST	472
The Tree Editor	475
Cotting Started	A75
Using the Mouse	473 477
Using the Nouse	477
Using the Buttons	4/8
Using the Function Keys	
Changing the Default Printer on UNIX Systems	
Running SEDIT With CodeCenter	483
Using S/REXX	487
Starting S/REXX on UNIX Systems	
Explicit Execution	
Automatic Execution	
Starting S/REXX on WINDOWS Systems	
Explicit Execution	
Choosing between srexx.exe and wsrexx.exe	
Automatic Execution	
Using anysrexx.exe	
Using the WINDOWS NT 3.51 File Manager	
Using the WINDOWS NT 4.0 and WINDOWS 95/98 Explorer	
Compiling a Program	
S/REXX Implementation	491
S/REXX Extensions	
Static Scoping	
Dynamic Memory Allocation	
The Operators Extensions	
Important Note for Mainframe Users	
Logical Operators	493
Dynamic Loading on UNIX Systems	
Using OPTION NOLOAD	
Setting Default Options for UNIX or WINDOWS REXX Programs	497
Setting Default Options for SEDIT REXX Macros	497
Dynamic Loading on WINDOWS Systems	
Setting Default Options for WINDOWS REXX Programs	
Extended PROCEDURE EXPOSE	
Extended LEAVE and ITERATE	
Using Backquotes	
Using { and }	

Using Bracket Indexing	
Using S/REXX within SEDIT	
S/REXX New or Extended Instructions	505
ADDRESS (UNIX) - Set Destination of Commands	506
ADDRESS (WINDOWS) - Set Destination of Commands	
Using UNIX Shells on WINDOWS	
CD - Change Directory	508
DESRUE - Clear Stack	508
DO - Controlled Loop	509
DROPBLIE - Remove Stack	510
EXECIO - Input/Output Operations	511
GLOBALV - Share Variables	517
LOWFR - Lower Case Translation	521
MAKEBUF - Create Stack	521
OPTION - Set Various Options	522
PARSE - Parsing	523
SAYN - Terminal Output	
SAYX - Displayed Execution	
SENTRIES - Ouery Stack	
TRACE - Debug Setting	
UPPER - Upper Case Translation	
S/REXX New or Extended Built-in Functions	529
ACOS - Arc Cosine	529
ARCH - Get Hardware Information	
ARCH - Get Hardware Information ARG - Returns Argument String	
ARCH - Get Hardware Information ARG - Returns Argument String ASIN - Arc Sine	
ARCH - Get Hardware Information ARG - Returns Argument String ASIN - Arc Sine ATAN - Arc Tangent	
ARCH - Get Hardware Information ARG - Returns Argument String ASIN - Arc Sine ATAN - Arc Tangent CHANGE - Change String	
ARCH - Get Hardware Information ARG - Returns Argument String ASIN - Arc Sine ATAN - Arc Tangent CHANGE - Change String CHARIN - Read Character Input Stream	
ARCH - Get Hardware Information ARG - Returns Argument String ASIN - Arc Sine ATAN - Arc Tangent CHANGE - Change String CHARIN - Read Character Input Stream CHDIR - Change Directory	
ARCH - Get Hardware Information ARG - Returns Argument String ASIN - Arc Sine ATAN - Arc Tangent CHANGE - Change String CHARIN - Read Character Input Stream CHDIR - Change Directory CLEAR or CLS - Clear the Screen	529
ARCH - Get Hardware Information ARG - Returns Argument String ASIN - Arc Sine ATAN - Arc Tangent CHANGE - Change String CHARIN - Read Character Input Stream CHDIR - Change Directory CLEAR or CLS - Clear the Screen CLOSE_CONS - Close a Console	529 529 529 529 529 529 529 529 530 531 531 531
ARCH - Get Hardware Information ARG - Returns Argument String ASIN - Arc Sine ATAN - Arc Tangent CHANGE - Change String CHARIN - Read Character Input Stream CHDIR - Change Directory CLEAR or CLS - Clear the Screen CLOSE_CONS - Close a Console CONCAT - Concatenate Files	529 529 529 529 529 529 529 530 531 531 531 531 532
ARCH - Get Hardware Information ARG - Returns Argument String ASIN - Arc Sine ATAN - Arc Tangent CHANGE - Change String CHARIN - Read Character Input Stream CHDIR - Change Directory CLEAR or CLS - Clear the Screen CLOSE_CONS - Close a Console CONCAT - Concatenate Files COS - Cosine	529 529 529 529 529 529 529 529 530 531 531 531 531 531 532 532
ARCH - Get Hardware Information ARG - Returns Argument String ASIN - Arc Sine ATAN - Arc Tangent CHANGE - Change String CHARIN - Read Character Input Stream CHDIR - Change Directory CLEAR or CLS - Clear the Screen CLOSE_CONS - Close a Console CONCAT - Concatenate Files COS - Cosine CP or COPY - Copy Files	529 529 529 529 529 529 529 530 531 531 531 531 532 532 532 532
ARCH - Get Hardware Information ARG - Returns Argument String ASIN - Arc Sine ATAN - Arc Tangent CHANGE - Change String CHARIN - Read Character Input Stream CHDIR - Change Directory CLEAR or CLS - Clear the Screen CLOSE_CONS - Close a Console CONCAT - Concatenate Files COS - Cosine CP Or COPY - Copy Files CPUID - Workstation CPU Identifier	529 529 529 529 529 529 529 530 531 531 531 531 532 532 532 532 532 533
ARCH - Get Hardware Information ARG - Returns Argument String ASIN - Arc Sine ATAN - Arc Tangent CHANGE - Change String CHARIN - Read Character Input Stream CHDIR - Change Directory CLEAR or CLS - Clear the Screen CLOSE_CONS - Close a Console CONCAT - Concatenate Files COS - Cosine CP or COPY - Copy Files CPUID - Workstation CPU Identifier CSH - Pass UNIX Command	529 529 529 529 529 529 529 530 531 531 531 531 531 532 532 532 532 532 532
ARCH - Get Hardware Information ARG - Returns Argument String ASIN - Arc Sine ATAN - Arc Tangent CHANGE - Change String CHARIN - Read Character Input Stream CHDIR - Change Directory CLEAR or CLS - Clear the Screen CLOSE_CONS - Close a Console CONCAT - Concatenate Files COS - Cosine CP or COPY - Copy Files CPUID - Workstation CPU Identifier CSH - Pass UNIX Command CUSERID, USERID - Get Userid	529 529 529 529 529 529 529 530 531 531 531 531 532 532 532 532 533 533 533
ARCH - Get Hardware Information ARG - Returns Argument String ASIN - Arc Sine ATAN - Arc Tangent CHANGE - Change String CHARIN - Read Character Input Stream CHDIR - Change Directory CLEAR or CLS - Clear the Screen CLOSE_CONS - Close a Console CONCAT - Concatenate Files COS - Cosine CP or COPY - Copy Files CPUID - Workstation CPU Identifier CSH - Pass UNIX Command CUSERID, USERID - Get Userid CVTAILS - Get Active Stems Tails	529 529 529 529 529 529 529 529 530 531 531 531 531 531 532 532 532 532 533 533 533 533
ARCH - Get Hardware Information ARG - Returns Argument String ASIN - Arc Sine ATAN - Arc Tangent CHANGE - Change String CHARIN - Read Character Input Stream CHDIR - Change Directory CLEAR or CLS - Clear the Screen CLOSE_CONS - Close a Console CONCAT - Concatenate Files COS - Cosine CP or COPY - Copy Files CPUID - Workstation CPU Identifier CSH - Pass UNIX Command CUSERID, USERID - Get Userid CVTAILS - Get Active Stems Tails CWD, GETCWD, GETWD - Get Current Directory	529 529 529 529 529 529 529 530 531 531 531 531 532 532 532 532 533 533 533 533
ARCH - Get Hardware Information ARG - Returns Argument String ASIN - Arc Sine ATAN - Arc Tangent CHANGE - Change String CHARIN - Read Character Input Stream CHDIR - Change Directory CLEAR or CLS - Clear the Screen CLOSE_CONS - Close a Console CONCAT - Concatenate Files COS - Cosine CP or COPY - Copy Files CPUID - Workstation CPU Identifier CSH - Pass UNIX Command CUSERID, USERID - Get Userid CVTAILS - Get Active Stems Tails CWD, GETCWD, GETWD - Get Current Directory C20 - Character to Octal	529 529 529 529 529 529 529 530 531 531 531 531 532 532 532 532 533 533 533 533 533 533 534 534
ARCH - Get Hardware Information ARG - Returns Argument String ASIN - Arc Sine ATAN - Arc Tangent CHANGE - Change String CHARIN - Read Character Input Stream CHDIR - Change Directory CLEAR or CLS - Clear the Screen CLOSE_CONS - Close a Console CONCAT - Concatenate Files COS - Cosine CP or COPY - Copy Files CPUID - Workstation CPU Identifier CSH - Pass UNIX Command CUSERID, USERID - Get Userid CVTAILS - Get Active Stems Tails CWD, GETCWD, GETWD - Get Current Directory C20 - Character to Octal DATE - Get Current Date	529 529 529 529 529 529 529 529 530 531 531 531 531 531 532 532 532 532 532 533 533 533 533 534 534 534
ARCH - Get Hardware Information ARG - Returns Argument String ASIN - Arc Sine ATAN - Arc Tangent CHANGE - Change String CHARIN - Read Character Input Stream CHDIR - Change Directory CLEAR or CLS - Clear the Screen CLOSE_CONS - Close a Console CONCAT - Concatenate Files COS - Cosine CP or COPY - Copy Files CPUID - Workstation CPU Identifier CSH - Pass UNIX Command CUSERID, USERID - Get Userid CVTAILS - Get Active Stems Tails CWD, GETCWD, GETWD - Get Current Directory C20 - Character to Octal DATE - Get Current Date DEL or RM - Delete Files	529 529 529 529 529 529 529 530 531 531 531 531 532 532 532 532 533 533 533 533 533 533
ARCH - Get Hardware Information ARG - Returns Argument String ASIN - Arc Sine ATAN - Arc Tangent CHANGE - Change String CHARIN - Read Character Input Stream CHDIR - Change Directory CLEAR or CLS - Clear the Screen CLOSE_CONS - Close a Console CONCAT - Concatenate Files COS - Cosine CP or COPY - Copy Files CPUID - Workstation CPU Identifier CSH - Pass UNIX Command CUSERID, USERID - Get Userid CVTAILS - Get Active Stems Tails CWD, GETCWD, GETWD - Get Current Directory C2O - Character to Octal DATE - Get Current Date DEL or RM - Delete Files DIR or LS - List Files	529 529 529 529 529 529 529 530 531 531 531 531 532 532 532 532 533 533 533 533 533 534 534 534 535 535 535
ARCH - Get Hardware Information ARG - Returns Argument String ASIN - Arc Sine ATAN - Arc Tangent CHANGE - Change String CHARIN - Read Character Input Stream CHDIR - Change Directory CLEAR or CLS - Clear the Screen CLOSE_CONS - Close a Console CONCAT - Concatenate Files COS - Cosine CP or COPY - Copy Files CPUID - Workstation CPU Identifier CSH - Pass UNIX Command CUSERID, USERID - Get Userid CVTAILS - Get Active Stems Tails CWD, GETCWD, GETWD - Get Current Directory C2O - Character to Octal DATE - Get Current Date DEL or RM - Delete Files DIR or LS - List Files DIR or LS - List Files	529 529 529 529 529 529 529 530 531 531 531 531 532 532 532 532 532 533 533 533 533 533 533 533 534 534 534 534 535 535 535 535 536 536 536
ARCH - Get Hardware Information ARG - Returns Argument String ASIN - Arc Sine ATAN - Arc Tangent CHANGE - Change String CHARIN - Read Character Input Stream CHDIR - Change Directory CLEAR or CLS - Clear the Screen CLOSE_CONS - Close a Console CONCAT - Concatenate Files COS - Cosine CP or COPY - Copy Files CPUID - Workstation CPU Identifier CSH - Pass UNIX Command CUSERID, USERID - Get Userid CVTAILS - Get Active Stems Tails CWD, GETCWD, GETWD - Get Current Directory C20 - Character to Octal DATE - Get Current Date DEL or RM - Delete Files DIR or LS - List Files DY_BEEP - Sound the Alarm	529 529 529 529 529 529 529 530 531 531 531 531 532 532 532 532 533 533 533 533 533 533 533 533 534 534 534 534 535 535 535 536 536 536

DY_BUTTON_COLOR - Change a Button Dialog Item Color	537
DY_CH - Make a Choice Dialog Item	537
DY_CH_COLOR - Change a Choice Dialog Item Color	538
DY_DESTROY - Destroy a Dialog Box	538
DY_DSCL - Remove a Set of Strings from a Scrolled List	538
DY_END - End a Dialog Box	539
DY_FOCUS - Give a Dialog Input Item the Keyboard Focus	540
DY_FONT - Set the Dialog Font	540
DY_HEADER - Set the Dialog Box Header	540
DY_INPUT - Make a Dialog Input Item	541
DY_INPUT_COLOR - Change an Input Dialog Item Color	541
DY_LABEL - Make a Dialog Label Item	542
DY_LABEL_COLOR - Change a Label Dialog Item Color	542
DY_MAP - Map a Dialog Box	542
DY_OPEN (UNIX) - Displays the Contents of a Directory	543
DY_OPEN (WINDOWS) - Displays the Contents of a Directory	547
DY_PRINTER - Set the Default Printer	547
DY_PSCL - Set the First Displayed String	547
DY_REFRESH - Redraw the Dialog Box	548
DY_RSCL - Replace a String in a Scrolled List	548
DY SCH - Set a Choice Value	548
DY SINPUT - Set a Dialog Input Item Value	548
DY SCL - Make a Scrolled List Dialog Item	549
DY SCL COLOR - Change a Scrolled List Dialog Item Color	553
DY_SLABEL - Set a Dialog Label Item Value	553
DY SSCL - Select or Unselect a String Within a Scrolled List	553
DY START - Start a Dialog Box	553
DY STG - Set a Dialog Toggle Value	554
DY TG - Make a Dialog Toggle	555
DY TG COLOR - Change a Toggle Dialog Item Color	556
DY UNMAP - Unmap a Dialog Box	556
DY VINPUT - Get a Dialog Input Item Value	556
DY VCH - Get a Dialog Choice Value	556
DY VSCL - Retrieve a Scrolled List Ranks and Contents of the Selected Strings	557
DY VTG - Get a Dialog Toggle Item Value	557
DY WARP - Set Mouse Handling	557
EXEC - Pass UNIX Command Directly	557
EXTERNALS - Pending Input	558
FD - Get File-Directory	558
FILECONV - UNIX or WINDOWS File Conversion	558
FLFILES - Get FLIST Files	559
FN - Get Filename	559
FOLLOW - Follow Symbolic Links	559
FORK - Spawn a New Process	560
FT - Get Filetype	561
GETDISKSPACE - Get Free Disk Space	561
GETENV - Get Environment Variable	561
GETFILE - Get File Content	561
GETPID - Process Identifier	562

HOSTNAME - Workstation Hostname	
JUSTIFY - Justify String	.562
KILL - Terminate a Process	.563
KSH - Pass UNIX Command	.563
LINEIN, LINEOUT - Input / Output	.563
MKDIR - Make a Directory	.565
MV or RENAME - Rename a File	.565
OPEN CONS - Open a Console	.565
PARG - Parse Argument	.566
OPID - Query Process Death	.567
REGISTRY DEL - Delete REGISTRY Key Contents	.568
REGISTRY GET - Retrieve REGISTRY Key Contents	.568
REGISTRY KEYS - REGISTRY Subkeys Enumeration	.570
REGISTRY SET - Set REGISTRY Key Contents	.571
REGISTRY VALUES - REGISTRY Values Enumeration	.572
RM / DEL / RECYCLE - Delete Files	.573
RMDIR - Delete a Directory	573
SCRIPT - Record Session	573
SERVICE CREATE - Create a Service	574
SERVICE DELETE - Delete a Service	574
SERVICE STOP - Stop a Service	575
SERVICE START - Start a Service	575
SERVICE STATUS - Status of a Service	575
SETENV PLITENV - Set Environment Variable	576
SIN - Sine	576
SI FFP - Suspend Execution	576
Sock Accept - Accept an Incoming Request	576
SockClose - Close a Socket	576
SockBind - Bind a Socket	577
SockConnect - Connect a Socket	578
SockDronFunce - Compatibility Function	570
SockGetHostByAddr - Search for Information for a Host	570
SockGetHostByName - Search for Information for a Host	580
SockGetHostId Get the Dot Address of the Host	581
SockGetBoorName Get the Name of the Connected Boor	591
SockGetSockName Get the Current Socket Name	
SockGetSockName - Get the Current Socket Name	
SockOetSockOpt - Oet Socket Options	
Sockinit - Compatibility Function	
Sockiocii - Perioriii Special Operations on Socket	
SockListen - Listen for incoming Requests	
SockLoadFuncs - Compatibility Function	
SockPSock_EITIO - Last EITOF Code	
SockReev - Receive Data	
SockKeevFrom - Keelve Data	
SockSelect - Monitor Sockets	
SockSend - Send Data	
SockSend10 - Send Data	
SockSetSockOpt - Set Socket Options	
NockNhutDown - Close a Nocket	

SockSocket - Create a Socket	
SockSoClose - Close a Socket	
SockSock_Errno - Last Error Code	
SockVersion - Version Number of Socket Library	
SORT - Sort a List	
STATE / LSTATE - Query File State	
STIME - Set System Time	
STREAM - Compatibility Function	
SUBDIRS - Find Subdirectories	
SysCls - Clear the Screen	
SysFileDelete - Delete File	
SysFileSearch - Scan File	
SysFileTree - Scan Directory	
SysGetKey - Read Character Input Stream	
SysMkDir - Delete a Directory	
SysRmDir - Delete a Directory	
SysSearchPath - Search Files in Path	
SysSetPriority - Change the Priority	
SysSleep - Suspend Execution	
SysTempFileName - Make a Unique File Name	
SysVersion - Operating System Description	
TAN - Tangent	
TBADD - Insert Table Line	
TBCLOSE - Close Current Table	
TBDEL - Delete Table Line	
TBDISPL - Display Table	
TBGET - Get Table Line	
TBOPEN - Open a Table	604
TBPUT - Update Table Line	604
TBSAVE - Save Table	605
TCSH - Pass UNIX Command	
TEE - Pass UNIX Command	
UNIX or SH - Pass UNIX Command	605
UNSETENV - Remove Environment Variable	
USLEEP - Suspend Execution	606
UTIME - Change File Timestamp	606
VALUE - Set or Retrieve a Variable	606
VERSION- Windowing Identifier	606
WAITPID - Wait for a Process Termination	607
WINDOWS - Pass WINDOWS Command	607
WIPE - Wine Files	608
XHOME - Installation Directory	608
S/REXX Dialog Management	609
OpenLook Specifics	609
WINDOWS Specifics	609

S/REXX Dialog Management within SEDIT	613
S/REXX ISPF-like Tables	619
S/REXX Programming Interface	629
Creating a New Address Environment	629
ENV_RX - Initiate a Host Command Environment	630
EXIT_RX - Cleans up and Exits	
GETVAL_RX - Get an S/REXX Variable	633
PULL_RX - Extract External Data Queue Item	635
PUSH_RX - Add a String on Top of the External Data Queue	637
QUEUE_RX - Add a String to the External Data Queue	638
QUEUED_RX - Query External Data Queue Length	640
RUN_RX - Run an S/REXX Program	642
SETVAL_RX - Set an S/REXX Variable	645
STOP_RX - Stop an S/REXX Program.	647
Adding Built-in Functions	649
Using the RXD Debugger	
Entering RXD Explicitly	653
Entering RXD Implicitly	653
Setting Stops	656
Customizing RXD	656
Using the Function Keys	659
Appendix A: Keyboard Layouts	661
SUN Type 3 Keyboard 3270 Simulation Layout	
SUN Type 4 Keyboard 3270 Simulation Layout	
SUN Type 5 Keyboard Layout	664
SUN Keyboard Mapping	665
IBM, Silicon Graphics and PCs Keyboard Mapping	667
DEC/COMPAQ/HP TRUE64 Station Keyboard Mapping	669
HP Keyboard Mapping	671
WINDOWS Keyboard Mapping	673
Character Mode Terminals Mapping	675
Appendix B: Hardware String	677
SEDIT Release Notes	679
The 3.60 File Editor Enhancements	679
New Commands	679
Miscellaneous	679
The 3.60 Directory Editor Enhancements	
The 3.60 Tree Editor Enhancements	
The 4.0 File Editor Enhancements	681
New or Enhanced Commands	681
Miscellaneous	
The 4.0 Directory Editor Enhancements	
The 4.0 Tree Editor Enhancements	
The 4.10 File Editor Enhancements	684

New or Enhanced Commands	
Miscellaneous	
The 4.10 Directory Editor Enhancements	
The 4.10 Tree Editor Enhancements	
The 4.20 File Editor Enhancements	
New or Enhanced Commands	
Miscellaneous	
The 4.20 Directory Editor Enhancements	
The 4.20 Tree Editor Enhancements	
The 4.30 File Editor Enhancements	
New or Enhanced Commands	
Miscellaneous	
The 4.30 Directory Editor Enhancements	
The 4.30 Tree Editor Enhancements	
The 4.40 File Editor Enhancements	
New or Enhanced Commands	
Miscellaneous	
The 4.40 Directory Editor Enhancements	
The 4.50 File Editor Enhancements	
New or Enhanced Commands	
Miscellaneous	
The 4.50 Directory Editor Enhancements	
The 4.50 Tree Editor Enhancements	
The 4.60 File Editor Enhancements	
New or Enhanced Commands	
Miscellaneous	
The 4.60 Directory Editor Enhancements	
The 4.70 File Editor Enhancements	
New or Enhanced Commands	
Miscellaneous	
The 4.70 Directory Editor Enhancements	
The 4.70 Tree Editor Enhancements	
S/REXX Release Notes	
1.10 Enhancements	
Enhanced Built-in Functions	
Miscellaneous	
1.20 Enhancements	
New or Extended Instructions	
New Built-in Functions	
Enhanced Built-in Functions	
Miscellaneous	
2.00 Enhancements	
New or Extended Instructions	
New Built-in Functions	
Miscellaneous	
2.10 Enhancements	
New or Enhanced Built-in Functions	697
Miscellaneous	

2.20 Enhancements	698
New or Enhanced Built-in Functions	698
Miscellaneous	698
2.30 Enhancements	698
New or Enhanced Built-in Functions	698
Miscellaneous	699
2.40 Enhancements	699
New or Enhanced Built-in Functions	699
Miscellaneous	701
2.50 Enhancements	701
New or Enhanced Built-in Functions	701
Miscellaneous	701
2.60 Enhancements	701
New or Enhanced Built-in Functions	701
Miscellaneous	701
2.70 Enhancements	702
Miscellaneous	702

Table of Contents

Installing SEDIT on UNIX Systems¹

SEDIT can be installed in any directory. In this manual, it is assumed that **SEDIT** will be installed in /home/xed.

First, the user must create a /home/xed directory. This procedure may require the user to be the superuser. Type:

mkdir /home/xed
cd /home/xed

To load from a tape, use the procedure described in the READ THIS FIRST document.

To load from diskettes, use the procedure printed on each diskette.

The following files will then be loaded:

•	README	This file contains up-to-date information that may not be included in the manual. Process this file carefully before continuing the installation.
•	xed	The file editor calling script (in XEDIT foreground mode).
•	sedit	The file editor calling script (in XEDIT background mode).
•	pxed	The file editor calling script (in PDF foreground mode).
•	psedit	The file editor calling script (in PDF background mode).
•	fli	The directory editor calling script.
•	tree	The tree editor calling script.
•	profile.sedit	This file will be executed as a command macro when SEDIT starts with the sedit, xed, psedit, pxed, fli or tree commands.
•	xedit	The file editor calling script (in full XEDIT compatibility mode).
•	prof_xedit.sedit	This file will be executed as a command macro when SEDIT starts with the xedit command.
•	pdf	The file editor calling script (in full PDF compatibility mode).
•	prof_pdf.sedit	This file will be executed as a command macro when SEDIT starts with the pdf command.
•	./xmac	A subdirectory containing useful macros.
•	XF	A workspace allowing SEDIT to be used within Dyalog APL.
•	PROFILE.sedit	This file will be executed as a command macro when SEDIT starts under Dyalog APL.

^{1.} **SEDIT** and **S/REXX** are generally bundled together. Installing **SEDIT** will also install **S/REXX**, although different activation keys are needed.

Using a Grey Scale Monitor

If a grey scale monitor is used, the user must include the command "color off" in the profile.sedit and/or PROFILE.sedit and/or prof_xedit.sedit files and/or prof_pdf.sedit files.

Setting the Background Color

The profile.sedit initialization file (or the prof_xedit.sedit file when starting **SEDIT** with the xedit command described on page 31, or the prof_pdf.sedit file when starting **SEDIT** with the pdf command described on page 36) sets the background color in accordance with the architecture **SEDIT** is running on. For example, on an IBM station:

```
when arch = 'ibm' then do
  'set_ibm'
  if version ~= 'curses' then do
  'color background 255 255 190'
```

To have a white background, replace 'color background 230 230 190' with 'color background 255 255'. See the COLOR command on page 182 for more details.

Setting the Path

SEDIT has the ability to follow the path when searching for files. If the user wants a particular path for **SEDIT** operations, an XPATH special environment variable must be created int the .cshrc file. For example, if the system uses the C-SHELL, the user can edit the .cshrc file and add the following lines:

```
# General path
   set path = (~ . /bin /usr/bin /usr/ucb /etc /usr/etc )
# Additional path for xed
   set fpath = ($path /home/xed/font /usr/lib/fonts/fixedwidthfonts)
# Now we set XPATH
   setenv XPATH "$fpath"
```

SEDIT may also use a XCDPATH environment variable while searching for directories, processing the commands <u>ACCESS</u>, <u>CD</u>, <u>FLIST</u>, <u>TREE</u>, and <u>FD</u> in a way similar to that used by the C-SHELL using \$cdpath. If the user wants to use this facility, an XCDPATH must be created in the .cshrc file. For example:

```
set cdpath = (.. ~ /home /usr /)
setenv XCDPATH "$cdpath"
```

Note that **SEDIT** ignores items which do not begin with a "/", and always searches first for directories which root in the current directory.

The <u>DACCESS</u> command may be used to update the cdpath within **SEDIT**.

Setting the Password for CPU Bound Licenses

The user must type the following commands:

The user will be prompted for the information displayed in the password sheet. The following is a typical installation example on an IBM RS/6000:

```
% ./install SEDIT
******* Beginning to install SEDIT
Do you want to add a new password ? y
Enter the HOSTNAME (I) :
Enter the UNAME (000003063100) :
Enter the PASSWORD () : 25674-75433-03258-71687
You have typed the following information:
HOSTNAME: I
UNAME : 000003063100
PASSWORD: 25674-75433-03258-71687
OK ? y
Do you want to add a new password ? n
%
```

Workstation	Query	Unix command
SUN SunOS	HOSTID	hostid
SUN Solaris	HOSTID	/usr/ucb/hostid
Siemens SINIX	HOSTID	hostid
IBM RS/6000	UNAME	uname -m
Hewlett Packard	UNAME	uname -i
Silicon Graphics	SYSID	sysinfo -s
Linux PC	SEDITID	./seditid
SCO PC	SEDITID	./seditid
Unixware PC	SEDITID	./seditid
Digital Equipment	ETHERNET ADDRESS	see below

On the different workstations, the UNAME query will be replaced by one of the following:

CPU Identifier on Digital Equipment Stations

On DEC Alpha stations, the cpu identifier is the ethernet address, which can be displayed by typing the following command:

```
% /usr/sbin/uerf -R -r 300 | more
----- EVENT INFORMATION -----
EVENT CLASS
                                OPERATIONAL EVENT
                         300.
                                SYSTEM STARTUP
OS EVENT TYPE
SEQUENCE NUMBER
                         Ο.
OPERATING SYSTEM
                                DEC OSF/1
                           tu0: DEC TULIP Ethernet Interface,
                         _hardware address: 08-00-2B-E4-F3-0B
                            tu0: console mode: selecting AUI
Ŷ
```

The cpu identifier is the last four ethernet address bytes. In this example, it would be 2BE4F30B.

Alternately, the user may install **SEDIT** and type the following:

```
% cd xed
/home/xed
% ./seditid
2BE4F30B
%
```

install may also be used to modify existing passwords, or to add new passwords for different workstations, allowing the user to centralize all the password information for multiple workstations on the same network.

Example:

```
% ./install sedit
******* Beginning to install SEDIT
The following passwords have been installed:
1: HOSTNAME: I UNAME: 000003063100
        PASSWORD: 25674-75433-03258-71687
Do you want to modify one of these passwords ? n
Do you want to add a new password ? y
Enter the HOSTNAME () :
```

It will be possible to start **SEDIT** now with one of the following commands:

xed	starts SEDIT in the foreground in XEDIT mode
sedit	starts SEDIT in the background in XEDIT mode
pxed	starts SEDIT in the foreground in PDF mode
psedit	starts SEDIT in the background in PDF mode
xedit	starts SEDIT in full XEDIT compatible mode
pdf	starts SEDIT in full PDF compatible mode

Note for advanced users:

install creates or updates the /home/xed/passwds file. The user can edit and modify it directly to add, remove or modify passwords.

Setting the Keyboard Mapping

Depending on the command used to start it, **SEDIT** uses one of the following *.sedit initialization macros:

Unix COMMAND	Initialization macro	
xed	profile.sedit	
sedit	profile.sedit	
pxed	profile.sedit	
psedit	profile.sedit	
xedit	prof_xedit.sedit	
pdf	prof_pdf.sedit	

To simplify the keyboard mapping, the various **SEDIT** *.sedit initialization macros automatically call the following macros:

•	set_sun_t5	for SUN workstations using the type 5 keyboard. Please see SUN Type 5 Keyboard Layout on page 664 for more information about fully using this keyboard.
•	set_sgi	for SiliconGraphics workstations.
•	set_ibm	for IBM RS/6000 workstations.
•	set_alphapc	for a DEC Alpha station using a PC style keyboard.
•	set_hp	for HP workstations using HP style keyboard.
•	set_linux	for PCs running Linux.
•	set_sco	for PCs running SCO UNIX.
•	set_uxw	for PCs running Unixware.
•	set_sinix	for Siemens workstations running SINIX.

The user can redefine every keyboard key using the KEYBOARD command described on page 291. In addition, the keyboard can be mapped dynamically by using the menu button described on page 101.

Using SUN Type 4 or Type 3 Keyboards

When a type 4 keyboard is in use on a SUN workstation, the set_sun_t5 statement in the *.sedit files in use must be replaced with the set_sun_t4 statement. When a type 3 keyboard is in use on a SUN workstation, the set_sun_t5 statement must be replaced with the set_sun_t3 statement.

Using HP PC-Style Keyboard

When a PC style keyboard is in use on a HP workstation, the set_hp statement in the *.sedit files in use must be replaced with the set_hppc statement.

Using Native DEC Keyboard

When a native DEC keyboard is in use on an alpha workstation, the set_alphapc statement in the *.sedit files in use must be replaced with the set_alpha statement.

Setting the MOTIF Resources

When using the **MOTIF** version, the user can customize various colors and fonts using the X11 resources facilities, by including this resource description in the ~/.Xdefaults file.

SEDIT provides the following /home/xed/.Xdefaults file to be used as a template:

```
!
! menus
T
smenu*background: grey90
smenu*foreground:
                       black
!smenu*fontList:
                       courier-bold-14
!smenu*fontList:
                       screen-bold-14
!
! popups
!
salert*background:
                       Wheat
salert*foreground:
                        Black
!
! editor buttons
!
sedit*panel*background: Wheat
sedit*panel*foreground: Black
!
! tree buttons
!
tree*tpanel*background: Wheat
tree*tpanel*foreground: Black
!
! tree scroolbars
!
tree*scrool*background: Wheat
tree*scrool*foreground: Black
!
! dialog boxes
1
dialog*background: Wheat
dialog*foreground: Black
```

It is recommended that the contents of this file be inserted in the private \sim /.Xdefaults file.

The user can override the setting described in the ~/.Xdefaults file by using the -xrm starting option at **SEDIT** invocation.

Example: xed -xrm '"salert*background: red"'

All the color names supported by the system are generally located in the /usr/lib/X11/rgb.txt file.

Setting the Keyboard Translations for an ASCII Terminal

SEDIT can run on ASCII terminals.

Such terminals send escape sequences when the user presses a function or an arrow key.

When starting in ASCII terminal mode, **SEDIT** reads the TERM environment variable, and then tries to load the keyboard/terminfo/1/\$TERM.esc file describing these escape sequences, where 1 is the first \$TERM letter. **SEDIT** checks in the current directory first, then in the home directory and finally in the installation directory.

SEDIT provides several *.esc files. However, if the terminal is not described by one of these files, the user will receive the message "warning: no \$TERM.esc file available", and the terminal function keys might not work properly. **SEDIT** provides the mkesc utility to easily generate such a file.

The *.esc files provided are derived from the usual terminfo files provided with UNIX. These terminfo files are often incomplete with respect to the function keys, so it is highly recommended that the user run mkesc for every ASCII terminal that will use SEDIT.

Using MKESC

mkesc will create by default a description file in the /home/xed/keyboard directory, so the user must have write authorization on this directory before starting. However, a description file can be written in any other directory by passing the directory name as the first argument. Every user can use a specific description file created by typing for example: mkesc ~

The user must use mkesc on the terminal that is being described. mkesc "looks" at each escape sequence generated in response to questions and equates these keys to the received sequence.

Type the following commands:

% cd /home/xed
% ./mkesc

This will display the following screen:

```
Press the "UP ARROW" Key
E EXIT
S SAVE
N Next Key
P Previous Key
F Next Key type
B Previous Key type
C Cancel key
```

The user must now press the "UP ARROW" key, as indicated on the top of the screen.

This will display (for example) the following screen:

```
Press the "RIGHT ARROW" Key
Key "UP ARROW" saved as ^[ [ A
E EXIT
S SAVE
N Next Key
P Previous Key
F Next Key type
B Previous Key type
C Cancel key
```

This means that the "UP ARROW" key has been recorded as the "^[[A" escape sequence.

The keywords below have the following meanings:

- E terminates mkesc without saving changes.
- S saves the changes.
- N skips the current key.
- P returns to the previous key.
- F skips the current family key. The families are the following: Up arrow key
 - Right arrow key Down arrow key
 - Left arrow key
 - Left function keys
 - Top function keys
 - Right function keys
 - Insert key
 - Delete key
 - Numerical pad Enter key
 - Numerical pad + key Numerical pad - key
- B returns to the previous family key.
- C cancels the key. You must choose this option if your terminal does not support that key.

When saving the file, mkesc will backup the old file by appending a % character to the old filename.

Usage notes:

The right function keys are generally mapped as following:

R1 Print Screen Scroll Lock R2 R3 Pause R4 Insert R5 Home Rб Page Up R7 End R9 Page Down

With the following physical layout:



If the escape sequence appears to be one character long, it means that the terminal does not handle this key properly. In such a case, it is recommended the user cancel the key. In these situations, mkesc will display a warning.

Most keyboards do not support the left keys named Li, so the user must type C to cancel them.

Some of the top F_i keys may be used by the emulator directly, and will not be usable by **SEDIT**.

Must emulators only support R4, R5, R6, R7 and R9 (**NOT** R8), so it is generally recommended to cancel all the other R*i* keys.

When prompted for the INSERT key, press INSERT, the same key used to define R4.

The Numerical pad keys generally need to be cancelled.

Installing SEDIT on WINDOWS Systems¹

SEDIT can be installed in any directory. In this manual, it is assumed that **SEDIT** will be installed in "C:\Program Files\SEDIT".

The user must place the first **SEDIT** diskette in the diskette reader, use the **WINDOWS** file manager to display its contents, and double-click on the setup.exe file when running **WINDOWS NT 3.51**, or on the setup application icon when running **WINDOWS NT 4.0**+ or **WINDOWS 95**+.

setup will prompt the user for each disk as the installation progresses. Once the installation is done, setup displays the following screen:

C:\Program Files\SEDIT\Register		
Thank you for choosing SEDIT and S/REXX.		
You must register these programs before using them.		
Your CPU ID is: 11489959		
Please note this number and contact your vendor to obtain an activation key.		
If you need to restart this procedure in the future, please choose the "Register" item in the SEDIT folder.		
"Register" is an S/REXX program.		
Cancel Register SEDIT Register S/REXX		

^{1.} **SEDIT** and **S/REXX** are generally bundled together. Installing **SEDIT** will also install **S/REXX**, although different activation keys are needed.

Clicking on the "Register SEDIT" button will display the following screen:

C:\Program Files\SEDIT\Register		
te te t	***** SEDIT Registration	****
CPU ID:	1014879803	
кеу:	β3008-31849-03107-66750	
Cancel		Register SEDIT

Enter the activation key, and click on the "Register SEDIT" button. The first dialog box is displayed again. If you do not need to register another product, click on the "Cancel" button.

Note for advanced users:

setup creates or updates the C:\Program Files\SEDIT\passwds file. The user can edit and modify it directly to add, remove or modify activation keys.

Installing S/REXX on UNIX Systems¹

S/REXX can be installed in any directory. In this manual, it is assumed that S/REXX will be installed in /home/xed.

First, the user must create a /home/xed directory. This procedure may require the user to be the superuser. Type:

mkdir /home/xed
cd /home/xed

To load from a tape, use the procedure described in the READ THIS FIRST document.

To load from diskettes, use the procedure printed on each diskette.

^{1.} **SEDIT** and **S/REXX** are generally bundled together. Installing **S/REXX** will also install **SEDIT**, although different activation keys are needed.

Setting the Password in Fixed License Mode

The user must type the following commands:

```
% cd /home/xed  # Assuming /home/xed is the installation directory
% ./install srexx
```

The user will be prompted for the information displayed in the password sheet. The following is a typical installation example on an IBM RS/6000:

```
% ./install srexx
******* Beginning to install S/REXX
Do you want to add a new password? y
Enter the HOSTNAME (I) :
Enter the UNAME (000003063100) :
Enter the PASSWORD () : 01455-32956-26199-54243
You have typed the following information:
HOSTNAME: I
UNAME : 000003063100
PASSWORD: 01455-32956-26199-54243
OK ? y
Do you want to add a new password ? n
%
```

Workstation	Query	UNIX command
SUN SunOS	HOSTID	hostid
SUN Solaris	HOSTID	/usr/ucb/hostid
Siemens SINIX	HOSTID	hostid
IBM RS/6000	UNAME	uname -m
Hewlett Packard	UNAME	uname -i
Silicon Graphics	SYSID	sysinfo -s
Linux PC	SEDITID	./seditid
SCO PC	SEDITID	./seditid
Unixware PC	SEDITID	./seditid
Digital Equipment	ETHERNET ADDRESS	see below

On the different workstations, the UNAME query will be replaced by one of the following **UNIX** commands:

CPU Identifier on DEC/COMPAQ/HP TRUE64 Stations

On DEC Alpha stations, the cpu identifier is the ethernet address, which can be displayed by typing the following command:

```
% /usr/sbin/uerf -R -r 300 | more
1 ***************
---- EVENT INFORMATION -----
EVENT CLASS
                                  OPERATIONAL EVENT
OS EVENT TYPE
                          300.
                                  SYSTEM STARTUP
SEQUENCE NUMBER
                           0.
OPERATING SYSTEM
                                  DEC OSF/1
                             tu0: DEC TULIP Ethernet Interface,
                           _hardware address: 08-00-2B-E4-F3-0B
                              tu0: console mode: selecting AUI
°
```

The cpu identifier is the last four ethernet address bytes. In this example, it would be 2BE4F30B.

./seditid can also be used in the **SEDIT** installation directory to display the cpu identifier.

install may also be used to modify existing passwords or to add new passwords for different workstations, allowing the user to centralize all the password information for multiple workstations on the same network.

Example:

```
% ./install srexx
******* Beginning to install S/REXX
The following passwords have been installed:
1: HOSTNAME: I UNAME: 000003063100
PASSWORD: 01455-32956-26199-54243
Do you want to modify one of these passwords ? n
Do you want to add a new password ? y
Enter the HOSTNAME () :
```

Note for advanced users:

install creates or updates the /home/xed/passwds file. The user can edit and modify the passwds file directly to add, remove or modify passwords.

Installing S/REXX on WINDOWS Systems¹

S/REXX can be installed in any directory. In this manual, it is assumed that S/REXX will be installed in "C:\Program Files\SEDIT".

The user must place the first **S/REXX** diskette in the diskette reader, use the **WINDOWS** file manager to display its contents, and double-click on the setup . exe file when running **WINDOWS NT** 3.51, or on the setup application icon when running **WINDOWS NT** 4.0+ or **WINDOWS 95**+.

setup will prompt the user for each disk as the installation progresses. Once the installation is done, setup displays the following screen:

C:\Program Files\SEDIT\Register
Thank you for choosing SEDIT and S/REXX.
You must register these programs before using them.
Your CPU ID is: 11489959
Please note this number and contact your vendor to obtain an activation key.
If you need to restart this procedure in the future, please choose the "Register" item in the SEDIT folder.
"Register" is an S/REXX program.
Cancel Register SEDIT Register S/REXX

^{1.} **SEDIT** and **S/REXX** are generally bundled together. Installing **S/REXX** will also install **SEDIT**, although different activation keys are needed.

Clicking on the "Register S/REXX" button will display the following screen:

-	C:\Program Files\SEDIT\R	egister
	******* SREXX Registration	***
CPU ID:	1014879803	
кеу:	22815-83825-09462-22449	
Cancel]	Register SREXX

Enter the activation key, and click on the "Register S/REXX" button. The first dialog box is displayed again. If you do not need to register another product, click on the "Cancel" button.

Note for advanced users:

setup creates or updates the C:\Program Files\SEDIT\passwds file. The user can edit and modify it directly to add, remove or modify activation keys.

Using the License Server

Note: the license server should not be installed if a fixed license is used.

The same license server is used for both **SEDIT** and/or **S/REXX**. Throughout this chapter, we will refer to the **SEDIT** software only for simplification. **S/REXX** will be mentioned only when **S/REXX** specific information is provided.

SEDIT may run with a license server named xserv. In this case, **SEDIT** will be installed only on one server workstation, and the other stations will have to mount the **SEDIT** filesystem from that server. We will assume that **SEDIT** is installed in the server directory /home/xed or C:\Program Files\SEDIT, but it may be installed anywhere.

Installing xserv on UNIX systems

To use xserv, the user must execute the following:

1) Decide which workstation to install **SEDIT** on.

We will name this station xserver in the following explanations.

2) Install the password information by typing the following commands:

```
% cd /home/xed  # Assuming /home/xed is the installation directory
% ./install xserv
```

The user will be prompted for the information displayed in the password sheet.

This is a typical installation example on a SUN:

```
% ./install xserv
Do you want to install the license server for SEDIT? y
 ******* Beginning to install the license server "xserv"
Enter the HOSTNAME (sun1):
Enter the HOSTID (714021ca):
Enter the PASSWORD (): 27113-68498-24283-37166
Enter the SERIAL number (): 1202
Enter the PORT number (1112):
Enter the Expiration date (): none
Enter the VERSION (UNIX):
Enter the number of licenses (): 202
Enter the installation directory (/home/xed):
The server is configured with the following parameters:
HOSTNAME: sun1
HOSTID:
             714021ca
PASSWORD: 27113-68498-24283-37166
SERIAL:
            1202
PORT:
            1112
EXPIRE:
           none
VERSION:
           UNIX
LICENSES: 202
HOME:
            /home/xed
Do you want to modify these settings ? n
Do you want to save these settings ? y
The "/home/xed/seditusers" file has been saved.
* * *
       Warning: DO NOT install the license server for S/REXX
* * *
                if you do not have an S/REXX license.
Do you want to install the license server for S/REXX? no
Do you want to start the license server ? y
... Checking for "xserv" processes; wait.
.... Starting "xserv"
xserv: checking for other servers with serial number 1202.
xserv: please wait for 10 seconds.
xserv: process 832 listening
xserv: process 836 listening
.... "xserv" started.
2
```

3) Make xserver start the /home/xed/xserv program at initialization.

For a SUN workstation running SunOS, the following statement must be included in the /etc/rc.local file:

/home/xed/xserv /home/xed 30>/dev/console

On a Sun workstation running Solaris, create the following /etc/rc3.d/S99xserv file:

```
#!/bin/sh
if [ -f /home/xed/xserv ]; then
    echo "Starting SEDIT license server"
    /home/xed/xserv /home/xed 30
fi
```

For an IBM RS/6000, issue the following command:

% mkitab "xserv:2:once:/home/xed/xserv /home/xed 30 > /dev/console 2>&1"

On HP systems, add the following line in the /etc/inittab file:

serv:34:once:/home/xed/xserv /home/xed 30

Note that the installation directory must be passed to xserv. The second parameter passed to xserv (30 in these examples) is a delay value in seconds. If xserv is started when the system is booting up, some resources may not be available, and xserv may fail. Making xserv wait 30 seconds before start-up allows the system to stabilize.

4) Make the other network workstations that have the /home/xed xserver directory mounted use the following command:

% mount xserver:/home/xed /home/xed

Note: A UNIX license server cannot be used with WINDOWS clients.

Installing xserv on WINDOWS NT systems

To use xserv, the user must execute the following:

- 1) Decide which workstation to install **SEDIT** and/or **S/REXX** on.
- 2) Install **SEDIT** and/or **S/REXX** as described page 12 and page 19.
- 3) Select the Start -> Program -> SEDIT -> License Server Setup menu item.

The user will be prompted with the following screen:

C:\Program Files\SEDIT4\SetServ	×
******** SEDIT-S/REXX License Server Setup ********	
SetServ installs the license server for SEDIT and/or S/REXX.	
You need to install the license server only if you have a network password. In this case, your password sheet must display the 2 additional fields:	
licenses : xxxx serial number: xxxx	
To install a standalone password, use the "Register" facility	
"SetServ" is an S/REXX program.	
Install License Server Goto to "Register" Exit SetServ	

Click on the Install License Server button, to get:

C:\Program Files\SEDIT4\SetServ	×
******** SEDIT-S/REXX License Server Setup ********	
Enter SEDIT key Enter S/REXX key Start the server E	xit
Then, click on the Enter SEDIT key button, to get:

C:\Program Files\SEDIT4\SetServ			
4e \$	***** SEDIT License Server Settings ******		
Hostname:	nt		
CPU ID:	935773815		
Password:			
Serial:			
Port:	1112		
Expire:			
Options:			
Licenses:			
Home:	C:\Program Files\SEDIT		
Cancel	Register SEDIT		

Once the licensing information for **SEDIT** and/or **S/REXX** has been entered, use the Start the server button to start xserv. xserv will be installed as a **WINDOWS NT** service, and will restart automatically when the server reboots.

Notes: You do not need to reboot the station when installing the license server. WINDOWS 95 and WINDOWS 98 cannot be used as license servers. A WINDOWS license server cannot be used with UNIX clients.

Using an Alternate Server

The user may install **SEDIT** on an alternate server to be used, as a backup when the main server is inoperable. The installation is the same as for the main server, with only a different hostname and a different password. The serial number remains the same, which prevents xserv from being used on both servers at the same time.

The users will have to mount the **SEDIT** files from the alternate server instead of the main server.

Reserving Licenses on UNIX Systems

By adding the following statement in the seditusers or srexxusers file:

```
reserved jumbo :0.0
```

a license will be permanently allocated to the jumbo workstation, on the :0.0 display.

Reserving Licenses on WINDOWS systems

By adding the following statement in the seditusers or srexxusers file:

reserved jumbo

a license will be permanently allocated to the jumbo workstation.

Configuring a UNIX Heterogeneous Network

xserv is able to support a heterogeneous network. For example, to install xserv on a SUN, and grant IBM users access to the floating licenses installed on a SUN, use install on the SUN server as described above.

When **SEDIT** is installed, install creates a seditusers file. When **S/REXX** is installed, install creates a srexxusers file.

Copying seditusers and/or srexxusers in the IBM **SEDIT** installation directory will enable the use of the SUN xserv server by IBM users. install must not be used on the IBM installation directory

Setting the SEDIT Idle Time

The following statement in the seditusers file:

idle 4

will make any user not using **SEDIT** for more than 4 hours lose their license. The license will then be available to other users. Do not set an idle time for **S/REXX**, since an **S/REXX** script may run for an indefinite amount of time.

Setting the S/REXX Linger Time

The default value for the linger time is 5 minutes. To change the linger time, edit the srexxusers file, and add the following line:

linger 10

Then, restart xserv. The linger time will be now set to 10 minutes. The linger time allows a user to perform several edit and debug cycles without losing the license being used. It is not recommended to set the linger time to low.

Logging Activity on UNIX systems

The license server xserv saves a log of its activity when started with the following command:

```
% /home/xed/xserv -log /tmp/xserv.logfile /home/xed
```

Every time a user starts or ends using **SEDIT**, the logfile is updated, with information in the following format:

```
xserv at 94/09/20 14:11:20:granting SEDIT license to process 8509 :0@C
xserv at 94/09/20 14:13:37:freeing SEDIT license from process 8509 @ C
```

Every time xinfo is used, the logfile is updated with the following information:

```
xserv(SEDIT): 1/2 1 available
..... hostname = C pid(s) = 8517@:0
```

To display the information requested by xinfo in a window other than the window xserv was started from, type the following commands:

```
% xinfo
% cat /tmp/xserv.logfile
```

Usage Notes

Every time a user tries to start **SEDIT**, **SEDIT** asks the license server x serv for an authorization. If x serv has not exhausted all of the available licenses, it permits **SEDIT** to execute.

On **UNIX** systems, one **SEDIT** floating license allows any number of sessions on up to 4 displays connected to a given cpu. If the DISPLAY environment variable does not exist, and on **WINDOWS** systems, xserv takes in account the userid.

When a user terminates an S/REXX session, S/REXX sends a message to xserv to release the license. If that S/REXX session was the last session active on the given display, xserv

waits for a specified amount of time called the linger time. If no request is received during the linger time for that display, xserv will release the license.

When a user terminates an **SEDIT** session, **SEDIT** sends a message to xserv to release one license. If that **SEDIT** session was the last one active on the given display, xserv can now grant one more license to another display.

The user must not halt a workstation on which an **SEDIT** process is running. This would prevent **SEDIT** from sending a message to xserv to release the user's license, thus making that license permanently in use. Should this happen by inadvertent error, the user must restart the xserv process.

This is an example of how to kill and restart xserv on UNIX systems:

```
% cd /home/xed
% ./install xserv restart
Do you want to start the license server ? y
... Checking for "xserv" processes; wait.
The following "xserv" processes are running:
     860 ? S
                  0:00 /home/xed/xserv
     861 ? S 0:00 /home/xed/xserv
They must be killed before restarting the new license server.
Do you want to kill these processes? y
... killing 860
... killing 861
xserv: child died
.... All "xserv" processes killed; please wait for 10 seconds.
.... Starting "xserv"
xserv: checking for other servers with serial number 1001.
xserv: please wait for 10 seconds.
xserv: process 875 listening
xserv: process 879 listening
.... "xserv" started.
2
```

On **WINDOWS** systems, xserv is a service, and can be stopped and restarted using the service manager located on the control panel.

Using XINFO

xinfo is a utility that informs the user who is using **SEDIT**.

This is an example of xinfo usage on UNIX systems:

```
% cd /home/xed
% xinfo -s
C{xed}% xinfo -s
SEDIT licenses: 2/3 1 available
..... hostname = asterix pid(s) = 881 912
..... hostname = obelix pid(s) = 12323
```

This means that 2 **SEDIT** licenses are in use. There are two sessions on the asterix workstation, and one on the obelix workstation.

The -s option makes xinfo display the licensing information on the console. Used without option, xinfo opens a dialog box for display.

On **WINDOWS** systems, use the Start -> Program -> SEDIT -> License Server Query menu item.

Stopping the Server on UNIX Systems

xsdown is a utility that stops xserv.

This is an example of xsdown usage:

```
% cd /home/xed
% private/xsdown -s
xserv: exiting.
xserv: shutdown performed.
xserv: exiting with return code 0
C{xed}%
```

The -s option makes xsdown display the licensing information on the console. Used without option, xsdown opens a dialog box for display.

The private subdirectory is configured to be accessible only by the root account, in order to prevent other users from stopping the server.

Stopping the Server on WINDOWS Systems

xserv is a service, and can be stopped and restarted using the **WINDOWS NT** service manager located on the control panel.

INSTALLING S/REXX ON WINDOWS

SEDIT Compatibility issues

XEDIT Compatibility Issues

SEDIT has been designed as an **XEDIT** enhancement rather than an exact copy. These enhancements make some commands behave differently. Since experienced **XEDIT** users may find these enhancements confusing at first, **SEDIT** provides the MODE command to restore full **XEDIT** compatibility.

To configure **SEDIT** for full **XEDIT** compatibility, uncomment the following line in the /home/xed/profile.sedit (**UNIX**) or

c:\Program Files\SEDIT\profile.sedit (**WINDOWS**) file by removing the /* and */ comment characters:

```
/* 'set_xedit' */
```

set_xedit is the /home/xed/xmac/set_xedit.x or

c:\Program Files\SEDIT\set_xedit.x macro, which calls the **SEDIT** <u>MODE</u> command described on page 318.

To run **SEDIT** on ASCII terminals, uncomment the following statement:

```
/*
 * If you want SEDIT to leave when quitting the last edited file,
 * uncomment the following line
 */
/* 'mode autoexit on' */
```

Remove these /* and */ comment signs

See the <u>MODE</u> command on page 318 for more details.

To have the exact initial **XEDIT** key settings, the user may alternately start **SEDIT** by typing on **UNIX** systems:

/home/xed/xedit

On WINDOWS systems, click on the XEDIT - Exactly icon.

This starts **SEDIT** with the /home/xed/prof_xedit.sedit or c:\Program Files\SEDIT\prof_xedit.sedit profile.

The prof_xedit macro sets up **SEDIT** to be the closest to **XEDIT**, searches for a user ~/xeditprof.sedit file, and executes it when found.

Note: On **WINDOWS** systems, the HOME environment variable is usually not defined. In this case, the " $\sim/$ " or " \sim \" directory shortcut is translated into "C:\".

Note that on **UNIX** systems, using xedit rather than sedit to start **SEDIT** disables some useful features, such as the Cut and Paste key settings.

xedit will assign the following function keys:

•	F1	HELP	
•	F2	SOS LINEADD	adds a line at the cursor location.
•	F3	QUIT	exits the current file.
•	F4	SOS TABF	moves the cursor as if the NEXT_FIELD key had been depressed.
•	F5	XEDIT	switches to the next file in the ring.
•	F6	?	recalls and displays previously entered commands in a circular sequence.
•	F7	BACKWARD	
•	F8	FORWARD	
•	F9	=	repeats the last command without displaying it.
•	F10	RGTLEFT	scrolls to the right, and then to the left.
•	F11	SPLTJOIN	splits or joins lines.
•	F12	CURSOR HOME	switches the cursor position between the command and the data fields.

SEDIT Differences

The following **XEDIT** commands are not implemented in **SEDIT**:

- ALTER
- CMS (replaced with the SHELL and XSHELL commands)
- CP
- EXPAND
- JOIN
- LOAD
- LPREFIX
- MODIFY
- OVERLAY
- PARSE
- RECOVER (replaced with the more powerful undo/redo feature)
- RENUM
- SET: APL BRKKEY COLPTR ESCAPE ETARCBCH ETMODE FILLER FMODE FULLREAD IMAGE MASK MSGLINE MSGMOE NONDISP NULLS PAN PACK RANGE REMOTE SERIAL SIDCODE SPILL TERMINAL TEXT TOFEOF TRANSLAT
- SI (replaced with the auto-indentation feature: typing ENTER at the end of the line when no command is displayed in the command area adds a line, and places the cursor with respect to the previous line indentation)
- SOS: NULLS PFn POP PUSH
- SPLIT (SPLITJOIN is implemented)
- STATUS (Without operands, the SET command displays the function key setting in fullscreen mode)
- TRANSFER
- TYPE

ACTION	FULLREAD	SEQ8
APL	IMAGE	SERIAL
BASEFT	INPMODE	SIDCODE
BRKKEY	LIBNAME	SPILL
COLPTR	LIBTYPE	TERMINAL
EDIRNAME	LOCK	TEXT
EFMODE	MASK	TOF
EFNAME	MEMBER	TOPEOF
EFTYPE	NBSCOPE	TOL
EOF	NONDISP	TRANSLAT
FOI.	NTIT T C	
	NULLS	UNIQUEID
ESCAPE	PA	UNIQUEID UNTIL
ESCAPE ETARBCH	PA PACK	UNIQUEID UNTIL UPDATE
ESCAPE ETARBCH ETMODE	PA PACK PFn	UNTIL UPDATE VERSHIFT
ESCAPE ETARBCH ETMODE FILLER	NOLLS PA PACK PFn RANGE	UNTIL UPDATE VERSHIFT WINDOW

The following EXTRACT operands are not supported by **SEDIT**:

Compared to **XEDIT**, **SEDIT** features the following main differences:

- The profile.sedit macro is executed only at initialization. reprofile.sedit (or reprofile.ex) is executed every time a new file is loaded.
- Unlike **XEDIT**, in which the ALL command always refers to the complete file, the SEDIT ALL command applies only to the visible lines. This can be overridden by writing the following {install-dir}/xmac/all.sedit macro:

```
parse arg a
'command all'
'command all 'a
```

- The column targets do not support the | operand.
- COMPRESS is a completely different command, meant only for APL users.
- EMSG {message-id} is not supported. EMSG TEXT is supported.
- HEXTYPE creates a new file in the ring.
- INPUT needs an operand.
- POWERINPUT does not display a blank screen. Instead, when set to ON, the file is still displayed on the screen. When the cursor reaches the end of the MARGINS zone during typing, a new line is created starting with the unfinished word the user was typing on the previous line.
- Most of the **SEDIT** commands display their status when used without an operand, making it unnecessary to use the QUERY command. QUERY is nonetheless implemented in **SEDIT**.

• <u>SCHANGE</u> is a full command, to be entered with the following syntax:

```
sc/str1/str2/ arg1 arg2 arg3
```

The confirmation key (F12) can be changed with the <u>SCKEYS</u> command described on page 374.

- The SORT command does not accept a general target.
- The ? buffer is associated with the entire session instead of being associated with a file, and records only the strings entered in the command line.
- There is no End Of File prefix zone.

When the set_xedit macro is not used within the profile, **SEDIT** features many differences outlined in the description of the <u>MODE</u> command on page 318.

ISPF/PDF Compatibility Issues

SEDIT supports the following set of PDF commands:

BOUNDS	CREATE	LOCATE*
BUILTIN	DELETE*	RCHANGE
CANCEL*	EDIT	REPLACE*
CAPS	END	RESET
CHANGE *	EXCLUDE*	RFIND
COPY*	FIND*	

The commands marked with an * have the same name as **XEDIT** commands.

SEDIT uses the MODE COMMAND status to choose between the **ISPF/PDF** and the **XEDIT** behavior.

For example, when MODE COMMAND XEDIT is in effect:

- FIND calls the XEDIT FIND command.
- PDFFIND calls the PDF FIND command.

When MODE COMMAND PDF is in effect:

- FIND calls the PDF FIND command.
- XEDFIND calls the XEDIT FIND command.

To start **SEDIT** in **XEDIT** mode, use the following on **UNIX** systems:

{install-dir}/xed	starts SEDIT in the foreground.			
{install-dir}/sedit	starts SEDIT in the background.			
On WINDOWS systems, use the SE	DIT - XEDIT mode icon.			
To start SEDIT in PDF mode, use the following on UNIX systems:				
{install-dir}/pxed	starts SEDIT in the foreground.			
{install-dir}/psedit	starts SEDIT in the background.			

On **WINDOWS** systems, use the SEDIT - PDF mode icon.

These scripts or icons use the standard profile.sedit initialization macro, which assigns a complete set of function keys optimized for every type of supported keyboard. See the sections "Using function keys on xxxx keyboards" for more information.

To have PDF-style function key settings, the user may alternately start **SEDIT** by typing on **UNIX** systems:

{install-dir}/**pdf**

On WINDOWS systems, use the XEDIT - PDF Exactly icon.

The pdf script or icon starts **SEDIT** with the /home/xed/prof_pdf.sedit (or C:\Program Files\prof_pdf.sedit) profile. This macro sets up **SEDIT** to simulate PDF as closely as possible, searches for a user ~/pdfprof.sedit file, and executes it when found.

Note: On **WINDOWS** systems, the HOME environment variable is usually not defined. In this case, the " $\sim/$ " or " \sim \" directory shortcut is translated into "C:\".

Note that on **UNIX** systems, using pdf rather than psedit to start **SEDIT** disables some useful features, such as the Cut and Paste key settings.

pdf will assign the following function keys:

- F1 HELP
- F2 SCREEN 2 splits the screen.
- F3 END terminates the **SEDIT** session, after saving all the modified files.
- F4 SWITCH

switches between files.

- F5 RFIND
- F6 RCHANGE
- F7 BACKWARD
- F8 FORWARD
- F9 LEFT 40
- F10 RIGHT 40
- F11 SOS TABCMDF moves the cursor to the next screen.
- F12 SCREEN 1 unsplits the screen.

Usage Notes

Being derived from **XEDIT**, **SEDIT** brings to ISPF/PDF users some new, powerful features.

The Editing Ring

SEDIT is able to edit any number of files simultaneously. To edit another file, simply type edit filename.

To switch between files, the user may click with the left mouse button on the file name displayed at the top of the window. The SWITCH and ISWITCH commands described on page 412 and page 289 may also be used. Entering EDIT without an argument also switches between files, but without the priority ordering provided by the <u>SWITCH</u> command.

Note that EDIT is a synonym to the <u>XEDIT</u> command described on page 440.

The Current Line

Most **SEDIT** commands apply from the current line, which is the line displayed in red on a specific screen location. See the <u>CURLINE</u> command on page 207.

PDF commands do not use the current line concept. For example, FIND uses the argument keyword (FIRST, LAST, etc...) to determine the search starting point.

Free File Manipulation

Although the CREATE and REPLACE commands are implemented, it is easier to use the <u>SAVE</u> (page 370) and <u>FN</u> (page 271) commands to manage file names.

The <u>FLIST</u> utility described on page 453 is a powerful fullscreen file manager. Editing a new file within FLIST is as simple as clicking on its name, or placing the cursor on it and hitting the F4 key on ASCII terminals.

The PROFILE File

When **SEDIT** is invoked, it uses the profile.sedit REXX macro file as its initialization macro.

profile.sedit is first searched for in the current directory, then in the user's home directory, and if still not found, in the **SEDIT** installation directory.

The -p option described on page 46 may be used to start **SEDIT** with a different profile file.

See Customizing SEDIT (UNIX) on page 39 for more information.

When a reprofile macro has been loaded at initialization by using the <u>HASH</u> command described on page 281, reprofile will be used every time a new file is loaded.

This permits the reprofile macro to set up a different **SEDIT** environment for specific files.

reprofile may be either a reprofile.sedit REXX macro or a reprofile.ex external macro. See Using EXTERNAL Macro Commands (UNIX Only) on page 133 for more information.

Customizing SEDIT (UNIX)

Using XED, SEDIT, PXED, PSEDIT or KEDIT

When called by the XED, SEDIT, PXED, PSEDIT or KEDIT scripts, **SEDIT** uses the standard profile.sedit initialization macro, which assigns a complete set of function keys optimized for every type of supported keyboard. See "Using function keys on xxxx keyboards" section for more information.

To customize the **SEDIT** session, copy the {install-dir}/profile.sedit file into the user's home directory:

```
% cp /home/xed/profile.sedit ~
```

Any **SEDIT** command added in this file must be surrounded by single or double quotes. We recommend adding all user modifications at the end the file, after the comment line tagged "**START of user modification**". For example, to change the function key settings for F7 and F8:

```
/* START of user modification */
  'set f7 pgup'
  'set f8 pgdown'
/* END of user modification */
```

Using XEDIT or PDF

XEDIT and PDF use a special profile file which checks for a ~/xeditprof.sedit or ~/pdfprof.sedit file and executes it when found.

Therefore, to customize the **SEDIT** session, the user must create an xeditprof.sedit or pdfprof.sedit file into the user's home directory **from scratch**.

Any **SEDIT** command in this file must be surrounded by single or double quotes.

For example, to change the function key settings for F7 and F8:

```
'set f7 rchange'
'set f8 rfind'
```

Customizing SEDIT (WINDOWS)

Using the XEDIT-MODE, PDF-MODE and KEDIT-MODE Icons

When called by the XEDIT-MODE, PDF-MODE or KEDIT-MODE icons, **SEDIT** uses the standard profile.sedit initialization macro, which assigns a complete set of function keys.

See Using Function Keys on WINDOWS on page 80 for more information.

To customize the **SEDIT** session, the user must copy the {install-dir}\profile.sedit file into the C:\ directory.

Any **SEDIT** command added in this file must be surrounded by single or double quotes. We recommend adding all user modifications at the end the file, after the comment line tagged "**START of user modification**". For example, to change the function key settings for F7 and F8:

```
/* START of user modification */
  'set f7 pgup'
  'set f8 pgdown'
/* END of user modification */
```

Using the XEDIT-EXACTLY or PDF-EXACTLY Icons

XEDIT and PDF use a special profile file which checks for a C:\xeditprof.sedit or C:\pdfprof.sedit file and executes it when found.

Therefore, to customize the **SEDIT** session, the user must create an xeditprof.sedit or pdfprof.sedit file into the C:\ directory **from scratch**:

Any **SEDIT** command in this file must be surrounded by single or double quotes. For example, to change the function key settings for F7 and F8:

```
'set f7 rchange'
'set f8 rfind'
```

SEDIT User's Guide

The 3270 Screen Interface

SEDIT has a user interface which emulates an IBM¹ 3270 terminal device. This means that data is displayed using fields in a strictly WYSIWYG manner.

There are absolutely no invisible control characters on the screen. When the user sees a space, it is an actual space, and the user can overtype it without entering spaces before it, as required with most **UNIX** editors.

A field is an area of the screen on which alphanumeric data is written by the editor, and on which either data or commands may be written. Some fields are input fields, which allow data input, and others are output fields where data entry is prohibited. If data entry is attempted on an output field the screen will flash.

There are a few keys which make it possible to move the cursor in a way similar to that of a 3270 device:

•	NEXT FIELD	Key TAB will move the cursor to the next input field. If there is no field at the right in the same line, the cursor will be moved to the first input field on the line below. Note: Type Control-TAB to enter a tabulation, or Control-t when running in ASCII terminal mode.
•	PREV FIELD	The key Shift-TAB will move the cursor to the previous input field. If there is no field at the left on the same line, the cursor will be moved to the last input field on the line before. On DECstation keyboards, this function is assigned to the SELECT (R6) key. On HP keyboards, it is assigned to the Numerical Pad TAB key.
•	DOWN FIELD	On Sun keyboards, the AltGraph key will move the cursor to the first input field on the line below. On DECstation keyboards, it is assigned to the PF4 (L4) key. On HP keyboards, it is assigned to the Right Extended Char key. On other keyboards, this function is assigned to the right Control key.
•	UP FIELD	On Sun type 4 keyboards, the key Line feed will move the cursor to the first input field on the upper line. On DECstation keyboards, it is assigned to the PF3 (L3) key. On HP keyboards, it is assigned to the Select key. On other keyboards, this function is assigned to the right Alt key.

^{1.} IBM is a registered trademark of International Business Machines, Inc.

HOME On Sun, IBM and SiliconGraphics keyboards, the Home key will move the cursor to the first input field on the screen. On HP keyboards, it is assigned to the key labeled with a w.. This key is defined as the R7 key.
 IHOME On Sun, IBM and SiliconGraphics keyboards, the key End key will move the cursor to the last input field on the screen. On HP keyboards, it is assigned to the Shift-R7 key.

The user can also move the cursor using the CURSOR KEYS or using the third mouse button.

The following keys are used to manage data on a field:

•	INS	On Sun type 3 keyboards, the R11 key will toggle between INSERT and REPLACE mode. On HP keyboards, INS is assigned to the Ins Char key. On other keyboards, this function is assigned to the Insert key.
•	CAPS	On Sun type 3 keyboards, the R13 key will toggle between lower case and caps-lock upper case mode. Unlike the standard CAPS Sun Key, <u>every</u> key will be treated as shifted, not only alphabetical keys. On other keyboards, this function is assigned to the Caps Lock key. Note that function keys are not modified by the caps-lock status.
•	APL	On Sun type 3 keyboards, the R15 key will toggle between STANDARD and APL mode. APL mode is meaningless unless using an APL font.
•	ERASE EOF	On Sun keyboards, the key L3 (usually labelled Props) will clear the field starting at the cursor location. When shifted, it will erase the entire field, and place the cursor at the beginning of the field. On HP keyboards, this function is assigned to the Reset key. On IBM and SiliconGraphics keyboards, this function is assigned to the Escape key. Control-Escape will erase the entire field. On WINDOWS systems, use Escape and Shift-Escape. On DECstation keyboards, use the F13 key.
•	DELETE	Key Delete (Remove on DECstations and Delete Char on HP keyboards) will erase the character at the cursor location and shift to the left all the characters remaining on the field to the right of the cursor.
•	BACKSPACE	Key Back Space will erase the character at the left of the cursor location. If the user is in INSERT mode, SEDIT will shift the characters that remain to the right of the cursor to the left.

Note: Most **UNIX** editors, such as **VI**, use tabulations to indent text. **SEDIT** does not do this because using such control characters prevents using two dimensional features such as rectangular selection.

So, if the user wants to edit files previously created with tabulations, the user may use the TABEXP command to replace tabulations with spaces. The user may simulate the standard **UNIX** tabulations using the TABSET command.

The following key is also useful:

• **PRINTSCREEN** On Sun keyboards, the Meta-L3 key will print a screen copy. The meta key is labelled left or right on Sun type 3 keyboards, and \Diamond on the type 4 and 5 keyboards.

On IBM and SiliconGraphics keyboards, the user must use the Shift-Control-Escape key.

On HP keyboards, the meta key is the left Extended Char key, and the user must use the Meta-Reset key.

On DECstation keyboards, the meta key is the Compose key, and the user must use the Meta-F13 key.

Getting Started (UNIX)

Starting SEDIT Within DYALOG APL

Under APL, the user must first copy the functions included in the /home/xed/XF workspace, and then issue the command "XF'TEST'" to edit the APL object TEST. This object may be any kind of APL object, but \Box OR object representation.

In case of a nested array, or of an object with rank greater than two, the user will see a two dimensional display representation, but the user will not be allowed to issue the FILE command to fix it in the active workspace.

The function XF maintains the last modification time in a variable named TSOBJ, and **SEDIT** displays this information in the first screen line.

Starting SEDIT Under UNIX

To start **SEDIT**, use one of the following commands:

xed	starts SEDIT in the foreground in XEDIT mode
sedit	starts SEDIT in the background in XEDIT mode
pxed	starts SEDIT in the foreground in PDF mode
psedit	starts SEDIT in the background in PDF mode
xedit	starts SEDIT in full XEDIT compatible mode
pdf	starts SEDIT in full PDF compatible mode
kedit	starts SEDIT with a KEDIT-like keyboard layout. See
	page 87.

After installing **SEDIT**, the user may type, for example:

% sedit test.c

Assuming file test.c exists, the screen will look like this:

/usr/m1/test.c	Len:5	mod:
test.c		
00001 /*		
00002 * This is a sample file for SEDIT		
00003 *		
00004 */		
====> _		
1:Q 2:E 3:Save 4:Sp 5:X 6:cu 7:U 8:D 9:? R1:h R3	3:=g S-R2:to	op S-R3:bot

Note: **SEDIT** looks for this test.c file in the current directory first. If it does not exist in this directory, **SEDIT** searches in the directories described either in the environment variable XPATH (if there is one) or in PATH, or in directories accessed by the ACCESS command. If the file is not found, **SEDIT** starts with an empty file.

The UNIX Command Line Options

The user can pass to **SEDIT** the following options:

-Ww or -w -Wh or -h -Wf or -f -dy_font -display -Wp or -p -WP or -j -xrm	vidth height font position lcon_position	columns lines fontname fontname display x y x y x y '"resource	the number of columns. the number of lines. the font to be used at initialization. the font to be used by dialog boxes. the X11 display to be used. the SEDIT window location. the SEDIT icon location.
			overrides a specific X11 resource when running in the MOTIF mode. See Setting the MOTIF Resources on page 7 for more details about X11 resources. resource must be enclosed within ' " and " '.
-p or -P -np		filename	the profile file to be read at initialization, profile.sedit by default. Note that filename is executed before loading any file. no profile file will be read at initialization
-C		' "cmd" '	executes the SEDIT command cmd after initialization. cmd must be enclosed within ' " and " '.
-batch			starts SEDIT in batch mode. See Using the BATCH Option on page 144 for more information.
-filec		filename	starts SEDIT in batch mode, loads first the various files passed as parameters, and executes the filename macro. See Using the BATCH Option on page 144 for more information.
Example:	xed -c '"f * This statement sta editor upon every	c"' foo.c rts editing the *.c file.	file foo.c, and then calls the directory

If the sedit script is used to start **SEDIT** in the background, the user can pass to it the same options.

Getting Started (WINDOWS)

Starting SEDIT

setup creates the following icons:



SEDIT - XEDIT Mode

SEDIT starts with XEDIT defaults. The keyboard layout is described on page 80.

SEDIT will use the C: $\Program Files\\SEDIT\\profile.sedit file as initialization profile.$

SEDIT - PDF Mode

SEDIT starts with PDF defaults. The keyboard layout is also described on page 80.

SEDIT will use the C:\Program Files\SEDIT\profile.sedit file as initialization profile.

SEDIT - XEDIT Exactly

SEDIT starts with XEDIT defaults. The keyboard layout is similar to XEDIT, and is described in the section XEDIT Compatibility Issues on page 31.

SEDIT will use the C:\Program Files\SEDIT\prof_xedit.sedit file as initialization profile.

SEDIT - PDF Exactly

SEDIT starts with PDF defaults. The keyboard layout is similar to PDF, and is described in the section ISPF/PDF Compatibility Issues on page 36.

SEDIT will use the C:\Program Files\SEDIT\prof_pdf.sedit file as initialization profile.

SEDIT - KEDIT Mode

SEDIT starts with KEDIT-like keyboard defaults. The keyboard layout is described on page 87.

SEDIT will use the C:\Program Files\SEDIT\profile.sedit file as initialization profile.

After starting **SEDIT**, the user may type, for example:

====> xed test.c

Assuming file test.c exists, the screen will look like this:

```
C:\Program Files\SEDIT\demo\demo1\test.c Len:5 mod:

00001 /*

00002 * This is a sample file for SEDIT

00003 *

00004 */

1:Q 2:E 3:Save 4:Sp 5:X 6:cu 7:U 8:D 9:? R1:h R3:=g S-R2:top S-R3:bot
```

Note: xed looks for this test.c file in the current directory first. If it does not exist, **SEDIT** searches in the directories accessed by the ACCESS command. If the file is not found, xed starts with an empty file.

The WINDOWS Command Line Options

The user can pass to **SEDIT** the following options:

-Ww or -w -Wh or -h -Wp or -p -p or -P	vidth neight position	columns lines x y filename	<pre>the number of columns. the number of lines. the SEDIT window location. the profile file to be read at initialization, profile.sedit by default. Note that filename is executed before loading any file.</pre>
-np			no profile file will be read at initialization.
-C		cmd	executes the SEDIT command cmd after initialization. cmd must be enclosed within quotes when containing blanks.
-noauto			SEDIT normally records the font in use and its window location when exiting, and uses the recorded settings when started again. With the -noauto option, SEDIT does not use the recorded settings when starting, and does not save new ones when exiting.
-batch			starts SEDIT in batch mode. See Using the BATCH Option on page 144 for more information.
-filec		filename	starts SEDIT in batch mode, loads first the various files passed as parameters, and executes the filename macro. See Using the BATCH Option on page 144 for more information.
Example:	xed -c 'f *	c' foo.c	file for a read then calls the directory

This statement starts editing the file foo.c, and then calls the directory editor upon every *.c file.

Using a UNIX Keyboard Layout

To start **SEDIT** with a **UNIX** like keyboard layout, edit the profile in use as described on page 47 and uncomment the following line by removing the /* and */ comment characters:

/* 'set_unix' */

set_unix is the C:\Program Files\SEDIT\xmac\set_unix.x macro. The
keyboard layout will be modified in the following way:

KEY	WINDOWS SETTINGS	UNIX SETTINGS
F2	adds a line below the cursor location	removes the selected characters
F3	saves the file	copies the selection into the clipboard
F4	splits or joins the current line	pastes from the clipboard
^a	selects all	adds a line below the cursor location
^A		selects all
^c	copies the selection into the clipboard	compiles the current file
^C	compiles the current file	
^g		compiles in debug mode
^G	compiles in debug mode	
^ <u>s</u>	opens the SAVE AS dialog box	splits or joins the current line
^X	removes the selected characters	starts editing the file selected with the mouse
Mouse Mode	Windows (see page 127)	Open Look (see page 123)

Exploring the SEDIT SCREEN

The screen is divided into 6 major types of fields:

1) The **STATUS FIELD**:

/usr/m1/test.c	Len:5	mod:	
----------------	-------	------	--

indicates the full name of the file being edited, its length and shows an "*" behind "mod:" when the file has been modified but not yet saved.

2) The **MESSAGE FIELD**:

test.c

shows either the names of different files being edited at the same time or an error message when necessary.

To switch from one file to another, click the filename in this field with the left or center mouse button (M1/M2).

3) The **PREFIX FIELDS**:

00005

give the number of each line displayed.

The user can type commands in these fields. The commands will affect only the corresponding line.

4) The **DATA FIELDS**:

This line is line 5 of this file

The user can modify the data by typing over it.

If the length of this field is not sufficient for the data, place the cursor on it and press the F2 (extend feature) key.

5) The **DIRECT INPUT FIELDS**:

These are the fields between the last data field and the COMMAND FIELD, and between the message field and the first data field.

The user can type in data directly. When the user validates the data entered by pressing Return, new lines will be added to the file.

6) The **COMMAND FIELD**:

====>

is used to pass commands to the editor.

Commands generally work from the CURRENT LINE towards the end of the file.

The CURRENT LINE is the line which is displayed on the 8th physical line of the screen. If a color display is used, the current line will appear in red and the corresponding prefix field appears bold-faced.

Note that the physical location of the CURRENT LINE may be changed with the "CURL N" command.

The convention for command description is the following:

Add $\{N\}$ means that the command ADD can be shortened by "A" or "AD", and that the numerical parameter "N" may be omitted.

Note that any command may be entered in upper or lower case letters.

The user may also pass commands using buttons, or OpenLook style walking menus. See the commands <u>BUTTON</u> and <u>MENU</u> for more information.

Moving Through a File

1) Entering commands

The user can go to line N by typing N followed by "Return" in the COMMAND FIELD.

The user can scroll up N lines by typing "Up $\{N\}$ ".

The user can scroll down N lines by typing "Down $\{N\}$ ".

"TOP" moves the current line to the top of the file.

- "Bottom" moves the current line to the bottom of the file.
- 2) Using the function keys

A 3270 keyboard may use up to 24 functions named PF1 to PF24.

PF1 to PF12 are mapped on keys F1 to F12.

On old Sun keyboards, PF10 to PF12 are mapped on keys R1 to R3.

PF13 to PF24 are mapped on the same keys, modified by the shift key.

Key F7 scrolls up one page: the current line becomes the last line displayed.

Key F8 scrolls down one page: the last line displayed becomes the current line.

Keys PF19 (Shift-F7) and PF20 (Shift-F8) scrolls the whole screen: the last line displayed becomes first, and vice versa.

3) Using the mouse in OpenLook mode (the default mode on **UNIX** systems)

When the arrow is in a PREFIX FIELD, M1 and M2 (Left and Middle) keys work like F7 and F8.

"Control-M1" will move the current line to the top of the file.

"Control-M2" will move the current line to the bottom of the file.

When the arrow is in the first screen line, M1 and M2 will scroll UP and DOWN 4 lines on the screen. When shifted, they will scroll 8 lines. When holding the meta key, they will scroll one page.

M3 (the third mouse button) is usually used to move the cursor, but when shifted, the line on which it is used will become the current line.

Note that the same can be achieved by typing "/" and "Return" in a PREFIX FIELD.

4) Using the mouse in **WINDOWS** mode

M1 is the left mouse button, and M3 is the right mouse button. When using a 3 button mouse, M2 is the middle mouse button.

When the arrow is in a PREFIX FIELD, "Control-M1" will move the current line to the top of the file.

"Control-M2" will move the current line to the bottom of the file.

M3 is usually used to display a menu, but when shifted, the line on which it is used will become the current line.

Note that the same can be achieved by typing "/" and "Return" in a PREFIX FIELD.

Editing Multiple Files

The basic command for editing a file is "xed unixname".

If there is no directory indicator such as "/", "./", "~/" or "\" on **WINDOWS**, the current directory will be searched first. If not found, it will be looked for in the directories described by the environment variable XPATH, or PATH.

The user can change the current directory using the CD command, or add a new directory in the path by using the ACCESS command.

There are short-cuts to make editing another file easier. When editing a certain type of file, for example "test.c", and the user wants to edit another file of the same type, for example "test1.c", the user may type "x test1" instead of "xed test1.c".

There are also several abbreviations for the most frequent unix types of files:

```
"xc test" <===> "xed test.c"
"xf test" <===> "xed test.f"
"xp test" <===> "xed test.p"
"xh test" <===> "xed test.h"
"xt test" <===> "xed test.txt"
"xm test" <===> "xed test.mem"
"xx test" <===> "xed test.x"
"xi" <===> "xed test.x"
"xi <===> "xed test.ex"
"xs test" <===> "xed test.ex"
```

Under APL, you edit in priority another APL object, but nothing prevents you from editing a **UNIX** file either by specifying a path with a "/", " \sim /" or "/" starting filename, or using one of the above x{?} abbreviations.

Assume that "x test1" or "xc test1" is typed. The screen will look like this:

```
/usr/m1/test1.c Len:5 mod:

test.c test1.c

00001 /*
00002 * This is a second sample file for SEDIT
00003 *
00004 *
00005 main()
00006 /* This file is 6 lines long */

====> _

1:Q 2:E 3:Save 4:Sp 5:X 6:cu 7:U 8:D 9:? R1:h R3:=g S-R2:top S-R3:bot
```

The message field indicates that you are editing two files, named "test.c" and "test1.c".

The user can switch between files either by using F5 or by clicking with the left or middle mouse button on the name of the file.

Using Function Keys on SUN Keyboards

Most of the SUN function keys are dedicated to execute commands.

The Right function keys only available on Sun type 3 and type 4 keyboards are mapped in the following way on type 5 keyboards:

- R1 Print Screen
- R2 Scroll Lock
- R3 Pause
- R7 Home
- R9 Page Up
- R13 End
- R15 Page Down

See SUN Type 5 Keyboard Layout on page 664 for more details about the right function keys.

The Left function keys are the following keys:

•	L1	Stop
•	L2	Again
•	L3	Props
•	L4	Undo
•	L5	Front
•	L6	Copy
•	L7	Open
•	L8	Paste
•	L9	Find
•	L10	Cut
•	L11	Help

The principal key definitions are referenced on the last line of the window.

L2	MATCH finds a matching delimiter. { [(< matches }]) >.
L3	Erase end of field clears the field starting at the cursor location.
Shift-L3	Erase all field clears the entire field, and places the cursor at the beginning of the field.
L4	UNDO undoes the last action.
Shift-L4	REDO undoes the last undo.
L6	S_COPY copies the selection into the internal buffer named shelf.
L8	S_PASTE pastes the shelf contents at the cursor location.

Control-L8	S_PASTE PRIMARY pastes the selection content at the cursor location. May be used to retrieve the selection from another window.
Shift-L8	S_PASTE OVERLAY overlays the shelf contents at the cursor location.
L9	S_FIND searches a string matching the current selection.
L10	S_CUT cuts the current selection.
F1	QUIT is used to abandon the file without saving it. If the file has been modified during the session, the user will be prompted to confirm the key to quit.
Control-F1	FLQUIT will do the same as F1, and then switch to the directory editor.
F2	C_EXT is used to extend the length of the field selected by the cursor.
F3	SAVE transforms the unchanged source file into a backup file by appending a "%" to its name, and creates a new file with the original name from the edited memory image, without exiting it.
Shift-F3	FILE saves the file and then presents a new screen.
Control-F3	FLFILE will do the same as Shift-F3 and then switch to the directory editor.
F4	C_SPLIT when the cursor is before the last non-blank character, the line will be split, with indentation if the auto-indent feature is ON (See command "AUTOI on off"). When the cursor is after the last non-blank character, the next line will be joined to that one.
F5	SWITCH moves from one file to another in a circular sequence.
Shift-F5	ISWITCH does the same as F5 in a reversed sequence.
F6	C_ENDLINE if the cursor is in a DATA FIELD, it will be moved to the end of that field.
Shift-F6	C_ENDCURL moves the cursor to the end of the CURRENT LINE FIELD.

F7	BACKWARD scrolls backward one page.
Meta-F7	S_LSHIFT the text from the column where the selection starts will be moved to the left.
F8	FORWARD scrolls forward one page.
Meta-F8	S_RSHIFT the text from the column where the selection starts will be moved to the right.
F9	? displays the previous commands executed in the COMMAND FIELD. The user can edit and re-execute them.
Shift-F9	?I does the same as F9 in a reversed order.
Control-F9	XSHOWHISTORY displays the commands memorized in the history buffer in fullscreen mode.
Meta-F9	SHOWHISTORY displays the commands memorized in the history buffer.
F10	CURSOR HOME if the cursor is in a DATA FIELD, it will be moved to the COMMAND FIELD. A subsequent action will restore its previous location.
F12	=
	repeats the last command without displaying it.
R1	COMPLETE allows command line filename completion.
Shift-R1	COMPLETE REVERSE allows command line filename completion in reverse order.
S-R2 or S-F11	TOP moves the current line to the beginning of the file.
S-R3 or S-F12	BOT moves the current line to the end of the file.
Control-R5	filter <pre>\$xhome/filters/\$arch/toggle_comment comments in or out the selected or cursor lines.</pre>
Control-Left-Arrow	moves the cursor to the previous word.
Control-Right-Arrow	moves the cursor to the next word.
Control-1	MACRO set_bookmark 1 sets the bookmark number 1 at the cursor location.

Control-2	MACRO set_bookmark 2 sets the bookmark number 2 at the cursor location.
Control-3	MACRO set_bookmark 3 sets the bookmark number 3 at the cursor location.
Control-4	MACRO set_bookmark 4 sets the bookmark number 4 at the cursor location.
Control-5	MACRO set_bookmark 5 sets the bookmark number 4 at the cursor location.
Control-6	MACRO goto_bookmark 1 goes to the bookmark number 1.
Control-7	MACRO goto_bookmark 2 goes to the bookmark number 2.
Control-8	MACRO goto_bookmark 3 goes to the bookmark number 3.
Control-9	MACRO goto_bookmark 4 goes to the bookmark number 4.
Control-0	MACRO goto_bookmark 5 goes to the bookmark number 5.
Meta-0	MACRO rm_bookmarks removes all the bookmarks on the current file.
Control-a	C_LINEADD adds a line below the cursor location.
Control-c	MACRO smart_comp \$name 0 compiles the current file, splits the screen, shows the error messages and sets the cursor on the first error line. See the compile command on page 190 for more details.
Control-C	MACRO smart_comp \$name 1 compiles a file in the background.
Control-d	C_LINEDEL deletes the line at the cursor location.
Control-f	equivalent to the "f" command (see Directory editor section).
Control-g	same as Control-c, but in debug mode.
Control-G	same as Control-C, but in debug mode.
Control-h	C_SCRH splits the screen horizontally at the cursor location.
Control-l	S_LOWER translates the characters selected with the mouse into lowercase.
Control-n	FLIST \$fn * calls the directory editor showing all the files with the same

	filename as the current file.
Control-p	SHELL lpr -h \$name & prints the current file.
Control-r	TREE calls the tree editor.
Control-u	S_UPPER translates the characters selected with the mouse into uppercase.
Control-U	S_UPPER WORD translates the first letter of each selected word with the mouse into uppercase.
Control-v	C_SCRV splits the screen vertically at the cursor location.
Control-w	C_SCRJ restarts with an unsplit screen.
Control-x	S_XED starts editing a file selected with the mouse or at the cursor location, after expanding the selection to a word and appending the currently edited filetype.
Control-z	LEFT 0 resets the original VERIFY setting, displaying all the columns.
Control	NEXTERROR after a compilation is executed with the Control-c command, the cursor moves to the next error.
Control-=	C_DUP duplicates the line at the cursor location.
Shift+Control-a	MACRO adjust_cursor sets the start of the line at the cursor position.
Shift+Control-c	CENTER centers the line at the cursor location.
Shift+Control-f	FLOW formats the paragraph at the cursor location.
Shift+Control-o	S_PASTE OVERLAY SHELF overlays the contents of the clipboard at the cursor location.
Shift+Control-w	MACRO del_word deletes the word at the cursor location.
Meta-+	MACRO toggle_display toggles between viewing the entire file and viewing the selected lines.
Meta-=	MACRO dup_line duplicates the cursor or the current line.
Meta-u	S_SET OFF cancels the current selection.
--------	--
Meta-x	S_XED starts editing a file selected with the mouse or at the cursor location, after expanding the selection to a word and appending the currently edited filetype.

Using Function Keys on IBM, SiliconGraphics and PCs Keyboards

Most of the function keys are dedicated to execute commands.

The Right function keys (only available on Sun keyboards) are mapped in the following way:

•	R1	Print Screen
•	R2	Scroll Lock
•	R3	Pause
•	R4	Insert
•	R5	Home
•	R6	Page Up
•	R7	End
•	R9	Page Down

With the following physical layout:



Escape	Erase end of field clears the field starting at the cursor location.
Control-Escape	Erase all field clears the entire field, and places the cursor at the beginning of the field.
F1	S_FIND searches a string matching the current selection.
F2	S_CUT cuts the current selection.
F3	S_COPY copies the selection into the internal buffer named shelf.
F4	S_PASTE pastes the shelf contents at the cursor location.

Control-F4	S_PASTE PRIMARY pastes the selection content at the cursor location. May be used to retrieve the selection from another window.
Shift-F4	S_PASTE OVERLAY overlays the shelf contents at the cursor location.
F5	SWITCH moves from one file to another in a circular sequence.
Shift-F5	ISWITCH does the same as F5 in a reversed sequence.
F6	C_ENDLINE if the cursor is in a DATA FIELD it will be moved to the end of that field.
Shift-F6	C_ENDCURL moves the cursor to the end of the CURRENT LINE FIELD.
F7	BACKWARD scrolls backward one page.
Meta-F7	S_LSHIFT the text from the column where the selection starts will be moved to the left.
F8	FORWARD scrolls forward one page.
Meta-F8	S_RSHIFT the text from the column where the selection starts will be moved to the right.
F9	? displays the previous commands executed in the COMMAND FIELD. The user can edit and re-execute them.
Shift-F9	?I does the same as F9 in a reversed order.
Control-F9	XSHOWHISTORY displays the commands memorized in the history buffer in fullscreen mode.
Meta-F9	SHOWHISTORY displays the commands memorized in the history buffer.
F10	CURSOR HOME if the cursor is in a DATA FIELD, it will be moved to the COMMAND FIELD. A subsequent action will restore its previous location.
F11	UNDO undoes the last action.
Shift-F11	REDO undoes the last undo.

F12	= repeats the last command without displaying it.
R1	QUIT is used to abandon the file without saving it. If the file has been modified during the session, the user will be prompted to confirm the key to quit.
Control-R1	FLQUIT will do the same as R1, and then switch to the directory editor.
R2	COMPLETE allows command line filename completion.
Shift-R2	COMPLETE REVERSE allows command line filename completion in reverse order.
R3	SAVE ¹ transforms the unchanged source file into a backup file by appending a "%" to its name, and creates a new file with the original name from the edited memory image, without exiting it.
Shift-R3	FILE saves the file and then presents a new screen.
Shift-R6	TOP moves the current line to the beginning of the file.
Shift-R9	BOT moves the current line to the end of the file.
Control-R3	FLFILE will do the same as Shift-R3 and then switch to the directory editor.
Control-PageUp	filter <pre>\$xhome/filters/\$arch/toggle_comment comments in or out the selected or cursor lines.</pre>
Control-Left-Arrow	moves the cursor to the previous word.
Control-Right-Arrow	moves the cursor to the next word.
Control-1	MACRO set_bookmark 1 sets the bookmark number 1 at the cursor location.
Control-2	MACRO set_bookmark 2 sets the bookmark number 2 at the cursor location.
Control-3	MACRO set_bookmark 3 sets the bookmark number 3 at the cursor location.
Control-4	MACRO set_bookmark 4 sets the bookmark number 4 at the cursor location.

^{1.} On UNIXWARE PCs, the R3 key is not available. The SAVE function is assigned to the R2 key.

Control-5	MACRO set_bookmark 5 sets the bookmark number 4 at the cursor location.
Control-6	MACRO goto_bookmark 1 goes to the bookmark number 1.
Control-7	MACRO goto_bookmark 2 goes to the bookmark number 2.
Control-8	MACRO goto_bookmark 3 goes to the bookmark number 3.
Control-9	MACRO goto_bookmark 4 goes to the bookmark number 4.
Control-0	MACRO goto_bookmark 5 goes to the bookmark number 5.
Meta-0	MACRO rm_bookmarks removes all the bookmarks on the current file.
Control-a	C_LINEAdd adds a line below the cursor location.
Control-c	MACRO smart_comp \$name 0 compiles the current file, splits the screen, shows the error messages and sets the cursor on the first error line. See the compile command on page 190 for more details.
Control-C	MACRO smart_comp \$name 1 compiles a file in the background.
Control-d	C_LINEDEL deletes the line at the cursor location.
Control-f	equivalent to the "f" command (see Directory editor section).
Control-g	same as Control-c, but in debug mode.
Control-G	same as Control-C, but in debug mode.
Control-h	C_SCRH splits the screen horizontally at the cursor location.
Control-l	S_Lower translates the characters selected with the mouse into lowercase.
Control-m	MATCH finds a matching delimiter. { [(< matches }]) >.
Control-n	f \$fn * calls the directory editor showing all the files with the same filename as the current file.
Control-p	SHELL lpr -h \$name & prints the current file.

Control-r	TREE calls the tree editor.
Control-s	C_SPLIT when the cursor is before the last non-blank character, the line will be split, with indentation if the auto-indent feature is ON (See command "AUTOI on off"). When the cursor is after the last non-blank character, the next line will be joined to that one.
Control-u	S_UPPER translates the characters selected with the mouse into uppercase.
Control-U	S_UPPER WORD translates the first letter of each selected word with the mouse into uppercase.
Control-v	C_SCRV splits the screen vertically at the cursor location.
Control-w	C_SCRJ restarts with an unsplit screen.
Control-x	S_XED starts editing a file selected with the mouse, after expanding the selection to a word and appending the currently edited filetype.
Control-z	LEFT 0 resets the original verify setting, displaying all the columns.
Control	NEXTERROR after a compilation is executed with the Control-c command, the cursor moves to the next error.
Control-=	C_DUP duplicates the line at the cursor location.
Shift+Control-a	MACRO adjust_cursor sets the start of the line at the cursor position.
Shift+Control-c	CENTER centers the line at the cursor location.
Shift+Control-f	FLOW formats the paragraph at the cursor location.
Shift+Control-o	S_PASTE OVERLAY SHELF overlays the contents of the clipboard at the cursor location.
Shift+Control-w	MACRO del_word deletes the word at the cursor location.
Meta-+	MACRO toggle_display toggles between viewing the entire file and viewing the selected lines.

Meta-=	MACRO dup_line duplicates the cursor or the current line.
Meta-u	S_SET OFF cancels the current selection.
Meta-x	S_XED starts editing a file selected with the mouse or at the cursor location, after expanding the selection to a word and appending the currently edited filetype.

Using Function Keys on DEC/COMPAQ/HP TRUE64 station Keyboards

If the user is using a PC style keyboard, the user must insert in the *.sedit files described on page 6 the set_alpha statement. In this case, the function keys will match the IBM layout described on page 62.

Most of the function keys are dedicated to execute commands.

The Right and Left function keys (only available on Sun keyboards) are mapped in the following way:

- R4 Find
- R5 Insert Here
- R6 Select
- R7 Previous screen
- R9 Next screen
- L1 PF1
- L2 PF2
- L3 PF3
- L4 PF4

Using the following physical layout:



F1	S_FIND searches a string matching the current selection.
F2	S_CUT cuts the current selection.
F3	S_COPY copies the selection into the internal buffer named shelf.
F4	S_PASTE pastes the shelf contents at the cursor location.
Control-F4	S_PASTE PRIMARY pastes the selection content at the cursor location. May be used to retrieve the selection from another window.

Shift-F4	S_PASTE OVERLAY overlays the shelf contents at the cursor location.
F5	SWITCH moves from one file to another in a circular sequence.
Shift-F5	ISWITCH does the same as F5 in a reversed sequence.
F6	C_ENDLINE if the cursor is in a DATA FIELD it will be moved to the end of that field.
Shift-F6	C_ENDCURL moves the cursor to the end of the CURRENT LINE FIELD.
F7	BACKWARD scrolls backward one page.
Meta-F7	S_LSHIFT the text from the column where the selection starts will be moved to the left.
F8	FORWARD scrolls forward one page.
Meta-F8	S_RSHIFT the text from the column where the selection starts will be moved to the right.
F9	? displays the previous commands executed in the COMMAND FIELD. The user can edit and re-execute them.
Shift-F9	?I does the same as F9 as above in a reversed order.
Control-F9	XSHOWHISTORY displays the commands memorized in the history buffer in fullscreen mode.
Meta-F9	SHOWHISTORY displays the commands memorized in the history buffer.
F10	CURSOR HOME if the cursor is in a DATA FIELD, it will be moved to the COMMAND FIELD. A subsequent action will restore its previous location.
F11	UNDO undoes the last action.
Shift-F11	REDO undoes the last undo.
F12	= repeats the last command without displaying it.

F13	Erase end of field clears the field starting at the cursor location.
Shift-F13	Erase all field clears the entire field, and places the cursor at the beginning of the field.
F14	FILTER \$xhome/filters/\$arch/toggle_comment comments in or out the selected or cursor lines.
F15	HELP displays the help panel.
S-F15	HELP TASK displays the help task panel.
F16	SAVE transforms the unchanged source file into a backup file by appending a "%" to its name, and creates a new file with the original name from the edited memory image, without exiting it.
Shift-F16	FILE saves the file and then presents a new screen.
L1 (Labelled PF1)	QUIT is used to abandon the file without saving it. If the file has been modified during the session, the user will be prompted to confirm the key to quit.
Control-L1	FLQUIT will do the same as $L1$, and then switch to the directory editor.
L2	MATCH finds a matching delimiter. { [(< matches }]) >.
L3	3270 UP FIELD moves the cursor to the first input field on the upper line.
L4	3270 DOWN FIELD moves the cursor to the first input field on the lower line.
R7	BACKWARD scrolls backward one page.
Shift-R7	TOP moves the current line to the beginning of the file.
R9	FORWARD scrolls forward one page.
Shift-R9	BOT moves the current line to the end of the file.
Control-Left-Arrow	moves the cursor to the previous word.
Control-Right-Arrow	moves the cursor to the next word.

Control-1	MACRO set_bookmark 1 sets the bookmark number 1 at the cursor location.
Control-2	MACRO set_bookmark 2 sets the bookmark number 2 at the cursor location.
Control-3	MACRO set_bookmark 3 sets the bookmark number 3 at the cursor location.
Control-4	MACRO set_bookmark 4 sets the bookmark number 4 at the cursor location.
Control-5	MACRO set_bookmark 5 sets the bookmark number 4 at the cursor location.
Control-6	MACRO goto_bookmark 1 goes to the bookmark number 1.
Control-7	MACRO goto_bookmark 2 goes to the bookmark number 2.
Control-8	MACRO goto_bookmark 3 goes to the bookmark number 3.
Control-9	MACRO goto_bookmark 4 goes to the bookmark number 4.
Control-0	MACRO goto_bookmark 5 goes to the bookmark number 5.
Meta-0	MACRO rm_bookmarks removes all the bookmarks on the current file.
Control-a	C_LINEADD adds a line below the cursor location.
Control-c	MACRO smart_comp \$name 0 compiles the current file, splits the screen, shows the error messages and sets the cursor on the first error line. See the compile command on page 190 for more details.
Control-C	MACRO smart_comp \$name 1 compiles a file in the background.
Control-d	C_LINEDEL deletes the line at the cursor location.
Control-f	equivalent to the "f" command (see Directory editor section).
Control-g	same as Control-c, but in debug mode.
Control-G	same as Control-C, but in debug mode.
Control-h	C_SCRH splits the screen horizontally at the cursor location.
Control-l	S_LOWER translates the characters selected with the mouse into lowercase.

Control-n	f \$fn * calls the directory editor showing all the files with the same filename as the current file.
Control-p	SHELL lpr -h \$name & prints the current file.
Control-r	TREE calls the tree editor.
Control-s	C_SPLIT when the cursor is before the last non-blank character, the line will be split, with indentation if the auto-indent feature is ON (See command "AUTOI on off"). When the cursor is after the last non-blank character, the next line will be joined to that one.
Control-u	S_UPPER translates the characters selected with the mouse into uppercase.
Control-U	S_UPPER WORD translates the first letter of each selected word with the mouse into uppercase.
Control-v	C_SCRV splits the screen vertically at the cursor location.
Control-w	C_SCRJ restarts with an unsplit screen.
Control-x	S_XED starts editing a file selected with the mouse, after expanding the selection to a word and appending the currently edited filetype.
Control-z	LEFT 0 resets the original verify setting, displaying all the columns.
Control	NEXTERROR after a compilation is executed with the Control-c command, the cursor moves to the next error.
Control-=	C_DUP duplicates the line at the cursor location.
Shift+Control-a	MACRO adjust_cursor sets the start of the line at the cursor position.
Shift+Control-c	CENTER centers the line at the cursor location.
Shift+Control-f	FLOW formats the paragraph at the cursor location.
Shift+Control-o	S_PASTE OVERLAY SHELF overlays the contents of the clipboard at the cursor location.

Shift+Control-w	MACRO del_word deletes the word at the cursor location.
Meta-+	MACRO toggle_display toggles between viewing the entire file and viewing the selected lines.
Meta-=	MACRO dup_line duplicates the cursor or the current line.
Meta-u	S_SET OFF cancels the current selection.
Meta-x	S_XED starts editing a file selected with the mouse or at the cursor location, after expanding the selection to a word and appending the currently edited filetype.

Using Function Keys on HP Keyboards

If the user is using a PC style keyboard, the user must insert in the *.sedit files described on page 6 the set_hppc statement. In this case, the function keys will match the IBM layout described on page 62.

Most of the function keys are dedicated to execute commands. The Right and Left function keys (only available on Sun keyboards) are mapped in the following way:

•	L1	Reset
•	L2	Stop
•	L3	Menu
•	L4	User
•	L6	Print
•	R1	Clear
•	R2	Clear Display
•	R3	Insert Line
•	R4	Delete Line
•	R5	Insert Char
•	R6	Delete Char
•	R7	<i>K</i>
•	R9	Prev
•	R11	Next
•	R13	Numerical Pad Tab Key

Using the following physical layout:

L1 L2	F1 F2 F3 F4	L3 L4	F5 F6 F7 F8	R1 R2
				R3 R4
				R5 R6
				R7 R9
				R11
L6				

L1	Erase end of field clears the field starting at the cursor location.
Shift-L1	Erase all field clears the entire field, and places the cursor at the beginning of the field.
L6	COMPLETE allows command line filename completion.
Shift-L6	COMPLETE REVERSE allows command line filename completion in reverse order.
F1	S_FIND searches a string matching the current selection.
F2	S_CUT cuts the current selection.
F3	S_COPY copies the selection into the internal buffer named shelf.
F4	S_PASTE pastes the shelf contents at the cursor location.
Control-F4	S_PASTE PRIMARY pastes the selection contents at the cursor location. May be used to retrieve the selection from another window.
Shift-F4	S_PASTE OVERLAY overlays the shelf contents at the cursor location.
F5	SWITCH moves from one file to another in a circular sequence.
Shift-F5	ISWITCH does the same as F5 in a reversed sequence.
F6	C_ENDLine if the cursor is in a DATA FIELD it will be moved to the end of that field.
Shift-F6	C_ENDCURL moves the cursor to the end of the CURRENT LINE FIELD.
F7	BACKWARD scrolls backward one page.
Meta-F7	S_LSHIFT the text from the column where the selection starts will be moved to the left.
F8	FORWARD scrolls forward one page.
Meta-F8	S_RSHIFT the text from the column where the selection starts will be moved to the right.

F9	? displays the previous commands executed in the COMMAND FIELD. The user can edit and re-execute them.
Shift-F9	?I does the same as above in a reversed order.
Control-F9	XSHOWHISTORY displays the commands memorized in the history buffer in fullscreen mode.
Meta-F9	SHOWHISTORY displays the commands memorized in the history buffer.
F10	CURSOR HOME if the cursor is in a DATA FIELD, it will be moved to the COMMAND FIELD. A subsequent action will restore its previous location.
F11	UNDO undoes the last action.
Shift-F11	REDO undoes the last undo.
F12	=
	repeats the last command without displaying it.
R1	QUIT is used to abandon the file without saving it. If the file has been modified during the session, the user will be prompted to confirm the key to quit.
Control-R1	FLQUIT will do the same as R1, and then switch to the directory editor.
R2	SAVE transforms the unchanged source file into a backup file by appending a "%" to its name, and creates a new file with the original name from the edited memory image, without exiting it.
Shift-R2	FILE saves the file and then presents a new screen.
Control-R2	FLFILE will do the same as Shift-R2 and then switch to the directory editor.
R9	BACKWARD scrolls backward one page.
Shift-R9	TOP moves the current line to the beginning of the file.
R11	FORWARD scrolls forward one page.

Shift-R11	BOT moves the current line to the end of the file.	
Control-R9	FILTER \$xhome/filters/hp/toggle_comment comments in or out the selected or cursor lines.	
Control-Left-Arrow	moves the cursor to the previous word.	
Control-Right-Arrow	moves the cursor to the next word.	
Control-1	MACRO set_bookmark 1 sets the bookmark number 1 at the cursor location.	
Control-2	MACRO set_bookmark 2 sets the bookmark number 2 at the cursor location.	
Control-3	MACRO set_bookmark 3 sets the bookmark number 3 at the cursor location.	
Control-4	MACRO set_bookmark 4 sets the bookmark number 4 at the cursor location.	
Control-5	MACRO set_bookmark 5 sets the bookmark number 4 at the cursor location.	
Control-6	MACRO goto_bookmark 1 goes to the bookmark number 1.	
Control-7	MACRO goto_bookmark 2 goes to the bookmark number 2.	
Control-8	MACRO goto_bookmark 3 goes to the bookmark number 3.	
Control-9	MACRO goto_bookmark 4 goes to the bookmark number 4.	
Control-0	MACRO goto_bookmark 5 goes to the bookmark number 5.	
Meta-0	MACRO rm_bookmarks removes all the bookmarks on the current file.	
Control-a	C_LINEAdd adds a line below the cursor location.	
Control-c	MACRO smart_comp \$name 0 compiles the current file, splits the screen, shows the error messages and sets the cursor on the first error line. See the compile command on page 190 for more details.	
Control-C	MACRO smart_comp \$name 1 compiles a file in the background.	
Control-d	C_LINEDEL deletes the line at the cursor location.	
Control-f	equivalent to the "f" command (see Directory editor section).	
Control-g	same as Control-c, but in debug mode.	

Control-G	same as Control-C, but in debug mode.
Control-h	C_SCRH splits the screen horizontally at the cursor location.
Control-l	S_LOWER translates the characters selected with the mouse into lowercase.
Control-m	MATCH finds a matching delimiter. { [(< matches }]) >.
Control-n	f \$fn * calls the directory editor showing all the files with the same filename as the current file.
Control-p	SHELL lpr -h \$name & prints the current file.
Control-r	TREE calls the tree editor.
Control-s	C_SPLIT when the cursor is before the last non-blank character, the line will be split, with indentation if the auto-indent feature is ON (See command "AUTOI on off"). When the cursor is after the last non-blank character, the next line will be joined to that one.
Control-u	S_UPPER translates the characters selected with the mouse into uppercase.
Control-U	S_UPPER WORD translates the first letter of each selected word with the mouse into uppercase.
Control-v	C_SCRV splits the screen vertically at the cursor location.
Control-w	C_SCRJ restarts with an unsplit screen.
Control-x	S_Xed starts editing a file selected with the mouse, after expanding the selection to a word and appending the currently edited filetype.
Control-z	LEFT 0 resets the original verify setting, displaying all the columns.
Control	NEXTERROR after a compilation is executed with the Control-c command, the cursor moves to the next error.
Control-=	C_DUP duplicates the line at the cursor location.

Shift+Control-a	MACRO adjust_cursor sets the start of the line at the cursor position.
Shift+Control-c	CENTER centers the line at the cursor location.
Shift+Control-f	FLOW formats the paragraph at the cursor location.
Shift+Control-o	S_PASTE OVERLAY SHELF overlays the contents of the clipboard at the cursor location.
Shift+Control-w	MACRO del_word deletes the word at the cursor location.
Meta-+	MACRO toggle_display toggles between viewing the entire file and viewing the selected lines.
Meta-=	MACRO dup_line duplicates the cursor or the current line.
Meta-u	S_SET OFF cancels the current selection.
Meta-x	S_XED starts editing a file selected with the mouse or at the cursor location, after expanding the selection to a word and appending the currently edited filetype.

Using Function Keys on WINDOWS

Most of the function keys are dedicated to execute commands. The Right function keys are mapped in the following way:

•	R1	Print Screen
•	R2	Scroll Lock
•	R3	Pause
•	R4	Insert
•	R5	Home
•	R6	Page Up
•	R7	End
•	R8	Up Arrow
•	R9	Page Down
•	R10	Left Arrow
•	R12	Right Arrow
•	R14	Down Arrow

Using the following physical layout:



Escape	Erase end of field clears the field starting at the cursor location.
Shift-Escape	Erase all field clears the entire field, and places the cursor at the beginning of the field.
F1	S_FIND searches a string matching the current selection.
Shift-F1	S_FIND searches backwards a string matching the current selection.
Control-F1	S_FIND searches a word matching the current selection.

F2	C_LINEADD adds a line below the cursor location.
Shift-F2	C_EXT is used to extend the length of the field selected by the cursor.
F3	SAVE transforms the unchanged source file into a backup file by appending a "%" to its name, and creates a new file with the original name from the edited memory image, without exiting it.
Shift-F3	FILE saves the file and then presents a new screen.
Control-F3	FLFILE saves the file, quits the file and then switches to FLIST.
F4	C_SPLIT when the cursor is before the last non-blank character, the line will be split, with indentation if the auto-indent feature is ON (See the AUTOINDENT command). When the cursor is after the last non-blank character, the next line will be joined to that one.
F5	SWITCH moves from one file to another in a circular sequence.
Shift-F5	ISWITCH does the same as F5 in a reversed sequence.
F6	C_ENDLINE if the cursor is in a DATA FIELD it will be moved to the end of that field.
Shift-F6	C_ENDCURL moves the cursor to the end of the CURRENT LINE FIELD.
F7	BACKWARD scrolls backward one page.
Shift-F7	PGUP scrolls backward one screen.
Control-F7	LEFT40 scrolls left 40 columns.
Meta-F7	S_LSHIFT the text from the column where the selection starts will be moved to the left.
F8	FORWARD scrolls forward one page.
Shift-F8	PGDOWN scrolls forward one screen.

Control-F8	RIGHT40 scrolls right 40 columns.
Meta-F8	S_RSHIFT the text from the column where the selection starts will be moved to the right.
F9	? displays the previous commands executed in the COMMAND FIELD. The user can edit and re-execute them.
Shift-F9	?I does the same as F9 in a reversed order.
Control-F9	XSHOWHISTORY displays the commands memorized in the history buffer in fullscreen mode.
Meta-F9	SHOWHISTORY displays the commands memorized in the history buffer.
F10	CURSOR HOME if the cursor is in a DATA FIELD, it will be moved to the COMMAND FIELD. A subsequent action will restore its previous location.
Control-F10	DELAY . HOME (. is the command separator) clears the command field without moving the cursor.
F11	UNDO undoes the last action.
Shift-F11	REDO undoes the last undo.
F12	= repeats the last command without displaying it.
PrintScreen	AQUIT is used to abandon the file without saving it. If the file has been modified during the session, the user will be prompted to confirm the key to quit.
Control-PrintScreen	FLQUIT will do the same as PrintScreen (R1), and then switch to the directory editor.
ScrollLock	COMPLETE allows command line filename completion.
Shift-ScrollLock	COMPLETE REVERSE allows command line filename completion in reverse order.

Pause	SAVE transforms the unchanged source file into a backup file by appending a "%" to its name, and creates a new file with the original name from the edited memory image, without exiting it.
Shift-PageUp	TOP moves the current line to the beginning of the file.
Control-PageUp	FILTER \$xhome/filters/\$arch/toggle_comment comments in or out the selected or cursor lines.
Shift-PageDown	BOT moves the current line to the end of the file.
Control-Left-Arrow	moves the cursor to the previous word.
Control-Right-Arrow	moves the cursor to the next word.
Control-1	MACRO set_bookmark 1 sets the bookmark number 1 at the cursor location.
Control-2	MACRO set_bookmark 2 sets the bookmark number 2 at the cursor location.
Control-3	MACRO set_bookmark 3 sets the bookmark number 3 at the cursor location.
Control-4	MACRO set_bookmark 4 sets the bookmark number 4 at the cursor location.
Control-5	MACRO set_bookmark 5 sets the bookmark number 4 at the cursor location.
Control-6	MACRO goto_bookmark 1 goes to the bookmark number 1.
Control-7	MACRO goto_bookmark 2 goes to the bookmark number 2.
Control-8	MACRO goto_bookmark 3 goes to the bookmark number 3.
Control-9	MACRO goto_bookmark 4 goes to the bookmark number 4.
Control-0	MACRO goto_bookmark 5 goes to the bookmark number 5.
Meta-0	MACRO rm_bookmarks removes all the bookmarks on the current file.
Control-a	S_SET ALL all of the file will be selected.
Control-c	S_COPY copies the selection into the clipboard (or shelf).

Shift-Control-c	MACRO smart_comp \$name 0 compiles the current file, splits the screen, shows the error messages and sets the cursor on the first error line.
Control-d	C_LINEDEL deletes the line at the cursor location.
Control-f	equivalent to the FLIST command (see the Directory editor section).
Shift-Control-f	FLOW formats the paragraph corresponding to the cursor location.
Shift-Control-g	same as Shift-Control-c, but in debug mode.
Control-h	C_SCRH splits the screen horizontally at the cursor location.
Shift-Control-h	S_HELP starts editing the help file selected with the mouse. If the selection is one character wide, it will be expanded to the word.
Control-l	S_LOWER translates the characters selected with the mouse into lowercase.
Shift-Control-l	LEFTADJUST positions the first non-blank character at the left margin defined with the MARGIN command.
Control-m	MATCH finds a matching delimiter. { [(< matches }]) >.
Shift-Control-m	MATCH CURSOR finds a matching delimiter. { [(< matches }]) >, and moves the cursor at that location.
Control-n	f "\$fn" * calls the directory editor showing all the files with the same filename as the current file.
Shift-Control-n	f "\$fn" * "\$fd" calls the directory editor showing all the files with the same filename as the current file in the same directory as the current file.
Control-p	PRINTFILE prints the current file.
Control-q	AQUIT is used to abandon the file without saving it. If the file has been modified during the session, the user will be prompted to confirm the key to quit.
Control-r	TREE calls the tree editor.

Shift-Control-r	RIGHTADJUST positions the last non-blank character at the right margin defined with the MARGIN command.
Control-s	DY_SAVE calls the standard SAVE AS dialog box.
Control-t	TREE calls the TREE editor.
Control-u	S_UPPER translates the characters selected with the mouse into uppercase.
Control-U	S_UPPER WORD translates the first letter of each selected word with the mouse into uppercase.
Control-v	S_PASTE SHELF pastes the clipboard (or shelf) contents at the cursor location.
Control-V	S_PASTE SHELF OVERLAY overlays the clipboard (or shelf) contents at the cursor location.
Control-w	C_SCRJ restarts with an unsplit screen.
Control-x	S_CUT cuts the current selection, placing it in the clipboard.
Shift-Control-x	S_XED starts editing a file selected with the mouse, after expanding the selection to a word and appending the currently edited filetype.
Control-z	UNDO undoes the last action.
Control	NEXTERROR after a compilation is executed with the Shift-Control-c command, the cursor moves to the next error.
Control-=	C_DUP duplicates the line at the cursor location.
Shift+Control-a	MACRO adjust_cursor sets the start of the line at the cursor position.
Shift+Control-c	CENTER centers the line at the cursor location.
Shift+Control-f	FLOW formats the paragraph at the cursor location.
Shift+Control-o	S_PASTE OVERLAY SHELF overlays the contents of the clipboard at the cursor location.

Shift+Control-w	MACRO del_word deletes the word at the cursor location.
Meta-+	MACRO toggle_display toggles between viewing the entire file and viewing the selected lines.
Meta-=	MACRO dup_line duplicates the cursor or the current line.
Meta-u	S_SET OFF cancels the current selection.
Meta-x	S_XED starts editing a file selected with the mouse or at the cursor location, after expanding the selection to a word and appending the currently edited filetype.

Using Function Keys in KEDIT Mode

The principal key definitions are referenced on the last line of the window.

On SUN stations:

L2	MATCH finds a matching delimiter. { [(< matches }]) >.
L3	Erase end of field clears the field starting at the cursor location.
Shift-L3	Erase all field clears the entire field, and places the cursor at the beginning of the field.
L4	UNDO undoes the last action.
Shift-L4	REDO undoes the last undo.
L6	S_COPY copies the selection into the internal buffer named shelf.
L8	S_PASTE pastes the shelf contents at the cursor location.
Control-L8	S_PASTE PRIMARY pastes the selection content at the cursor location. May be used to retrieve the selection from another window.
Shift-L8	S_PASTE OVERLAY overlays the clipboard contents at the cursor location.
L9	S_FIND searches a string matching the current selection.
L10	S_CUT cuts the current selection.
On other stations:	
Escape	Erase end of field clears the field starting at the cursor location.
Shift-Escape	Erase all field clears the entire field, and places the cursor at the beginning of the field.
On all stations:	
F1	MACRO ahelp displays the on-line PDF help.
F2	MACRO add_line adds a new line below the cursor or current line.

F3	QUIT is used to abandon the file without saving it. If the file has been modified during the session, the user will be prompted to confirm the key to quit.
F4	SOS TABF moves the cursor to the next tab column.
F5	MACRO cursor_to_curr the cursor lines becomes the current line.
F6	? displays the previous commands executed in the COMMAND FIELD. The user can edit and re-execute them.
F7	MACRO beg_line moves the cursor to the beginning of the line.
F8	MACRO dup_line duplicates the cursor or the current line.
F9	= repeats the last command without displaying it.
F10	HOME if the cursor is in a DATA FIELD, it will be moved to the COMMAND FIELD. A subsequent action will restore its previous location.
F11	C_SPLIT STAY when the cursor is before the last non-blank character, the line will be split, with indentation if the auto-indent feature is ON (See command "AUTOI on off").
	When the cursor is after the last non-blank character, the next line will be joined to that one.
F12	CURSOR CMDLINE moves the cursor to the command line.
PrintScreen	AQUIT is used to abandon the file without saving it. If the file has been modified during the session, the user will be prompted to confirm the key to quit.
Control-PrintScreen	FLQUIT will do the same as PrintScreen, and then switch to the directory editor.
ScrollLock	COMPLETE allows command line filename completion.
Shift-ScrollLock	COMPLETE REVERSE allows command line filename completion in reverse order.

Pause	SAVE transforms the unchanged source file into a backup file by appending a "%" to its name, and creates a new file with the original name from the edited memory image, without exiting it.
Shift-F1	MACRO locate_redo reissues the last LOCATE command.
Shift-F2	MACRO goto_current moves the cursor to the current line.
Shift-F3	MATCH finds a matching delimiter. { [(< matches }]) >.
Shift-F4	SWITCH moves from one file to another in a circular sequence.
Shift-F5	S_UPPER translates the characters selected with the mouse into uppercase.
Shift-F6	S_LOWER translates the characters selected with the mouse into lowercase.
Shift-F7	S_LSHIFT the text from the column where the selection starts will be moved to the left.
Shift-F8	S_RSHIFT the text from the column where the selection starts will be moved to the right.
Shift-F9	LEFT 40 scrolls the displayed data 40 columns to the left.
Shift-F10	RIGHT 40 scrolls the displayed data 40 columns to the right.
Shift-F11	TOP the first line becomes the current line.
Shift-F12	HOME if the cursor is in a DATA FIELD, it will be moved to the COMMAND FIELD. A subsequent action will restore its previous location.
Control-F1	UNDO undoes the last action.
Control-F2	REDO undoes the last undo.
Control-a	S_SET ALL all of the file will be selected.

Control-c	S_COPY copies the selection into the clipboard (or shelf).
Control-f	DY_FIND displays the FIND dialog box.
Control-h	DY_FIND displays the FIND dialog box.
Control-i	MACRO dy_fill fills a block with a specified string.
Control-l	LEFTADJUST left adjusts the text at the cursor or command line location.
Control-n	NEWFILE initiates a new file.
Control-o	MACRO dy_open opens the OPEN dialog box.
Control-p	PRINTFILE on WINDOWS systems, opens the print dialog box. On UNIX systems, prints the file.
Control-r	RIGHTADJUST right adjusts the text at the cursor or command line location.
Control-s	SAVE transforms the unchanged source file into a backup file by appending a "%" to its name, and creates a new file with the original name from the edited memory image, without exiting it.
Control-t	TREE starts the TREE editor.
Control-u	S_UPPER translates the characters selected with the mouse into uppercase.
Control-U	S_UPPER WORD translates the first letter of each selected word with the mouse into uppercase.
Control-v	S_PASTE INSERT SHELF pastes the clipboard contents at the cursor location.
Control-w	C_SCRJ restarts with an unsplit screen.
Control-x	S_CUT cuts the current selection.
Control-y	REDO undoes the last undo.
Control-z	UNDO undoes the last action.

Shift+Control-a	MACRO adjust_cursor adjusts the text at the cursor location.
Shift+Control-c	CENTER centers the line at the cursor location.
Shift+Control-f	FLOW formats the paragraph at the cursor location.
Shift+Control-l	LEFTADJUST left adjusts the text at the cursor location.
Shift+Control-o	S_PASTE OVERLAY SHELF overlays the clipboard contents at the cursor location.
Shift+Control-p	MACRO new_para stars a new paragraph at the cursor location.
Shift+Control-w	MACRO del_word deletes one word at the cursor location.
Shift+Control-x	FLIST * * displays the parent directory.
Meta-b	C_ENDSR marks a rectangular selection.
Meta-c	MACRO copy_and_paste copies the selection into the clipboard (or shelf) and then pastes it at the cursor location. The selection is unmarked.
Meta-d	MACRO delete_line deletes the cursor or the current line.
Meta-g	S_CUT cuts the current selection.
Meta-j	MACRO force_join overlays the next line at the cursor location.
Meta-k	MACRO copy_and_paste 1 copies the selection into the clipboard (or shelf) and then pastes it at the cursor location. The selection remains marked.
Meta-l	C_ENDS marks a linear selection.
Meta-m	MACRO move_block removes a marked block, and pastes it at the cursor location.
Meta-r	UNDO undoes the last action.
Meta-s	MACRO split_only splits the line at the cursor location.

Meta-u	S_SET OFF unmarks the current selection.
Meta-x	S_XED starts editing a file selected with the mouse or at the cursor location, after expanding the selection to a word and appending the currently edited filetype.
Meta-z	C_ENDS marks a linear selection.
Meta-+	MACRO toggle_display toggles between viewing the complete file and viewing selected lines.
Meta-=	MACRO dup_line duplicate the cursor or the current line.
Meta-0	MACRO rm_bookmarks removes all the bookmarks.
Meta-1	MACRO set_bookmark 1 sets the bookmark number 1 at the cursor location.
Meta-2	MACRO set_bookmark 2 sets the bookmark number 2 at the cursor location.
Meta-3	MACRO set_bookmark 3 sets the bookmark number 3 at the cursor location.
Meta-4	MACRO goto_bookmark 1 goes to the bookmark number 1.
Meta-5	MACRO goto_bookmark 2 goes to the bookmark number 2.
Meta-6	MACRO goto_bookmark 3 goes to the bookmark number 3.
Enter	MACRO enter_split when no command is present on the command line, splits the line at the cursor location.
Control-Enter	MACRO start_nextline goes to the start of the next line.
Shift+Control+Enter	MACRO toggle_prefix_file toggles between the data and the prefix area.
Control-Up-Arrow	? displays the previous commands executed in the COMMAND FIELD. The user can edit and re-execute them.
Control-Down-Arrow	?i does the same as Control-Up-Arrow in a reversed order.
Control-Left-Arrow	PREVWORD moves the cursor to the previous word.

Control-Right-Arrow	NEXTWORD moves the cursor to the next word.
Shift-Up-Arrow	MACRO extsel_up extends the selection up one line.
Shift-Down-Arrow	MACRO extsel_down extends the selection down one line.
Shift-Left-Arrow	MACRO extsel_left extends the selection one character left.
Shift-Right-Arrow	MACRO extsel_right extends the selection one character right.
Shift+Control-Left-Arr	OW
	MACRO extsel_leftw extends the selection one word left.
Shift+Control-Right-A	rrow
0	MACRO extsel_rightw extends the selection one word right.
Home	C_STARTL moves the cursor to the start of the line.
End	C_ENDL moves the cursor to the end of the line.
Shift+Home	MACRO extsel_start extends the selection to the start of the line.
Shift+End	MACRO extsel_end extends the selection to the end of the line
Control Homo	extends the selection to the end of the fine.
Control-Home	MACRO goto_start moves to the beginning of the file.
Control-Fiome	MACRO goto_start moves to the beginning of the file. MACRO goto_end moves to the end of the file.
Control-Fione Control-End Shift+Control-Home	MACRO goto_start moves to the beginning of the file. MACRO goto_end moves to the end of the file. MACRO extsel_startf extends the selection to the beginning of the file.
Control-Fione Control-End Shift+Control-Home Shift+Control-End	MACRO goto_start moves to the beginning of the file. MACRO goto_end moves to the end of the file. MACRO extsel_startf extends the selection to the beginning of the file. MACRO extsel_endf extends the selection to the end of the file.
Control-End Shift+Control-Home Shift+Control-End Shift-Page-Up	MACRO goto_start moves to the beginning of the file. MACRO goto_end moves to the end of the file. MACRO extsel_startf extends the selection to the beginning of the file. MACRO extsel_endf extends the selection to the end of the file. MACRO extsel_wback extends the selection one window backward.

Using Function Keys on ASCII Terminal Keyboards

Most of the function keys are dedicated to execute commands. The Right function keys (only available on Sun keyboards) are generally mapped in the following way:

•	R1	Print Screen
•	R2	Scroll Lock
•	R3	Pause
•	R4	Insert
•	R5	Home
•	R6	Page Up
•	R7	End
•	R9	Page Down

Using the following physical layout:



Escape	Erase end of field clears the field starting at the cursor location.
F1	QUIT is used to abandon the file without saving it. If the file has been modified during the session, the user will be prompted to confirm the key to quit.
F2	NEXTERROR after a compilation executed with the Control-c command, moves the cursor to the next error.
F3	SAVE transforms the unchanged source file into a backup file by appending a "%" to its name, and creates a new file with the original name from the edited memory image, without exiting it.

F4	C_SPLIT when the cursor is before the last non-blank character, the line will be split, with indentation if the auto-indent feature is ON (See command "AUTOI on off"). When the cursor is after the last non-blank character, the next line will be joined to that one.
F5	SWITCH moves from one file to another in a circular sequence.
F6	C_ENDLINE if the cursor is in a DATA FIELD, it will be moved to the end of that field.
F7	BACKWARD scrolls backward one page.
F8	FORWARD scrolls forward one page.
F9	? displays the previous commands executed in the COMMAND FIELD. The user can edit and re-execute them.
F10	CURSOR HOME if the cursor is in a DATA FIELD, it will be moved to the COMMAND FIELD. A subsequent action will restore its previous location.
F11	UNDO undoes the last action.
F12	= repeats the last command without displaying it.
Control-a	C_LINEADD adds a line below the cursor location.
Control-b	C_STARTS starts the selection at the cursor location.
Control-c	MACRO smart_comp \$name 0 compiles the current file, splits the screen, shows the error messages and sets the cursor on the first error line. See the compile command on page 190 for more details.
Control-d	C_LINEDEL deletes the line at the cursor location.
Control-e	C_ENDS extends the selection at the cursor location.
Control-f	enters the DOWN-FIELD 3270 command. It cannot be changed.
Control-g	same as Control-c, but in debug mode.
Control-h	enters a Backspace. It cannot be changed.

Control-i	enters the NEXT-FIELD 3270 command. It cannot be changed.
Control-j	enters the UP-FIELD 3270 command. It cannot be changed.
Control-l	enters the line-feed command separator. It cannot be changed.
Control-m	is equivalent to the Return or the Enter key. It cannot be changed.
Control-n	C_ENDSR extends the selection at the cursor location, making it rectangular.
Control-o	S_COPY copies the selection into the internal buffer named shelf.
Control-p	SHELL lpr -h \$name & prints the current file.
Control-r	REFRESH Clear redraws the whole screen.
Control-t	enters the tab character. It cannot be changed.
Control-u	S_UPPER translates into uppercase the characters selected with the Control-b, Control-e and Control-n commands.
Control-v	C_SCRV splits the screen vertically at the cursor location.
Control-w	C_SCRJ restarts with an unsplit screen.
Control-x	S_XED sets a selection at the cursor location, expands the selection to a word, appends the currently edited filetype and starts editing this file.
Control-y	S_PASTE pastes the shelf contents at the cursor location.
Control-z	LEFT 0 resets the original verify setting, displaying all the columns.
Using the Keyboard

The best way to move to a distant location is to use the third mouse button.

The best way to move to the first character of a field is to use PREV FIELD (R7 for Sun type 3 keyboards, and Shift-Tab for other ones) or NEXT FIELD (Tab) key. This is much faster and easier than using the arrow keys.

The best way to access a PREFIX FIELD is to use DOWN FIELD (Line-feed or AltGraph for Sun keyboards, Right Extend-Char for HP, Right Control for IBM and SiliconGraphics keyboards, and PF4 for DECstation keyboards) or UP FIELD (Alternate for Sun keyboards, Select for HP, Right Alt for IBM and SiliconGraphics keyboards, and PF3 for DECstation keyboards).

The best way to move to the COMMAND FIELD is to use the CURSOR HOME command, which is mapped to key F10.

Key R6 on Sun workstations, or key HOME gives access to the first PREFIX field, or the first DIRECT INPUT field.

The best way to clear a field is to use the ERASE EOF key (L3 on Sun workstations, F13 on DECstations, Reset on HP workstations and Escape on others). This will clear the field from the cursor location to the end of the field.

Shift-ERASE EOF (or Control-ERASE EOF with the MWM window manager) will erase the entire field, and place the cursor at the beginning of the field.

Remember that the insert key (R11 on Sun workstations with a type 3 keyboard) toggles between insert and replace mode.

Using the Default Buttons (UNIX)

The standard /home/xed/profile.sedit initialization macro creates a set of menu buttons:



Clicking with the third mouse button displays a menu.

Clicking with the left mouse button executes directly the first menu item.

Using the Default MenuBar (WINDOWS)

The standard C:\Program Files\SEDIT\profile.sedit initialization macro creates the following menubar:



Clicking with the left mouse button displays a menu.

The menubar can be modified by editing the C:\Program Files\SEDIT\sedit.menubar file.

The File Menu

Save	transforms the unchanged source file into a backup file by appending a "%" to its name, and creates a new file from the edited memory image, without exiting it.
Save & Leave	saves the file and then presents a new screen.
Leave	is used to abandon the file without saving it. If the file has been modified during the session, the user will be prompted to confirm.
Save As	starts the <u>DY_SAVE</u> dialog box described on page 231.
Open	starts the <u>DY OPEN</u> dialog box described on page 227.
Open <selection></selection>	opens the file selected with the mouse.
Exit	exits SEDIT .
Exit with memory	exits SEDIT . The next time SEDIT is started in the same directory, it will load the same files it was editing before it was exited.

On **UNIX** systems, the File menu can be customized by modifying the /home/xed/file.bu file.

The EDIT Menu

Find	finds the selected characters.
Find	starts the <u>DY_FIND</u> dialog box described on page 225.
Сору	saves the selection.
Paste	retrieves the previously saved selection at the cursor location.
Cut	deletes the current selection, saving it for further use by the Paste facility.
Undo	undoes the last editing action.
Undo ALL	undoes all the editing actions done since the last Save.
Redo	redoes the last undone editing action.
Show ALL	shows all the file lines.
Show	starts the <u>DY_ALL</u> dialog box described on page 223.
Show more	starts the <u>DY_SHOW</u> dialog box described on page 235.
Hide	starts the <u>DY_EXCLUDE</u> dialog box described on page 224.

On UNIX systems, the EDIT menu can be customized by modifying the /home/xed/edit.bu file.

The SPECIAL Menu

/	
First line	selects the first line as the current line.
Last line	selects the last line as the current line.
Print	prints the current file.
Keyboard	(UNIX specific) sets up various keyboards. The user will need to use it when displaying SEDIT on a different platform than the one it was started from.
Spell	(UNIX specific) creates 3 buttons for spell-checking purposes.
Tab	replaces tabulations by the appropriate number of spaces, either for the current file or for the selected lines.
Screen	splits or unsplits the screen.
AX	(UNIX specific) sets up the UNIX execution authorization upon the current file.
Toolbar	(WINDOWS specific) toggles ON and OFF the toolbar display.
Close Console	(WINDOWS specific) closes the DOS console opened by S/REXX when using input or output REXX statements.
Keyboard	(WINDOWS specific) sets up the keyboard either in WINDOWS mode, or in UNIX mode. See page 50 for more information.

When selecting the SPELL menu item, the user creates the following buttons:



On **UNIX** systems, the SPECIAL menu can be customized by modifying the /home/xed/sp.bu file.

The COMPILE Menu



On **UNIX** systems, the COMPILE menu can be customized by modifying the /home/xed/comp.bu file.

The FLIST Menu

The FLIST menu allows the user to start <u>FLIST</u> upon various directories, and can be customized on **UNIX** systems by modifying the /home/xed/f.bu file.

The TREE Menu

The TREE menu allows the user to start <u>TREE</u> upon various directories, and can be customized on **UNIX** systems by modifying the /home/xed/tree.bu file.

The HELP Menu

The HELP menu allows the user to display either command or task help, and can be customized on **UNIX** systems by modifying the /home/xed/help.bu file.

Using the DEFAULT Menu

The **SEDIT** menu is activated by depressing the third mouse button on the first or second screen line:

FILE	\rightarrow
EDIT	\rightarrow
SPECIAL	\implies
COMPILE	\Rightarrow
FLIST	\implies
TREE	\Rightarrow
HELP	\rightarrow
MENU	\implies

The seven first items are similar to the menu buttons described on page 98.

The X submenu of the MENU item edits the sedit.menu file, allowing the user to customize the menu. The DO submenu activates the changes.

Prefix Commands

The prefix commands are commands the user can type in a PREFIX FIELD in order to directly manipulate a data line. There are two types of prefix commands:

- * Single prefix commands (such as $D \{N\}$) which act on ONE or N lines.
- * Double prefix commands (such as DD) which act on a group of lines localized by the command entered in two prefix fields.

The command <u>MODE</u> PREFIX XEDIT or MODE PREFIX ISPF allows the user to switch between the IBM **XEDIT** editor behavior and the **ISPF/PDF** behavior. The default is the **XEDIT** behavior.

SEDIT takes into account only the characters which are entered by the user in the prefix area. These characters are decoded in the following manner:

- Any number is interpreted as an operand.
- An * is taken as an operand. For a built-in prefix command, an * is replaced by a number equal to the number of lines remaining in the file after the prefix command position. D* deletes all the remaining lines.
- If a prefix command name starts with a letter, it will end at the first character which is not a letter.
- If a prefix command name starts with a non-alphabetic character, it will end at the first blank, alphabetic character, or number.
- Whatever follows a name is interpreted as an operand.

For example:

PREFIX	NAME	OP1	OP2	OP3
*d	d	*	NULL	NULL
4i12	i	4	12	NULL
%zzz	%	ZZZ	NULL	NULL
<<4	<<	4	NULL	NULL
12d <w< td=""><td>d</td><td>12</td><td><w< td=""><td>NULL</td></w<></td></w<>	d	12	<w< td=""><td>NULL</td></w<>	NULL

SEDIT and S/REXX Reference Manual

Single Prefix Commands

SEDIT features 16 single prefix commands:

- Add (or I as "Insert") Α Copy С Delete D Put ΡU ' or ' Duplicate (' is the APL quote) (or R as "Replace" in ISPF mode) Replace / Get G Е Extend Shift right > Shift left < Move Μ Х eXclude S Show
- SCale Set scale line
- Tabl Set tabline
- .symb assigns the symb string to be a symbolic name for the matched line. If symb has been already assigned to another line, this older line will no longer be assigned this symbolic name.

The M and C commands need one of the following line indicators:

- F Following (or A as After in ISPF mode)
- P Previous (or B as Before in ISPF mode)
- 0 Overlay
- 00 Overlay

A adds a specified number of lines:

```
00001 /*

00002 * This is a second sample file for SEDIT

a2003 *

00004 *

00005 main()

00006 /* This file is 6 lines long */
```

gives:

```
00001 /*

00002 * This is a second sample file for SEDIT

00003 *

00004

00005

00006 *

00007 main()

00008 /* This file is 6 lines long */
```

Note: Only the number the user enters in the prefix field will be used to determine the number of lines to be added. Any previous number found in the field will be ignored. On color displays, the character typed will appear in blue.

The user can insert a line by typing 'Control-A' at the cursor location as well.

When the auto-indent feature is on (command <u>AUTOI</u> ON), which is the default when the editor is started, the cursor is automatically placed on the first inserted line. The indentation is identical to that of the previous line.

D deletes a specified number of lines. It works in the same way as A. D* deletes all subsequent lines.

Prefix commands

SEDIT USER'S GUIDE

C is used with the P(previous) or F(following) indicators to copy one line:

```
00001 /*

c0002 * This is a second sample file for SEDIT

00003 *

f0004 *

00005 main()

00006 /* This file is 6 lines long */
```

gives:

00001 /* 00002 * This is a second sample file for SEDIT 00003 * 00004 * 00005 * This is a second sample file for SEDIT 00006 main() 00007 /* This file is 6 lines long */ **PU** is used to save the contents of the lines selected in an internal buffer. These lines may be moved to the file being edited by the G prefix command.

```
00001 /*
PU202 * This is a second sample file for SEDIT
00003 *
00004 *
00005 main()
00006 /* This file is 6 lines long */
```

and:

```
00001 /*

00002 * This is a second sample file for SEDIT

00003 *

0G004 *

00005 main()

00006 /* This file is 6 lines long */
```

gives:

```
00001
       /*
00002
       * This is a second sample file for SEDIT
00003
        *
00004
       *
00005
       * This is a second sample file for SEDIT
00006
        *
00007
      main()
80000
        /* This file is 6 lines long */
```

"

or '(apostrophe) or '(APL quote) copies the lines selected:

```
00001 /*
"202 * This is a second sample file for SEDIT
00003 *
00004 *
00005 main()
00006 /* This file is 6 lines long */
```

gives:

```
00001
       /*
00002
      * This is a second sample file for SEDIT
00003
        * This is a second sample file for SEDIT
        * This is a second sample file for SEDIT
00004
00005
        *
00006
        *
00007
     main()
00006
         /* This file is 6 lines long
                                        */
```

Note: The user can also duplicate a line by typing 'Control-=' on the cursor location.

(slash) chooses the selected line as the current line.This can also be done by clicking the line with the shift-third mouse button.

G gets the lines previously saved by PU.

E extends the data field and places the cursor at the last non-blank character. Its action is similar to that of the F2 key.

00001 /* 00002 * This is a second sample file for SEDIT e0003 * This is a second sample file for SEDIT 00004 * 00005 * 00006 main()

gives:

```
00001 /*

00002 * This is a second sample file for SEDIT

00003 * This is a second sample file for SEDIT_

00004 *

00005 *

00006 main()
```

>{N} shifts data N positions to the right on the selected line.

<{N} shifts data N positions to the left on the selected line. < sounds the alarm when the left of the line is truncated.

When the user is editing a FORTRAN file (for example test.f), if the first character is a tabulation or some single alphabetical character, the shifting will proceed from the second column. If the line begins with a label the shifting will proceed from the first non-blank character in order to preserve that label.

~ 1002 do $100 = 1000$	>6 001	1 C	This is a comment
>4002 . at 100 1=1,1000	>4 002	2.	do 100 i=1,1000
>3003 100 k = k+1	>3 003	3 100	k = k+1

gives:

00001 0	C	This is a comment
00002		do 100 i=1,1000
00003	100	k = k+1

Prefix commands

SEDIT USER'S GUIDE

M is used with the P(previous) or F(following) indicators to move one line:

```
00001 /*

m0002 * This is a second sample file for SEDIT

00003 *

f0004 *

00005 main()

00006 /* This file is 6 lines long */
```

gives:

```
00001 /*

00002 *

00003 *

00004 * This is a second sample file for SEDIT

00005 main()

00006 /* This file is 6 lines long */
```

X excludes a line from display:

```
00001 /*

x0002 * This is a second sample file for SEDIT

00003 *

00004 *

00005 main()

00006 /* This file is 6 lines long */
```

gives:

```
00001 /*

00002 ------ 1 line not displayed -----

00003 *

00004 *

00005 main()

00006 /* This file is 6 lines long */
```

S shows excluded lines represented by a shadow line:

```
00001 /*

s0002 ------ 1 line not displayed ------

00003 *

00004 *

00005 main()

00006 /* This file is 6 lines long */
```

gives:

```
00001 /*

00002 * This is a second sample file for SEDIT

00003 *

00004 *

00005 main()

00006 /* This file is 6 lines long */
```

Sn shows the first n hidden lines.

S-n shows the last n hidden lines.

SCale sets the scale line to be displayed at this location.

- **Tabl** sets the tabline to be displayed at this location.
- **.symb** assigns the symb string to be a symbolic name for the matched line. If symb has been already assigned to another line, this older line will no longer be assigned this symbolic name.

Double Prefix Commands

A double prefix command is a command which acts on a sequence of lines.

The prefix must appear on the first and the last line.

SEDIT features 8 double prefix commands:

CC	Сору
MM	Move
DD	Delete
PP	Put
"" or ''	Duplicate (or RR in ISPF mode)
"" or '' >>	Duplicate (or RR in ISPF mode) Shift right
"" or '' >> <<	Duplicate (or RR in ISPF mode) Shift right Shift left

Note: Any prefix command which needs another prefix command to be executed, as M needs F, is called a **PENDING** command.
Pending commands remain in the prefix field and will be executed when the associated prefix command is entered. This allows the user to scroll through the file. To erase all pending commands, type <u>RESET</u> in the COMMAND FIELD.
Delete a pending command by typing spaces over it.

CC copies a group of lines:

cc001 /*
000cc *
00003 *
f0004 * This is a second sample file for SEDIT
00005 main()
00006 /* This file is 6 lines long */

gives:

```
00001 /*

00002 *

00003 *

00004 * This is a second sample file for SEDIT

00005 /*

00006 *

00007 main()

00008 /* This file is 6 lines long */
```

MM moves a group of lines:

```
mm001 /*
000mm *
00003 *
f0004 * This is a second sample file for SEDIT
00005 main()
00006 /* This file is 6 lines long */
```

gives:

```
00001 *

00002 * This is a second sample file for SEDIT

00003 /*

00004 *

00005 main()

00006 /* This file is 6 lines long */
```

DD deletes a group of lines.

PP saves a group of lines into the internal buffer.

"" or ' ' duplicates a group of lines.

>> or << shifts a group of lines. << sounds the alarm when the left of the line is truncated.

>> 3 01	C	This is a comment
00002	•	do 100 i=1,1000
0>>03	100	k = k+1

gives:

00001	С	This is a comment
00002		do 100 i=1,1000
00003	100	k = k+1
1		

XX excludes a group of lines from display.

```
00001 /*

xx002 * This is a second sample file for SEDIT

00003 *

xx004 *

00005 main()

00006 /* This file is 6 lines long */
```

gives:

00001 /* 00002 ------ 3 lines not displayed -----00005 main() 00006 /* This file is 6 lines long */

Overlaying Lines

The O or OO line commands specify the destination of data that is to be copied by the C and CC prefix commands or moved by the M and MM prefix commands.

Only blanks characters in the lines specified with O or OO are overlaid with corresponding characters from the source lines specified with the C, CC, M or MM prefix commands. Only characters within the column boundaries specified with the ZONE command are overlaid.

The number of source and receiving lines may be different. If there are more receiving lines, the source lines are repeated until all the receiving lines are processed.

00000				
oo 001	1	1234	12345	1234567
00002	2	1234	12345	1234567
00003	3	1234	12345	1234567
oo 004	4	1234	12345	1234567
cc 005	5	abcdefgl	nijklmnopqr	stuvwxyzABCDEFGHI
00006			2 lines	not displayed
cc 008	б	ABCDEFGI	HIJKLMNOPQR	STUVWXYZabcdefghi

gives:

00000
00001 1 a1234fghij12345pqrs1234567ABCDEFGHI
00002 2 A1234FGHIJ12345PQRS1234567abcdefghi
00003 3 a1234fghij12345pqrs1234567ABCDEFGHI
00004 4 A1234FGHIJ12345PQRS1234567abcdefghi
00005 5 abcdefghijklmnopqrstuvwxyzABCDEFGHI
00006 2 lines not displayed
00008 6 ABCDEFGHIJKLMNOPQRSTUVWXYZabcdefghi

Writing Prefix Macros

SEDIT allows the user to write prefix macros, which are entered in the same way the built-in prefix commands are. There are several steps to follow to create a prefix macro:

- Create an S/REXX or an external macro. For example, we will discuss the making of the supplied uumac.sedit S/REXX macro. This macro will be saved in a specific macro directory.uumac is the {install-dir}/xmac/uumac.sedit file.
- Issue a HASH {install-dir}/xmac (in this example) command. This HASH command is automatically issued by the profile.sedit standard initialization macro. We recommend the user create a specific directory for the user's macros.
- Create synonyms for that uumac macro. For example:

prefix	synonym	u	uumac
prefix	synonym	uu	uumac
prefix	synonym	1	uumac
prefix	synonym	11	uumac
prefix	synonym	U	uumac
prefix	synonym	UU	uumac
prefix	synonym	L	uumac
prefix	synonym	LL	uumac

Once the macro terminates, **SEDIT** restores the current line and the current file.

To actually modify the current line, a prefix macro must issue a command such as:

:12pending on /

Once all the prefix macros end, the pending list is scanned and executed again: the / prefix command will be performed upon line 12. Line 12 will become the current line.

uumac.sedit is the following:

```
parse arg pref ff line op1 op2 op3
if pref ~= 'PREFIX' then
 { 'emsg uumac: must be invoqued as a PREFIX macro.'
   exit
 }
select
 when ff = 'SHADOW' then
  { 'emsg uumac: not on a shadow line.'
    exit
  }
 when ff = 'CLEAR' then
  { 'msg uumac: aborted.'
    exit
  }
 when ff = 'SET' then
  { parse source . . . . name .
    if lower(name[1]) = 'l' then cmd = 'command lowercas'
    else
                                 cmd = 'command uppercas'
    if length(name) = 1 then
     { /*
        * Simple form macro (L or U)
        * /
        ':'line
        if op1 = '' then op1 = 1
        cmd op1
        exit
     }
    /*
     * Double form macro (LL or UU)
     * /
    'extract/pending block' name ':0 :'line
    if pending.0 ~= 0 then
     { ':'pending.1' pending off'
       cmd ':'line+1
     }
         ':'line 'command pending block' name
    else
    exit
  }
end
```

parse arg pref ff line op1 op2 op3

The macro receives the following arguments:

pref	PREFIX	flags a prefix call.
ff	SET	the selected line is a data line.
	SHADOW	the selected line is a shadow line. The corresponding file line is not visible.
	CLEAR	the user has cleared a pending macro by typing spaces.
line		the line number on which the prefix macro was entered.
opl,	ор2, ор2	the macro operands, as described on the Prefix Commands section.

When name starts with a 1, the macro will translate the matched lines into lowercase, by using the <u>LOWERCAS</u> command. Otherwise, the <u>UPPERCAS</u> command will be used. When writing an external prefix macro, the user may use the <u>EXTRACT</u>/SOURCE/ facility to determine the name of the macro.

```
if length(name) = 1 then
{ /*
    * Simple form macro (L or U)
    */
    ':'line
    if op1 = '' then op1 = 1
    cmd op1
    exit
}
```

When the user enters a synonym to the uumac macro, name contains this synonym, allowing the macro to know if a single form (U) or a double form (UU) was used.

The single form is handled by executing the LOWERCAS or UPPERCAS command immediately.

Before a prefix macro starts, it is removed from the pending list. Therefore, the first time a double form macro, such as UU, is executed, it does not belong to the pending list, and pending.0 is set to 0. The ':'line 'command pending block' name command places this macro in the pending list again.

The second time UU will be executed, pending. 0 will not be 0, and uumac will execute the LOWERCAS or UPPERCAS command starting at the line the first UU string was found up to the line the second UU string was found. Remember that UPPERCAS:12 means up to but not including the line 12.

See the <u>EXTRACT</u> command on page 249 and the <u>PENDING</u> command on page 329 for more information.

Using the Mouse on UNIX systems

On UNIX systems, the default MOUSEMODE value is OPENLOOK.

Using the mouse to scroll is explained in the section Moving Through a File on page 53.

There is another important mouse application: moving data. This **SEDIT** feature resembles the Sun Textedit mouse move-text feature.

Making a Linear Selection

The left mouse button starts a selection. One click selects a character which will appear in reverse video.

Clicking several times in less than a .4 second interval is called a multi-click.

Multi-click twice will select a word.

Multi-click 3 times will select a line.

The user can select a line by shifting the middle mouse button as well, which is faster than clicking 3 times.

The user can cancel any selection by shifting the left mouse button.

The middle mouse button allows the user to extend a selection.

The Sun Selection Related Keys

• COPY-SELECTION	L6
• PASTE-SELECTION	L8
• FIND-SELECTION	L9
• CUT-SELECTION	L10
• META-KEY	◊ key on type 4 or 5 keyboards, and Left and Right keys on old type 3 keyboards

The Other Workstations Selection Related Keys

- COPY-SELECTION F3
- PASTE-SELECTION F4
- FIND-SELECTION F1
- CUT-SELECTION F2
- META-KEY Left Alt key on IBM and SiliconGraphics. Compose key on DECstations. Left Extend Char key on HP keyboards.

Deleting the Selected Characters

To delete a selection, press the CUT key.

Note that there is no control character on the screen. To remove an entire line using the CUT key (L10/F2), multi-click 3 times or use the Shift-M2 mouse button.

If only the first and the last characters of the line are selected, the line will be cleared without deleting it.

Copying the Selected Characters

There are three ways to copy a selection.

• COPY then PASTE

- 1) Make a selection.
- 2) Use the COPY key (L6/F3) to store a copy of the characters selected in an internal buffer.
- 3) Move the cursor to the destination.
- 4) Depress the PASTE key (L8/F4).

Note that the cursor position is independent of the selection.

To copy text to the current cursor location, make a selection and depress COPY and PASTE. The cursor will be moved to the end of the text copied.

• SELECT and COPY

- 1) Make a selection.
- 2) Press and hold the COPY (L6/F3) key.
- 3) Move the cursor with the LEFT mouse button.
- 4) Release the COPY key.

Select and Copy is a faster way to copy selected text to a location other than where the cursor is located.

• PASTE and SELECT

- 1) Press and hold the PASTE (L8/F4) key
- 2) Make a selection.
- 3) Release the PASTE key.

Paste and Select is an alternate way to copy characters to the cursor location. It resembles the Sun secondary selections, but it uses the same buffer as the two previous methods.

To **<u>overlay</u>** the copy instead of inserting it, hold down the shift-key when proceeding. In this case, no lines will be inserted in the file.

Moving the Selected Characters

To move a set of selected characters, do a PENDING-DELETE selection by using Control-M1 and Control-M2, and then proceed to copy the text selected.

When using a color display, the selected characters will appear in pink.

Searching for Selected Characters

Once a selection is completed, the FIND key (L9/F1) may be used in various ways:

FIND	finds the next string identical to the string selected.		
Shift-FIND	finds backward the next identical string.		
Control-FIND	finds the next identical name: if the user selects "i" SEDIT will find it in "i=3" but not in "if (".		
Shift-Control-FIND			

finds backward the next identical name.

Making a Rectangular Selection

A selection made holding the META key will be rectangular instead of linear.

A rectangular selection can be used in the same way as a linear one, with a few differences:

- A line cannot be deleted, only its content is deleted.
- New lines are not inserted when the selection is more than one line.
- On a color display, the first character selected appears in green and the last one in orange.

Selecting Whole Lines

Multi-click 3 times will select a line. There are two shortcuts to select lines more easily:

- Press SHIFT and the middle mouse button. Dragging the mouse then will extend the selection line by line.
- Move the mouse on the fields located between the prefix fields and the data fields, and press the first mouse button. The mouse shape changes when it is located on the line selection fields. Dragging the mouse then will extend the selection line by line.

Moving Data to Other Windows

When **SEDIT** is running in the Open Look environment, data can be moved to other windows using the COPY and PASTE method.

When running the **MOTIF SEDIT** version, use the primary selections to move data to any XTERM windows.

To move text from **SEDIT** to XTERM, select the text, move the mouse into the XTERM window and press the middle mouse button.

To move text from XTERM to **SEDIT**, select the text, move the mouse into the **SEDIT** window and press Control-PASTE (F4 or L8).

When <u>MOUSEMODE</u> MOTIF is in effect, the middle mouse button may be used instead of Control-PASTE.

Using the Mouse in MOTIF Mode

When adding the following statement in the profile.sedit initialization macro file:

'mousemode motif'

the mouse buttons perform in the following way:

M1	starts a selection.
M1 (dragged)	extends a selection.
Shift-M1	extends a selection.
М2	pastes the current selection at the cursor location.
Control-M3	cancels the selection.

Using the Mouse on WINDOWS Systems

Note: The UNIX mouse settings described on page 123 are more powerful than the default WINDOWS settings. To use UNIX settings on WINDOWS, a 3 button mouse is needed. Then, add in the profile.sedit file the "set_unix" macro call.

Making a Linear Selection

On **WINDOWS** systems, the default <u>MOUSEMODE</u> value is WINDOWS.

In this mode, the keyboard and mouse behave in similar ways to most **WINDOWS** applications. The main difference is that the cursor can be moved independently of the selection. The Delete key removes only the character at the cursor location. To remove the selected characters, the x key must be used.

Clicking the left mouse button moves the cursor, without changing the current selection.

Dragging the left mouse button starts a selection, displaying a character which will appear in reverse video.

Clicking several times in less than a .4 second interval is called a multi-click.

Multi-click twice will select a word.

Multi-click 3 times will select a line.

The user can cancel any selection by shifting the right mouse button.

Shifting the left mouse button allows the user to extend a selection.

The Selection Related Keys

• COPY-SELECTION	Control-c
• PASTE-SELECTION	Control-v
• FIND-SELECTION	Fl
• CUT-SELECTION	Control-x
• META-KEY	Left Alt key

Deleting the Selected Characters

To delete a selection, press the CUT key.

Note that there is no control character on the screen. To remove an entire line using the CUT key $(^x)$, multi-click 3 times.

If only the first and the last characters of the line are selected, the line will be cleared without deleting it.

Copying the Selected Characters

Unlike with the OPENLOOK or MOTIF <u>MOUSEMODE</u> settings described on page 124, there is only one way to copy characters:

• COPY then PASTE

- 1) Make a selection.
- 2) Use the COPY key (^c) to store a copy of the characters selected in an internal buffer.
- 3) Move the cursor to the destination.
- 4) Depress the PASTE key (^v).

To **<u>overlay</u>** the copy instead of inserting it, hold down the shift-key when proceeding. In this case, no lines will be inserted in the file.

Note that the mouse and keyboard **UNIX** settings described on page 50 offer many more capabilities, but require a 3 button mouse.

Searching for Selected Characters

Once selection is accomplished, the FIND key (F1) may be used in various ways:

FIND	finds the next string identical to the string selected.
Shift-FIND	finds backward the next identical string.
Control-FIND	finds the next identical name: if the user selects "i" SEDIT will find it in "i=3" but not in "if (".

Shift-Control-FIND

finds backward the next identical name.

Making a Rectangular Selection

A selection made holding the Left Alt key will be rectangular instead of linear.

A rectangular selection can be used in the same way as a linear one, with a few differences:

- A line cannot be deleted, only its content is deleted.
- New lines are not inserted when the selection is more than one line.

Selecting Whole Lines

Multi-click 3 times will select a line. There are two shortcuts to select lines more easily:

- When using a 3 buttons mouse, press SHIFT and the middle mouse button. Dragging the mouse then will extend the selection line by line.
- Move the mouse on the fields located between the prefix fields and the data fields, and press the first mouse button. The mouse shape changes when it is located on the line selection fields. Dragging the mouse then will extend the selection line by line.

Undoing

On Sun workstations, the UNDO key is mapped to the L2 key. On others workstations, it is mapped to the F11 key.

Pressing the UNDO key undoes the last action. The user can undo until cancelling all modifications in the file.

Pressing Shift-UNDO restores the modifications undone by the UNDO key.

Note that all modifications undone are lost if the file is modified before pressing Shift-UNDO.

The undo memory is reset every time a file is saved.

Using MAKE

The following make.x macro is provided in the {install-dir}/xmac directory:

compile make \$argv

This allows the user to call the **UNIX** make program builder by simply issuing, for example, the following command directly within **SEDIT**:

```
====> make splitfile
```

The make macro calls the <u>COMPILE</u> **SEDIT** command using the make splitfile string as argument.

COMPILE will run the make program in a different subprocess, split the screen, display the make output, and call directly the <u>NEXTERROR</u> command.

The NEXTERROR command will attempt to parse the make output in order to load the file in error, and set the cursor upon the first line in error.

For example, the following make output could be displayed:

```
/home/m1/pro/no_file.compile
                                                                  Len · 8
                                                                            mod ·
no_file.compile_inc.h
00001 cc -c -o splitfile.o splitfile.c
00002 "./inc.h", line 5: illegal type combination
00003 "splitfile.c", line 24: syntax error at or near symbol ;
00004 Compilation failed
00005 *** Error code 1
00006 make: Fatal error: Command failed for target `splitfile.o'
====>
/home/m1/pro/inc.h
                                                                  Len:5
                                                                            mod:
no_file.compile inc.h
00001 int 1;
00002
00003 char *foo;
00004
00005 double int;
 1:Q
     2:E
          3 : Save
                  4:Sp 5:x 6:cu 7:U 8:D 9:? 10:h 12:= S-11:top S-12:bot
```

Typing ^ - (Control -) when running in a windowing environment, or F2 when running with an ASCII terminal will call the NEXTERROR command, which will load the splitfile.c file, and set the cursor upon line 24.

Using ASCII Terminals

At initialization, **SEDIT** checks the environment to start in the appropriate mode.

If the OPENWINHOME environment variable exists, it will start in the OPEN WINDOWS¹ mode. If OPENWINHOME does not exist, but DISPLAY does, it will start in the **MOTIF** mode. Otherwise, **SEDIT** starts in ASCII mode.

Before being able to use the function keys in ASCII mode, the user must use the mkesc utility described on page 8.

The ASCII mode offers only a subset of the **SEDIT** facilities:

- There is no mouse support, and therefore no menu and no button support.
- It is not possible for **SEDIT** to know the "shift", "control" and "meta" key state. Therefore, it is not possible to assign a specific command to function keys when holding down these modifier keys. For example, "set s-f1 flquit" will not make **SEDIT** call the "flquit" command when hitting "shift-f1". For the same reason, "set ^A command" will not be recognized. Only "set ^a command" will be recognized.
- The following "^cc" keys cannot be changed:
 - *`t* enters the tab character (instead of *`tab*).
 - ^i enters the next-field 3270 command.
 - ^j enters the up-field 3270 command.
 - ^f enters the down-field 3270 command (instead of the Alt key on Suns, and the right Control key on other workstations)
 - ^h enters a backspace.
 - ^l enters the line-feed separator character.
 - ^m is equivalent to the Return or Enter key.
- The tree editor is not supported.

^{1.} Sun only.

Using INTERNAL Macro Commands

An **SEDIT** internal macro is a file with an "x" filetype which is called from the **SEDIT** environment.

In order to make a file available for such usage, the user must first enter (for example in the "profile.sedit" initialization file) the "hash {dir1 {dir2} { \ldots }}" command.

Then, if the command searched for corresponds to the filename of one of these files, every line of this particular file will be executed as a command.

Note that macro names are case sensitive and SEDIT commands are not.

A macro can call another macro, but recursive calls are not allowed.

Note that if the user edits an "*.x" file, the user need not enter a "hash" command again after saving it, the internal hash table will be updated.

"hash" does not automatically start to avoid initialization delay because macro commands are optional.

Example: Assume there is a file named "/home/userl/xmac/xff.x" containing the line "x \$1.F". If the user includes the command "hash /home/userl/xmac" in the "profile.sedit" file, typing "xff prog1" will start editing file "prog1.F".

Variable Substitution

When executing a macro, SEDIT will replace any string like "\$i" with the argument number i passed at invocation. For a file "/usr/ml/test.f", and a macro call like "macroname arg1 arg2", the following substitutions will take place:

\$0	expands to	ma	macroname				
\$1	expands to	ar	argl				
\$argv	expands to	argl arg2					
\$fn	expands to	te	test				
\$lfn	expands to	/usr/ml/test					
\$ft	expands to	f					
\$fd	expands to	/usr/ml					
\$name	expands to	/usr/ml/test.f					
\$xhome	expands to	the installation directory (usually /home/xed or C:\Program Files\SEDIT)					
\$arch	expands to	the hardware dependent string described in Appendix B: Hardware String on page 677.					
Example:	"set the	^p shell currently	lpr : edited	\$name file	&" will by	l allow the typing	UNIX user to print "control-p".
Using EXTERNAL Macro Commands (UNIX Only)

An external macro command is a file with an "ex" filetype which is called from the **SEDIT** environment.

In order to make a file available for such usage, the user must first enter (for example in the "profile.sedit" initialization file) the "hash {dirl {dir2} {...}}" command. This macro can be written in any interpreted language able to call **UNIX** commands and retrieve their result, such as the C-SHELL language, or in C.

"reprofile.ex" is a particular file which is executed every time **SEDIT** loads a new file.

Using an Interpreted Language

SEDIT provides two modules which enable communication between the C-SHELL language (for example) and itself:

- sends arg1 {arg2} { . . . } sends the arg*i* parameters to **SEDIT** to be executed as **SEDIT** commands. A command failure will stop the process.
- extract arg retrieves from **SEDIT** the requested arg value.

arg may be any one of the words described on page 241.

SEDIT provides the /home/xed/xmac/Bye.ex macro:

```
#! /bin/csh -f
#
#
  Saves in the file "./restart.x" the files currently
#
  edited for further use by the "profile.sedit" macro
#
set a = 'extract ring'
if ( $a[2] == '0' ) then
  sends 'exit'
  exit(0)
endif
set a = (\$a[3-])
if (-e restart.x ) then
 rm restart.x
endif
touch restart.x
foreach ff ($a)
  echo $ff
  echo "xed $ff" >> restart.x
  sends "xed $ff"
  set line = 'extract line'
  echo ":$line[1]" >> restart.x
end
sends 'cancel' 'exit'
```

This macro saves every edited file name into the "restart.x" file, and then terminates the **SEDIT** session. Since the "profile.sedit" file searches for the "restart.x" file at **SEDIT** initialization, the next time the user starts **SEDIT** in the same directory, the macro "profile.sedit" will load the same files edited when the user left **SEDIT**, and set up the current line at its previous location.

Note that the user needs to process the command "hash \$xhome/xmac" in the "profile.sedit" file before calling this macro.

Usage notes:

- Commands sent to **SEDIT** must be embedded within quotes since every word passed to the 'sends' module will be treated as a single command.
- 'sends down 2' is not the same as 'sends "down 2"'.
- It will be faster to pass multiple arguments to the 'sends' module. 'sends "top" "down 2"' will perform faster that 'sends "top"' followed by 'sends "down 2"'.
- The macro file must have execution permission.
- If the macro attempts to read from its standard input, **SEDIT** must run in the foreground.
- An external macro can be stopped by typing Control-C.

Using the C Language (UNIX Only)

SEDIT provides the "/home/xed/lib/\$arch/libex.a" library, which allows the user to write external C macros.

This library provides the following routines:

```
#include "ex_sedit.h"
int sends(com)
    char *com;
char *extract(value)
    char *value;
void extract2(r_char, r_int, value)
    char **r_char, *value;
    int **r_int;
void free_extract(r_char, r_int)
    char ***r_char;
    int **r_int;
void ex_ini();
void ex_end(rc)
    int rc;
```

is located in the "/home/xed/include" ex_sedit.h directory. initiates the connection with **SEDIT**. It must be the ex ini first routine called. is used to send the null terminated string com to sends **SEDIT** to be executed as a command. sends will return the **SEDIT** return code. 0 will indicate that the command succeeded. is used to retrieve an internal SEDIT value. value extract is a keyword similar to those described in the section "Using an interpreted language". extract is an obsolete routine replaced by the more usable extract2 routine.

extract2	is used to retrieve an internal SEDIT value. value is a keyword similar to those described in the section "Using an interpreted language". r_char is allocated with the extracted values stored as characters. A NULL value may be passed when this information is not needed. r_int is allocated with the extracted values stored as integers. A NULL value may be passed when this information is not needed.
free_extract	releases previously extract2() allocated memory.
ex_end	terminates the connection with SEDIT , and then performs the "exit(rc)" system call.

The file "/home/xed/demo/demo_ex/invsel.c" is an example of such a macro:

```
/*
 *
    invsel: makes every visible line invisible, and vice-versa.
 * /
#include <stdio.h>
#include "ex_sedit.h"
#define DBX_SLEEP 0
main()
{
  char **r_display, buff[50], bu_vi[50], bu_invi[50];
  int *display, *line, *sele, lex;
 register i;
 ex ini();
#if DBX_SLEEP
  fprintf(stderr, "invsel: process %d sleeping\n", getpid());
  i = 1;
  while(i)
    usleep(100000);
#endif
  sends("preserve");
  sends("scope all"); /* We need it for scanning the file line by
line */
  sends ("bot");
  extract2(&r_display, &display, "display");
  extract2(NULL, &line, "line");
  sprintf (bu_invi, "select %d", display[2] + 1);
  sprintf (bu_vi, "select %d", display[1]);
  for (i=1; i<=line[1]; i++)</pre>
   { sprintf(buff, ":%d", i);
     sends(buff);
     extract2(NULL, &sele, "select");
     if (sele[1]>= display[1] && sele[1]<= display[2])</pre>
       sends(bu_invi);
     else
       sends(bu_vi);
     free_extract(NULL, &sele);
   }
  free_extract(&r_display, &display);
  free_extract(NULL, &line);
  sends("restore");
  sends("top");
  ex_end(0);
}
```

To create the macro "invsel.ex", use the following commands:

```
% cd /home/xed/demo/demo_ex
% cc -o invsel.ex invsel.c -I/home/xed/include
   -L/home/xed/lib/arch -lex -lc -lm
% chmod a+x invsel.ex
```

Where *arch* is the hardware dependent string described in Appendix B: Hardware String on page 677.

Then issue the command "hash /home/xed/demo/demo_ex" command within SEDIT. The user can now run invsel as an SEDIT command.

Using S/REXX Macro Commands

An **S/REXX** macro command is a file with an sedit filetype which is called from the **SEDIT** environment.

In order to make a macro file available for such usage, the user must first enter (for example in the profile.sedit initialization file) the "<u>HASH</u> {dir1 {dir2} {...}}" command described on page 281.

profile.sedit is a particular macro file which is searched for first in the current directory, then in the user's home directory (C:\ on **WINDOWS** systems) and finally in the **SEDIT** installation directory. profile.sedit tailors **SEDIT** to satisfy the user's preferences, for example to emulate an editor with which the user is familiar and to set the function keys to conform the user's workstation.

reprofile.sedit is a particular file which is executed every time **SEDIT** loads a new file.

All the **S/REXX** instructions and built-in functions are available within the **SEDIT** environment. The extract command described in page 241 may be used to transfer information from **SEDIT** to **S/REXX** variables.

Usage notes:

- Once made available with the <u>HASH</u> command, a macro may be used by typing its filename in the command field.
- Commands to be executed by **SEDIT** must be surrounded by single or double quotes, including the extract command, which is an **SEDIT** command and not an **S/REXX** command.
- The default macro address value is ADDRESS SEDIT. It can be changed by using the <u>ADDRESS</u> command described on page 506.
- When running S/REXX within SEDIT in a UNIX windowing environment such as OPEN WINDOWS or MOTIF, all input and output operations are redirected to the window SEDIT was started from.

In order to allow the input operations to execute properly, **SEDIT** *must run in the foreground*.

Starting **SEDIT** in the background with a command like "xed &" or "sedit" will make **SEDIT** hang every time a TRACE ? or a PULL instruction is executed.

• When running **S/REXX** within **SEDIT** on **WINDOWS**, all input and output operations are redirected to a console window created by **S/REXX**. This console window can be removed by the Special-Close Console menubar item.

S/REXX:macro commands

The {install-dir}/xmac/bye.sedit is an S/REXX macro example:

```
/*
   Saves in the file "./restart.x" the files currently
    edited for further use by the "profile.sedit" macro
 *
 * /
'prompt OK to quit ?'
if rc <> 0 then exit
'extract /ring'
if ring.1 <> '0' then
do
   'extract /name'
   if state('restart.x') then address unix 'rm restart.x'
  do i = 2 to ring.0
     call lineout 'restart.x', 'xed 'ring.i
     'xed 'ring.i
     "extract /line/rw"
     call lineout 'restart.x', ':'line.1
     call lineout 'restart.x', 'rw' rw.1
   end
   call lineout 'restart.x', 'xed 'name.1
   call lineout 'restart.x'
   'cancel'
 end
'exit'
```

The profile.sedit macro executes the restart.x macro created by the bye.sedit macro, allowing the user to restart **SEDIT** editing the same files the user was editing before leaving **SEDIT** by using the bye command.

Using EXTRACT

EXTRACT is used to retrieve information from **SEDIT**. EXTRACT can be used in 2 ways. The command method:

```
/*
 * downline: moves the cursor down one line
 *
 *
    Usage in a profile file:
             'autoi off'
             'set enter ignore downline'
 * /
signal on novalue
'extract/cursor/size/nbfile'
if nbfile.1 = 0 then return
if cursor.3 ~= -1 then
 { line = cursor.3 + 1
   if line <= size.1 then 'cursor file 'line 1 'priority
100'
 }
else
{ /*
    * Prefix zone ??
    * /
   'extract/prefix/lscreen'
   if prefix.1 ~= 'ON' then return
   if (prefix.2 = 'LEFT' & cursor.2 <= 5) |,
     (prefix.2 = 'RIGHT' & cursor.2 >= lscreen.2-5) then
    { line = cursor.1 + 1
       if line < lscreen.1-1 then 'cursor screen 'line 1
'priority 29'
   }
 }
```

EXTRACT is used as an **SEDIT** command ('extract/cursor') which sets the variables corresponding to the requested extraction (cursor.0, cursor.1, ...).

The built-in method:

```
/*
  downline: moves the cursor down one line
     Usage in a profile file:
             'autoi off'
             'set enter ignore downline'
 *
 * /
signal on novalue
if nbfile.1() = 0 then return
if cursor.3() \sim = -1 then
 { line = cursor.3 + 1
  if line <= size.1() then 'cursor file 'line 1 'priority
100'
 }
else
 { /*
    * Prefix zone ??
    * /
   if prefix.1() ~= 'ON' then return
   if (prefix.2 = 'LEFT' & cursor.2 <= 5) |,
     (prefix.2 = 'RIGHT' & cursor.2 >= lscreen.2()-5) then
    { line = cursor.1 + 1
      if line < lscreen.1()-1 then 'cursor screen 'line 1
'priority 29'
    }
 }
```

Calling any prefix.n() built-in performs an 'extract/prefix' command, and returns the prefix.n value. The remaining prefix.i variables can then be used directly.

Note: When extracting an important amount of data, such as with 'extract/file', use the built-in method only with the first call (nb_lines = file.0()), and then use the generated variables (data = file.23456). Using the built-in method every time (data = file.23456()) would extract the entire file repeatedely, which would result in a significant overhead.

Using the BATCH Option

When started with the -batch or -filec option, **SEDIT** runs in the following mode:

- The **SEDIT** window is not displayed.
- No profile is used at initialization. Use the "-p filename" option to use filename.sedit as initialization profile.
- Once **SEDIT** is done processing commands submitted with the "-c command" option, or processing the macro file submitted with the -filec option, **SEDIT** exits. **SEDIT** will quit all files, including unsaved modified files.
- Error messages are saved in the sedit.@messages file when **SEDIT** exits. The <u>MESSAGESDIR</u> command can be used to specify the location of this file.
- The following commands are silently ignored:

BUTTON	FLIST	SRCHANGE
COLOR	FLQUIT	TOOLBAR
COMPILE	FONT	TREE
COMPLETE	GET_PANEL	UNBUTTON
CREATE	HELP	XCSHELL
C_APLSTOP	LISTEN	XKSHELL
C_APLTRACE	MBUTTON	XSHELL
C_DUP	MENU	XTCSHELL
C_ENDCURL	MENUBAR	XWINDOWS
C_ENDLINE	NEXTERROR	
C_ENDS	PDFCOPY	
C_ENDSALL	PDFREPLACE	
C_ENDSR	PRINTSCREE	N
C_EXT	PROMPT	
C_LINEADD	READ	
C_LINEDEL	READSCREEN	
C_SCRH	REFRESH	
C_SCRJ	RFLIST	
C_SCRV	SCHANGE	
C_SPLIT	SCN	
C_STARTLINE	SCREEN	
C_STARTS	SCROLLBAR	
DY_ALL	SET	
DY_EXCLUDE	SETP	
DY_FIND	SOS	
DY_FONT	SPELL	
DY_SHOW	SPELL_ADD	
FLFILE	SPELL_NEXT	

• On **WINDOWS** systems, **PRINTFILE** is also silently ignored.

• The following commands behave differently:

AQUIT	performs as PQUIT.		
EXIT	unconditionally exits, without checking for modified files.		
FILE and SAVE	If the file name has been changed during the editing session so that it is identical to that of an existing file, or if the file has been modified by another user, FILE and SAVE do not overwrite the existing file.		
IMPCMSCP	is OFF by default.		
PRINTFILE (UNIX)	needs the PRINTER, DAEMON, WIDTH and HEIGHT parameters.		

UNIX Examples

xed -batch -c '"change/first/last"' -c file sample.c

first loads the sample.c file, then performs the change/first/last command, performs the file command and finally exits.

Bracketing a command with ' " and " ' is necessary because xed is a shell script.

xed runs in the foreground: if this command is issued from a program, the program will pause until xed exits.

Note that xed starts in **XEDIT** mode.

```
xed -batch -c '"mode command ispf"' -c '"change first last
all"' -c end sample.c
```

applies the **PDF** change command to sample.c.

xed -batch -c '"pdfchange first last all"' -c end sample.c

applies the **PDF** change command to sample.c.

xed -batch -p batch1

runs the batchl.sedit macro and exits. Note that typing "xed -batch -p batchl sample.c" would run batchl.sedit **before** loading sample.c.

xed -filec batch1 sample.c

loads the sample.c file, loads the batch1.sedit macro, runs batch1.sedit and exits.

WINDOWS Examples

xed -batch -c "change/first/last" -c file sample.c

first loads the sample.c file, then performs the change/first/last command, performs the file command and finally exits.

xed.exe runs in the background: if this command is issued from a program, the program will not pause until xed exits.

Note that xed starts in **XEDIT** mode.

```
xed -batch -c "mode command ispf" -c "change first last
all" -c end sample.c
```

applies the **PDF** change command to sample.c.

```
xed -batch -c "pdfchange first last all" -c end sample.c
```

applies the **PDF** change command to sample.c.

xed -batch -p batch1

runs the batch1.sedit macro and exits. Note that typing "xed -batch -p batch1 sample.c" would run batch1.sedit **before** loading sample.c.

xed -filec batch1 sample.c

loads the sample.c file, loads the batch1.sedit macro, runs batch1.sedit and exits.

Note: Windows considers single quotes as being part of an argument, so -c 'sort' for example will pass 'sort' instead of sort to **SEDIT**. Use double quotes if you need to pass commands with embedded blanks.

SEDIT Command Reference Guide

Commands are entered in the COMMAND FIELD. They are executed with the "Return" or "Enter" key.

Several commands can be entered at the same time using the line-feed separator.

This character will appear as a period. You can disable this feature or change the separator with the <u>SEP</u> or <u>LINEND</u> command. The <u>LINEND</u> command on page 298 explains how to enter the line-feed character.

For example, "xf test./var1" will start editing the "test.f" file and then search for a "var1" string.

Throughout the command reference guide, the following file naming convention is used:

For any file such as "/usr/m1/test.f":

"/usr/ml"	is called	"filedirectory".
"test"	is called	"filename".
"£"	is called	"filetype".

Most commands assume the current line location as a starting position.

The current line is usually displayed in red at the eighth physical line of the screen, and the corresponding prefix field appears bold-faced.

Variable Substitution

For any command except "set" or "button", and for a file "/usr/ml/test.f", the following substitutions will take place:

\$fn	expands to	test
\$lfn	expands to	/usr/ml/test
\$ft	expands to	f
\$fd	expands to	/usr/ml
\$name	expands to	/usr/ml/test.f
\$xhome	expands to	the installation directory (usually /home/xed or C:\Program Files\SEDIT)
\$arch	expands to	the hardware-dependent string described in Appendix B: Hardware String on page 677.

Avoiding Variable Substitution

When the \$ sign is escaped with a backslash, substitution does not occur:

\\$fn expands to	\$fn
arch expands to	\sun4 for a SPARC workstation.
c/\\$fd/\\$arch	changes the \$fd string with the \$arch string.

When <u>ARBCHAR</u> is set to ON \$, variable substitution does not occur within the <u>ALL</u>, <u>CHANGE</u>, <u>CLOCATE</u>, <u>CDELETE</u>, <u>CN</u>, <u>SCHANGE</u>, <u>SCN</u>, <u>/</u>, and -/ commands, which use \$ as arbitrary character.

The \underline{MODE} EXPAND command described on page 321 allows to disable the variable substitution.

ACCess - Add Directory To the Path

ACCess dir {dir2 { \ldots }}

ACCESS adds the various diri directories to the path in which SEDIT looks for files.

If diri does not start with a standard directory indicator (/.~), **SEDIT** will search first in the current directory and then through the directories described in the cdpath. See the DACCESS command for more information on the cdpath.

If diri contains blanks, it must be surrounded with quotes or double quotes. If a directory contains a quote or a double quote, the quote must be escaped with a backslash.

Exam	ples:	Assume the home directory is "usr/m1" and the current directory is	
		"/usr/ml/d	irl".
acc	dir2	will access	/usr/ml/dir2 directory
acc	dir2	a second time	will move /usr/ml/dir2 in second position.
acc	~/dir3	will access	/usr/m1/dir3 directory
acc	./dir4	will access	/usr/ml/dirl/dir4 directory
acc	/dir4	will access	/usr/dir4 directory
acc	"c:\Prog	gram Files"	will access the WINDOWS Program Files directory.
acc ~/quote\"dir will access the ~/quote"dir directory.			
acc ~/foo ~/test will access these 2 directories.			
The u	ser will rec	eive the messag	ge" Accessed in xx".

See the directory editor **FLIST** section for "xx" use.

Reordering Accessed Directories

Accessing the same directory twice places it in second position in the path. The first position is always the current directory.

This may be useful when files with the same name exist in different directories, and the user wants to edit in priority files within a given directory.

For example, there may be a wsrc directory containing **WINDOWS** source files, and a msrc directory containing sources files for the same project in the **MOTIF** environment. The current directory might be either a wobj or a mobj directory.

Before working with the **MOTIF** files, issue an "acc msrc" command. Similarly, "acc wsrc wsrc" would place the wsrc directory before the msrc directory.

See Also: <u>DACCESS</u>, <u>DRELEASE</u>, <u>RELEASE</u>, <u>SHOWPATH</u>, <u>SHOWCDPATH</u>

Add - Add Lines

Add $\{N\}$

inserts 1 or N line(s) starting at the current line location.

Scope: Display

Return Codes: 0 Normal 5 Invalid Number ALl { target } selects the lines containing the target specified.

Scope: Display

If target is not specified, **SEDIT** will set the selection level for every line in the file to the upper value of the DISPLAY range, making all of them visible.

If target is specified, **SEDIT** will set the selection level for every line currently in the scope matching this target to the upper value of the DISPLAY range, and to this value plus one for all the other lines, hiding them. **SEDIT** will then put <u>SCOPE</u> DISPLAY in effect, and select the first line displayed as the current line. With <u>SCOPE</u> DISPLAY in effect, lines that are excluded from the display are also excluded from processing by most **SEDIT** commands and prefix commands. With <u>SCOPE</u> ALL in effect, all lines will be processed. If <u>SHADOW</u> ON is in effect, a shadow line appears on your display wherever lines have been excluded.

target may be one of the following:

- /string{/} will select every line containing string. Note that the last / is optional unless string ends with a / or a blank.
- ~/string{/} will select every line not containing string.
- \string{/} will select every line containing the name string.
- ~\string{/} will select every line not containing the name string.
- $r/exp{/}$ will select every line matching the regular expression exp.
- $\sim r/\exp\{/\}$ will select every line not matching the regular expression exp.
- Blank will select every blank line.
- ~Blank will select every non-blank line.

See the R/ command for a complete regular expression syntax description.

It is possible to mix several targets by using the AND (&) or the OR (|) operator.

& and | characters are treated as logical characters when enclosed with a valid delimiter, such as '/' or 'r/'.

To imbed an & or a | character within a target such as "&/" where the & is not to be considered as a logical operator, the user must escape the logical character with a \backslash .

Examples:	all i/k	will select every line containing the names i or k.
		"if (j==1)" will not be selected.
		" $i=3$ " and " $k++$ " will be.
	all /if/&\k	will select every line containing the string if
		and the name k. "if $(k==3)$ " will be selected.
	all ~∖i	will select every line not containing the name i.
	all //**//	will select every line containing the string /**/.
		Note that the last / is required here because the
		string ends with a /.
	all b	will select every blank line.
	all r/[A-Z]	will select every line containing an uppercase letter.
	all/str/\&/a,	/ will select every line containing "str/&/a".

Return Codes:	0	Normal
	2	Target not found
	5	Invalid Operand

See Also: DISPLAY, DY ALL, EXCLUDE, R/, SCOPE, SELECT, SHADOW, SHOW, VISIBLE

ALT - Change The Number of Alterations

ALT {NA {NS}} changes the number of alterations.

Scope: File

If NA is specified, the number of alterations that have been made to the file since the last AUTOSAVE operation is set to NA.

If NS is specified, the number of alterations that have been made to the file since the last save operation is set to NS. If NS is 0 and SAVECLEARUNDO is set to ON, the undo memory is cleared.

Used without arguments, ALT displays the number of alterations that have been made to the file since the last AUTOSAVE operation and since the last save.

See Also: <u>AUTOSAVE</u>, <u>SAVECLEARUNDO</u>

APL - Pass a Command to APL

APL {command}

APL transmits the command string to **Dyalog APL** for execution and displays the possible result in the message field.

Used without parameter, APL returns to Dyalog APL.

To get back to **SEDIT**, the user must type the $\rightarrow \square LC$ APL instruction.

Note: It is not necessary to type APL if command starts with " ρ " or " \Box ".

ARBchar - Set Arbitrary Character

```
ARBchar ON | OFF { char }
```

defines an arbitrary character to be used by string matching commands.

Initial value: OFF \$ Level: Global

ARBCHAR without arguments displays the current status.

When ARBCHAR is ON, the ALL, CHANGE, CLOCATE, CDELETE, CN, SCH, SCN, /, and -/ commands use the char character as an arbitrary separation character. The variable substitution described on page 148 will not occur.

Examples: /the\$plane/ will locate the big plane as well as the last plane. clocate/[\$] will locate the first bracketed expression.

Every time an arbitrary character is matched with a string in a change command, the matched string is memorized in an internal buffer, and will be used to replace the equivalent arbitrary character found in the second string passed to the change command.

Examples: If the scanned file contains the following line:

all birds can fly in the sky

Typing:

c/all\$can\$sky/most\$may\$air

Changes the line to:

most birds may fly in the air

Typing:

c/\$string/string/

deletes all characters that precede string.

Typing:

c/string\$/string/

deletes all characters that follow string.

The second string may not contain more arbitrary characters than the first string.

See Also: <u>All</u>, <u>Change</u>, <u>Clocate</u>, <u>Cdelete</u>, <u>Cn</u>, <u>Schange</u>, <u>Scn</u>, <u>/</u>, <u>-/</u>

AUTOBin - Auto-Binary Feature

AUTOBin ON | OFF {c1 .. cn} sets the auto-binary feature ON or OFF.

Initial value: ON 0x09 0x0A 0x0C 0x0D 0x1A Level: Global

When AUTOBIN is set to ON, before loading a file, **SEDIT** checks the first 1024 characters of this file, and sets the BINARY mode to ON when it finds control characters not generally found within text files which value is lower than 0×20 , and different from the ci characters which are allowed in text files.

The ci characters can be specified in decimal (nn) or hexadecimal (0xnn or x'nn') format.

By default, **SEDIT** removes all trailing blanks in every line when loading a file, when editing a line and when saving a file. **SEDIT** also searches for the **WINDOWS** control characters ^M and ^Z, and automatically removes them from display setting the loaded file <u>FILECONV</u> to WINDOWS.

Trailing blanks are generally meaningless within text files, but may be essential within binary files. When BINARY is set to ON, **SEDIT** does not remove trailing blanks setting <u>KEEPBLANKS</u> to 1, does not check for **WINDOWS** file control characters and always sets the loaded file <u>FILECONV</u> to UNIX.

In addition, **SEDIT** does not write a new line character after the last file line. When reading a file in binary mode, if **SEDIT** finds a new line character at the end of the file, **SEDIT** displays an empty line at the end of the file.

Examples: autob autob on autob on 9 0x0a x'0c'

See Also: BINARY, FILECONV, KEEPBLANKS, SHBLANK, XBIN, XKB

AUTOExp - Auto-Expand Feature

AUTOExp ON | OFF

sets the autoexpand feature ON or OFF.

Initial value: ON Level: Global

When autoexpand is on, the data fields expand automatically when necessary. This happens when the cursor reaches the end of a line while typing, or when the last non-blank character reaches the end of a line in insertion mode.

It is useful to disable this feature if the user does not want to be allowed to write beyond a certain column.

For example, FORTRAN users may start **SEDIT** with the parameter "-width 78", and set the command "AUTOEXP OFF" in the "profile.sedit" file. This will create 72 column wide data fields when <u>PREFIX</u> is on.

See Also: **POWERINPUT**

AUTOI - Auto-Indent Feature

AUTOI ON | OFf { Stay | Nostay } sets the auto-indent feature ON or OFF.

Initial value: ON STAY Level: Global

When auto-indent is ON:

- Typing "Return" when the cursor is at the end of a data line without any character located in the command field will insert a line.
- When inserting lines, the cursor is automatically placed on the first inserted line. The indentation is identical to that of the previous line, and with the same number of starting tabulations.

When NOSTAY is in effect, typing "Return" when the cursor is on a data line, but before the last non-blank character will place the cursor on the command field. This behavior mimics the IBM **XEDIT** editor behavior.

AUTOI without arguments displays the auto-indent status.

Note: When the ENTER key is defined, by using the SET ENTER command, the auto-indentation is disabled.

See Also: <u>SET</u>

AUtosave - Auto-Save Feature

AUtosave N	OFF dir	sets or resets the automatic save feature.
Initial value: Level:	OFF Global	

When AUTOSAVE is ON, the current file will be saved in the directory dir each time the specified number N of alterations is reached.

The file will be saved with the name "autosaveppp_fd_fn.ft" where:

• ppp	is the current SEDIT process number.
• fd	is the current file filedirectory.
• fn	is the current file filename.
• ft	is the current file filetype.

AUTOSAVE without arguments displays the autosave status.

Note: When AUTOSAVE is in effect, the SAVE and FILE commands will erase the previous autosaved file. QUIT will not.

BACKUP - Set Backup Mode

BACKUP ON | OFF { STR } sets backup mode ON or OFF. *Initial value:* ON % *Level:* Global

By default, the FILE and SAVE commands save the previous content of the current file into a backup file by appending a % character to the file's name.

When BACKUP is OFF, **SEDIT** erases the backup file after a successful save. Should an error happen during the save operation, the backup file would not be erased.

STR specifies the backup string.

If STR contains blanks, it must be surrounded with quotes or double quotes. If STR contains a quote or a double quote, the quote must be escaped with a backslash.

Examples:	backup off	
	backup on .back	
	backup on "% %"	the backup strings contains a blank.
	backup on \setminus '	the backup string is a simple quote.

See Also: <u>FILE</u>, <u>SAVE</u>

BAckward - Scroll Backward

BAckward	{N *}	scrolls up N pages; the current line becomes the last
		line displayed. This process is repeated N times.
Scope:	Display	
		(*1 1* .1 . 1*

BACKWARD 0 makes the last file line the current line.

BACKWARD * makes the top of file to be the current line.

When the current line is the top of file, and when MODE SCROLL WRAP is in effect, BACKWARD makes the last line to be the current line.

This command is mapped to the F7 key by default.

Return Codes:0Normal1Top Of File Reached5Invalid Operand

See Also: MODE

BEEP - Set Beep Mode

BEEP {ON | OFF} enables or disables the warning beep.

Initial value: ON

SEDIT sounds a warning beep when the user types an unknown command with IMPCMSCP set to OFF, and when a locate or change command does not find the target string.

BEEP OFF disables the warning beep.

BEEP without arguments displays the BEEP status.

BInary - Set Binary Mode

BInary ON | OFF {FT string} disables or enables binary mode.

Initial value: ON FT o a (UNIX)
 ON FT com obj lib exe dll (WINDOWS)
 OFF FT *
Level: File

By default, **SEDIT** removes all trailing blanks in every line when loading a file, when editing a line and when saving a file. **SEDIT** also searches for the **WINDOWS** control characters ^M and ^Z, and automatically removes them from display setting the loaded file <u>FILECONV</u> to WINDOWS.

Trailing blanks are generally meaningless within text files, but may be essential within binary files. When BINARY is set to ON, **SEDIT** does not remove trailing blanks setting <u>KEEPBLANKS</u> to 1, does not check for **WINDOWS** file control characters and always sets the loaded file <u>FILECONV</u> to UNIX.

In addition, **SEDIT** does not write a new line character after the last file line. When reading a file in binary mode, if **SEDIT** finds a new line character at the end of the file, **SEDIT** displays an empty line at the end of the file.

When not running in character mode, when SHBLANK is set to ON (the default), and when the last character in a line is a blank, **SEDIT** displays a thin vertical bar just after that last blank character.

If you specify FT string, this setting will become the default for every new file with a string filetype. If FT is *, this will be the default for any file. A period (.) may be used if no filetype is required. This setting is also applied to the current file, unless its filetype does not match FT.

To force the opening of a file in BINARY ON mode, the user can use the XBIN command.

Examples: bi on bi on ft o

SEDIT sets BINARY mode ON for files with an ". o" extension.

Notes: KEEPBLANKS ON is not sufficient to preserve binary files integrity. Use BINARY ON or XBIN instead.

Using BINARY ON on a file already loaded is not sufficient to preserve its integrity since trailing blanks removal and control character checking is done at load time before the file is actually displayed. Use either XBIN file or BINARY ON FT xx before loading file.xx.

When AUTOBIN is set to ON, **SEDIT** checks the file contents in order to set the binary mode automatically.

See Also: AUTOBIN, FILECONV, KEEPBLANKS, SHBLANK, XBIN, XKB

Bottom - Bottom of File

Bottom

selects the last line as the current line.

Scope: Display

BOUNDS - Set the Edit Boundaries

BOUNDS is a synonym for the <u>VERIFY</u> command. See page 435 for more details.

BUILTIN - Process a Built-in Command

BUILTIN is a synonym for the <u>COMMAND</u> command. See page 189 for more details.

BUtton - Create Button

BUtton string1 string2

creates a button using string1 as a label.

Available on: UNIX Batch Mode: Not Available

When selected with the left mouse button, the string "string2" is executed as a command. With this command, the "Control-line-feed" separator is disabled, allowing the user to program several commands on the same button.

Example: bu COMP shell cc -g -c -o \$fn.o \$fn.c & Clicking on COMP will compile the C program currently edited.

See Also: <u>MBUTTON</u>, <u>UNBUTTON</u>, <u>LINEND</u>, <u>SEP</u>

CANcel (XEDIT MODE)- Abandon Files

XEDCANcel

CANcel

abandons all unmodified files.

When <u>MODE</u> COMMAND XEDIT is in effect, CANCEL calls the XEDIT mode XEDCANCEL command. PDFCANCEL may be used to call the ISPF/PDF mode CANCEL command.

CANcel (ISPF MODE)- Cancel Edit Changes

PDFCANcel

CANcel

abandons the current file, without saving any of the changes.

When <u>MODE</u> COMMAND ISPF is in effect, CANCEL calls the ISPF mode PDFCANCEL command. XEDCANCEL may be used to call the XEDIT mode CANCEL command.

PDFCANCEL is identical to the XEDIT <u>QQUIT</u> command described on page 345.

CAppend - Append Text

CAppend {text} appends text to the end of the current line.

If text is not specified, the column pointer will be placed after the end of the current line. text starts after the first blank following the command cappend, which allows the user to enter blanks. The column pointer will be placed under the first appended character.

Example:

Current line:

```
00001 i = 3
<...|...1...+...2...+...3...+...4...+...5...+...6
====> CAPPEND ; /* This was a syntax error */
00001 i = 3 ; /* This was a syntax error */
<...+|...1...+...2...+...3...+...4...+...5...+...6</pre>
```

CAPS {ON | OFF }

enables or disables case conversion.

Initial value: OFF Level: File

CAPS without argument is the same as CAPS ON.

When CAPS ON is in effect, **SEDIT** will translate lowercase letters to uppercase whenever data is retrieved for editing.

When CAPS OFF is in effect, SEDIT respects the capitalization.

CAPS applies to the current file, and is an ISPF/PDF compatible subset of the XEDIT <u>CASE</u> command.

To automatically set CAPS ON for every new file, the user may enter the following command:

case u ft *

See Also: <u>CASE</u>, <u>CHANGE</u>, <u>CN</u>, <u>SCH</u>, <u>SCN</u>, <u>SFIND</u>, <u>R/</u>, <u>R-/</u>, <u>/</u>, <u>-/</u>, λ , <u>-</u>

CASE - Case Respect

CASE {Mixed|Uppercase} {Respect|Ignore} {CRespect|CIgnore} {SRespect|SIgnore} {Ft string}

enables or disables case respect.

Initial value: Mixed Respect CRespect SRespect ft * Level: File

If CASE UPPERCASE is in effect, **SEDIT** will translate lowercase letters to uppercase.

If FT string is specified, this setting will become the default for every new file with a string filetype. If FT is *, this will be the default for any file. If FT is a period, it will concern files with no filetype. This setting is also applied to the current file, unless its filetype does not match FT.

Examples:	case	u	r ft	f	will create FORTRAN uppercase files.
	case	r	ft *		
	case	i	ft .		

If CASE IGNORE is in effect, **SEDIT** will not consider capitalization when searching strings.

Example: case i /Old/ will find old.

If CASE CIGNORE is in effect, **SEDIT** will not consider capitalization when changing strings.

Example: case ci c/Old/new/ will change old with new.

If CASE SIGNORE is in effect, **SEDIT** will not consider capitalization when the <u>SORT</u> command is applied.

```
Example: case si
sort * will sort the current file ignoring capitalization.
```

See Also: <u>CAPS</u>, <u>CHANGE</u>, <u>CN</u>, <u>SCH</u>, <u>SCN</u>, <u>SORT</u>, <u>SFIND</u>, <u>R/</u>, <u>R-/</u>, /, <u>-/</u>, Δ , <u> $-\Delta$ </u>

CD - Change Directory

CD directory-name

changes the current directory.

If the directory is not valid, an error message is displayed.

If directory-name does not start with a standard directory indicator (/. \sim), **SEDIT** will search first in the current directory and then through the directories in the cdpath accessed with the <u>DACCESS</u> command.

If directory-name contains blanks, it must be surrounded with quotes or double quotes. If a directory contains a quote or a double quote, the quote must be escaped with a backslash.

Examples: Assume the home directory is /usr/m1, and the current directory is /usr/m1/dir1.

cd	dir2	will switch to	/usr/m1/dir2 directory
cd	~/dir3	will switch to	/usr/ml/dir3 directory
cd	./dir4	will switch to	/usr/ml/dirl/dir4 directory
cd	/dir5	will switch to	/usr/ml/dir5 directory
cd	"c:\Prog	ram Files"	
		will switch to	c:\Program Files

See Also: DACCESS

CDElete - Delete Characters

CDElete c-target	deletes	characters	starting	at	the	current	column
	pointer	position up	to, but n	ot i	nclu	ding, the	column
	target c	-target.					

Scope: Display

The target must be in the <u>ZONE</u> range in order to be located.

c-target may be one of the following:

:N	moves the column pointer to column N.
-N	moves the column pointer N columns to the left.
$\{+\}N$	moves the column pointer N columns to the right.
/text{/}	searches the string text.
-/text{/}	searches backward the string text.
/	<pre>searches the word text. "\i/" will spot "i" in "i=3" but not in "if(".</pre>
-\text{/}	searches backward the word text.

If <u>STREAM</u> ON is in effect, **SEDIT** searches each line in the file. If STREAM OFF is in effect, **SEDIT** searches only the current line.

Example:

```
Current line:

00001 if ( a == 1 || b == 2 )

<...+...1..|.+...2...+...3...+...4...+...5...+...6

====> cde / )

00001 if ( a == 1 )

<...+...1...+...2.|..+...3...+...4...+...5...+...6
```

See Also: $\underline{\text{STREAM}}$, $\underline{\text{ZONE}}$

CEnter - Center Text

CEnter	{target}	centers text defined by target operand.
Scope:	All	

Scope:

CENTER reformats a portion of the current file defined by the target operand. CENTER centers the text within the current margins defined with the MARGINS command.

target may be one of the following:

All	The entire file is formatted.
Sel	Centers the selected lines. If the selection is rectangular, CENTER centers the contents of the selected area, the text outside the selection not being modified.
:N	Up to but not including the line N.
+N	Down N lines.
-N	Up N lines.
+* or *	Down to the end of file.
_ *	Up to the top of file.
.symb	Up or Down to the line which has been assigned the .symb symbolic name by using the POINT command, or a .symb prefix command.
string expression	Defines a group of characters to be located.

The general format of a string expression is the following:

{+|-}{~}/string1{/{&}|{|}{~}/string2 }

See the **LOCATE** command on page 300 for a precise string expression definition.

When target is not specified, CENTER formats the line corresponding to the cursor location. When the cursor is not located upon a line of the current file, CENTER reformats the current line.

Examples:	CENTER	
	CENTER	all
	CENTER	sel
	CENTER	/str/

See Also: FLOW, FORMAT, LEFTADJUST, LOCATE, MARGINS, POWERINPUT, RIGHTADJUST

CENTER_End - End Connection with Codecenter

CENTER_End

terminates a connection with the CodeCenter 4.x software¹.

Available on: UNIX

This command makes **SEDIT** stop listening on the socket opened with the CENTER_INIT command. It also makes **SEDIT** stop being the current CodeCenter EDIT session.

Note that **SEDIT** will notice if the CodeCenter process it is connected to ends, and automatically execute a CENTER_END command.

The CENTER_XXX commands are intended to be used with the CodeCenter 4.x release.

Please see the SABER_XXX commands when running CodeCenter 3.x.

See Also: <u>CENTER INIT</u>, <u>CENTER SEND</u>, <u>LISTEN</u>, <u>SABER INIT</u>, <u>SABER SEND</u>,

^{1.} Saber-C and CodeCenter are trademarks of CenterLine Software, Inc.

CENTER_Init - Initialize Connection with CodeCenter

CENTER_Init

starts a connection with the CodeCenter 4.x software¹.

Available on: UNIX

CodeCenter 4.x uses what is called a CLMS session to achieve communication between the core CodeCenter session and auxiliary services, such as an EDIT or COMPILE server.

If **SEDIT** finds that only one CLMS session is running, it will establish the connection with it immediately. If more than one CLMS session is running, **SEDIT** will display a fullscreen panel showing all the CLMS identifiers, and the user will have to click with the mouse on the identifier of the CLMS session to be talked to using the CENTER_Send command.

Establishing a connection with a CLMS session will make **SEDIT** the current EDIT server. All editing requests made within CodeCenter will be sent to **SEDIT**.

The CENTER_XXX commands are intended to be used with the CodeCenter 4.x release.

Please see the SABER_XXX commands when running CodeCenter 3.x.

Note that since CENTER_Init is dependent on another vendor's product, future releases of CodeCenter may not be compatible with this interface.

See Also: <u>CENTER END</u>, <u>CENTER SEND</u>, <u>LISTEN</u>, <u>SABER INIT</u>, <u>SABER SEND</u>

^{1.} Saber-C and CodeCenter are trademarks of CenterLine Software, Inc.

The CodeCenter integration is not available on all platforms and all operating systems.
CENTER_Send - Send Command to CodeCenter

CENTER_Send cmd

sends cmd to the CodeCenter¹ CLMS session which has been recognized by the CENTER_INIT command.

Available on: UNIX

If no connection has been established with a CenterLine CLMS session, **SEDIT** executes a CENTER_INIT command. Then, **SEDIT** sends cmd to that session.

The file "sedit.menu" contains the following lines to uncomment if you are using CodeCenter:

```
"CENTER" MENU

"load " MENU

".c" center_send load $fn.c

".o" center_send load $fn.o

"load " END

"unload" center_send unload $fn

"swap " center_send swap $fn

"stop " MENU

"stop in" center_send stop in $fn

"stop at" Center_stopat

"stop " END

"ini " center_init

"list " center_send list $fn

"end " center_end
```

^{1.} Saber-C and CodeCenter are trademarks of CenterLine Software, Inc.

Center_stopat is the "\$xhome/xmac/Center_stopat.ex" macro, and sets a stop in the current file at the cursor location:

```
#! /bin/csh -f
#
# Center_stopat: sets a stop at the cursor line
#
set cursor = 'extract cursor'
if ( $cursor[4] == -1 ) then
    sends 'emsg .... Center_stopat: invalid cursor position'
    exit 0
endif
set fname = 'extract fname'
set ftype = 'extract fname'
set a = 'center_send stop "'"$fname[2]""$ftype[2]"'":'$cursor[4]
sends "$a"
```

The CENTER_XXX commands are intended to be used with the CodeCenter 4.x release.

Please see the SABER_XXX commands when running CodeCenter 3.x.

See Also: <u>CENTER END</u>, <u>CENTER INIT</u>, <u>LISTEN</u>, <u>SABER END</u>, <u>SABER INIT</u> <u>SABER SEND</u>

CFirst - Move Column Pointer

CFirst

moves the column pointer to the beginning of the zone.

See Also: <u>ZONE</u>

Change (XEDIT MODE) - Change String

Change /string1/string2{/{target $\{N | *\} \{P\}}$ } XEDChange

changes string1 with string2.

Scope: Display

When <u>MODE</u> COMMAND XEDIT is in effect, CHANGE calls the XEDIT mode XEDCHANGE command. PDFCHANGE may be used to call the ISPF/PDF mode CHANGE command.

/ may be replaced with any delimiting character that does not appear in the character strings involved in the replacement.

target defines the number of lines to be scanned for a match. Lines are changed starting with the current line, up to but not including the target line. target may be one of the following:

:N	Up to but not including the Nth line.
N or +N	N lines.
+* or *	The end of file.
.symb	The line which has been assigned the .symb symbolic name by using the POINT command, or a .symb prefix command.
string expression	Defines a group of characters to be located.

The general format of a string expression is the following:

{+|-}{~}/string1{/{&}|{|}{~}/string2}

See the **LOCATE** command on page 300 for a precise string expression definition.

When target is omitted, all lines between the current line and the end of file will be scanned. However, if MODE CHANGE ONE is in effect, only the first line will be changed.

N is the number of occurrences of string1 to be changed on each line.

If omitted, all occurrences of string1 will be changed. However, if <u>MODE</u> CHANGE ONE is in effect, only the first occurrence will be changed.

If specified as *, all occurrences of string1 will be changed.

P is the relative number of the first occurrence of string1 to be changed in each line. Its default value is 1.

When string1 is omitted, string2 is inserted in the column which has a value defined by the first <u>ZONE</u> command operand (initially 1).

When <u>HEX</u> ON is in effect, the string*i* operands may be entered as hexadecimal values.

c /i=2/i=3/	will turn "i=2" in "i=3"
c .a=b/3.a=c/3.	will turn "a=b/3" in "a=c/3"
c ./**/	will delete all " / * * / " strings
c /test// :100 12	will delete the second "test" occurrence in
	each line until line 100
c //string	will insert string in the first zone column
c /x'31'/x'32'	with HEX ON in effect, changes all "1" with "2".
c/k/i//if	will turn "k" in "i" until the first line containing the "if" string.
arbchar on @	
zone 25 40	
c/@//**	will remove the columns 25 to 40.
	<pre>c /i=2/i=3/ c .a=b/3.a=c/3. c ./**/ c /test// :100 12 c //string c /x'31'/x'32' c/k/i//if arbchar on @ zone 25 40 c/@//**</pre>

If CASE CIGNORE is in effect, **SEDIT** will not consider capitalization when changing strings.

Example:	case ci	
	c/Old/new/	will change old with new.

- Note: The <u>ZONE</u> command allows the user to choose the starting and ending columns to be scanned.
- See Also: <u>ARBCHAR</u>, <u>BEEP</u>, <u>CASE</u>, <u>CN</u>, <u>HEX</u>, <u>LOCATE</u>, <u>MODE</u>, <u>RCHANGE</u>, <u>SRCHANGE</u>, <u>SCNANGE</u>, <u>SCN</u>, <u>STAY</u>, <u>ZONE</u>

Change (ISPF MODE)- Change String

Change	str1	str2	{range}	{ <u>next</u>	}	{ <u>CHARS</u> }	{X }	${col1}$	$\{col2\}$
PDFChange				{ALL	}	{PREFIX}	$\{NX\}$		
CHG				{FIRST	}	{SUFFIX}			
				{LAST	}	{WORD }			
				{PREV	}				

When <u>MODE</u> COMMAND ISPF is in effect, CHANGE calls the ISPF mode PDFCHANGE command. XEDCHANGE may be used to call the XEDIT mode CHANGE command.

CHANGE changes str1 with str2.

When CHANGE encounters a group of nonblank characters separated by more than one blank, CHANGE attempts to maintain the positional relationship between groups.

For example, the following data and commands:

1 abcl def 333 zcr333 kfl ====> chg 1 AAA all ====> chg 333 B all

would result in:

AAA	abcAAA	def	
В	zcrB	kfl	

str1 and str2 may be one of the following:

(strl only) The string used with the last FIND/EXCLUDE/CHANGE command.

Simple string

*

Any series of characters not starting with a single or double quote (' or ") and not containing any embedded blanks. The search will be case insensitive.

Delimited string

Any string enclosed by single or double quotes. The search will be case insensitive.

Hexadecimal string

Any delimited string of valid hexadecimal characters, preceded or followed by the character X, such as X'3132' or '3132'x. The search will be case sensitive.

Character string

Any delimited string, preceded or followed by the character C, such as C'ab cd' or 'ab cd'c. The search will be case sensitive.

Picture string (str1)

Any delimited string, preceded or followed by the character P, such as P'ab cd' or 'ab cd'p. The search will be case sensitive. Within a picture string, the following special characters may be used:

- = means any character.
- ~ means any character that is not a blank.
- . means a character which generally cannot be displayed. **SEDIT** will consider this any character which has a decimal value of less than 32.
- # means any numeric character.
- means any non-numeric character.
- @ means any alphabetic character.
- < means any lowercase alphabetic character.
- > means any uppercase alphabetic character.
- \$ means any special character, neither alphabetic or numeric.

Picture string (str2)

Any delimited string, preceded or followed by the character P, such as P'ab cd' or 'ab cd'p.

Within a picture string, the following special characters may be used:

- = means the same character as in str1.
- < means the same character as in strl translated in lowercase.
- > means the same character as in strl translated in uppercase.
- str2 must be the same length as str1.

CHANGE considers the following arguments:

Two labels that identify the lines to be searched for.
 A label may be created by typing a .xxxx string on a prefix zone, or by using the XEDIT POINT command described on page 331.
 A label may also be one of the ISPF/PDF predefined labels:

.zfor.zfirst	the first line.
.zlor.zlast	the last line.
.zcsr	the cursor line

When omitted, range defaults to .zfirst .zlast.

- **NEXT** Starts at the first position after the current cursor location and searches forward. NEXT is the default. When the cursor is not located on the data, the search starts from the first displayed line.
- **ALL** Starts at the top of the file and searches forward to find all occurrences of the string.
- **FIRST** Starts at the top of the file and searches forward to find the first occurrence of the string.

LAST	Starts at the bo of the string.	ttom of the file and searches backward to find the last occurrence
PREV	Starts at the occurrence of starts from the	cursor location and searches backward to find the previous the string. When the cursor is not located on the data, the search last displayed line
<u>CHARS</u>	Locates str a	nywhere the characters match. This is the default.
PREFIX	Locates str a find ab mate	t the beginning of a word: thes "abc", but does not match "ab" or "cabd" or "dab".
SUFFIX	Locates str a find ab mate	t the end of a word: ches "cab", but does not match "ab" or "cabd" or "abc".
WORD	Locates str as a whole word: find ab matches "d ab e", but does not match "cabd" or "abc".	
х	Scans only lines that are excluded from the display.	
NX	Scans only lines that are not excluded from the display.	
col1 and	col2	
	The columns F BOUNDS settir	TIND is to search. When omitted, the columns are limited by the ng described on page 159.
Example:		
	chg p': could cha	>###str' p'<===abc' all nge"T123str" with "t123abc".
Return Code	es: 0 4	Normal String Not Found

5 * has been used on the first CHANGE call

- 6 Invalid Hexadecimal String
 - 7 Invalid Label
 - 12 Syntax Error

See Also: BOUNDS, EXCLUDE, FIND, SEEK, VERIFY

CInsert - Insert Characters

CInsert text inserts characters at the column pointer position. The column pointer must be in the <u>ZONE</u> range.

Example:

Current line: 00001 if (a == 1) <...+...1..|.+...2...+...3...+...4...+...5...+...6 ====> ci || a == 2 (one blank typed in after the 2) 00001 if (a == 1 || a == 2) <...+...1..|.+...2...+...3...+...4...+...5...+...6

See Also: <u>ZONE</u>

CLAst - Move Column Pointer

CLAst

moves the column pointer to the end of the zone.

Examples:

```
====> ZONE 2 30
Current line:
00001 i = 3;
    .<..|...1..+...2..+...>..+..4..+..5..+...6
====> CLAST
00001 i = 3;
    .<..+...1..+...2..+...|...+..4..+..5..+...6</pre>
```

See Also: <u>ZONE</u>

CLEARErrors - Clear Compiling Errors

CLEARErrors

removes the line symbolic names assigned by the <u>COMPILE</u> command.

See Also: COMPILE

CLocate - Locate Characters

CLocate c-target searches for c-target.

Scope: Display

CLOCATE scans the file searching for the column target c-target, and moves the column pointer to that target. The search starts with the column following or preceding the column pointer in the current line.

The target must be in the ZONE range in order to be located.

c-target may be one of the following:

:N	moves the column pointer to column N.
-N	moves the column pointer N columns to the left.
{ + } N	moves the column pointer N columns to the right.
/text{/}	searches the string text.
-/text{/}	searches backward the string text.
/	<pre>searches the word text. "\i/" will spot "i" in "i=3" but not in "if(".</pre>
-\text{/}	searches backward the word text.

If <u>STREAM</u> ON is in effect, **SEDIT** searches each line on the file. If STREAM OFF is in effect, **SEDIT** searches only the current line.

Example:

Current line: 00001 i = 3 <|..+...1...+...2...+...3...+...4...+...5...+...6 ====> CL/3 00001 i = 3 <...|...1..+...2...+...3...+...4...+...5...+...6

See Also: <u>STREAM</u>, <u>ZONE</u>

CLOSEConsole - Close the Console

Available on: WINDOWS

When an **S/REXX** macro uses a standard output statement within a **WINDOWS** environment, such as a SAY statement, **SEDIT** creates a console window to display the output.

CLOSECONSOLE removes such a console.

CMDline - Set the Command Line Position

CMDline ON | OFf | Top | Bottom changes the command line position. *Initial value:* ON BOTTOM *Level:* View

CMDLINE ON enables the command line on the screen at its previous location.

CMDLINE OFF removes the command line from the screen.

CMDLINE TOP sets the command line on the top of the logical screen.

CMDLINE BOTTOM sets the command line on the bottom of the logical screen.

When CMDLINE is OFF, using the HOME or CURSOR HOME command restores the command line in order to let the user process a command. Once the command is processed, the command line is removed. Using the ? command has the same effect.

The command line is always displayed when no file is currently being edited.

Note that the CURSOR HOME command is mapped to the F10 key, and the ? command is mapped to the F9 key.

Examples: cmd t cmdline off top

See Also: <u>CURSOR</u>, <u>HOME</u>, <u>?</u>, <u>?</u>I

CN - Change Name String

```
CN /string1/string2{/{target {N|*} {P}}}
changes name string1 with string2.
```

Scope: Display

A name is a string which is preceded or followed by an invalid C variable character. This command is very useful in modifying a variable.

/ may be any delimiting character that does not appear in the character strings involved in the replacement.

target defines the number of lines to be scanned for a match. Lines are changed starting with the current line, up to but not including the target line. target may be one of the following:

:N	Up to but not including the Nth line.
N or +N	N lines.
+* or *	The end of file.
.symb	The line which has been assigned the .symb symbolic name by using the POINT command, or a .symb prefix command.
string expression	Defines a group of characters to be located.

The general format of a string expression is the following:

{+|-}{~}/string1{/{&}|{|}{~}/string2 }

See the **LOCATE** command on page 300 for a precise string expression definition.

When target is omitted, all lines between the current line and the end of file will be scanned. However, if <u>MODE</u> CHANGE ONE is in effect, only the first line will be changed.

N is the number of occurrences of string1 to be changed on each line.

If omitted, all occurrences of string1 will be treated. However, if MODE CHANGE ONE is in effect, only the first occurrence will be changed.

If specified as *, all occurrences of string1 will be treated.

P is the relative number of the first occurrence of string1 to be changed in each line. Its default value is 1.

When string1 is omitted, string2 is inserted in the column which has a value defined by the first <u>ZONE</u> command operand (initially 1).

When <u>HEX</u> ON is in effect, the string*i* operands may be entered as hexadecimal values.

Example: cn /i/j/will turn name "i" in "j" but will leave unchanged string "if".

If CASE CIGNORE is in effect, **SEDIT** will not consider capitalization when changing strings.

Example: case ci cn/Old/new/ will change old with new.

- Note: The ZONE command allows the user to choose the starting and ending columns to be scanned.
- See Also: <u>ARBCHAR</u>, <u>CASE</u>, <u>CHANGE</u>, <u>HEX</u>, <u>LOCATE</u>, <u>MODE</u>, <u>SCN</u>, <u>STAY</u>, <u>ZONE</u>

COLor - Set Color

COlor ON OFF	enables / disables color.	
COlor field * co	olor associates a specific color with all fields when * is spec	vith the field area, or ified.
COlor colorid r	g b changes the red/green/blue colorid.	setting for the color
Initial value: ON Level: Globa	1	

Color off must be included in your profile.sedit file when you use a grey scale monitor.

field can be any of the fields listed below:

For the file editor:

Arrow	the arrow pointing to the command line.
CMdline	the line where the commands are entered.
CURLine	the current line.
CURrent	when no message is displayed, the message field shows the files currently in the editing ring. The file actually displayed will be highlighted with the color specified.
CURSor	the cursor and the display of the INSERT status.
Edited	when no message is displayed, the message field shows the files currently in the editing ring. The files not displayed will be highlighted with the color specified when modifed.
Filearea	the file data area, excluding the current line.
Idline	the file identification on line 1 on the logical screen.
MOd	the field indicating the number of file modifications.
MSgline	the field used to display messages.
Nocurrent	when no message is displayed, the message field shows the files currently in the editing ring. The files not displayed will be highlighted with the color specified when not modifed.
PDelete	the pending-delete selections.
POint	the symbolic names in the prefix area.
PEnding	the pending commands in the prefix area.
PFline	the function keys line.
PRefix	the prefix area.
REnd	the last character selected with a rectangular selection.
RStart	the first character selected with a rectangular selection.
SCale	the scale line.
SHadow	the shadow lines resulting from selective editing.
SIze	the field indicating the file size.
Tabline	the line displaying tabulations.

For the directory editor:

FL_Cmdline	the lines where the commands are entered.
FL_Directories	the lines where the accessed directories are displayed.
FL_Idline	the level identification on line 1 on the screen.
FL_MOde	the field where the file modes are displayed.
FL_MSgline	the field used to display messages.
FL_Names	the field used to display the filenames.
FL_Pfline	the function keys line.
FL_Removed	the files which have been removed by the ${\tt rm}$ command.
FL_Size	the field where the file sizes are displayed.

For the tree editor:

TR_Box	the color used to draw a box around a directory name.
TR_CPBox	the color used to draw a box after selecting it for a directory copy or move operation.
TR_CUrrent	the color used to draw a box around the current directory.
TR_HBox	the color used to highlight a box when moving the mouse pointer with a key depressed.
TR_HIdden	the color used to draw a box around a directory with hidden subdirectories.

color can be any one of the following colors:

Aquamarine	INdianred	Orange
BEige	Indigo	PALEGoldenrod
BLAck	KHaki	PALETurquoise
BLUe	LAwngreen	PInk
BRown	LEmonchiffon	PUrple
CAdetblue	LIGHTCyan	ROSybrown
CHArtreuse	LIGHTGOLDENRODYellow	ROYalblue
CHOcolate	LIGHTGoldenrod	Red
COral	LIGHTSEagreen	SADdlebrown
Cyan	LIGHTSLateblue	SALmon
DARKGOLdenrod	MAGENTA2	SIenna
DARKOLIvegreen	MAGenta	SLATEBlue
DARKSLATEBlue	MAROON2	SLATEGray
DARKSLATEGray	MARoon	SPringgreen
DEeppink	MEDIUMAquamarine	STeelblue
DImgray	MEDIUMSEagreen	TUrquoise
FIrebrick	MEDIUMSPringgreen	VIOLETRed
FOrestgreen	MIdnightblue	WHEat
GOld	MOccasin	White

Green	OLivedrab	Yellow
HOtpink	ORchid	

In addition, "color background r g b" and "color foreground r g b" may be used to change the background and foreground colors.

r g b can be any integer between 0 and 255. The WHITE and BLACK colors cannot be changed. WHITE is always 255 255 255, and BLACK 000.

Initial values (UNIX):

ARROW	PINK
CMDLINE	BLACK
CURLINE	RED
CURRENT	MAROON
EDITED	RED
FILEAREA	BLACK
IDLINE	MAROON
MOD	BLUE
MSGLINE	RED
NOCURRENT	BLUE
POINT	RED
PDELETE	MAGENTA2
PENDING	BLUE
PFLINE	MAROON
PREFIX	MAROON2
REND	ORANGE
RSTART	GREEN
SCALE	GREEN
SHADOW	BLUE
SIZE	MAROON
TABLINE	BLUE
FL_CMDLINE	BLACK
FL_DIRECTORIES	MAROON2
FL_IDLINE	MAROON
FL_MODE	BLACK
FL_MSGLINE	RED
FL_NAMES	BLACK
FL_PFLINE	MAROON
FL_REMOVED	BLUE
FL_SIZE	MAROON2
TR_BOX	MAROON2
TR_CPBOX	MAGENTA
TR_CURRENT	BLUE
TR_HBOX	RED

TR_HIDDEN

MAGENTA

AQUAMARINE	127	255	212
BACKGROUND	255	255	190
FOREGROUND	0	0	0
BEIGE	245	245	220
BLUE	0	0	255
BROWN	165	42	42
CADETBLUE	95	158	160
CHARTREUSE	127	255	0
CHOCOLATE	210	105	30
CORAL	255	127	80
CYAN	0	255	255
DARKGOLDENROD	184	134	11
DARKOLIVEGREEN	85	107	47
DARKSLATEBLUE	72	61	139
DARKSLATEGRAY	47	79	79
DEEPPINK	255	20	147
DIMGRAY	105	105	105
FIREBRICK	178	34	34
FOREGROUND	0	0	0
FORESTGREEN	34	139	34
GOLD	255	215	0
GREEN	0	255	0
HOTPINK	255	105	180
INDIANRED	205	92	92
INDIGO	0	115	255
KHAKI	240	230	140
LAWNGREEN	124	252	0
LEMONCHIFFON	255	250	205
LIGHTCYAN	224	255	255
LIGHTGOLDENROD	238	221	130
LIGHTGOLDENRODYELLOW	250	250	210
LIGHTSEAGREEN	32	178	170
LIGHTSLATEBLUE	132	112	255
MAGENTA	128	0	128
MAGENTA2	255	0	255
MAROON	232	157	0
MAROON2	133	74	0
MEDIUMAQUAMARINE	50	100	85
MEDIUMSEAGREEN	60	179	113
MEDIUMSPRINGGREEN	0	250	154
MIDNIGHTBLUE	25	25	112

MOCCASIN	255	228	181
OLIVEDRAB	107	142	35
ORANGE	192	б4	0
ORCHID	218	112	214
PALEGOLDENROD	238	232	170
PALETURQUOISE	175	238	238
PINK	185	125	107
PURPLE	128	0	178
RED	255	0	0
ROSYBROWN	188	143	143
ROYALBLUE	65	105	225
SADDLEBROWN	139	69	19
SALMON	250	128	114
SIENNA	160	82	45
SLATEBLUE	106	90	205
SLATEGRAY	112	128	144
SPRINGGREEN	0	255	127
STEELBLUE	70	130	180
TURQUOISE	32	112	104
VIOLETRED	8	32	144
WHEAT	245	222	179
WHITE	255	255	255
YELLOW	200	200	0

Initial values (WINDOWS):

ARROW	PINK
CMDLINE	BLACK
CURLINE	RED
CURRENT	MAROON
CURSOR	BLUE
EDITED	RED
FILEAREA	BLACK
FL_CMDLINE	BLACK
FL_DIRECTORIES	MAROON2
FL_IDLINE	MAROON
FL_MODE	BLACK
FL_MSGLINE	RED
FL_NAMES	BLACK
FL_PFLINE	MAROON
FL_REMOVED	BLUE
FL_SIZE	MAROON2
IDLINE	MAROON
MOD	BLUE

MSGLINE	RED	RED		
NOCURRENT	BLUI	BLUE		
PDELETE	MAGI	MAGENTA2		
PENDING	BLUI	BLUE		
PFLINE	MARC	DON		
POINT	RED			
PREFIX	MARC	DON2		
REND	ORAI	IGE		
RSTART	GREI	EN		
SCALE	RED			
SHADOW	BLUI	E		
SIZE	MARC	DON		
TABLINE	BLUI	C		
TR_BOX	MARC	DON2		
TR_CPBOX	MAGI	ENTA		
TR_CURRENT	BLUI	C		
TR_HBOX	RED			
TR_HIDDEN	MAGI	ENTA		
BACKGROUND	255	255	190	
FOREGROUND	0	0	0	
AQUAMARINE	127	255	212	
BEIGE	4	130	92	
BLUE	0	0	255	
BROWN	165	42	42	
CADETBLUE	95	158	160	
CHARTREUSE	10	184	57	
CHOCOLATE	210	105	30	
CORAL	255	127	80	
CYAN	0	181	181	
DARKGOLDENROD	184	134	11	
DARKOLIVEGREEN	85	107	47	
DARKSLATEBLUE	72	61	139	
DARKSLATEGRAY	47	79	79	
DEEPPINK	255	20	147	
DIMGRAY	105	105	105	
FIREBRICK	178	34	34	
FORESTGREEN	34	139	34	
GOLD	255	215	0	
GREEN	0	255	0	
HOTPINK	255	105	180	
INDIANRED	205	92	92	
INDIGO	0	115	255	

KHAKI	240	230	140
LAWNGREEN	124	252	0
LEMONCHIFFON	170	58	252
LIGHTCYAN	0	202	202
LIGHTGOLDENROD	238	221	130
LIGHTGOLDENRODYELLOW	223	26	174
LIGHTSEAGREEN	32	178	170
LIGHTSLATEBLUE	132	112	255
MAGENTA	128	0	128
MAGENTA2	128	128	0
MAROON	66	45	19
MAROON2	133	74	0
MEDIUMAQUAMARINE	50	100	85
MEDIUMSEAGREEN	60	179	113
MEDIUMSPRINGGREEN	0	250	154
MIDNIGHTBLUE	25	25	112
MOCCASIN	255	228	181
OLIVEDRAB	107	142	35
ORANGE	192	64	0
ORCHID	218	112	214
PALEGOLDENROD	238	232	170
PALETURQUOISE	175	238	238
PINK	185	125	107
PURPLE	128	0	178
RED	255	0	0
ROSYBROWN	188	143	143
ROYALBLUE	65	105	225
SADDLEBROWN	139	69	19
SALMON	250	128	114
SIENNA	160	82	45
SLATEBLUE	106	90	205
SLATEGRAY	112	128	144
SPRINGGREEN	0	255	127
STEELBLUE	70	130	180
TURQUOISE	32	112	104
VIOLETRED	8	32	144
WHEAT	245	222	179
WHITE	255	255	255
YELLOW	200	200	0

The macro {install-dir}/xmac/resetcolor.x may be used as a template for setting colors.

The macro $\{install-dir\}/xmac/reverse.xmay$ be used to work in reverse video mode.

COMmand - Execute a Command

COMmand	command	executes an SEDIT command without first checking
		if command is a macro or a synonym.

Normally, **SEDIT** gives priority to a macro or a synonym over a built-in command. COMMAND is useful to override a macro with the same name as a built-in command.

You may, for example, create a cd macro which will execute a set of <u>ACCESS</u> and <u>DACCESS</u> commands depending on the name of the directory passed to it, and then issue the real command cd command without calling itself recursively.

Return Codes:	nn	Return code of the command specified as operand
	-1	Command not found
	0	Normal

See Also: <u>MACRO</u>, <u>SYNONYM</u>

COMPIle - Compile a Program

COMPIle cmd {&}	executes the UNIX or WINDOWS command cmd,
	and displays its result in an SEDIT window.
COMPIle -Load	loads the sedit_compile.rules file.

Batch Mode: Not Available

Without a final &, COMPILE first executes the cmd string in a subshell, like the shell command would do.

If the file sedit_compile.rules has not yet been loaded, **SEDIT** loads it. Then, if the screen is not yet split, **SEDIT** splits the screen horizontally and displays the error messages issued by the command cmd in the upper screen.

SEDIT will match these error messages with the rules described in the sedit_compile.rules file. It will set the current line to the line containing the first error, and place the cursor on the current line.

Calling the <u>NEXTERROR</u> command afterwards will move the current line and the cursor to the next error in the file. The NEXTERROR command is assigned by default to the ^- key.

Every line in error will be assigned a symbolic name equal to its line number, displayed in red in the prefix area, and used by the NEXTERROR command. This allows NEXTERROR to find the lines in error even when the user adds or deletes lines. These symbolic names can be removed with the <u>CLEARERRORS</u> command.

With a final &, compile executes cmd in the background and displays the error messages in the window **SEDIT** was started from on **UNIX** systems¹.

On **WINDOWS** systems, the cmd application may create its own console.

COMPILE -LOAD searches for the sedit_compile.rules file in the current directory. If not found, **SEDIT** searches in the home directory and if still not found, in the installation directory. Once found, this file will be loaded and used as a pattern for error matching.

^{1.} This facility is not available on **UNIX** ASCII terminals, since the cmd output would overwrite the **SEDIT** screen.

This is an example of the sedit_compile.rules file on SUN workstations:

```
#
#
   Rules for FORTRAN files
#
f:
 line [0-9][0-9]*
F:
 line [0-9][0-9]*
#
  Rules for C files
#
#
c:
 line [0-9][0-9]*
 [0-9][0-9]*: Can't
#
# A rule for lint
#
 \.c([0-9][0-9]*)
h:
 line [0-9][0-9]*
 \.c([0-9][0-9]*)
 \c([0-9][0-9]*)
```

Blank lines or lines starting with a # are ignored.

f:

matches any file with a f filetype, or in other words, a FORTRAN file. The subsequent lines, until the next filetype descriptor, are regular expressions matching the error messages issued by the compiler. These rules must start with a blank or a tabulation, which will not be part of the rule.

See the R/ command for a complete regular expression syntax description.

For example:

line [0-9][0-9]*

matches a line with the string "line ", followed by at least one number between 0 and 9, such as:

"foo.f", line 1: Error: unclassifiable statement

The standard profile binds the xmac/smart_comp.sedit macro to the ^c key on UNIX stations, and on ^C (Shift-Control-c) on WINDOWS systems.

This macro checks for the current filetype, and calls the COMPILE command with the usual C, C++ or FORTRAN compiler.

The ^g key does the same using the debug version of this macro (xmac/smart_compd).

^G and ^C will compile the current file in the background on **UNIX** systems.

A compilation may be cancelled by hitting the ^c key again.

The user can unsplit the screen afterwards by hitting the ^w key.

Special Options

When finding an error, most compilers print first the name of the source file, and then the number of the line in error. Some compilers may print a line such as:

line23(13)

where line is not the name of the source file, and where the first number is not the error line number. To deal with such compilers, **SEDIT** accepts the following syntax within the rules file:

```
b:2 nosource
line[0-9][0-9]*([0-9][0-9]*)
```

The numerical value after the colon, 2 in this example, indicates that the second numerical value is the line number.

The **nosource** keyword indicates that the source file is not displayed within the error message.

See Also: <u>Clearerrors</u>, <u>C SCRH</u>, <u>C SRCRJ</u>, <u>C SCRV</u>, <u>MESSAGESDIR</u>, <u>NEXTERROR</u>, <u>R/</u>, <u>SCREEN</u>, <u>SHELL</u>

COMPLete - File Name Completion

COMPLete {Reverse} allows command line file name completion.

Batch Mode: Not Available

The COMPLETE command must be assigned to a function key, which is called here the trigger. When a partial file name is typed in the command field, hitting the trigger will make **SEDIT** try to fill in the remaining characters of a matching file name from the current directory, or from the directory typed in the command field when the partial file name contains a "/" character.

If several matches are possible, **SEDIT** will beep and display the first match. Hitting again the trigger will display the next match. Hitting Shift-trigger, which must be assigned the "COMPLETE REVERSE" command, will reverse the display order.

COMPLETE is assigned to the following keys, according to the workstation in use:

SUN	R1 (PrintScreen)
IBM RS/6000	R2 (ScrollLock)
SiliconGraphics	R2 (ScrollLock)
DecStations	L3
НР	L6
HP with PC keyboards	R2 (ScrollLock)
Windows NT and 95	R2 (ScrollLock)

COMPRess - Compress Data

COMPRess

compresses data for an APL function or operator in the same way \Box FX would do, but in respect to trailing comments position.

Scope: All file

This command is mapped to the F11 key by default when running under APL.

Example:

Before using F11:

```
[66] GDTEST fsqury 4 1 8

[67] LAF HTF LAC HTC LEFT TOP LA HT\inRC[2 3 4 5 6 7 8 9]

[68]

[69] LAD HTD\inDIM[2 1]+ 0 1 a This is a trailing comment

[70] \& (LAD <0)/ 'LAD\in<sup>-1+</sup>[LAF\divLAC' a This is another trailing comment

[71] \& (HTD \leq0) /'HTD\in<sup>-1+</sup>[HTF\divHTC' a Zoom

[72] PX PY\inDIM[3 4]
```

After using F11:

```
[66] GDTEST fsqury 4 1 8

[67] LAF HTF LAC HTC LEFT TOP LA HT\inRC[2 3 4 5 6 7 8 9]

[68]

[69] LAD HTD\inDIM[2 1]+0 1 A This is a trailing comment

[70] \pounds(LAD<0)/'LAD\in-1+[LAF\divLAC' A This is another trailing comment

[71] \pounds(HTD\leq0)/'HTD\in-1+[HTF\divHTC' A Zoom

[72] PX PY\inDIM[3 4]
```

COpy (XEDIT MODE) - Copy File Lines

```
COpy target1 target2
```

```
XEDCOpy target1 target2
```

When <u>MODE</u> COMMAND XEDIT is in effect, COPY calls the XEDIT mode XEDCOPY command. PDFCOPY may be used to call the ISPF/PDF mode COPY command.

COPY copies the number of lines defined by target1, starting from the current line, at the location defined by target2.

The last copied line becomes the current line.

target may be one of the following:

:N	Up to but not including the Nth line.
N or +N	N lines.
-N	Up N lines.
+* or *	The end of file.
_ *	The top of file.
.symb	The line which has been assigned the .symb symbolic name by using the POINT command, or a .symb prefix command.
string expression	Defines a group of characters to be located.

The general format of a string expression is the following:

 $\{+|-\}\{-\}/string1\{/\{\&\}|\{|\}\{-\}/string2 \dots\}$

See the <u>LOCATE</u> command on page 300 for a precise string expression definition.

Examples:	copy 2 :5	copies 2 lines after the line 5.
	copy /str /main	copies the lines up to but not including the
		str string after the line including the main
		string.

Return Codes:	0	Normal
	2	Target Not Found
	5	Invalid Operand

COpy (ISPF MODE) - Copy Data

COpy {file} {AFTER label} PDFCOpy {BEFORE label}

Batch Mode: Not Available

When <u>MODE</u> COMMAND ISPF is in effect, COPY calls the ISPF mode PDFCOPY command. XEDCOPY may be used to call the XEDIT mode COPY command.

COPY specifies a file to be copied into the data being edited.

file A file. **SEDIT** will first search for it in the current directory, and then in the directories described in the PATH environment variable, or accessed by using the ACCESS command.

When file is omitted, SEDIT displays the following fullscreen panel:

```
Copy from file ===>

First line ===>

Last line ===>

Press Enter to copy, F3 or ^c to cancel
```

The user must specify the file name, and the first and last line to be copied.

AFTER label

The data will be copied after the specified label.

A label may be created by typing a .xxxx string on a prefix zone, or by using the XEDIT POINT command described on page 331.

A label may also be one of the ISPF/PDF predefined labels:

.zfor.zfirst	the first line.
.zlor.zlast	the last line.
.zcsr	the cursor line.

BEFORE label

The data will be copied before the specified label.

When a destination label is not specified, the user must enter an A (or F when MODE PREFIX XEDIT in effect) or an B (or P) in a prefix zone to specify the destination.

Specifying a prefix destination can be done either before or after using the COPY command.

Examples: copy ./fool after .a copy copy before .zcsr

COUnt - Count String Occurrences

```
COUnt /str{/} {target}
```

COUNT displays the number of times a the str string appears in the lines defined by target, starting from the current line.

/ is the first non-blank character found after the COUNT command.

target may be one of the following:

:N	Up to but not including the Nth line.
N or +N	N lines.
-N	Up N lines.
+* or *	The end of file.
_ *	The top of file.
.symb	The line which has been assigned the .symb symbolic name by using the POINT command, or a .symb prefix command.
string expression	Defines a group of characters to be located.

The general format of a string expression is the following:

 $\{+|-\}\{-\}/string1\{/\{\&\}|\{|\}\{-\}/string2 \dots\}$

See the **LOCATE** command on page 300 for a precise string expression definition.

When omitted, target defaults to the value of 1.

COUNT displays the following message:

Found nn occurrences.

In a macro, the EXTRACT/LASTMSG/ command may be used to retrieve the number of occurrences.

Examples:	count/foo//main	counts the occurrences up to but not
		including the line including the main string.

```
count;/**/;:5
```

Return Codes:	0	Normal
	2	Target Not Found
	5	Invalid Operand

See Also: STAY

COVerlay - Selectively Replace Characters

```
COVerlay text
```

selectively replaces characters in the current line with text.

An underscore character in the text operand replaces the corresponding character in the current line with a blank.

A blank character in the text operand does not alter the corresponding character in the current line.

No replacement will take place if the column pointer is out of the **ZONE** range.

The column pointer will not be moved.

Example:

```
Current line:
```

See Also: <u>ZONE</u>

CREAte - Create a New File

CREAte {file} {range}

saves data into a new file.

```
Batch Mode: Not Available
```

CREATE saves the data being edited into a file.

file A file which does not exist. Use the <u>REPLACE</u> ISPF/PDF command when updating an existing file.

When file is omitted, **SEDIT** displays the following fullscreen panel:

Create file ===> Press Enter to create, F3 or ^c to cancel

Two labels that identify the lines to be saved.
 A label may be created by typing a .xxxx string on a prefix zone, or by using the XEDIT POINT command described on page 331.

A label may also be one of the ISPF/PDF predefined labels:

ast line.
cursor line

When a range is not specified, the user must enter either a C, CC, M or a MM prefix command in a prefix zone to specify the lines to be copied. Specifying a prefix origin can be done either before or after using the CREATE command.

Examples: create ~/foo .a .zl create .a .b create

See Also: FILE, REPLACE, SAVE

CReplace - Replace Characters

CReplace text replaces characters in the current line with text. No replacement will take place if the column pointer is out of the <u>ZONE</u> range. The column pointer will not be moved. Example:

Current line:

```
00001 i = 3; \* This is a bad comment */
    <...|...1...+...2...+...3...+...4...+...5...+...6
====> cr 4; /
00001 i = 4; /* This is a bad comment */
    <...|...1...+...2...+...3...+...4...+...5...+...6</pre>
```

See Also: <u>ZONE</u>

CTags - Use a Tags File

```
CTags ON | OFF {tag_file}
```

enables or disables the use of tag_file as a target file.

```
Initial value: ON tags
Level: Global
```

CTAGS without arguments displays the current status.

Very often, programmers include several functions in the same file. For example, the user could have the following "test.c" file:

```
main()
{
    printf ("main called\n");
    subl();
}
subl()
{
    printf ("subl called\n");
}
```

The **UNIX** "ctags" command (and <u>not</u> the **SEDIT** one) is used to create a tags file giving the locations of specified objects in a group of files.

Typing in a terminal window the command "ctags test.c" will create the following "tags" file:

Mtest test.c /^main()\$/
subl test.c /^subl()\$/

This file indicates that the target function "subl" is located in the "test.c" file.

If "ctags" is ON, when starting a new file "subl.c", **SEDIT** proceeds as follows:

- First, **SEDIT** searches for that file in the current directory.
- If not found, **SEDIT** searches for a file "tag_file".

If "tag_file" is found, **SEDIT** scans it for the target "subl". The file associated with this target ("test.c" in this example), must have the same filetype as the new file ("c" in this example).

If the new file has a "c" filetype, the associated file may also have a "h" filetype.

- Then, if not found, **SEDIT** will repeat this process in each directory described in the PATH or XPATH environment variable.
- If not found at all, **SEDIT** will create a new file in the editing ring.

Note that unlike the **UNIX** editor **VI**, the user need not specify a tags file to be processed when starting a new file.

The user may, for example, just select a letter in the word sub1, and use the S_XED command (by typing Control-X) to load the "test.c" file, even if located in another directory. Then, **SEDIT** will set the current line at the location given by the tags file searching pattern (here "/^sub1()\$/").

If **SEDIT** does not find this pattern, it will display an error message.
CTLCHAR - Define Control Character

```
CTLchar cmd cc Escape
```

```
OFF

Protect {color} {exthi} {Hight|Nohigh|Invisible} {PSs}

Noprotect {color} {exthi} {Hight|Nohigh|Invisible} {PSs}

OFF
```

Initial value: OFF *Level:* Global

CTLCHAR defines a control character which specifies the color, extended highlighting, protection and visibility of a portion of a line reserved with the RESERVED command.

The operands are the following:

CC	is any ASCI character.	I character, which will be used as a control	
OFF	resets all control characters (CTLCHAR OFF), or a specified character (CTLCHAR cc OFF).		
Escape	specifies that of text, the next of	cc is an escape character: when cc appears in the character is a control character.	
Protect	specifies that t user.	he string following cc cannot be modified by the	
Noprotect	specifies that user.	the string following cc can be modified by the	
color	the color to be addition, col	e used, as described by the COLOR command. In or may be:	
	White Turquoise	same as BLACK same as MAGENTA	
exthi	may be:		
	BLink	Maintained for XEDIT compatibility, but not	
		supported within SEDIT.	
	REVvideo	supported within SEDIT. Displays in reverse video.	
	REVvideo Underline	supported within SEDIT. Displays in reverse video. Underlines the displayed characters.	
	REVvideo Underline None	supported within SEDIT. Displays in reverse video. Underlines the displayed characters. No extended highlighting. This is the default.	
High Nohigh	REVvideo Underline None specifies that to specifies that bold. This is the	supported within SEDIT. Displays in reverse video. Underlines the displayed characters. No extended highlighting. This is the default. the string following cc is to be displayed in bold. the string following cc is not to be displayed in ne default.	

PSs Maintained for **XEDIT** compatibility, but not supported within **SEDIT**.

Without operands, CTLCHAR displays the control characters in usage.

Examples: ctlchar @ escape defines @ as an escape character.

ctlchar & noprotect red revvideo nohigh reserved m+1 noh Enter your name: @& defines an input red field displayed in reverse video.

See Also: MODE, READ, RESERVED

CURLine - Change Current Physical Line

CURLine {ON} line

selects the physical screen line to display the current line.

Initial value: 8 Level: View

ON is an optional parameter with no special meaning.

line can be specified in three ways:

CUrline	n +n	selects the line n of the view to display the current line, where the first line is line 1.
CUrline	-n	selects the line n from the bottom of the view, where the last line is line -1.
CUrline	M+n M-n	selects the line n lines above or below the middle line of the view.
Examples:	CURLINE	2
	CURLINE	-3
	CURLINE	ON M
	CURLINE	M+2

CURsor - Move Cursor

CURsor	CMdline	{colno	{Priority N}}
	Column		{Priority N}
	File	lineo {colno	{Priority N}}
	Home		{Priority N}
	Screen	lineo {colno	{Priority N}}

CURSOR moves the cursor to the specified position.

CMdline

moves the cursor to the command line in the column colno relative to the first command field column. If not specified, colno will be set to 1.

Column

moves the cursor to the current line in the current column position.

File

moves the cursor to the specified file line and column position. If colno is not specified and the cursor is within the file area, the cursor will be placed in the same column. Otherwise, the cursor is placed in the first column. If colno is specified as 0, the cursor is placed in the first column of the corresponding prefix field.

Home

if the cursor is on a data field, it will be moved to the command line. If it is on the command line, it will move to its last position in the file if possible.

CURSOF Home is a synonym for the HOME command.

When CMDLINE is OFF, using the CURSOR HOME command restores the command line to allow the user to pass a command. Once the command is processed, the command line is removed.

Screen

moves the cursor relative to the beginning of the split screen. If colno is not specified, the cursor will be placed in the same column where it was.

```
Priority N
```

is the priority number assigned to the cursor displacement. When **SEDIT** updates the screen, the highest priority will define the position of the cursor.

N should be specified as greater than or equal to 0, and lower than 256. When omitted, N defaults to 257.

When using either Enter or a function Key, the cursor position on the screen is memorized with a priority set to 20.

The various prefix commands move the cursor using the following priorities:

А	or	Ι	60
Ε			60
/			50
"	or	'	40
М			30
С			30
S			30

< or >	30
G	30
Scale	30
Tabl	30
PU	30
Х	30
D	10

The set_xedit macro assigns the "ignore cursor cmdline 1 priority 30" string to the Enter (or Return on some keyboards) key.

Note: the screen will be updated only when using the REFRESH command.

See Also: <u>CMDLINE</u>, <u>HOME</u>, <u>REFRESH</u>

C_APLStop - Reverse APL Stop Setting

C_APLStop

reverse the stop setting for the APL function currently edited at the cursor location.

Scope: Display Batch Mode: Not Available

The prefix command field will be underlined when the stop is on.

This command is mapped to the *`s* key by default.

C_APLTrace - Reverse APL Trace Setting

C_APLTrace

reverse the trace setting for the APL function currently edited at the cursor location.

Scope: Display Batch Mode: Not Available

The data field will be underlined when the trace is on.

This command is mapped to the ^e key by default.

C_Dup - Duplicate Cursor Line

C_Dup

duplicates the line at the cursor location.

Scope: Display Batch Mode: Not Available

This command is mapped to the ^= key by default.

C_ENDCurl - Goto End of Current Line

C_ENDCurl the cursor will be moved to the end of the CURRENT LINE FIELD.

Scope: Display Batch Mode: Not Available

This command is mapped to the S-F6 (PF18) key by default.

C_ENDLine - Goto End of Cursor Line

C_ENDLine

If the cursor is in a DATA FIELD or in the command line, it will be moved to the end of the data displayed on that field. If not, it will be moved to the end of the data displayed on the CURRENT LINE FIELD.

Scope: Display Batch Mode: Not Available

This command is mapped to the F6 key by default.

C_ENDS - End Selection

C_ENDS

extends the selection at the cursor location.

Batch Mode: Not Available

If the selection already ends at the cursor location, the selection will be cancelled.

C_ENDS is intended to replace the second mouse button when running in ASCII mode.

This command is mapped to the ^e key by default when running in ASCII mode.

See Also: <u>C_ENDSALL</u>, <u>C_ENDSR</u>, <u>C_STARTS</u>

C_ENDSAll - End Selection at End of Line

C_ENDSAll

extends the selection at the end of the line where the cursor is located.

Batch Mode: Not Available

C_ENDSALL is intended to replace the shifted second mouse button when running in ASCII mode.

See Also: <u>C</u> ENDS, <u>C</u> ENDSR, <u>C</u> STARTS

C_ENDSR - End Rectangular Selection

C_ENDSR

extends the selection at the cursor location, making it rectangular.

Batch Mode: Not Available

If the selection already ends at the cursor location, the selection will be cancelled.

C_ENDSR is intended to replace the second mouse button when running in ASCII mode.

This command is mapped to the ^n key by default when running in ASCII mode.

See Also: <u>C_ENDSALL</u>, <u>C_ENDS</u>, <u>C_STARTS</u>

C_EXT - Extend Field

C_EXT

extends the length of the field selected by the cursor.

Scope: Display Batch Mode: Not Available

This command is mapped to the F2 key by default.

C_LINEAdd - Add Line

C_LINEAdd

adds a line below the cursor location.

Scope: Display Batch Mode: Not Available

This command is mapped to the ^a key by default.

C_LINEDel - Delete Line

C_LINEDel deletes the line at the cursor location.

Scope: Display Batch Mode: Not Available

This command is mapped to the ^d key by default.

C_SCRH - Split Screen Horizontally

C_SCRH splits the screen horizontally at the cursor location. Batch Mode: Not Available This command is mapped to the ^h key by default.

See Also: <u>SCREEN</u>

C_SCRJ - Unsplit Screen

C_SCRJ

restarts with an unsplit screen.

Batch Mode: Not Available

This command is mapped to the ^w key by default.

See Also: <u>SCREEN</u>

C_SCRV - Split Screen Vertically

C_SCRV

splits the screen vertically at the cursor location.

Batch Mode: Not Available

This command is mapped to the v key by default.

See Also: <u>SCREEN</u>

C_SPlit - Split/Join Lines

C_SPLIT {Stay | Nostay} when the cursor is before the last non-blank character, the line will be split, with indentation if the auto-indent feature is on. When the cursor is after the last non-blank character, the next line will be joined to the current location.

Scope: Display Batch Mode: Not Available

If STAY is specified, the cursor remains at the same location. Otherwise, the cursor is moved to the new line with proper indentation respect.

This command is mapped to the F4 key on Sun keyboards, and to the ^s key on other ones.

See Also: <u>AUTOI</u>, <u>SPLTJOIN</u>

C_STARTLine - Goto Start of Cursor Line

C_STARTLine

if the cursor is in a DATA FIELD it will be moved to the start of that field. If not, it will be moved to the start of the CURRENT LINE FIELD.

Scope: Display Batch Mode: Not Available

C_STARTS - Start Selection

C_STARTS

starts the selection at the cursor location.

Batch Mode: Not Available

C_STARTS is intended to replace the first mouse button when running in ASCII mode. This command is mapped to the ^b key when running in ASCII mode.

See Also: <u>C_ENDS</u>, <u>C_ENDSALL</u> <u>C_ENDSR</u>

DACCess- Add Directory to the CDPATH

DACCess dir {dir2 {..}} add directories to the cdpath.

DACCESS adds the diri directories to the cdpath in which **SEDIT** searches for directories.

When searching for directories, **SEDIT** uses the cdpath content. DACCESS extends dynamically the cdpath.

Note that if a XCDPATH environment variable exists when **SEDIT** starts, it is used to initialize the cdpath.

If diri does not start with a standard directory indicator (/. ~), **SEDIT** will search first in the current directory and then through the directories described in the cdpath.

If diri contains blanks, it must be surrounded with quotes or double quotes. If a directory contains a quote or a double quote, the quote must be escaped with a backslash.

Example: Assume your home directory is "usr/m1", and "/usr/m1/dir2" exists.

dacc dir2 will add the "/usr/m1/dir2" directory.

Then, if "/usr/ml/dir2/dir3" exists, typing "cd dir3" will change the current directory to it without the need to specify the whole pathname.

dacc "c:/Program Files"

Quotes are used to specify a directory with embedded blanks.

See Also: <u>ACCESS</u>, <u>CD</u>, <u>DRELEASE</u>, <u>FLIST</u>, <u>FD</u>, <u>RELEASE</u>, <u>SHOWPATH</u>, <u>SHOWCDPATH</u>

DELete (XEDIT MODE) - Delete Line

DELete	{target}	will delete lines starting with the current line.
XEDDELete		

Scope: Display

When <u>MODE</u> COMMAND XEDIT is in effect, DELETE calls the XEDIT mode XEDDELETE command. PDFDELETE may be used to call the ISPF/PDF mode DELETE command.

target defines the number of lines to be deleted. Lines are deleted starting with the current line, up to but not including the target line. target may be one of the following:

:N	Up to but not including the Nth line.
N or +N	N lines.
-N	Up N lines.
+* or *	The end of file.
_*	The top of file.
.symb	The line which has been assigned the .symb symbolic name by using the POINT command, or a .symb prefix command.
string expression	Defines a group of characters to be located.

The general format of a string expression is the following:

{+|-}{~}/string1{/{&}|{|}{~}/string2 }

See the **LOCATE** command on page 300 for a precise string expression definition.

If target is omitted, a value of 1 is assumed.

On a forward delete, the line following the last deleted line becomes the current line. On a backward delete, the line preceding the last deleted line becomes the current line.

Examples:	del	deletes one line.
	del:5	deletes all lines up to line 4.
	del*	deletes the rest of the file.

See Also: <u>All</u>, <u>SCOPE</u>, <u>SELECT</u>

DELete (ISPF MODE) - Delete Line

DELete	$\{ ALL \}$	{X}	$\{NX\}$	{range}
PDFDELete				

deletes lines from the currently edited file.

When <u>MODE</u> COMMAND ISPF is in effect, DELETE calls the ISPF mode PDFDELETE command. XEDDELETE may be used to call the XEDIT mode DELETE command.

DELETE deletes lines from the currently edited file.

- **ALL** deletes all the lines, from the start to the bottom of the file.
- Two labels that identify the lines to be deleted. range A label may be created by typing a .xxxx string on a prefix zone, or by using the XEDIT POINT command described on page 331. A label may also be one of the ISPF/PDF predefined labels: the first line. .zfor.zfirst .zlor.zlast the last line. the cursor line .zcsr deletes only lines that are excluded from the display. х deletes only lines that are not excluded from the display. NX Examples: delete all
- delete all x delete all nx delete .a .zcsr x

DELAY - Display a String

DELAY {string} displays a string in the command field.

This command displays a string in the command field, allowing further editing. Its main usage is with the <u>SET</u> command. If string is missing, the command field will be cleared.

Examples: set r5 delay fn test

Pressing key R5 will display "fn test" in the command field and set the cursor after "test".

set r1 delay.cursor home
 (. is the Control-Line-Feed separator)

Pressing key R1 will clear the command field, and then restore the cursor position.

DFlist - Call Directory Editor

DFlist { FN {FT {FM}}} will call the directory editor upon directories.

Batch Mode: Not Available

DFLIST only displays directories. See The Directory Editor FLIST on page 453 for further explanations.

See Also: DACCESS, DFLIST, FLIST, FLATH, FLPP, FMACRO, RFLIST

DISPlay - Set Display Range

DISPlay $\{n1 \ \{n2\}\}$

will display lines whose selection level falls into the range n1 through n2.

Initial value: 0 0 Level: View

Each line in the file has a number associated with it, called its selection level, which is set to zero by default and may be modified by the commands <u>ALL</u> and <u>SELECT</u>, and by the prefix commands X and S. When a line selection level does not fall in the range n1 through n2, it will not be displayed.

If n2 is omitted, it will assume the value of n1.

If n2 is *, it will assume the maximum value 2147483648.

If both n1 and n2 are omitted, the current setting will be displayed.

With <u>SHADOW</u> ON (by default) excluded lines are shown by a shadow line indicating the number of excluded lines. With SHADOW OFF, excluded lines are not represented.

With <u>SCOPE</u> DISPLAY (by default) most **SEDIT** commands and prefix commands will not apply to the excluded lines. With SCOPE ALL, commands will apply to all lines.

See Also: <u>ALL</u>, <u>SCOPE</u>, <u>SELECT</u>, <u>SHADOW</u>, <u>VISIBLE</u>

Down/Next - Scroll Down

Down $\{N \mid *\}$ will scroll down N lines.

Scope: Display

If N is omitted, a value of 1 is assumed. Down * makes the End Of File the current line. Next is a synonym to the Down command.

Return Codes:	0	Normal
	1	End Of File Reached
	5	Invalid Operand

DUPlicat - Current Line Duplication

DUPlicat {N {target}} duplicates N times the lines defined by target.

DUPLICAT duplicates N times the lines defined by target starting with the current line. When N or target is omitted, a value of 1 is assumed. The last line duplicated becomes the current line.

target defines the number of lines to be duplicated. Lines are duplicated starting with the current line, up to but not including the target line. target may be one of the following:

:N	Up to but not including the Nth line.
N or +N	N lines.
+* or *	The end of file.
.symb	The line which has been assigned the .symb symbolic name by using the POINT command, or a .symb prefix command.
string expression	Defines a group of characters to be located.

The general format of a string expression is the following:

{+|-}{~}/string1{/{&}|{|}{~}/string2}

See the <u>LOCATE</u> command on page 300 for a precise string expression definition.

See Also: <u>C_DUP</u>

DRELEase - Removes a Directory from the CDPATH

DRELEase {dir1 {dir2 ...}}

DRELEASE removes from the cdpath directories accessed with the <u>DACCESS</u> command. If the dir*i* directory is not accessed, or is the home directory, DRELEASE silently ignores it.

DRELEASE * removes all the directories from the cdpath, except the home directory.

DRELEASE without arguments scans the cdpath, and removes nonexistent directories.

See Also: <u>DACCESS</u>, <u>SHOWCDPATH</u>

DY_All - Start the ALL Dialog Box

DY_All

uses a dialog box to search for lines containing specified text string.

Batch Mode: Not Available

DY_ALL displays the following dialog box:



The user must enter a target string in the input field.

SEDIT will set the selection level for every line currently in the scope matching this target to the upper value of the DISPLAY range, and to this value plus one for all the other lines, hiding them. **SEDIT** will then put <u>SCOPE</u> DISPLAY in effect, and select the first line displayed as the current line. With SCOPE DISPLAY in effect, lines that are excluded from the display are also excluded from processing by most **SEDIT** commands and prefix commands. With SCOPE ALL in effect, all lines will be processed. If <u>SHADOW</u> ON is in effect, a shadow line appears on your display wherever lines have been excluded.

When Consider Case is not checked, **SEDIT** will ignore capitalization when matching the target.

When Whole Word is checked, **SEDIT** will match a whole word. For example, if target is the string "i", **SEDIT** will match "i = 3", but will not match "if ()".

See Also: <u>ALL</u>, <u>DISPLAY</u>, <u>DY EXCLUDE</u>, <u>DY FONT</u>, <u>DY SHOW</u>, <u>SCOPE</u>, <u>SELECT</u>, <u>SHADOW</u>, <u>VISIBLE</u>

DY_Exclude - Start the EXCLUDE Dialog Box

DY_Exclude

uses a dialog box to search for every line that does not have text matching specified text string.

Batch Mode: Not Available

DY_EXCLUDE displays the following dialog box:



The user must enter a target string in the input field.

SEDIT will set the selection level for every line currently in the scope **not** matching this target to the upper value of the DISPLAY range, and to this value plus one for all the other lines, hiding them. **SEDIT** will then put <u>SCOPE</u> DISPLAY in effect, and select the first line displayed as the current line. With SCOPE DISPLAY in effect, lines that are excluded from the display are also excluded from processing by most **SEDIT** commands and prefix commands. With SCOPE ALL in effect, all lines will be processed. If <u>SHADOW</u> ON is in effect, a shadow line appears on your display wherever lines have been excluded.

When Consider Case is not checked, **SEDIT** will ignore the capitalization when matching the target.

When Whole Word is checked, **SEDIT** will search for whole words. For example, if target is the string "i", **SEDIT** will not match "i = 3", but will match "if ()".

See Also: <u>ALL</u>, <u>DISPLAY</u>, <u>EXCLUDE</u>, <u>DY ALL</u>, <u>DY FONT</u>, <u>DY SHOW</u>, <u>SCOPE</u>, <u>SELECT</u>, <u>SHADOW</u>

DY_FInd - Start the FIND Dialog box

DY_FInd

Batch Mode: Not Available

DY_FIND displays the following dialog box:

xed @ C - (NONE), dir:/home/m1/pro
FIND:
From Column: <u>1</u> To Column: <u>2147483647</u>
✓ Consider Case Whole Word Backward Forward
CHANGE TO:
From Line: To Line:
Find Change Change & Find Again Change All

The user must enter a target string in the FIND input field.

Clicking on the Find button will select the first matching string in the current file.

Clicking on the Change button will change the selected string with the string entered in the CHANGE TO input field.

The Change & Find Again button does the change, and searches for the next occurrence of the target.

The Change All button changes all the occurrences.

The user may restrict the columns to be searched for by entering values in the From Column and To Column fields. The lines to be searched for are specified in the From Line and in the To Line fields.

See Also: <u>CHANGE</u>, <u>SCHANGE</u>, <u>CN</u>, <u>DY_FONT</u>, <u>SCN</u>, <u>S_FIND</u>

DY_FILL - Start the FILL dialog box

DY_FILL

opens a dialog box to enter a text string which will be used to fill a rectangular area.

The user must make a rectangular selection before calling DY_FILL. See Making a Rectangular Selection on page 125 and on page 128 for more information.

DY_FILL is the /home/xed/xmac/dy_fill.sedit macro.

DY_FOnt - Set the Dialog Font

DY_FOnt	fontname	make the va font.	arious dia	alog boxes	use the	fontname
D 11/1						

Batch Mode: Not Available

See Also: DY ALL, DY EXCLUDE, DY FIND, DY OPEN, DY SAVE, DY SHOW, DY EXCLUDE, DY SHOW

DY_LASTFILES - Display Last Edited Files

DY_LASTFILES {ht_scrl {la_scrl}}

DY_LASTFILES is the {install-dir}/xmac/dy_lastfiles.sedit macro, which displays the last opened files, allowing the user to open them again.

- ht_scrl the number of rows used by the scrolled list to display the files. ht_scrl defaults to 15 when omitted.
- la_scrl the width of the scrolled list. la_scrl defaults to 50 when omitted.

See Also: LASTFILES

DY_OPEN (UNIX) - Start the OPEN Dialog Box

DY_OPEN {dir {filt-f {filt-d {lg_reg}}}}
opens a dialog box to match text strings contained in
files and directories.

Unlike with the **SEDIT** 4.0 release, DY_OPEN is not an **SEDIT** command, but the /home/xed/xmac/dy_open.sedit macro.

DY_OPEN displays the following dialog box:



dir	is the directory to be scanned. When omitted, the current directory will be scanned. When dir is the special //last string, the directory of the last opened file with the DY_OPEN macro will be scanned.
filt_f	is the filter used to select which files are to be displayed. When omitted, it defaults to *, which means any file. When the regular expression switch is off, * means any set of characters. a*df* would for example match a_123.dfte. Several filters can be specified by using a ; separator. Example:*.c;*.h
filt_d	is the filter used to select which directories are to be displayed.
lg_reg	when set to 1, toggles on the regular expression search. When omitted, or set to 0, toggles off the regular expression search.

A regular expression is a character string used to describe, in an extended way, a string to be matched. It uses special characters, called meta characters to describe the match to be done.

The meta characters are the following:

*	matches only at the beginning of a line.
\$	matches only at the end of a line.
\<	matches only at the beginning of a word.
\>	matches only at the end of a word.
•	matches any single character.
[]	matches any character in a character class.
\(delimits the start of a subexpression. It is available for VI compatibility, but has no special meaning.
\)	delimits the end of a subexpression. It is available for VI compatibility, but has no special meaning.
*	repeats the preceding 0 or more times.

If you want to use a meta character as an ordinary character, you must precede it with a backslash $(\)$ character.

Examples:

^af

matches the string "af" only at the beginning of a line.

af\$

matches the string "af" only at the end of a line.

dc....is

matches the string "dc" followed by any 7 characters followed by the string "is".

[A-Z][a-z]

[A-Z] means any	character from A to Z.
-----------------	------------------------

[a-z] means any character from a to z.

The whole expression above matches any alphabetical string starting with a capital

letter.

The string "File001" will be matched. "F001" will not.

Note that the meta characters are not treated specially when enclosed in brackets:

[.\$]

matches the string ". \$". Without brackets, the user should type:

´_\.\\$

for the same match.

Supported User Actions

The user can perform the following actions:

- Clicking once with the left mouse button upon a displayed file selects this file, and displays its name in the file input zone.
- With the **MOTIF** version, holding the Shift key down while clicking extends the selection to several contiguous files. Holding the Control key down extends the selection to another, possibly non-contiguous, file.
- Double clicking on a file makes DY_OPEN return. This file will be opened.
- Clicking once with the left mouse button upon a displayed directory selects this directory, and displays its name in the directory input zone.
- Double clicking on a displayed directory initiates a scan of this directory.
- Using the Return or Enter key when the keyboard focus is in the File input zone makes DY_OPEN return. The file displayed in that File input zone will be opened.
- Using the Return or Enter key when the keyboard focus is in the Directory input zone initiates a scan of the directory displayed in that zone. When this directory name does not start with a / or a ~, it will be considered as a subdirectory of the previously scanned directory.
- Using the Return or Enter key when the keyboard focus is in the File or Directory filter zone initiates a new scan of the previously scanned directory.
- Clicking on the OPEN button makes DY_OPEN return. The selected files will be opened.
- Clicking on the CANCEL button makes DY_OPEN return without further action.
- Clicking on the SCAN button initiates a new scan of the previously scanned directory.

See Also: <u>ACCESS</u>, <u>DY LASTFILES</u>, <u>XEDIT</u>

DY_OPEN (WINDOWS) - Start the OPEN Dialog Box

DY_OPEN {dir {filt-f}} opens a dialog

opens a dialog box to match text strings contained in files and directories.

```
DY_OPEN is not an SEDIT command, but the
```

C:\Program Files\SEDIT\xmac\dy_open.sedit macro.

DY_OPEN displays the standard **WINDOWS** OPEN FILE dialog box.

- dir is the directory to be scanned. When omitted, the current directory will be scanned. When dir is the special //last string, the directory of the last opened file with the DY_OPEN macro will be scanned.
- filt_f is the filter used to select which files are to be displayed. When omitted, it defaults to * . *, which means any file. Several filters can be specified by using a ; separator. Example:*.c;*.h

See Also: <u>ACCESS</u>, <u>DY_LASTFILES</u>, <u>XEDIT</u>

DY_SAVE (UNIX) - Start the SAVE Dialog Box

DY_SAVE {dir {filt-f {filt-d {lg_reg}}}}
opens a dialog box to save the current file.

Unlike with the **SEDIT** 4.0 release, DY_SAVE is not an **SEDIT** command, but the /home/xed/xmac/dy_save.sedit macro.



DY_SAVE displays the following dialog box:

dir	is the directory to be scanned. When omitted, the directory of the current file will be scanned.
filt_f	is the filter used to select which files are to be displayed. When omitted, it defaults to $*$, which means any file. When the regular expression switch is off, $*$ means any set of characters. $a*df*$ would for example match a_123.dfte.
filt_d	is the filter used to select which directories are to be displayed.
lg_reg	when set to 1, toggles on the regular expression search. When omitted, or set to 0, toggles off the regular expression search.

A regular expression is a character string used to describe, in an extended way, a string to be matched. It uses special characters, called meta characters to describe the match to be done.

The meta characters are the following:

^	matches only at the beginning of a line.
\$	matches only at the end of a line.
\<	matches only at the beginning of a word.
\>	matches only at the end of a word.
•	matches any single character.
[]	matches any character in a character class.
\(delimits the start of a subexpression. It is available for VI compatibility, but has no special meaning.
\)	delimits the end of a subexpression. It is available for VI compatibility, but has no special meaning.
*	repeats the preceding 0 or more times.
ou want to us	a a mot o character as an ordinary character, you must precede it with

If you want to use a meta character as an ordinary character, you must precede it with a backslash $(\)$ character.

Examples:

^af

matches the string "af" only at the beginning of a line.

af\$

matches the string "af" only at the end of a line.

dc....is

matches the string "dc" followed by any 7 characters followed by the string "is".

[A-Z][a-z]

[A-Z] means any character from A to Z.

[a-z] means any character from a to z.

The whole expression above matches any alphabetical string starting with a capital letter.

The string "File001" will be matched. "F001" will not.

Note that the meta characters are not treated specially when enclosed in brackets:

[.\$]

matches the string ". \$". Without brackets, the user should type:

\.\\$

for the same match.

When DOS File is checked, **SEDIT** adds a ^M character at the end of each line, and a ^Z character at the end of the file, thus making the file compatible with personal computers using the DOS operating system.

When Keep Time-Stamp is checked, **SEDIT** leaves unchanged the saved file timestamp.

When Overwrite is checked, **SEDIT** does not check for an existing file before saving the file.

Supported User Actions

The user can perform the following actions:

- Clicking once with the left mouse button upon a displayed file selects this file, and displays its name in the file input zone.
- Double clicking on a file makes DY_SAVE return. The current file will be renamed accordingly to the selected file, and saved.
- Clicking once with the left mouse button upon a displayed directory selects this directory, and displays its name in the directory input zone.
- Double clicking on a displayed directory initiates a scan of this directory.
- Using the Return or Enter key when the keyboard focus is in the File input zone makes DY_SAVE return. If the name of the file is displayed in the File input zone, the current file will be renamed accordingly to this name, and saved.
- Using the Return or Enter key when the keyboard focus is in the Directory input zone initiates a scan of the directory displayed in that zone. When this directory name does not start with a / or a ~, it will be considered as a subdirectory of the previously scanned directory.
- Using the Return or Enter key when the keyboard focus is in the File or Directory filter zone initiates a new scan of the previously scanned directory.
- Clicking on the SAVE button makes DY_SAVE return. If the name of the file is displayed in the File input zone, the current file will be renamed accordingly to this name, and saved.
- Clicking on the CANCEL button makes DY_SAVE return without performing further action.

• Clicking on the SCAN button initiates a new scan of the previously scanned directory.

See Also: FILE, SAVE

DY_SAVE (WINDOWS) - Start the SAVE Dialog Box

DY_SAVE {dir {filt-f}} opens a dialog box to save the current file.

DY_SAVE is not an SEDIT command, but the

C:\Program Files\SEDIT\xmac\dy_save.sedit macro.

- DY_SAVE displays the standard WINDOWS SAVE FILE dialog box
- dir is the directory to be scanned. When omitted, the directory of the current file will be scanned.

See Also: <u>FILE</u>, <u>SAVE</u>

DY_SHow - Start the SHOW Dialog Box

DY_SHow

Batch Mode: Not Available

DY_SHOW displays the following dialog box:

	**** Enter a s	tring to match *****
۰		
	🖌 Consider Ca	se 🗌 Whole Word
	Continue	Cancel

The user must enter a target string in the input field.

SEDIT will scan all the lines **not** displayed matching the target in order to display them.

When Consider Case is not checked, **SEDIT** will ignore the capitalization when matching the target.

When Whole Word is checked, **SEDIT** will search for whole words. For example, if target is the string "i", **SEDIT** will match "i = 3", but will not match "if ()".

See Also: <u>All</u>, <u>DISPLAY</u>, <u>DY ALL</u>, <u>DY EXCLUDE</u>, <u>SCOPE</u>, <u>SELECT</u>, <u>SHADOW</u>, <u>SHOW</u>

EDIT

EDIT is an ISPDF/PDF synonym to the XEDIT command described on page 440.

EMSG - Display Text

EMSG text

displays text in the message field and sounds the alarm.

See Also: MSG

END - End the Edit Session

END

END saves all the modified files, and terminates the SEDIT session.

See Also: EXIT, EEXIT, FILE, SAVE

ESCAPEdelay - Set Escape Sequence Time-out

ESCAPEdelay {nn}

sets ASCII terminals escape sequence time-out.

Initial value: 4

ESCAPEDELAY without argument displays the current value.

ASCII terminals send to **SEDIT** an escape sequence every time the user hits a function key, such as the F1 key.

An escape sequence starts with the ^[escape character, and is followed by an arbitrary length set of characters. For example, a VT100 ASCII terminal sends a ^[OP string to identify the F1 key.

In order to decide when the escape sequence is complete, **SEDIT** uses a time-out of nn tenths of a second. When no more characters are received during this elapsed time, **SEDIT** decides that the escape sequence has ended, and treats the following characters as user typed characters.

The default ESCAPEDELAY value is generally a good choice. However, when using **SEDIT** with a very slow connection, such as a SLIP connection using a 9600 baud modem, it may be necessary to increase the ESCAPEDELAY value.

ESCAPEDELAY is ignored when **SEDIT** is not in ASCII terminal mode.

EXClude (XEDIT MODE) - Global Selective Line Editing

EXClude {target} selects the lines *not* containing the target specified. XEDEXClude

Scope: Display

When MODE COMMAND XEDIT is in effect, EXCLUDE calls the XEDIT mode XEDEXCLUDE command. PDFEXCLUDE may be used to call the ISPF/PDF mode EXCLUDE command.

EXCLUDE is like the ALL command, except that the matched lines are excluded from display, instead of being kept.

See the ALL command on page 151 for a description of the target operand.

See Also: <u>All</u>, <u>Show</u>

EXCLude (ISPF MODE) - Exclude Lines from Display

EXCLude	str	{range}	$\{\underline{\text{NEXT}}\}$	{ <u>CHARS</u>	}	{X }	${col1}$	$\{col2\}$
PDFEXCLude			$\{ALL\}$	{PREFI	X }	$\{NX\}$		
			$\{FIRST\}$	{SUFFI	X }			
			$\{LAST\}$	{WORD	}			
			{PREV }					

When <u>MODE</u> COMMAND ISPF is in effect, EXCLUDE calls the ISPF mode PDFEXCLUDE command. XEDEXCLUDE may be used to call the XEDIT mode EXCLUDE command.

EXCLUDE searches lines that contains the str PDF string and then excludes those lines from display.

A PDF string may be the following kind of string:

The string used with the last FIND/EXCLUDE/CHANGE/SEEK command.

Simple string

*

Any series of characters not starting with a single or double quote (' or ") and not containing any embedded blanks. The search will be case insensitive.

Delimited string

Any string enclosed by single or double quotes. The search will be case insensitive.

Hexadecimal string

Any delimited string of valid hexadecimal characters, preceded or followed by the character X, such as X'3132' or '3132'x. The search will be case sensitive.

Character string

Any delimited string, preceded or followed by the character C, such as C'ab cd' or 'ab cd'c. The search will be case sensitive.

Picture string

Any delimited string, preceded or followed by the character P, such as P'ab cd' or 'ab cd'p. The search will be case sensitive. Within a picture string, the following special characters may be used:

- = means any character.
- ~ means any character that is not a blank.
- . means a character which generally cannot be displayed. **SEDIT** will consider this any character which has a decimal value of less than 32.
- # means any numeric character.
- means any non-numeric character.
- @ means any alphabetic character.
- < means any lowercase alphabetic character.
- > means any uppercase alphabetic character.
- \$ means any special character, neither alphabetic or numeric.

EXCLUDE considers the following arguments:

range	Two labels that identify the lines to be searched for. A label may be created by typing a .xxxx string on a prefix zone, or by using the XEDIT POINT command described on page 331. A label may also be one of the ISPF/PDF predefined labels: .zf or .zfirst the first line. .zl or .zlast the last line. .zcsr the cursor line		
	When omitted, range defaults to .zfirst .zlast.		
<u>NEXT</u>	Starts at the first position after the current cursor location and searches forward. NEXT is the default. When the cursor is not located on the data, the search start from the first displayed line.		
ALL	Starts at the top of the file and searches forward to find all occurrences of the string.		
FIRST	Starts at the top of the file and searches forward to find the first occurrence of the string.		
LAST	Starts at the bottom of the file and searches backward to find the last occurrence of the string.		
PREV	Starts at the cursor location and searches backward to find the previous occurrence of the string. When the cursor is not located on the data, the search start from the last displayed line		
<u>CHARS</u>	Locates str anywhere the characters match. This is the default.		
PREFIX	Locates str at the beginning of a word: find ab matches "abc", but does not match "ab" or "cabd" or "dab".		

SUFFIX	Locates str at the end of a word: find ab matches "cab", but does not match "ab" or "cabd" or "abc".
WORD	Locates str as a whole word: find ab matches "d ab e", but does not match "cabd" or "abc".
x	Scans only lines that are excluded from the display.
NX	Scans only lines that are not excluded from the display.
col1 and	col2

The columns EXCLUDE is to search. When omitted, the columns are limited by the BOUNDS setting described on page 159.

Examples:

exclude 'ab cd'	matches 'ab cd' as well as 'Ab Cd'.
exclude c'ab cd'	matches only 'ab cd'.
exclude x'31' last	matches the last '1' character.
exclude p'>###"	could match 'A123'.

Return Codes:	0 4 5 6 7	Normal String Not Found * has been used on the first EXCLUDE call Invalid Hexadecimal String Invalid Label
	7	Invalid Label
	12	Syntax Error

See Also: BOUNDS, CHANGE, FIND, SEEK, VERIFY

EXIT / EEXIT - Exit

EXIT {Save Nosave}	will terminate SEDIT if no modified file is currently
	active in the editor. When SEDIT runs in batch
	mode, EXIT will unconditionally terminate SEDIT .
EEXIT {Save Nosave}	will unconditionally terminate SEDIT .

On **WINDOWS** systems, **SEDIT** normally records the font in use and its window location when exiting, and uses the recorded settings when started again. When Nosave is specified, **SEDIT** does not save these settings. When **SEDIT** has been started with the -noauto option, **SEDIT** does not record its settings by default. Using the Save option will make EXIT and EEXIT save these settings.

If one or more files have been modified, EXIT will be displayed as a prompt in an alert box.

Note that you can use the frame menu for the same purpose only if no modified file is currently edited.
EXTract - Retrieve Information

EXTract arg

is used within **S/REXX** or external macros to retrieve information from **SEDIT**.

EXTRACT may only be used within an external or an **S/REXX** macro. The syntax used depends on the macro language. See the examples discussed in the Using EXTERNAL Macro Commands (UNIX Only) section on page 133 and in Using S/REXX Macro Commands on page 140.

EXTRACT returns a string we will name str. The first str word named str[0] is a number indicating the str length.

arg may be any one of the following words:

ALT	HEX	RW
ARBchar	HIghlight	SCALE
ARCH	IMPcmscp	SCOPE
AUTOExpand	INSert	SELECTION
AUTOI	KEEPBlanks	SElect
AUtosave	LASTLorc	SEP
BInary	LASTmsg	SET
CASE	LENgth	SHBlank
CDpath	LFName	SHADow
CLipboard	LIne	SIZe
CMDline	LRecl	SOftbench
COLOR	LScreen	SOURCE
CRing	MACRO	SPAN
COLumn	MARgins	STAY
CTags	MATCH	STReam
CTLchar	MOUSEMODE	SYNonym
CURLine	NAme	TABLine
CURSor	NBFile	TABS
DISPlay	NBSCope	TARGet
=	NUMber	TRUnc
ENTer	PENDing	VARblank
ENViron	Point	Verify
EXTRACT	POWerinput	VIsible
FDirectory	PREfix	VERsion
FILE	PROFile	Width
FLscreen	PWD	WRap
FName	RESERved	Xhome
FONt	REXX	XSHell
FORMAT	RING	Zone
FType	RMATCH	

ALT	
returns the number	of alterations that have been made to the file.
str[0]	number of variables returned
str[1]	number of modifications since the last autosave
str[2]	number of modifications since the last save
ARBchar	
returns the current	ARBCHAR setting defined by the ARBCHAR command.
str[0]	number of variables returned
str[1]	ON OFF
Str[2]	arbitrary character.
ARCH	and and stains described in Americalis D. Handsson Stains and
page 677.	re-dependent string described in Appendix B: Hardware String on
str[0]	number of variables returned
str[1]	hardware dependent string
AUTOExpand	
returns the current	AUTOEXPAND status defined by the AUTOEXPAND command.
str[0]	number of variables returned
str[1]	ON OFF
AUtosave	
returns the current	autosave status defined by the AUTOSAVE command.
str[0]	number of variables returned
str[1]	OFF N
str[2]	autosave file full name
str[3]	number of modifications since the last autosave
str[4]	autosave directory
AUTOI	
returns the current	auto-indent status defined by the AUTOI command.
str[0]	number of variables returned
str[1]	ON OFF
str[2]	STAY NOSTAY
BInary	
returns the current	binary status defined by the BINARY command.
str[0]	number of variables returned
str[1]	ON OFF
CASE	
returns the current	CASE setting defined by the CASE command.
str[0]	number of variables returned
str[1]	RESPECT IGNORE

CDpath

returns the directories described in the cdpath accessed by the DACCESS command.

str[0]	number	of	variables	returned
str[i]	directo	bry	name	

CLipboard {Raw}¹

_ _

returns the contents of the clipboard. When Raw is not specified, the contents will be split line by line, and any ^M character found at the end of a line will be discarded.

str[0]	number	of va	riable	s returned
str[i]	line nu	umber	i cont	ents

CMDline

returns the current command line location defined by the CMDLINE command.

str[0]	number of variables returned
str[1]	TOP BOTTOM OFF
str[2]	line number on the logical screen. Not returned when CMDLINE is OFF.
str[3]	content of the command line. Not returned when the command line is empty.

COLOR {field | color-id | *}

returns the color associated with field, or the RGB value associated with color-id or all information about all fields and color-ids. See the color command for more information about field and color-id.

str[0]	number	of	varia	bles	returned
str[i]	color (or F	ЗGВ	value	S

CRing

returns the current file ring number. If N files are currently edited, str[1] ranges from 1 to N.

str[0]	number	of vai	riable	s returned
str[1]	current	file	ring	number

COLumn

returns the column number of the column pointer

number of variables returned str[0] str[1] current column pointer

CTaqs

returns the current TAGS setting defined by the CTAGS command.

number of variables returned str[0] ON | OFF str[1] str[2] TAGFILE

CTLchar

returns the escape character, and all control characters, if any, defined by the CTLCHAR command.

^{1.} Only available in the S/REXX environment.

str[0]	number of variables returned
str[1]	ON OFF
str[2]	escape character
str[3]	list of control characters (if any)

CURLine

returns the line number of the current line defined by the CURLine command.

str[0]	numbe	er of	varia	ables	s returned
str[1]	line	numbe	er on	the	screen
str[2]	line	numbe	er on	the	screen
str[3]	line	conte	ent		

CURSor

returns the current and the previous position of the cursor to the logical screen, the current and the previous position of the cursor in the file, the current mouse file ring number and the current position of the mouse in the file.

str[0]	number of variables returned
str[1]	line position of the cursor on screen
str[2]	column position of the cursor on screen
str[3]	line position of the cursor in file, or -1 when not on a data field
str[4]	column position of the cursor in file, or -1 when not on a data field
str[5]	previous line position of the cursor on screen
str[6]	previous column position of the cursor on screen
str[7]	previous line position of the cursor in file
str[8]	previous column position of the cursor in file
str[9]	current mouse file ring number
str[10]	line position of the mouse in file
str[11]	column position of the mouse in file
str[12]	line position of the cursor in file when the cursor is on the corresponding prefix field, or -1 when not on a prefix field

DISPlay

returns the range of selection levels defined by the DISPLAY command.

str[0]	number of variables returned
str[1]	start of display range
str[2]	end of display range

=

returns the command which will be executed when using the = command.

str[0]	numk	ber	of	va	ria	bles	5 1	returned
str[1]	the	con	man	d	in	the	=	buffer

\mathtt{ENTer}^1		

returns the ENTER, Shift-ENTER, Control-ENTER, Meta-ENTER, Shift+Control-ENTER, Shift+Meta-ENTER, Control+Meta-ENTER, Shift+Control+Meta-ENTER keys definitions.

str[0]	number of variables returned
str[1]	BEFORE AFTER ONLY IGNORE
str[2]	ENTER definition
str[3]	BEFORE AFTER ONLY IGNORE
str[4]	SHIFT-ENTER definition
str[5]	BEFORE AFTER ONLY IGNORE
str[6]	CONTROL-ENTER definition
str[7]	BEFORE AFTER ONLY IGNORE
str[8]	META-ENTER definition
str[9]	BEFORE AFTER ONLY IGNORE
str[10]	SHIFT+CONTROL-ENTER definition
str[11]	BEFORE AFTER ONLY IGNORE
str[12]	SHIFT+META-ENTER definition
str[13]	BEFORE AFTER ONLY IGNORE
str[14]	CONTROL+META-ENTER definition
str[15]	BEFORE AFTER ONLY IGNORE
str[16]	SHIFT+CONTROL+META-ENTER definition

ENViron VARNAME

returns the VARNAME environment variable.

str[0]	number of variables returned, or 0 if VARNAME
	is empty or does not exists.
str[1]	VARNAME content.

EXTRACT

returns this keyword list.

str[0]	number	of	variables	returned
str[i]	keyword	E		

FDirectory

returns the current file filedirectory.

str[0]	number	of	variables	returned
str[1]	filedin	rect	lory	

FILE²

returns the contents of all file lines.

file.0	number o	сf	varia	ables	returne	ed
file.i	content	of	the	line	number	i

FLscreen

returns the first and last line number of the current file displayed on the screen.

^{1.} Only available in the S/REXX environment.

^{2.} Only available in the S/REXX environment.

str[0]	number of variables returned	L
str[1]	first line	
str[2]	last line	

FName

returns the current file filename

str[0]	number	of	variables	returned
str[1]	filenam	ne		

FONt

returns the current active font name.

str[0]	number	of va	ariables	returned
str[1]	active	font	name	

FORMAT

returns the current FORMAT settings defined by the FORMAT command.

str[0]	number of variables returned
str[1]	JUSTIFY or NOJUSTIFY
str[2]	BLANK or EXTENDED
str[3]	SINGLE or DOUBLE

FType

returns the current file filetype preceded with a period if the current file has an extension (such as ".c"), or "0" if it does not. Note that this is slightly different from the ft expansion within an internal macro.

str[0]	number	of	variables	returned
str[1]	extensi	on		

HEX

returns the current HEX setting defined by the HEX command.

str[0]	numbe	er of	variables	returned
str[1]	ON	OFF		

HIghlight

returns the current HIGHLIGHT status defined by the HIGHLIGHT command.

str[0] number of variables returned str[1] ON | OFF

IMPcmscp

returns the current IMPCMSCP setting defined by the IMPCMSCP command.

str[0] number of variables returned str[1] ON | OFF | XON

INSert

returns the keyboard insertion mode status.

str[0]	numbe	er of	variables	returned
str[1]	ON	OFF		

KEEPBlanks

returns the current status defined by the KEEPBLANKS command.

str[0]	numbe	er (of	variables	returned
str[1]	ON	OF	F		

LASTLorc

returns the string passed to the LOCATE, CHANGE, SCHANGE, CN, SCN, FIND, FINDUP, NFIND and NFINDUP commands. This string can be modified by the SET LASTLORC command.

str[0]	number	of	variables	returned
str[1]	string	par	rameter	

LASTmsg

returns the last message issued by SEDIT.

str[0]	number	of	variables	returned
str[1]	last me	essa	age	

LENgth

returns the current line length. Note that SEDIT always deletes the trailing blanks.

str[0]	number	of va	riables	returned
str[1]	current	line	length	

LFName

returns the current file filename preceded with its filedirectory.

str[0]	numbe	er of	variables	returned
str[1]	long	file	name	

LIne

returns the current line number in the file.

str[0]	number	of	variables	returned
str[1]	line n	umbe	er	

LRecl

returns the current LRECL status defined by the LRECL command.

str[0]	number	of	variables	returned
str[1]	* N			

LScreen

returns the following information about the split screens:

str[0]	number of variables returned
str[1]	number of lines of the split screen
str[2]	number of columns of the split screen
str[3]	top left line number
str[4]	top left column number
str[5]	number of lines
str[6]	number of columns

MACRO

returns the current MACRO setting defined by the SET $\,$ MACRO command.

str[0]	numb	er	of	variables	returned
str[1]	ON	OF	F		

MARGINS

returns the current MARGINS settings defined by the MARGINS command.

str[0]	number of variables returned
str[1]	left margin
str[2]	right margin
str[3]	indent margin

MATCH¹

returns the strings matched with the arbitrary character when the last string matching command was performed with ARBCHAR set to ON.

match.0	number	of	varia	ables	returned	f
match.i	content	of	the	match	number	i

Example:

If the file contains the following line:

all birds can fly in the sky

The following S/REXX macro:

```
'arbchar on #'
'/all#fly#sky'
'extract/match'
'say "'match.0'" "' match.1'" "' match.2'"'
```

will print the following:

"2" " birds can " " in the "

MOUSEMode

returns the current MOUSEMODE setting defined by the MOUSEMODE command.

str[0]	number of	variable	es returned	
str[1]	OPENLOOK	MOTIF	FULLMOTIF	WINDOWS

NAme

returns the complete file name.

str[0] number of variables returned str[1] name

NBFile

returns the number of files in the editing ring.

str[0]	number	of	variables	returned
str[1]	number	of	files	

NBScope

When SCOPE is set to DISPLAY, returns the number of lines within the current scope,

^{1.} Only available in the S/REXX environment.

and the offset of the current line within that number.

When SCOPE is set to ALL, returns the number of lines of the file, and the current line number.

When the Top Of File is the current line, then str[2] = 0

str[0]	number o	of variak	oles ret	urne	d		
str[1]	number o	of lines	within	the	current	scope	
str[2]	position	of the	current	line	within	the scope	2

NUMber

returns the current NUMBER status defined by the NUMBER command.

str[0]	numb	er of	variables	returned
str[1]	ON	OFF		

PENDing {BLOCK} {OLDNAME} name * {target1 {target2}}

returns information about the pending lists described in the PENDING command on page 329.

BLOCK indicates that only the block pending list is to be searched for.

OLDNAME indicates that the specified name is the original name of the prefix command or macro. When OLDNAME is not specified, name is assumed to be a synonym defined by the PREFIX SYNONYM command.

name is the prefix command or macro to be searched for. When specified as *, the first pending list entry will be searched for.

target1 indicates the beginning of the range in the file where the associated prefix command or macro must be located. target1 will be located starting at the top of the file. When omitted, target1 defaults to 0.

target2 indicates the end of the range in the file where the associated prefix command or macro must be located. target2 will be located starting at the line defined by target1. When omitted, target2 defaults to the end of file.

str[0]	7, or 0 when no pending entry is found
str[1]	line number in the file
str[2]	newname - the name entered in the prefix area
str[3]	oldname - the real macro name
str[4]	BLOCK when the matching entry belongs to the
	block list, or null string otherwise
str[5]	op1, or null string when the first operand
	does not exist
str[6]	op2, or null string when the second operand
	does not exist
str[7]	op3, or null string when the third operand
	does not exist

Within an external macro, the null string is the "" string.

Point

returns the symbolic names associated with the current line.

str[0]	1, or 0 when	n no symbolic	name is	associated
str[1]	line number	followed by	the symbo	olic names

Point *1 returns all the symbolic names. str[0] number of variables returned str[i] line number followed by the symbolic names POWerinput returns the current input mode status defined by the POWERINPUT command. str[0] number of variables returned str[1] ON | OFF $PREfix^2$ returns the current prefix setting defined by the PREFIX command. str[0] number of variables returned str[1] ON | OFF LEFT | RGHT str[2] PREfix Synonym newname returns the original oldname associated with newname defined by the PREFIX SYNONYM command str[0] number of variables returned str[1] oldname PREfix Synonym * returns both the newname and the oldname associated with every prefix macro synonym defined by the PREFIX SYNONYM command. str[0] number of variables returned newname oldname str[i] PROFile returns the name of the file used at initialization as the profile. number of variables returned str[0] str[1] profile file name PWD returns the current **SEDIT** directory. Note that since an external macro executes in a different process, its current directory may be different from **SEDIT**'s directory. number of variables returned str[0] str[1] current directory RESERved returns a list reserved line numbers.

str[0]	numbe	er (of	variab	les	re	eturned
str[1]	list	of	re	eserved	liı	ne	numbers

^{1.} Only available in the S/REXX environment.

^{2.} Only available in the S/REXX environment.

RESERved $*^1$		
returns the status of	every reserved line.	
str[0]	number of variables	returned
str[i]	linenum color exthi	PSs HIGH NOHIGH text

REXX

returns information about the availability of S/REXX macros.

str[0]	nı	umber	of	var	iables 1	retur	rned	
str[1]	0	when	S/F	REXX	macros	are	not	available
	1	when	S/F	REXX	macros	are	avai	lable

RING

returns information about the files currently being edited.

str[0]	number	of	variak	oles	s ret	curned
str[1]	number	of	files	in	the	ring
str[i]	full fi	ile	name			

RMATCH

returns the matching line and column numbers, and the string matched with the last regular expression search performed by the $\underline{R/}$ command.

str[0]	number of variables returned
str[1]	matching line number
str[2]	matching column number
str[3]	string matched

Example:

Assuming line 7 of the current file is:

0007 na 102

and the following command has been issued:

====> r/a *[1-9][0-3]

rmatch.1 will contain: 7
rmatch.2 will contain: 2
rmatch.3 will contain: a 10

RW

returns the current RW status defined by the RW command.

str[0] number of variables returned str[1] ON | OFF

SCALE

returns information about the scale line defined by the SCALE command.

^{1.} Only available in the S/REXX environment.

str[0]	number of variables returned
str[1]	ON OFF
str[2]	scale line
str[3]	scale line

SCOPE

returns information about the scope status defined by the SCOPE command.

str[0]	number	c of	variables	returned
str[1]	ALL	DIS	PLAY	

SELECTION

returns information about the current selection.

str[0]	number of variables returned
str[1]	the full name of the file holding the
	selection
str[2]	LINEAR RECTANGULAR
str[3]	PENDING NOPENDING
str[4]	starting line
str[5]	starting column
str[6]	ending line
str[7]	ending column (-1 if including the ending
	virtual newline "\n" line termination)
str[8]	selection content. Each line is delimited by
	a newline "\n" character

SElect

returns the current line selection level and the maximum file selection level defined by the SELECT command.

str[0]	number of variables returned
str[1]	current line selection level
str[2]	maximum file selection level
str[3] ¹	a string of numbers showing the selection level for every line of the file.

SEP

returns information about the separator defined by the SEP command.

str[0]	number of	variables	returned
str[1]	ON OFF		
str[2]	separator	character	

SET

returns the current keyboard function key settings defined by the SET command.

str[0]	number	of	variables	returned
str[i]	key de	scr	iption	

SHBlank

returns the current status defined by the SHBLANK command.

^{1.} Only available in the S/REXX environment.

str[0]	numbe	er of	variables	returned
str[1]	ON	OFF		

SHADow

returns the current shadow status defined by the SHADOW command.

str[0] number of variables returned str[1] ON | OFF

SIZe

returns the current file length.

str[0]	number	of	variables	returned
str[1]	file l	engt	ch	

SOftbench

returns 1 when the current SEDIT session is a WorkBench EDIT session.

str[0]	number	of	variables	returned
str[1]	0 1			

SOURCE

returns the name of the currently executed macro or prefix macro.

str[0]	number	of	variables	returned
str[1]	macro	name	e	

SPAN

returns the current span setting defined by the SPAN command.

str[0]	number of variables returned
str[1]	ON OFF
str[2]	BLANK NOBLANK
str[3]	N or *

STAY

returns the current STAY setting defined by the STAY command.

str[0]	numbe	er of	variables	returned
str[1]	ON	OFF		

STReam

returns the current STREAM status defined by the STREAM command.

str[0]	number	of	variables	returned
str[1]	ON O	FF		

SYNonym¹

returns the current SYNONYM status.

str[0]	numbe	er of	variables	returned
str[1]	ON	OFF		

SYNonym name¹

returns the information about the name synonym.

^{1.} Only available in the S/REXX environment.

str[0]	number of variables returned
str[1]	name
str[2]	length of minimum abbreviation
str[3]	definition
str[4]	linend character if specified, or an empty
	string

SYNonym *1

returns the information about all the synonyms.

str[0]	number of variables returned
str[i]	<pre>name abbreviation {linend character}</pre>
	definition

TABLine

returns information about the tabulation line defined by the TABLINE command.

str[0]	number of	variables	returned
str[1]	ON OFF		
str[2]	tab line		
str[3]	tab line		

TABS

returns the tabulation column numbers defined by the TABS command.

str[0]	number	of	variables	returned
str[1]	tabulat	ior	n columns	

TARGet

returns the following data after a character string match with a LOCATE or CLOCATE target: line and column number of the first and last character in the string.

After a target specification as an absolute line number, a relative displacement or a line name, returns the line number and current column position.

When a target is specified with a logical & operator, the last match will be taken into account.

str[0]	number of variables returned
str[1]	line number of the first character
str[2]	column number of the first character
str[3]	line number of the last character
str[4]	column number of the last character

TRUnc

returns the current TRUNC status defined by the TRUNC command.

str[0] number of variables returned str[1] * | N

VARblank

returns the current VARBLANK status defined by the VARBLANK command.

str[0] number of variables returned str[1] ON | OFF

Verify returns the verify	columns defined by the VERIFY command.
str[0] str[1]	number of variables returned OFF
VIsible returns the numbe	er of visible lines.
str[0] str[1]	number of variables returned number of visible lines
VERsion returns the curren	t SEDIT version identifier.
str[0] str[1]	<pre>number of variables returned identifier: xview when running the Open Windows version. motif when running the MOTIF version. curses when running in ASCII terminal mode. windows when running the WINDOWS version.</pre>
Xhome returns the SEDI	F installation directory.
str[0] str[1]	number of variables returned installation directory
Width returns the length	of the longest line in the current file.
str[0] str[1]	number of variables returned length of the longest line
WRap returns the curren	t WRAP setting as defined by the WRAP command.
str[0] str[1]	number of variables returned ON OFF
XSHell returns the name commands.	of the last file created by the XSHELL, XCSHELL or XKSHELL
str[0] str[1]	number of variables returned name of the file
Zone returns the zone c	olumns as defined by the ZONE command.
str[0] str[1] str[2]	number of variables returned starting zone column ending zone column

FBUtton - Set Directory Editor Buttons

FBUtton ON OFf

When FBUTTON is set to ON, the directory editor supports its own set of buttons.

See Using the Buttons on page 461 for more information.

FD - Change File Directory

FD	directory-name	renames the filedirectory component of the file being
		edited.

If directory-name does not start with a standard directory indicator (/.~), **SEDIT** will search first in the current directory and then through the directories in the cdpath initialized with the <u>DACCESS</u> command.

If directory-name contains blanks, it must be surrounded with quotes or double quotes. If a directory name contains a quote or a double quote, the quote must be escaped with a backslash.

Examples: when editing /usr/ml/test.f:

fd /usr/m2 will change the name to /usr/m2/test2.f

fd essai will change the name to /home/ml/essai/test.f, if this directory exists and the cdpath initialized with the DACCESS command contains the string /home/ml.

fd "Program Files" will change the name to c:\Program Files\test.f if this directory exists and the cdpath initialized with the DACCESS command contains the string c:\.

fd is not allowed alone.

See Also: DACCESS

FIle / FFile / KFIle / DOSFile - Save and Leave File

FIle / FFile / KFIle/ DOSFile {fn {ft {fd}}}

These commands transform the unchanged source file into a backup file by appending a "%" to its name, creating a new file with the original name from the edited memory image, and then discontinuing the editing session. When SAVECLEARUNDO is set to ON (the default), the undo memory is reset.

When **SEDIT** is not running in batch mode, if the file name has been changed during the editing session so that it is identical to that of an existing file, or if the file has been modified by another user, FILE will ask for a confirmation to overwrite the existing file. FFILE will not. When **SEDIT** is running in batch mode, FILE does not overwrite the existing file.

The KFILE command performs the same function as the FILE command, but leaves the saved file timestamp unchanged. This may be useful, for example, when the modified file is an include file. Using KFILE will prevent a following make command from recompiling every file which relies on the saved file.

The DOSFILE command performs the same function as the FILE command, but adds a ^M character at the end of each line, and a ^Z character at the end of the file, thus making the file compatible with personal computers using the DOS operating system.

If fn is specified, the filename of the file will be changed before saving.

If ft is specified, the filetype of the file will be changed before saving.

If fd is specified, the filedirectory of the file will be changed before saving.

Under APL, the APL object will be fixed in the workspace. Should an error occur, the line at which the error occurred becomes the current line.

Warning: When KEEPBLANKS is set to OFF, **SEDIT** removes all trailing blanks in every line before saving a file. Do not save a file (such as an "*.o" file) where trailing blanks are part of the data.

See Also: <u>BACKUP</u>, <u>KEEPBLANKS</u>, <u>DY</u> <u>SAVE</u>, <u>RW</u>, <u>SAVE</u>, <u>SAVECLEARUNDO</u>, <u>VERIFY SAVE</u>

FILECONV - File Conversion

FILEConv CurrentFile {HowToRead {HowToCreate}

Initial value (UNIX):UNIXAUTO UNIXInitial value (WINDOWS):WINDOWSAUTO WINDOWSHowToRead Level:GlobalHowToCreate Level:GlobalCurrentFile Level:File

Every file in the **SEDIT** ring has a **UNIX** or **WINDOWS** status.

Within a **UNIX** file, lines are separated by the newline n character.

Within a **WINDOWS** file, lines are separated by the M character followed by the newline n character. In addition, a Z character indicates an end of file, and subsequent characters are ignored.

CurrentFile	Windows U	Unix			
	WINDOWS	When the file is saved to disk, lines are separated by the M character followed by the newline n character.			
	UNIX	When the file is saved to disk, lines are separated by the newline n character.			
		A period can be used as a place holder. This allows to specify HowToCreate or HowToRead without changing CurrentFile.			
HowToRead	Auto Unix				
	AUTO	SEDIT determines automatically the type of the file read from storage by checking the existence of ^M characters. ^M characters preceding a newline character are not displayed on the screen.			
	UNIX	SEDIT always considers the file a UNIX file. M characters are displayed on the screen.			
		A period can be used as a place holder. This allows to specify HowToCreate without changing HowToRead.			
HowToCreate	Windows U	nix			
	WINDOWS	A new file is a WINDOWS file. This is the default on WINDOWS systems.			
	UNIX	A new file is a UNIX file. This is the default on UNIX systems.			

Without parameters, FILECONV displays its current status.

Notes: The OpenLook, MOTIF and WINDOWS versions of SEDIT display on the upper border of the window a [U] symbol when the current file is a UNIX file, and a [W] symbol when the current file is a WINDOWS file.
On UNIX systems, the name of a WINDOWS file displayed on the first screen line is followed with a [W] symbol.

On **WINDOWS** systems, the name of a **UNIX** file displayed on the first screen line is followed with a [U] symbol.

Examples:	FILEC U A U	
	FILEC W	changes only the HowToCreate parameter.

A WINDOWS file displayed on a UNIX system:

SEDIT & C(m1) - testinstall.txt [W], dir: /home/xed/help /home.nt/pure/purify/testinstall.txt [W] Len:41 mod: testinstall.txt 00000 00001 [I] Starting Purify'd TestInstall.exe at 06/21/97 12:28:18 00002 Instrumented executable: C:\Pure\Purify\cache\TestInstall\$Pur ify_C_Pure_Purify.exe 00003 Working directory: C:\Pure\Purify Command line arguments: -quiet 00004 00005 Process ID: 0x196 00006 [I] Starting main 00007 [I] Searching for all memory leaks ... 00008 [W] MLK: Memory leak of 80 bytes from 1 block allocated in calloc 00009 Distribution of leaked blocks 00010 80 bytes from 1 block of 80 bytes (0x00142fd0) 00011 Allocation location ===> 1:Q 2:E 3:Save 4:Sp 5:x 6:cu 7:U 8:D 9:? 10:h 12:= S-11:top S-1

See Also: <u>FILE</u>, <u>SAVE</u>

FILTER

FILTer - Filter the Selection Contents

filtername must be an external program, able to retrieve data from its standard input, process it in some way and then send it back using its standard output.

nn is an optional time-out. If not specified, it will be set to 10 seconds.

options may be any option passed to filtername.

If the current file has no selection, **SEDIT** will select the cursor line.

SEDIT proceeds in the following manner:

- It deletes the selection, as if the CUT key had been used.
- It sends the shelf (the cut buffer) to filtername.
- It retrieves the data sent by filtername into the shelf.
- It does a paste, as if the PASTE key had been used.

A filter example is {install-dir}/filters/toggle_comment.c.

This filter is useful within C programs, allowing the user to comment in or out the selected or cursor lines.

On Sun workstations, the standard profile.sedit file assigns toggle_comment to Control-R5 in the following manner:

set c-r5 filter \$xhome/filters/\$arch/toggle_comment

On HP workstations, it is assigned to the Control-R9 (or Control-Prev) key:

set c-r9 filter \$xhome/filters/toggle_comment

On other workstations, it is assigned to the Control-R6 (or Control-Page-Up) key:

set c-r6 filter \$xhome/filters/toggle_comment

Note: use the -Bstatic flag when compiling a filter on a SunOS Sun workstation for shorter response time.

FINd (XEDIT MODE) - Find a Starting String

FINd	str	searches forward for a line that starts with str.
XEDFINd	str	

When <u>MODE</u> COMMAND XEDIT is in effect, FIND calls the XEDIT mode XEDFIND command. PDFFIND may be used to call the ISPF/PDF mode FIND command.

FIND searches forward for a line that starts with str.

When str contains imbedded blanks, those character positions in the file line are ignored.

When str contains underscore characters (_), those character positions in the file line must be blank.

When WRAP is set to OFF, the search continues down to the end of the file.

When WRAP is set to ON, the search will wrap to the first line in the file, and continue down to the current line.

See Also: FINDUP, NFIND, NFINDUP, STAY, WRAP

FINd (ISPF MODE) - Find a Data String

FINd	str	{range}	$\{\underline{\text{NEXT}}\}$	$\{\underline{CHARS}\}$	{X}	${coll}$	$\{col2\}$
PDFFINd			$\{ALL\}$	$\{PREFIX\}$	$\{NX\}$		
			$\{FIRST\}$	$\{SUFFIX\}$			
			$\{LAST\}$	{WORD }			
			{PREV }				

When <u>MODE</u> COMMAND ISPF is in effect, FIND calls the ISPF mode PDFFIND command. XEDFIND may be used to call the XEDIT mode FIND command.

FIND searches a line that contains the str PDF string. A PDF string may be the following kind of string:

* The string used with the last FIND/EXCLUDE/CHANGE/SEEK command.

Simple string

Any series of characters not starting with a single or double quote (' or ") and not containing any embedded blanks. The search will be case insensitive.

Delimited string

Any string enclosed by single or double quotes. The search will be case insensitive.

Hexadecimal string

Any delimited string of valid hexadecimal characters, preceded or followed by the character X, such as X'3132' or '3132'x. The search will be case sensitive.

Character string

Any delimited string, preceded or followed by the character C, such as C'ab cd' or 'ab cd'c. The search will be case sensitive.

Picture string

Any delimited string, preceded or followed by the character P, such as P'ab cd' or 'ab cd'p. The search will be case sensitive. Within a picture string, the following special characters may be used:

- = means any character.
- ~ means any character that is not a blank.
- . means a character which generally cannot be displayed. **SEDIT** will consider this any character which has a decimal value of less than 32.
- # means any numeric character.
- means any non-numeric character.
- @ means any alphabetic character.
- < means any lowercase alphabetic character.
- > means any uppercase alphabetic character.
- \$ means any special character, neither alphabetic or numeric.

FIND considers the following arguments:

range	Two labels that identify the lines to be searched for. A label may be created by typing a .xxxx string on a prefix zone, or by u the XEDIT POINT command described on page 331. A label may also be one of the ISPF/PDF predefined labels:			
	.zf or .zfirst .zl or .zlast .zcsr	the first line. the last line. the cursor line		
	When omitted, range defaults to .zfi	rst .zlast.		
<u>NEXT</u>	Starts at the first position after the current NEXT is the default. When the cursor is r from the first displayed line.	t cursor location and searches forward. not located on the data, the search start		
ALL	Starts at the top of the file and searches string.	forward to find all occurrences of the		
FIRST	Starts at the top of the file and searches the string.	forward to find the first occurrence of		
LAST	Starts at the bottom of the file and searcher of the string.	es backward to find the last occurrence		
PREV	Starts at the cursor location and search occurrence of the string. When the cursor start from the last displayed line	ches backward to find the previous r is not located on the data, the search		
<u>CHARS</u>	Locates str anywhere the characters ma	atch. This is the default.		
PREFIX	Locates str at the beginning of a word: find ab matches "abc", but does not n	natch "ab" or "cabd" or "dab".		
SUFFIX	Locates str at the end of a word: find ab matches "cab", but does not m	natch "ab" or "cabd" or "abc".		
WORD	Locates str as a whole word: find ab matches "d ab e", but does not be ab et a	not match "cabd" or "abc".		
х	Scans only lines that are excluded from t	he display.		
NX	Scans only lines that are not excluded from	om the display.		
coll and o	col2			

The columns FIND is to search. When omitted, the columns are limited by the BOUNDS setting described on page 159.

Examples:

find 'ab cd'	matches 'ab cd' as well as 'Ab Cd'.
find c'ab cd'	matches only 'ab cd'.
find x'31' last	matches the last '1' character.
find p'>###"	could match 'A123'.

Return Codes:	0	Normal
	4	String Not Found
	5	* has been used on the first FIND call
	6	Invalid Hexadecimal String
	7	Invalid Label

12 Syntax Error

See Also: BOUNDS, EXCLUDE, CHANGE, SEEK, VERIFY

FINDUp - Find a Starting String

FINDUp	str	searches backward for a line that starts with str.
FUp	str	

When str contains imbedded blanks, those character positions in the file line are ignored.

When str contains underscore characters (_), those character positions in the file line must be blank.

When <u>WRAP</u> is set to OFF, the search continues up to the start of the file.

When WRAP is set to ON, the search will wrap to the last file line, and continue up to the current line.

See Also: FIND, NFIND, NFINDUP, STAY, WRAP

FLAth - Directory Editor Permissions Display

```
FLAth {ON|OFF}
```

Initial value: ON

FLATH without argument displays the current value.

When FLATH is ON, the <u>FLIST</u> directory editor displays the file related permissions:

Level 0 40 Files				1 OF	40
-rw-rw- test	.f	a		1207	16/02/88 01:19
-rw-rw-rw- test1	.f	a		457	06/02/88 13:31
-rw-rw-rw- include	.h	a		11111	11/01/88 18:44
-rw-rw-rw- command*		a		9870	16/04/87 21:44
a : /usr/m1					
b : /usr/m1/cmd					
c : /usr/bin					
d : /usr/etc					
e : /etc					
1:/SN 3:END 4:XED	5:SWI	ГСН	6:/SB 7:U 8:D 9:/S	D 10:/ST	11:-> 12:CAN

When FLATH is OFF, the **FLIST** directory editor does not display the file related permissions:

Level 0	40 Files			1 OF	5 40
test	.f	а		1207	16/02/88 01:19
test1	.f	а		457	06/02/88 13:31
include	.h	а		11111	11/01/88 18:44
command*		а		9870	16/04/87 21:44
a : /usr/m	1				
b : /usr/m	1/cmd				
c : /usr/bi	n				
d : /usr/ete	c				
e : /etc					
1:/SN 3:H	END 4:XED	5:SW	ITCH 6:/SB 7:U 8:D 9:/SI	D 10:/ST	11:-> 12:CAN

allowing more space for displaying long file names.

When **FLIST** is running, typing ^a (Control-a) switches the FLATH mode.

FLDATE - Directory Editor Date Format

FLDATE {Europe|Us}

defines if date is displayed in European or American format.

Initial value: EUROPE

When FLDATE is set to EUROPE, <u>FLIST</u> displays dates using the DD/MM/YY format. When FLDATE is set to US, **FLIST** displays dates using the MM/DD/YY format.

<u>FLFile - File + FLIST</u>

FLFile

executes a FILE command and then switches to the directory editor.

Batch Mode: Not Available

This command is mapped to the **^**F3 key on Sun workstations, and **^**R3 (**^**Pause) on other workstations. See The Directory Editor FLIST on page 453 for further explanations.

Warning: Being a text editor, **SEDIT** removes all trailing blanks in every line before saving a file. Do not save a file (such as an "*.o" file) where trailing blanks are part of the data.

FFList - Call Directory Editor

Batch Mode: Not Available

FFLIST only displays non-directories. See The Directory Editor FLIST on page 453 for further explanations.

See Also: <u>DACCESS</u>, <u>DFLIST</u>, <u>FLIST</u>, <u>FLATH</u>, <u>FLPP</u>, <u>FMACRO</u>, <u>RFLIST</u>

Flist - Call Directory Editor

Flist { FN {FT {FM}}} will call the directory editor.

Batch Mode: Not Available

This command is mapped to the *f* key by default. See The Directory Editor FLIST on page 453 for further explanations.

See Also: <u>DACCESS</u>, <u>DFLIST</u>, <u>FFLIST</u>, <u>FLATH</u>, <u>FLPP</u>, <u>FMACRO</u>, <u>RFLIST</u>

FMACRO - Execute FLIST Macro

FMAcro ON OFF

Initial value: OFF *Level:* Global

When FMACRO is OFF, **FLIST** looks for native commands before looking for macros. When FMACRO is ON, **FLIST** looks for macros before looking for native commands. See Using S/REXX Macros Within FLIST section on page 472 for more information.

FLOW - Reformats Text

A11

FLOW {target} left justifies text and sets text within margins.

Scope:

This command is mapped to the Shift-Control-F (^F) key by default.

FLOW reformats a portion of the current file defined by the target operand. FLOW adjusts the text within a paragraph so that all lines start at the left margin column (the first line starts at the paragraph indent column though), and all lines end before the right margin.

According to the settings defined by the <u>FORMAT</u> command described on page 273, FLOW may justify every line, and insert one or two spaces at the end of each sentence.

The margins and paragraph indent values are set with the MARGINS command described on page 307.

target may be one of the following:

All	All of the file is formatted.
Cursor	Has a special meaning. See below.
CURSOR_Strict	Has a special meaning. See below.
:N	Up to but not including the line N.
+N	Down N lines.
-N	Up N lines.
+* or *	Down to the end of file.
_ *	Up to the top of file.
.symb	Up or Down to the line which has been assigned the .symb symbolic name by using the POINT command, or a .symb prefix command.
string expression	Defines a group of characters to be located.

The general format of a string expression is the following:

{+|-}{~}/string1{/{&}|{|}{~}/string2}

See the **LOCATE** command on page 300 for a precise string expression definition.

When target is not specified, FLOW formats the paragraph corresponding to the cursor location. When the cursor is not located upon a line of the current file, FLOW reformats the paragraph corresponding to the current line. If the cursor or the current line is a blank line, FLOW searches for the next non-blank line to locate the start of the paragraph to format.

The cursor is moved to the line below the last line processed by the FLOW command.

Examples: FLOW FLOW all FLOW cursor FLOW cursor_strict FLOW /str/ Consider the following text:

00001 target defines the number of lines to be scanned for a match. Lines are changed starting with the current line, up to but not including the target line. target may be one of the following:

With the cursor located here

With <u>MARGINS</u> set to "5 72 +0", FLOW will reformat that text in the following way:

00001	target defines the number of lines to be scanned for a match. Lines
00002	are changed starting with the current line, up to but not including
00003	the target line. target may be one of the following:

FLOW CURSOR does not modify the part of the data line located at the left of the cursor, and aligns the following lines between the cursor location and the right margin:

00001 target	defines the number of lines to be scanned for a match.
00002	Lines are changed starting with the current line, up to
00003	but not including the target line. target may be one of
00004	the following:

Using the CURSOR_STRICT Operand

The CURSOR_STRICT operand is similar to the CURSOR operand. The only difference is that **SEDIT** considers that the phrase starts at the cursor line instead of looking backwards for the start of the phrase.

See Also: <u>CENTER</u>, <u>FORMAT</u>, <u>LEFTADJUST</u>, <u>LOCATE</u>, <u>MARGINS</u>, <u>POWERINPUT</u>, <u>RIGHTADJUST</u>, <u>TRUNC</u>

FLPP - Directory Editor Parent Directory Display

FLPP {ON|OFF}

Initial value: ON

FLPP without argument displays the current value.

When FLPP is ON, the <u>FLIST</u> directory editor displays a "..." string. Clicking on this string opens a new **FLIST** level on the parent directory.

<u>FLQuit - AQUIT + F</u>

FLQuit

executes a AQUIT command and then switches to the directory editor.

Batch Mode: Not Available

This command is mapped to the ^F1 key on Sun workstations, and ^R1 (^Print-Screen) on other workstations.

FN - Change Filename

FN {filename} renames the filename component of the file being edited.

If filename contains a period ("."), the filetype will be changed too.

If filename contains blanks, it must be surrounded with quotes or double quotes. If a filename contains a quote or a double quote, the quote must be escaped with a backslash.

Example: assume /usr/ml/test.f is the file currently being edited:

fn test2 will change the name to/usr/ml/test2.f
fn will change the name to /usr/ml/.f
fn test2.c will change the name to /usr/ml/test2.c
fn "a b" will change the name to /usr/ml/a b.c

FOLLOW - Follow Links

FOLLOW {ON | OFF} Initial value: ON

Level: Global

When FOLLOW is ON, **SEDIT** checks to see if a loaded file is a symbolic link, and replaces it with the file to which the symbolic link points.

FOLLOW OFF disables this behavior. This may be useful when using automounted directories, in which real names are often confusing for the end user.

Without parameters, FOLLOW displays its current setting.

Examples: FOLLOW OFF FOLLOW

See Also: <u>XEDIT</u>

FONt - Change Font

FONt

{fontname}

Query FONt

Batch Mode: Not Available

With no parameters, the command FONT shows in a fullscreen manner the available fonts on the server.

A font may be selected by clicking on its name with the left mouse button.

A return to the editor is achieved by pressing the F1 key.

Depressing the F2 key or ^m adds a fonts.files file in the editing ring, containing all the font names.

QUERY FONT displays the active font.

FORMAT - Set Formatting Parameters

FORMAT	{Justify Nojustify} {Blank Extended DOT DOTExtended {NONE Single DOUble}
Initial value: NO Level: Fi	JUSTIFY BLANK DOUBLE le
FORMAT affects determines the sta	how paragraphs are formatted by the <u>FLOW</u> command, and how FLOW art and the end of a paragraph.
Justify	the paragraphs are justified within the margins defined with the <u>MARGINS</u> command.
Nojustify	the paragraphs are not justified.
Blank	paragraphs are separated with a blank line.
Extended	paragraphs may also be separated with a blank line. In addition, a new paragraph is encountered if the left margin value is 1, and a line starts with a tabulation character, a blank character, a colon or a period.
DOT	paragraphs may also be separated with a blank line. In addition, a new paragraph is encountered if the previous line ends with one of the following characters:
DOTExtended	combines the DOT and EXTENDED rules.
Single	 one space is inserted after each sentence. A sentence is a string of characters within a paragraph ending with one of the following characters: ? and followed by an uppercase character.
DOUble	two spaces are inserted after each sentence.
NONE	no spaces are inserted after each sentence.
These arguments	can be entered in any order.
Without an argun	nent, FORMAT displays the current setting.
Examples:	FORMAT B N S FORMAT
See Also: <u>CENTE</u>	ER, FLOW, LEFTADJUST, MARGINS, POWERINPUT,

RIGHTADJUST, TRUNC

FORward - Scroll Forward

```
FORward {N | *}
```

scrolls down N pages: the last line displayed becomes the current line N times.

Scope: Display

FORWARD 0 makes the first line in the file become the current line.

FORWARD * makes the end of file the current line.

When the current line is the end of file, and when <u>MODE</u> SCROLL WRAP is in effect, FORWARD makes the first line the current line.

This command is mapped to the F8 key by default.

Return Codes:	0	Normal
	1	End Of File Reached
	5	Invalid Operand

See Also: MODE

FT - Change Filetype

FT {filetype} renames the filetype component of the file being edited.

If filetype contains blanks, it must be surrounded with quotes or double quotes. If a filetype contains a quote or a double quote, the quote must be escaped with a backslash.

Examples: assume /usr/ml/test.f is the file currently being edited:

- ft p will change the name to /usr/m1/test2.p
- ft will change the name to /usr/ml/test
- ft "c d" will change the name to /usr/ml/test/c d

GET - Insert Data

```
Get {fn {ft {fd{ firstrec{ numrec}}}}} inserts data.
```

```
Get {fn{ firstrec{ numrec}}}
```

Without parameters, GET inserts data previously saved either by a PUT command or by a PU/PP prefix command at the current line location.

With parameters, GET will construct the file name to be searched for according to fn, ft and fd.

fn is the filename part of the file. However, if fn starts with "~", "/", "./" or "../", fn will be considered as a full **UNIX** or **WINDOWS** name, and ft and fd must not be specified.

ft is the filetype part of the file. When ft is omitted, the filetype of the current edited file will be used. When ft is specified as a period (.), no filetype will be used.

fd is the directory to be searched for. When not specified, or specified as a question mark (?), all the directories described in the PATH (or XPATH) environment variable, or accessed with the ACCESS command, will be searched for.

firstrec is the first line number to be inserted. When not specified, the first line in the file will be the first inserted line.

numrec specifies the number of lines to be inserted. When not specified, or specified as *, all the lines following the line firstrec will be inserted.

When MODE GET NOSTAY is in effect, the last inserted line becomes the current line.

Examples: If "test.f" is the file currently being edited:

get	test1			will load test1.f
get	testl F			will load test1.F
get	testl .			will load test1
get	./test1			will load ./test1
get	test1 .	?	2	5 will load 5 lines starting at line 2 of the
				test1 file, searching for this file in the
				accessed directories.
get	~/test1	2	5	does the same with \sim /test1.
get				will insert data previously saved by a PUT
				command.

Under APL, "get LIST" will insert the APL object "LIST".

See Also: <u>ACCESS</u>, <u>MODE</u>, <u>PUT</u>
GET_Panel - Fullscreen User Interface

panelfile refresh panelfile cursor nme panelfile refresh cursor nme panelfile

```
Batch Mode: Not Available
```

When the refresh option is specified, GET_PANEL displays the panel without waiting for a user action.

When the cursor nme option is specified, GET_PANEL places the cursor on the nme field.

If panelfile does not start with a directory indicator, like "/", "./", "~/", it will be searched for in the current directory first.

If not found, it will be searched for in the directories described by the environment variable XPATH, or PATH, or in the directories accessed by the command <u>ACCESS</u>.

Then, a fullscreen panel instance of panelfile will be displayed. The user will be able to fill in the input fields, and enter an action keystroke such as "return" or "F2".

After this action keystroke, **SEDIT** will save the contents of each input field into an environment variable whose name is the field name, save the action keystroke in the RETURN environment variable, save the mouse position in the MOUSE environment variable, save the cursor position in the CURSOR environment variable and return to the editor.

The file {install-dir}/demo/sample_panel is an example of such a file:

```
*
   Sample panel for the "get_panel" command
Button "Quit" "Save"
      header
name
start
       2 1
       1 90
size
color maroon
hi normal
type output
                  ***** PANEL HEADER
content "
     *
* Sample output field
name output1
start 41
      1 13
size
color black
hi normal
type output
content Enter option:
*
* Sample input field
*
name OPTION
      یک<sup>.</sup>۲۱(
4 15
۱
start
size
color
       red
        normal
hi
type
        input
intensity 1
content Option 0
menu "Option 1" "Option 2" "Option 3"
```

Typing get_panel {install-dir}/demo/sample_panel will display the following screen:

Quit Save	
*************** PANEL HEADER ************************************	
Enter option: Option 0)

Clicking with the third mouse button on the Option 0 field will bring up the following menu:



Releasing the mouse will fill this field with the selected option.

Typing ^r will redraw the original screen.

Typing ^c will cancel the get_panel command without further reading.

Clicking on the first button (Quit) will fill the RETURN variable with the string B1.

Each field is described by the following attributes:

Name nme	nme is the environment variable which will be used to store the field content.		
STart y x	the line and column starting location. Upper-left corner is 1 1.		
SIze ll cc	the field size: 11 is the number of lines, cc is the number of columns.		
Color col	col is the field color. See the COLOR command on page 182 for a complete list of all available colors.		
Hightlight hlt	hlt is the hightl	ight which will be used:	
	Normal Underline Reverse	No hightlight. The field will be underlined. The field will be displayed in reverse video.	
Type tpe	tpe may be one	of the following:	
	Input Output	You are allowed to type any character. You are not allowed to type anything. The field content will not be saved in the nme environment variable.	

	Numerical	You are allowed character.	1 to type any numeric
Menu stringl {str:	ing2} A menu made with time the user click The field will be fi	the different strings s on the field with illed with the select	gs will be displayed each the third mouse button. cted string.
Intensity 0 1 2	A 0 intensity allow are not displayed. A 2 intensity displ	vs the user to creat ays characters in I	e a field whose contents
CONtent cnt	The original field already exist, its c may start with an of The content cr	content. If the nm ontents will overr optional ". nt field may be on	e environment variable ide the cnt value. cnt mitted.

Note: The created environment variables will be defined in the **SEDIT** main process. Since external macros run on different processes, the user cannot call the get_panel command within an external macro, and then get the results directly in the same macro. The user must use the extract environ facility to retrieve the **SEDIT** environment variables.

GLOBALCase - Global File Case Handling

GLOBALCase {Respect | Ignore }

Initial value (UNIX): RESPECT Initial value (WINDOWS): IGNORE

The GLOBALCASE setting is used on the following occasions:

- When the XEDIT command is used, **SEDIT** checks if the requested file is in the editing ring before attempting to load it from disk. When GLOBALCASE is set to IGNORE, the checking is not case sensitive.
- When loading a new file in the editing ring, **SEDIT** checks the filetype of the file to match a filetype described with the SYNTAX command to apply the corresponding syntactic rules. When GLOBALCASE is set to IGNORE, the checking is not case sensitive.

Without parameters, GLOBALCASE displays its current setting.

HAsh - Scan Directories

```
HAsh {dir1 {dir2} {\ldots}}
```

HASH scans every directory passed as an argument, searching and loading in memory every *.x, *.ex and *.sedit file. These files will then be available as macro commands.

If no directory is specified, every directory described in the PATH or XPATH environment variables will be scanned.

Any of the dirn entries may also be a file instead of a directory.

Help - Fullscreen Help

Help		Shows in fullscreen mode all the available SEDIT commands help files.
Help	helpfile	Displays the command related helpfile help file. If helpfile is not a command related help file, the TASK and the REXX related help files will be searched for.
Help	TASK	Shows in fullscreen mode all the available task related help files.
HELP	Task helpfile	Displays the TASK related helpfile file.
Help	REXX	Shows in fullscreen mode all the available S/REXX related help files.
HELP	Rexx helpfile	Displays the S/REXX related helpfile file.
Help	-dir drd	The directory <i>drd</i> will be used when scanning for help files. By default, HELP uses the \$xhome/help directory.

Batch Mode: Not Available

HELP without arguments displays the following screen:

~	~ ~ ~ ~ ~	Click or Tab+	Return to displ	lay neip
#		autosave	c_starts	compile
*		backup	cancel	complete
+*		backward	cappend	compress
+		bottom	caps	сору
_*		bounds	case	count
-		builtin	cd	coverlay
-/		button	cdelete	create
- \		c_aplstop	center	creplace
/		c_apltrace	center_end	ctags
:		c_dup	center_init	ctlchar
=		c_endcurl	center_send	curline
?		c_endline	cfirst	cursor
?i		c_ends	change	daccess
\setminus		c_endsr	chg	delay
access		c_ext	cinsert	delete
add		c_lineadd	clast	display
all		c_linedel	clearerrors	down
apl		c_scrh	clocate	duplicat
aquit		c_scrj	cmdline	dy_all
arbchar		c_scrv	cn	dy_exclude
autoexp		c_split	color	dy_find
autoi		c_startline	command	dy_font
1/^c:OUTT	5:t:	ask 7:Scroll up	8:Scroll down	S = F11:top S = F12:b

Clicking on any item such as "cursor" loads the corresponding help file in Read Only mode. To customize and save this help file, you must issue the RW ON command before issuing the SAVE command.

On ASCII terminals, move the cursor (using the TAB key for example) and depress the Return or Enter key.

Depressing the F5 key shows a similar task help panel.

Depressing the F5 key again shows a similar **S/REXX** help panel.

HELP cmd immediately loads the cmd related file. The command cmd can be abbreviated in the same way it can be used within **SEDIT**.

HELP task displays the task fullscreen panel.

HELP rexx displays the **S/REXX** help fullscreen panel.

Examples:	h h	displays these help manual pages.
	help	
	help task	
	help hi	displays the HIGHLIGHT help file.
	help rexx	displays the S/REXX help files.
	help prefix	displays the PREFIX command help file.
	help t prefix	displays the PREFIX task help file.

On Sun workstations, the command HELP is mapped to the L11/HELP key by default. HELP TASK is mapped to Shift-HELP, and HELP REXX to Control-HELP.

See Also: RW

HEX - Hexadecimal Target

HEX ON OFF

Initial value: OFF

When HEX is set to ON, targets and string operands may be specified in hexadecimal notation.

Examples: hex on c /x'31'/x'32' changes all "1" with "2". /x'31' searches for "1".

See Also: <u>CHANGE</u>, /

HEXType - Hexadecimal Display

HEXType { target }	creates a new file displaying the current file content
	in both hexadecimal and ASCII representation.

When target is not specified, the current line will be typed.

target defines the number of lines to be typed. Lines are typed starting with the current line, up to but not including the target line. target may be one of the following:

N or +NN lines.+* or *The end of filesymbThe line which has been assigned the .symb symbolic name by using the POINT command, or a .symb prefix command.string expressionDefines a group of characters to be located.	:N	Up to but not including the Nth line.
+* or *The end of filesymbThe line which has been assigned the .symb symbolic name by using the POINT command, or a .symb prefix command.string expressionDefines a group of characters to be located.	N or +N	N lines.
. symbThe line which has been assigned the . symb symbolic name by using the POINT command, or a . symb prefix command.string expressionDefines a group of characters to be located.	+* or *	The end of file.
string expression using the POINT command, or a .symb prefix command. Defines a group of characters to be located.	.symb	The line which has been assigned the . ${\tt symb}$ symbolic name by
string expression Defines a group of characters to be located.		using the POINT command, or a .symb prefix command.
	string expression	Defines a group of characters to be located.

The general format of a string expression is the following:

{+|-}{~}/string1{/{&}|{|}{~}/string2}

See the **LOCATE** command on page 300 for a precise string expression definition.

The last typed line becomes the current line.

The new file will be named \$fn.hextype, where \$fn is the currently edited file filename.

Len:6

mod:

Example: assume the user is editing the following "test.c" file:

```
/usr/ml/test.c
test.c
00001 /*
00002 * test file
00003 */
00004 main()
00005 {
00006 }
```

SEDIT and S/REXX Reference Manual

Typing hextype / { / will create the following test.hextype file:

```
/usr/ml/test.hextype Len:6 mod:
test.c test.hextype
00001 2F2A
00002 / *
00003 202A2020 74657374 2066696C 65
00004 * test fil e
00005 202A2F
00006 * /
00007 6D61696E 2829
00008 main ()
```

HIghlight - Disable Highlight

HIghlight ON | OFFsets the highlight feature ON or OFF.Initial value:ONLevel:Global

Some ASCII terminals do not properly display reverse video characters. In such cases, review the "profile.sedit" macro to execute the "highlight off" command when running **SEDIT** on that terminal.

Example:

If your are running a "wyse50" terminal, type the following bold-faced line:

```
if version = 'curses' then
do
/*
 * If your terminal does not handle reverse video characters,
 * ucomment and update the following lines
 */
/* if $TERM = '??my-terminal??' then "highlight off" */
    if $TERM = 'wyse50' then "highlight off"
```

HIGHLIGHT without arguments displays the highlight status.

HIStory - Set the History Length Buffer

HIStory {N}

Initial value: 10 Level: Global

HISTORY sets to N the length of the history buffer where the commands entered in the command field are saved. These commands may be redisplayed by using the ? and ?I commands, generally assigned to the F9 and Shift F9 keys.

When N is not specified, the current value will be displayed.

See Also: SHOWHISTORY, XSHOWHISTORY, ?, ?I

HOme - Switch Cursor Position

HOme

If the cursor is in a DATA FIELD, it will be moved to the COMMAND FIELD. A subsequent action will restore its previous location.

This command is a shortcut for the "cursor home" command and is mapped to the F10 key by default.

When CMDLINE is OFF, using the HOME or CURSOR HOME command restores the command line in order to let the user enter a command. Once the command is processed, the command line is removed.

See Also: <u>CMDLINE</u>, <u>CURSOR</u>

IMPcmscp - Implicit UNIX or WINDOWS Execution

ON XON OFF
XON (non-batch mode)
OFF (batch mode)
Global

When IMPCMSCP is OFF, **SEDIT** issues an error message when the user types an unknown command. If BEEP is ON (the default), **SEDIT** sounds a warning beep.

On **UNIX** systems, when IMPCMSCP is ON, **SEDIT** passes to the Bourne Shell sh any unknown command, and displays its results in the window **SEDIT** was started from. If the command ends with an & sign, this command will run in the background.

When IMPCMSCP is XON, **SEDIT** also passes the unknown command to sh, but retrieves its results within an editable file. A final & sign will be ignored.

On **WINDOWS** systems, ON and XON execute the unknown command directly in a similar way.

See Also: <u>BEEP</u>, <u>MESSAGESDIR</u>, <u>SHELL</u>, <u>XSHELL</u>

Input- Add a Text Line

Input {text} adds a line after the current line.

A new line will be inserted after the current line. If text is omitted, the line will be a blank line.

ISOConv - Set ISO Conversion

ISOConv ON OFF

sets the automatic ISO conversion ON or OFF.

Initial value: ON Level: Global

On some architectures, the keyboard always sends to the application ISO8859-1 characters, while the environment setting may require the use of native font sets, such as IBM-850 characters on IBMs and Roman8 on HPs.

When ISOCONV is set to ON, automatic conversion between ISO8859-1 set and native set will take place.

The README FIRST document explains what architectures currently support this conversion.

A side effect of the ISOCONV ON command is that it will unload any translation table loaded with the KEYBOARD command.

See Also: KEYBOARD

ISwitch - Switch Between files

ISwitch

allows the user to switch from one file to another in a circular sequence in reversed order.

This command is mapped to the S-F5 key by default.

When the user is editing multiple files, using F5 and Shift-F5 will toggle between two of them without visiting others.

See Also: SWITCH

KEEPBLanks - Trailing Blanks Removal

```
KEEPBLanks ON|OFF {FT string}
```

disables or enables the automatic removal of trailing blanks.

```
Initial value: OFF FT *
Level: File
```

By default, **SEDIT** removes all trailing blanks in every line when loading a file, when editing a line and when saving a file.

Trailing blanks are generally meaningless within text files, but may be essential within binary files. When KEEPBLANKS is set to ON, **SEDIT** does not remove trailing blanks.

In addition, when not running in character mode, when <u>SHBLANK</u> is set to ON (the default), and when the last character in a line is a blank, **SEDIT** displays a thin vertical bar just after that last blank character.

If you specify FT string, this setting will become the default for every new file with a string filetype. If FT is *, this will be the default for any file. A period (.) may be used if no filetype is required. This setting is also applied to the current file, unless its filetype does not match FT.

To force the opening of a file in KEEPBLANKS ON mode, the user can use the XKB command.

Examples: keepbl on

keepbl on ft o

SEDIT will not remove blanks on files with an ".o" extension.

Notes: KEEPBLANKS ON is not sufficient to preserve binary files integrity. Use BINARY ON or XBIN instead.

Using KEEPBLANKS ON on a file already loaded is not sufficient to preserve its integrity since trailing blanks removal is done at load time before the file is actually displayed. Use either XKB file or KEEPBLANKS ON FT xx before loading file.xx

See Also: <u>AUTOBIN</u>, <u>BINARY</u>, <u>SHBLANK</u>, <u>XBIN</u>, <u>XKB</u>

KEYboard - Redefine Keyboard

KEYboard filename {type} redefines the keyboard according to the file filename.

type is an optional parameter specifying the keyboard type:

- 1 means an older style Sun keyboard with 9 top keys.
- 2 means a newer style Sun keyboard with 12 top keys.

"filename" is a file describing the keyboard mapping.

If the file name does not start with a directory indicator such as ".", "/" or "~", the current directory will be searched first, and then the directories described either in the environment variable XPATH (if there is one) or in PATH, or in directories accessed by the <u>ACCESS</u> command.

If filename is a single period, it will be ignored, allowing the user to specify the keyboard type without redefining the keyboard.

A blank line or a line starting with "*", "#" or "+" will be ignored.

Every line must contain three fields separated by a colon:

• The rank	0 means non-APL standard mode.
	1 means non-APL shifted mode.
	2 means non-APL meta mode.
	3 means APL standard mode.
	4 means APL shifted mode.
	5 means APL meta mode.
	6 describes the real physical keyboard. It must be used only if the keyboard is not an English QWERTY keyboard. In this case, all the keys must be described.
• The emitted character	is the character sent by the standard keyboard in non-APL mode.
• The displayed character	is the character mapped on the key corresponding to the emitted character as described above. A 0x00 value will inhibit the key. If the rank is 6, it must be the standard upper character.

A character may be described either quoted or in hexadecimal. The meta key is labelled left or right on Sun type 3 keyboards, and \Diamond on the new type 4 keyboards.

Examples:	0:'0':'0'	maps the '0' character to the '0' sun keyboard key in the non-APL standard mode.
	4:'i':0xD4	maps the iota APL character to the shift-i key in the APL shifted mode.

The hexadecimal value for a character is the value it has in the font used to display it. Note that the "Escape" key may be redefined for that usage by setting "0xlB" in the emitted character field. **SEDIT** on **UNIX** systems is distributed with two keyboard translation samples:

/home/xed/keyboard/STANDARD.TRANS

This file redefines the keyboard mapping to its original built-in setting. If the user wants to use this setting (described in Appendix A), the user must start DYALOG APL with the script "/home/xed/aplsedit" in order to have the same keyboard mapping within APL.

This setting is more logical than the default DYALOG APL setting because almost every character common to APL and non-APL modes is mapped to the same location.

/home/xed/keyboard/DYALOG.TRANS

This file redefines the keyboard mapping according to the usual DYALOG APL Sun keyboard mapping.

To use either one of these files, the user may include the command KEYBOARD in the "PROFILE.sedit" file for APL usage, and in the "profile.sedit" file for UNIX or WINDOWS usage.

Examples: keyboard DYALOG.TRANS keyboard . 2 keyboard STANDARD.TRANS 1

Using MKTRANS

mktrans is only available on **UNIX** systems.

mktrans is a utility which automatically generates a ./keyboard/\$1.TRANS keyboard translation table, where \$1 is the first argument passed to mktrans. The user must have write authorization on the current directory before starting.

The user must run mktrans using the keyboard the translation table is meant to.

For example, to create a /home/xed/keyboard/MY.TRANS translation table, type the following commands:

% cd /home/xed
% ./mktrans MY

This will display the following screen:

Use every key and then type ^n

Type ^c to cancel

The user must now use every ASCII key available on the keyboard. The functions or control keys, such as F1 or Shift must not be used.

When all the keys are typed in, the user must type Control-n (hold down the control key, and then type n while the control key is down).

When running on an ASCII terminal, the user will then have to hold down the shift key, and while keeping this key down, use again every ASCII key in same order. This step is not necessary when running the **MOTIF** mktrans version.

This translation table may now be used within the profile.sedit initialization file in the following manner:

'keyboard \$xhome/keyboard/MY.TRANS'

LASTFiles - Set the LASTFILES Parameters

LASTFiles {ON|OFF {N {loc}}

Initial value: ON 30 ~/sedit.lastfiles *Level:* Global

When LASTFILES is ON, **SEDIT** saves in the loc file the names of the N last opened files.

The {install-dir}/xmac/dy_lastfiles.sedit macro can be used to display the last opened files, allowing the user to open them again.

dy_lastfiles is assigned by default to the File - Open Last files menu.

Note: On **WINDOWS** systems, the HOME environment variable is usually not defined. In this case, the " \sim /" or " \sim \" directory shortcut is translated into "C:\".

See Also: DY LASTFILES

LASTLorc - Set LASTLORC Buffer

LASTLorc {	string}	sets the LASTLORC buffer.
QUERY LAST	Lorc	displays the LASTLORC buffer.
Initial value: Level:	Empty string Global	

The LASTLORC buffer memorizes the string passed to the LOCATE, CHANGE, SCHANGE, CN, SCN, FIND, FINDUP, NFIND and NFINDUP commands.

When string is not specified, the LASTLORC buffer is set to a zero length string.

See Also: LOCATE, CHANGE, SCHANGE, CN, SCN, FIND, FINDUP, NFIND, NFINDUP

LEft - Scroll Left

LEft $\{N\}$

is used to alter the columns that are to be displayed.

"startc" is the first column.

"endc" is the last column.

If N is omitted a value of 1 is assumed.

If N is 0, the original setting will be restored.

In all other cases, "startc" and "endc" will be decremented by N, shifting the data to the right by N positions.

The command "Left 40" is mapped to the C-F7 key by default.

See Also: <u>RIGHT</u>, <u>VERIFY</u>

LEFTAdjust - Left-Adjusting Text

LEFTAdjust {target}

A11

Scope:

This command is mapped to the Shift-Control-L (^L) key by default.

LEFTADJUST reformats a portion of the current file defined by the target operand. LEFTADJUST positions the first non-blank character at the left margin defined with the <u>MARGINS</u> command.

target may be one of the following:

All	All the file is formatted.
Sel	Left-adjusts the selected lines. If the selection is rectangular, LEFTADJUST left-adjusts the contents of the selected area, the text outside the selection not being modified.
:N	Up to but not including the line N.
+N	Down N lines.
-N	Up N lines.
+* or *	Down to the end of file.
_ *	Up to the top of file.
.symb	Up or Down to the line which has been assigned the .symb symbolic name by using the POINT command, or a .symb prefix command.
string expression	Defines a group of characters to be located.

The general format of a string expression is the following:

 $\{+|-\}\{-\}/string1\{/\{\&\}|\{|\}\{-\}/string2 \dots\}$

See the **LOCATE** command on page 300 for a precise string expression definition.

When target is not specified, LEFTADJUST formats the line corresponding to the cursor location. When the cursor is not located upon a line of the current file, LEFTADJUST reformats the current line.

Examples: LEFTADJUST LEFTADJUST all LEFTADJUST sel LEFTADJUST /str/

See Also: <u>CENTER</u>, <u>FLOW</u>, <u>FORMAT</u>, <u>LOCATE</u>, <u>MARGINS</u>, <u>POWERINPUT</u>, <u>RIGHTADJUST</u>

LIMIT - Set File Size Limit

LIMIT {nn{m}} Initial value: 0 Level: Global

The m modifier may be one of the following:

K	Kilobyte. One kilobyte is 1024 bytes.
М	Megabyte. One megabyte is 1024 kilobytes.
G	Gigabyte. One gigabyte is 1024 megabytes.
Т	Terabyte. One terabyte is 1024 gigabytes.

When LIMIT is set to 0, SEDIT accepts any file to edit.

When LIMIT is set to *nn*, **SEDIT** will not open a file larger than *nn* bytes.

Examples:	limit	displays the current limit.
	limit O	removes any size limitation.
	limit 1e6	forbids editing any file larger than 1000000 bytes.
	limit 100m	forbids editing any file larger than 104,857,600 bytes.

Large Files support

A large file is a file larger than 2,147,483,647 bytes. **SEDIT** supports large files on the operating systems displayed when typing HELP LARGEFILES.

However, the length of a line is limited to 2,147,483,647 characters, and the number of lines is also limited to 2,147,483,647 lines.

The amount of memory needed by **SEDIT** to edit a file increases when the average line size decreases. Editing a file of 1GB whose average line size is 80 bytes requires 2GB of memory.

See Also: <u>XEDIT</u>

LINECol

LINECol {ON|OFF}

sets the line/column display ON or OFF.

Initial value: ON Level: Global

When LINECOL is on, **SEDIT** displays the line and column number corresponding to the cursor position when the cursor is placed on a data field.

LINENd - Separator Change

```
LINENd ON|OFF {value}
```

enables or disables the character separator when passing commands.

Initial value: line-feed Level: Global

value is an optional parameter specifying the separator between commands. It is originally set to line-feed.

line-feed is assigned to the following keys, depending on the workstation in use:

SUN Type 4 keyboard	Control-line-feed
SUN Type 5 keyboard	Control-AltGraph
IBM RS/6000	Control-Right-Alt
SiliconGraphics	Control-Right-Alt
DecStations	Control-PF3
DecStations with PC keyboards	Control-Right-Alt
HP	Control-Select
HP with PC keyboards	Control-Right-Alt
ASCII terminals	Control-l
Windows systems	Control-Right-Alt

The SEP command is a synonym to the LINEND command.

Examples: linend on ; sets the separator to ";". top;c /i/j/ changes every "i" to "j" from the beginning of the file.

See Also: <u>SEP</u>

LIsten - Listen for External Commands

 Available on:
 UNIX

 Batch Mode:
 Not Available

 LIsten nnn
 makes SEDIT listen on a socket for commands sent by another application program. The socket port number will be nnn.

 LIsten OFF
 stops SEDIT listening.

The "\$xhome/saber/send_sedit.c" file is an example of how to communicate with **SEDIT** from another application.

Locate (XEDIT MODE) - Locate a Target

XEDLocate		
Locate	target	{cmd}
:	end-target	
/	end-target	
+	end-target	
-	end-target	
~	end-target	
	end-target	
*		
N		

When <u>MODE</u> COMMAND XEDIT is in effect, LOCATE calls the XEDIT mode XEDLOCATE command. PDFLOCATE may be used to call the ISPF/PDF mode LOCATE command.

The LOCATE command scans the file looking for the specified target.

When the target is reached, cmd will be executed as a standard SEDIT command.

When target starts with one of the ":/+-~.*" special characters, or with a digit, the LOCATE keyword may be omitted.

target may be one of the following:

:N	The Nth line becomes the current line.
N	When MODE NUMBER GOTO is in effect, the Nth line becomes
	the current line. The is the SEDIT default behavior.
	When MODE NUMBER SCROLL is in effect, SEDIT scrolls
	down N lines. This mode is the default when SEDIT is started
	with the /home/xed/xedit command.
	When used as another command operand, such as delete N,
	N always means N lines.
+N	Scrolls down N lines.
-N	Scrolls up N lines.
+* or *	The end of file.
_ *	The top of file.
.symb	The line which has been assigned the .symb symbolic name by using the POINT command, or a .symb prefix command.
string expression	Defines a group of characters to be located.

The general format of a string expression is the following:

 $\{+|-\}\{-\}/string1\{/\{\&\}|\{|\}\{-\}/string2 \dots\}$

The search direction is toward the end of the file (+), which is the default, or toward the top of the file (-).

The not (~) symbol means that **SEDIT** is to locate a file line which does not contain the specified string.

string may be a character string, such as Hello, or a hexadecimal string, such as x'313233' when HEX ON is in effect. The ARBCHAR command allows the user to specify strings with imbedded arbitrary characters.

The trailing / delimiter is necessary only when string ends with blanks, or when a logical operator is following.

The / delimiter is in fact the first non-blank character found after the locate command. It must be a slash when the LOCATE keyword is omitted. /Hello or LOCATE; Hello is the same command. The delimiter cannot be a period.

The OR | symbol means that the matched line must match the target before the |, or the target after the |.

The AND & symbol means that the matched line must match the target before the &, and the target after the &.

Notes: The <u>ZONE</u> command allows the user to choose the starting and ending columns to be scanned.

When MODE LOCATE NOSTAY is in effect (the **SEDIT** default), these columns are also restricted by the <u>VERIFY</u> column definition: the user can only scan the visible part of the file. The cursor will be moved to the beginning of the target. A subsequent search will start at the cursor location.

When MODE LOCATE STAY is in effect (the **XEDIT** behavior), the cursors stays in the command line, the search is not restricted by the VERIFY setting, and the next search will start on the next (or previous) line.

When <u>WRAP</u> is set to ON, **SEDIT** continues the search up to the line preceding the current line within the / or +/ commands. The search is continued following the current line within the -/ command.

When WRAP is set to OFF, the search ends at the end (of top) of file.

Examples:	/test	searches for the test string.
	/	searches again for the test string.
	/test /add	searches for the "test " string, and adds one line after the matched line.
	/a=b/cf/	searches for the $a=b/cf$ string.
	/a=b/cf	searches for the a=b string, and executes the cf command.
	///	searches for the / character.
	3	the line 3 becomes the current line, or scrolls down 3 lines when MODE NUMBER SCROLL is in effect.
	:4add3	adds 3 lines after the line 4.
	/str/&/x'31'	searches for a line containing both str and 1. $x'31'$ is the ASCII value of the "1" character.
	.part1 add2	adds 2 lines after the line which has been assigned the .part1 symbolic name.

0	Normal
1	TOF or EOF reached
2	Target Not Found
5	Invalid Operand
	0 1 2 5

See Also: <u>ARBCHAR</u>, <u>BEEP</u>, <u>CASE</u>, <u>MODE</u>, <u>POINT</u>, <u>STAY</u>, <u>ZONE</u>, <u>WRAP</u>, <u>R/</u>, <u>R-/</u>, $\underline{\lambda}$, $\underline{-\underline{\lambda}}$

Locate (ISPF MODE) - Locate a Line

Locate PDFLocate	$ \begin{cases} FIRST \\ LAST \\ \\ NEXT \\ \\ PREV \\ \end{cases} $	$\begin{array}{l} \left\{ \begin{array}{c} \text{COMMAND} \end{array} \right\} \\ \left\{ \begin{array}{c} \text{ERROR} \end{array} \right\} \\ \left\{ \begin{array}{c} \text{EXCLUDED} \end{array} \right\} \\ \left\{ \begin{array}{c} \text{X} \end{array} \right\} \\ \left\{ \begin{array}{c} \text{LABEL} \end{array} \right\} \end{array}$	{range}
Locate	.xxxx		

Locate number

When <u>MODE</u> COMMAND ISPF is in effect, LOCATE calls the ISPF mode PDFLOCATE command. XEDLOCATE may be used to call the XEDIT mode LOCATE command.

LOCATE positions the current line to the targeted line.

.xxxx	positions the current line on the line labelled .xxxx.	
number	positions the current line on the line number.	
FIRST	to search from the first line, proceeding forward.	
LAST	to search from the last line, proceeding backward.	
NEXT	to search from the first displayed line, proceeding forward. NEXT is the default.	
PREV	to search from the first displayed line, backward.	
COMMAND	to search for a line with a pending prefix command.	
ERROR	to search for a line with a compilation error.	
EXCLUDEI	or x to search for an excluded line.	
LABEL	to search for a line with any label.	
range	Two labels that identify the lines to be searched for. A label may be created by typing a .xxxx string on a prefix zone, or by using the XEDIT POINT command described on page 331. A label may also be one of the ISPF/PDF predefined labels: .zf or .zfirst the first line. .zl or .zlast the last line. .zcsr the cursor line.	
Examples:	13goes to line 3.l command lastsearches for the last pending command.l first error .a .b	

See Also: <u>COMPILE</u>, <u>NEXTERROR</u>

LOWercas - Translate Into Lowercase

LOWercas {target}

Scope: Display

target defines the number of lines to be translated into lowercase. Lines are translated starting with the current line, up to but not including the target line. target may be one of the following:

:N	Up to but not including the Nth line.
N or +N	N lines.
-N	Up N lines.
+* or *	The end of file.
_ *	The top of file.
.symb	The line which has been assigned the .symb symbolic name by using the POINT command, or a .symb prefix command.
string expression	Defines a group of characters to be located.

The general format of a string expression is the following:

{+|-}{~}/string1{/{&}|{|}{~}/string2 }

See the <u>LOCATE</u> command on page 300 for a precise string expression definition. If target is omitted, a value of 1 is assumed.

Examples:	low	translates one line.		
	low:5	translates all lines up to line 4.		
	lowercas*	translates the rest of the file.		

See Also: <u>STAY</u>, <u>S</u>LOWER

LRecl - Set Record Length

```
LRecl * |N {FT string} sets the line length.
```

Initial value: * Level: File

When the record length is set to the * value, no change will occur to the file when it is written to disk.

When the record length is set to the N value, saving a file will create a file in which every line length will be N bytes.

Lines longer than N will be truncated, and lines shorter than N will be padded with spaces.

If FT string is specified, this setting will become the default for every new file with a string filetype.

If FT is *, this will be the default for any file.

If FT is a period, this will become the default for files with no filetype. This setting is also applied to the current file, unless its filetype does not match FT.

Examples:	lrecl	80	ft	f	will create 80 character wide FORTRAN files.
	lrecl	*			
	lr 92	ft	•		

See Also: TRUNC

MACRO - Execute a Macro

MACRO		mac	
SET MACRO		ON OFF	
QUERY MACRO	C		displays ON or OFF.
Initial value: Level:	OFF Global		

When SET MACRO is OFF, **SEDIT** looks for native commands before looking for macros.

When SET MACRO is ON, SEDIT looks for macros before looking for native commands.

MACRO mac allows the mac macro to execute without checking for native commands or for synonyms.

MACRO also allows calls to a macro ending with non-alphabetic characters. For example, "PUT2" usually means "PUT 2". MACRO PUT2 means "execute the macro named PUT2".

In particular, the macros set_sun_t3, set_sun_t4 and set_sun_t5 must be executed by entering "macro set_sun_t*i*".

See Also: <u>COMMAND</u>

MAN - Display UNIX Reference Manual Pages

MAN string displays the UNIX reference manual pages in the same format as the UNIX man command.

MAN creates a new file *word*.man in the editing ring, where *word* is string with spaces replaced by the _ underscore character. If *word*.man already exists, it will be overwritten.

Examples: man open creates the open.man file. man -k file creates the -k_file.man file.

See Also: <u>MESSAGESDIR</u>, <u>S MAN</u>

MARgins - Set Text Margins

MARgins left right|* { {+|-} indent}
Initial value: 1 72 +0
Level: File

The MARGINS settings are used by the <u>CENTER</u>, <u>FLOW</u>, <u>FORMAT</u>, <u>LEFTADJUST</u>, <u>POWERINPUT</u> and <u>RIGHTADJUST</u> commands.

- left is the left margin. The left margin must be less than or equal to the right margin.
- right is the right margin. When specified as an asterisk, the right margin is set to the same value as the truncation column defined with the <u>TRUNC</u> command.
- indent is the paragraph indent column. indent may be specified as an absolute column number ("2"), or as a displacement relative to the left margin ("+3" or "-5"). If indent has been specified as a displacement, when the left and right margins are changed again, using the MARGIN command without specifying an

indent parameter, the paragraph indent column is reset to the new left value plus the previous indent value.

The scale line defined with the <u>SCALE</u> command displays a ^ character at the left margin position, a @ character at the first line indent position and a \$ character at the right margin position.

Without any argument, MARGINS displays the current setting.

Examples: MAR 2 75
The left margin is set to 2, the right margin is set to 75, and the paragraph indent column is unchanged.

MAR 2 75 +10
The paragraph indent column is set to 12.
MAR 10 50
The left margin is set to 10, the right margin is set to 50, and the paragraph indent column is set to 20.
MAR 2 75 10
The paragraph indent column is set to 10.
MAR 12 55
The left margin is set to 10, the right margin is set to 55, and the paragraph indent column remains unchanged, keeping the previous absolute 10 value.

MAR displays the current settings.

See Also: <u>CENTER</u>, <u>FLOW</u>, <u>FORMAT</u>, <u>LEFTADJUST</u>, <u>POWERINPUT</u>, <u>RIGHTADJUST</u>, <u>SCALE</u>, <u>TRUNC</u>

MAtch - Match Delimiters

MAtch {Sel | Cursor} finds a matching delimiter.

MATCH SEL If there is a selection within the current file, **SEDIT** attempts to match the first selected character. If not, **SEDIT** attempts to match the character at the current cursor position. If this character is one of the '{[(<' delimiters, **SEDIT** searches for its matching delimiter ('}])>'), and sets a rectangular selection displaying the bounds between delimiters.

MATCH CURSOR **SEDIT** attempts to match the character at the current cursor position. If this character is one of the '{[(<' delimiters, **SEDIT** searches for its matching delimiter ('}])>'), and moves the cursor to the matching delimiter, scrolling the file if necessary.

MATCH is mapped to the L2 key on Sun workstations by default, and to m on other workstations.

MATCH CURSOR is assigned to Shift-L2, and ^M (Shift-Control-m).

MBUtton - Create a Menu Button

MBUtton string1 ff

creates a button using string1 as a label. The menu described by the ff file will be attached to that button.

Available on: UNIX Batch Mode: Not Available

Using the left mouse button selects the first menu choice directly. Using the right mouse button displays the menu.

Example: mbu FILE /home/xed/ff

where /home/xed/ff is the following:

" Save current file " save " Save and leave current file " file " Abandon current file " MENU " quit " quit " qquit " qquit " Abandon current file " END

The first string (for instance " Save and leave current file ") is displayed within the menu, and the second string (for instance file) is executed as a command when the first one is selected with the third mouse button. When the second string is the string MENU, it starts a pullright menu which must end with a matching END string.

ff may reference another file as described on page 311.

See Also: <u>BUTTON</u>

MENu - Create a Menu

MENu filemenu

creates a walking menu described by the file filemenu.

```
Batch Mode: Not Available
```

filemenu is a file with a specific format.

If it does not start with a directory indicator such as "./", "/" or "~", it will be searched for in the current directory first, and then in the directories described either in the environment variable XPATH (if there is one) or in PATH, or in directories accessed by the <u>ACCESS</u> command.

Once this command is completed, there will be two ways to activate the menu:

- Pressing the right mouse button, while holding the meta-key¹.
- Moving the mouse cursor to one of the first two screen lines, and pressing the right mouse button.

Example:

The first string (for instance " Save and leave current file ") is displayed within the menu, and the second string (for instance file) is executed as a command when the first one is selected with the right mouse button. When the second string is the string MENU, it starts a pullright menu which must end with a matching END string.

^{1.} See page 123 (UNIX) or page 127 (WINDOWS) for the meta-key definition.

Including the Contents of a Different File

The following syntax:

"LABEL" MENU filename

will create a LABEL pullright menu, using the contents of the filename file. If filename starts with \$xhome/, \$xhome/ will be replaced with the actual **SEDIT** installation directory.

If the \$xhome/sp.bu file contains the following data:

"First line" top "Last line" bot "Print" shell lpr \$name &

the example on page 310 will expand to:

```
" FILE " MENU
" Save current file " save
" Save and leave current file " file
" Abandon current file " MENU
            " quit " quit
            " qquit " qquit
" Abandon current file " END
" FILE " END
"Special" MENU
"First line" top
"Last line" bot
"Print" shell lpr $name &
"Special" END
```

The following syntax:

INCLUDE filename

will include the contents of the filename file.

An included file may reference another file using the same syntax.

MENUBar - Create a Menubar

MENUBar filemenu

creates a menubar described by the file filemenu.

Available on: WINDOWS Batch Mode: Not Available

filemenu is a file with a specific format.

If it does not start with a directory indicator such as ".\", "\" or "~\", it will be searched for in the current directory first, and then in the directories accessed by the <u>ACCESS</u> command.

The C:\Program Files\SEDIT\sedit.menubar file is an example of such a file:

```
"File" MENU
   "Save"
                         save
   "Save && Leave"
                        file
   "Leave"
                         MENU
                                    "If not modified" quit
                                    "Anyway"
                                                        qquit
   "Leave"
                        END
   "Save As ..."
                       dy_save
   "Open ..."
                        MENU
                         "Last" dy_open //last
                         "Current" dy_open .
                         "C:\"
                               dy_open C:\
   "Open ..."
                       END
   "Open <Selection>" s_xed
   "Last Edited Files ... " dy_lastfiles
  "Print File ..." printfile
"Print Screen ..." printscreen
"Frit" prompt exit
                        prompt_exit
   "Exit"
   "Exit with memory"
                        bye
"File" END
"Edit" MENU
   "Find"
                    s_find
   "Find ..."
                   dy_find
                    s_copy
   "Copy"
   "Paste"
                   s_paste
   "Cut"
                   s_cut
   "Undo"
                   undo
   "Undo all"
                   undo all
   "Redo"
                   redo
               all
   "Show ALL"
   "Show ..."
                   dy_all
   "Show more ... " dy_show
   "Hide ..."
                   dy_exclude
   "Exchange ... " dy_exch
"Edit" END
```
The first string (for instance "Save") is displayed within the menu, and the second string (for instance save) is executed as a command when the first one is selected with the first mouse button. When the second string is the string MENU, it starts a pullright menu which must end with a matching END string.

The menubar displayed will be the following:

						SEDIT @	nt(m1) -
File	Edit	Special	Compile	Flist	Tree	Menubar	Help

filemenu may reference another file as described on page 311.

MErge - Merge Two Set of Lines

```
MErge target1 target2 {col}
```

MERGE overlays the set of lines starting from the current line up to the line defined by target1 on the set of lines starting with the line defined by target2.

The first set of lines is first shifted to the right to the column defined by the col value. When omitted, col defaults to the value of 1.

When the column position of the first set of lines contains a blank, the contents of the same column on the second set of line remains unchanged.

The two set of lines are not allowed to overlap.

The last merged line becomes the current line, and the first set of lines is deleted.

target may be one of the following:

:N	Up to but not including the Nth line.
N or +N	N lines.
-N	Up N lines.
+* or *	The end of file.
_ *	The top of file.
.symb	The line which has been assigned the .symb symbolic name by using the POINT command, or a .symb prefix command.
string expression	Defines a group of characters to be located.

The general format of a string expression is the following:

 $\{+|-\}\{-\}/string1\{/\{\&\}|\{|\}\{-\}/string2 \dots\}$

See the <u>LOCATE</u> command on page 300 for a precise string expression definition.

Example:

Assuming the following file, with line 7 being the current line:

```
00000

00001 123456789

00002 12345678901234

00003 123456789012345678

00004 aa

00005 aa

00006 aa

00007 a b c dA B C D

00008 b c dA B C D a

00009 b c dA B C D a b c d e f g h i j
```

Typing

merge 3 :1 2

will display:

00000 00001 alb3c5dA8B C D 00002 b2c4dA7B9C1D3a 00003 blc3dA6B8C0D2a4b6c8d e f g h i j 00004 aa 00005 aa 00006 aa

Line 3 will be the new current line.

MESsagesdir

MESsagesdir {dirname} changes the internal messages directory.

Initial value:

When more than one error message is to be displayed, or when using the MAN, COMPILE or various SHELL commands, **SEDIT** creates a new file in the editing ring. The directory of this file is the current "." directory by default, and can be changed with the MESSAGESDIR command.

Without any argument, MESSAGESDIR displays the current setting.

See Also: <u>COMPILE</u>, <u>IMPCMSCP</u>, <u>MAN</u>, <u>WINDOWS</u>, <u>XCSHELL</u>, <u>XKSHELL</u>, <u>XSHELL</u>

METAKey - Set the Meta Key

METAKey hexval changes the meta key definition.

Available on: UNIX, MOTIF version.

The meta key is described in the "Using the Mouse" sections on page 123 and page 127

The meta key is automatically set by the set server xxx command. The set command is used by the set_xxx macros, such as set_sunt5 or set_ibm, called by the profile.sedit initialization macro.

However, when running the **MOTIF SEDIT** version on a non-standard X terminal, it is possible that the code emitted by the terminal meta key does not match the workstation standard keyboard meta key code.

The METAKEY command allows the user to register the hexadecimal value sent by the terminal when the meta key is used. This value can be determined by starting the X11 xev program, and by using the meta key upon the xev window.

Example:

```
% xev
        { using the meta key upon the xev window }
KeyRelease event, serial 17, synthetic NO, window 0x1700001,
    root 0x80079, subw 0x0, time 1160548353, (102,115), root:(107,141),
    state 0x8, keycode 127 (keysym 0xffe7, Meta_L), same_screen YES,
    XLookupString gives 0 characters: ""
```

would lead to the following METAKEY usage:

====> metakey ffe7

See Also: <u>SET</u>

MODE - Set Various Modes

MODE keyword values

set values according to keyword.

Initial values: Locate Nostay Prefix Xedit Autoexit Off Number Goto Change All Redisplay On Topline 0 CUrsor 1 Get Nostay NOtimp On SCroll Nowrap REServed Skip COmmand Xedit EXpand On Noenv

MODE provides a way to customize the behavior of various **SEDIT** commands.

keyword may be one of the following:

MODE Locate Stay | Nostay changes the cursor behavior when using the various locate commands.

When locate nostay is in effect, searching for a string using the commands /, -/, \setminus , $-\setminus$ places the cursor upon the first matching string. In addition, the search columns are also restricted by the <u>VERIFY</u> column definition; the user can only scan the visible part of the file

When locate stay is in effect, the cursor remains in the command field. The search columns are only restricted by the <u>ZONE</u> column definition. This mode is mainly provided for **XEDIT** compatibility.

MODE	Prefix	Xedit	makes the prefix commands similar to the IBM XEDIT editor.
MODE	Prefix	Ispf	makes the prefix commands similar to the IBM ISPF editor. See Prefix Commands on page 105 for more details.
	Sinc	e ISPF users general	lly use the "e" command to start editing a file, when

"mode prefix ispf" is on, the user cannot use the "e" command to delete a file within the directory editor. Only the "rm" command can be used for that purpose. See page 469 for more details.

MODE Topline 0|1

When topline 0 is in effect, **SEDIT** uses a virtual line 0 as TOP OF FILE line.

This allows the user, for example, to insert data *before* the first line in the file by typing:

top get

When topline 1 is in effect, **SEDIT** uses the first line in the file as TOP OF FILE line.

This mode is mainly provided for previous **SEDIT** release compatibility, since a macro behavior may be affected when topline 0 is in effect.

MODE CUrsor Wrap | N

When cursor wrap is in effect, the cursor wraps around the screen when it reaches the top or the bottom of the screen.

When cursor N is in effect, **SEDIT** scrolls N lines when the cursor reaches the top or the bottom of the displayed file data.

MODE Get Stay Nostay

When get stay is in effect, the current line is not modified by a GET, a PUT or a PUTD command.

MODE Autoexit ON | OFf ON makes **SEDIT** exit after a QUIT or a FILE command is applied to the last edited file.

This mode is mainly provided for **XEDIT** compatibility. If the user desires to set it when running in ASCII terminal mode, the command "mode autoexit on" must be included in the "/home/xed/profile.sedit" **S/REXX** macro:

MODE Number Goto | Scroll changes the **SEDIT** behavior when entering a single number on the command line.

When Number Goto is in effect, entering N makes the current line become the Nth file line.

When Number Scroll is in effect, entering N makes the current line increased by N. This mode is mainly provided for **XEDIT** compatibility.

MODE Change All | One changes the **SEDIT** behavior when entering a change command without specifying the number of items to be changed. When Change All is in effect, entering "c /i/j/" will turn every i into j.

When Change One is in effect, entering "c /i/j/" will turn the first i into j.

This mode is mainly provided for **XEDIT** compatibility.

MODE Redisplay ON | OFf

ON makes **SEDIT** redisplay a command in error in the command field.

OFF is mainly provided for **XEDIT** compatibility.

MODE NOtimp On | OFf

When MODE NOTIMP is ON, **SEDIT** recognizes the following **XEDIT** commands:

SET	ALT	SET	NULls
SET	APL	SET	PA1
SET	BRKkey	SET	PA2
SET	COLPtr	SET	PA3
SET	ESCape	SET	PACK
SET	ETARBCH	SET	RANge
SET	ETMODE	SET	RECfm
SET	FILler	SET	REMOte
SET	FMode	SET	SERial
SET	FULLread	SET	SIDcode
SET	IMage	SET	SPILL
SET	LASTLorc	SET	TERMinal
SET	MASK	SET	TEXT
SET	MSGLine	SET	TOPEOF
SET	MSGMode	SET	TRANSLat
SET	NONDisp		

This mode is mainly provided for **XEDIT** compatibility, allowing existing **XEDIT** macros to run without error messages.

Note that these commands, which are not implemented, do not perform any action.

MODE Get Stay Nostay

When get stay is in effect, the current line is not modified by a GET, a PUT or a PUTD command.

MODE Scroll Wrap Nowrap

When scroll wrap is in effect, the BACKWARD, FORWARD, PGUP and PGDOWN commands wrap when they reach the end of the file.

```
MODE REServed Skip | Noskip
```

Sets the way **SEDIT** handles control characters. See the <u>RESERVED</u> command on page 359 for more details.

MODE COmmand Xedit

makes the commands similar to the IBM XEDIT editor.

MODE COmmand Ispf

makes the commands similar to the IBM ISPF/PDF editor.

MODE EXpand ON | OFf {Env | Noenv}

When MODE EXPAND is ON, the variable substitutions described on page 147 take place.

In addition, if MODE EXPAND ON ENV is in effect, all strings starting with a \$ not previously substituted will be replaced by the contents of the **UNIX** or **WINDOWS** environment variable with the same name.

Example:setenv mydir /home/proj1/vital cd \$mydir (makes /home/proj1/vital current)

See Also: <u>AUTOI</u>, <u>CHANGE</u>, <u>CN</u>, <u>FILE</u>, <u>FFILE</u>, <u>LOCATE</u>, <u>QUIT</u>, <u>QUIT</u>, <u>R/</u>, <u>R-/</u>, \setminus , <u>-</u>

MOUSEMode - Set Mouse Buttons

MOUSEMode {Openlook | Motif | Fullmotif | Windows}

Initial value (UNIX):	Openlook
Initial value (WINDOWS):	Windows
Level:	Global

When MOUSEMODE is set to OPENLOOK, the mouse buttons function in the following way:

M1	starts a selection.
M1 (dragged)	moves the selection start.
Shift-M1	cancels the selection.
M2	extends the selection.
Shift-M2	selects a line.
МЗ	moves the cursor, or displays the menu created with the <u>MENU</u> command when the mouse pointer is located on one of the two first screen lines.
Shift-M3	makes a line the current line.
Control-M3	cancels the selection.

When MOUSEMODE is set to MOTIF, the mouse buttons function in the following way:

M1	starts a selection.
M1 (dragged)	extends a selection.
Shift-M1	extends a selection.
M2	pastes the current selection at the cursor location.
Shift-M2	selects a line.
МЗ	moves the cursor, or displays the menu created with the MENU command when the mouse pointer is located on one of the two first screen lines.
Shift-M3	makes a line the current line.
Control-M3	cancels the selection.

When MOUSEMODE is set to FULLMOTIF or WINDOWS, the mouse buttons function in the following way:

Ml	moves the cursor.
M1 (dragged)	starts and extends the selection.
Shift-M1	extends the selection.
M2	pastes the current selection at the cursor location.
Shift-M2	selects a line.
МЗ	always displays the menu created with the MENU command.

Control-M3 cancels the selection.

Without any argument, MOUSEMODE displays the current setting.

MOve - Move File Lines

MOve target1 target2

MOVE moves the number of lines defined by target1, starting from the current line, to the location defined by target2. The last moved line becomes the current line.

target may be one of the following:

:N	Up to but not including the Nth line.
N or +N	N lines.
-N	Up N lines.
+* or *	The end of file.
_ *	The top of file.
.symb	The line which has been assigned the .symb symbolic name by using the POINT command, or a .symb prefix command.
string expression	Defines a group of characters to be located.

The general format of a string expression is the following:

 $\{+|-\}\{-\}/string1\{/\{\&\}|\{|\}\{-\}/string2 \dots\}$

See the <u>LOCATE</u> command on page 300 for a precise string expression definition.

Examples:	move 2 :5	moves 2 lines after the line 5.
	move /str /main	moves the lines up to but not including the
		str string after the line including the main
		string.

Return Codes:	0	Normal
	2	Target Not Found
	5	Invalid Operand

MSG - Display Text

MSG {text} displays text in the message field.

MSG does not sound the alarm. EMSG does.

If text is omitted, MSG clears all the pending messages.

When more than one message is issued from a macro, **SEDIT** creates a new file in the editing ring showing all the messages.

See Also: EMSG

N - Goto Nth Line

Ν

Scope:DisplayIf MODE NUMBER GOTO is in effect, the Nth lines becomes the current line.If MODE NUMBER SCROLL is in effect, the current line is increased by N.Examples:3goes to line 3 (or scrolls down 3 lines)4put5goes to line 4 and executes the command put5.

See Also: <u>DOWN</u>, <u>MODE</u>, <u>NEXT</u>

NEXTError - Error Scanning

NEXTError

scans the file \$fn.compile.

Batch Mode: Not Available

The command COMPILE creates a file with the same filename as the compiled file but with the filetype compile.

NEXTERROR scans this file looking for patterns matching the error rules described in the file sedit_compile.rules. See the command <u>COMPILE</u> on page 190 for more details about this file.

If found, **SEDIT** sets the current line to the error line and places the cursor on that line.

This command is mapped to the ^- key, or to the F2 key when running in ASCII terminal mode.

See Also: <u>COMPILE</u>, <u>R/</u>, <u>R-/</u>

NEXTWord - Cursor Moving to Next Word

NEXTWord

moves the cursor to the next word.

Available on: OPENLOOK, MOTIF and WINDOWS

When the cursor is located on a data field, NEXTWORD scans to the right of the cursor position. If NEXTWORD finds the start of a word, the cursor is moved onto that position. When the end of the line is reached without a match, the process is repeated on the next lines.

NEXTWORD is mapped to the Control-Right-Arrow (C-R12) key when not running in ASCII terminal mode.

See Also: <u>PREVWORD</u>

NFind - Find a Missing Starting String

NFind str

NFIND searches forward for a line that does not start with str.

When str contains imbedded blanks, those character positions in the file line are ignored.

When str contains underscore characters (_), those character positions in the file line must be blank.

When <u>WRAP</u> is set to OFF, the search continues down to the end of the file.

When WRAP is set to ON, the search will wrap to the first line in the file, and continue down to the current line.

See Also: FIND, FINDUP, MRAP

NFINDUp - Find a Missing Starting String

NFINDUp	str
NFUp	str

NFINDUP searches backward for a line that does not start with str.

When str contains imbedded blanks, those character positions in the file line are ignored.

When str contains underscore characters (_), those character positions in the file line must be blank.

When <u>WRAP</u> is set to OFF, the search continues up to the start of the file.

When WRAP is set to ON, the search will wrap to the last file line, and continue up to the current line.

See Also: FIND, FINDUP, NFIND, WRAP

NIS - Use NIS Users Database

NIS $\{ON | OFF \{cmd\}\}$

Initial value:OFF ypcat passwdLevel:GlobalAvailable on:UNIX

By default, **SEDIT** searches for the home directories of users (such as ~john) scanning the /etc/passwd file. **FLIST** also uses this file to display the owner names of files.

When a NIS data base is in usage, the contents of /etc/passwd is irrelevant. With NIS ON, **SEDIT** issues a ypcat passwd command to retrieve the list of users.

When cmd is provided, SEDIT will use cmd instead of ypcat passwd.

Without any argument, NIS displays the current setting.

Examples: nis off nis on nis on ypcat -d domain2 passwd nis

See Also: NISG

NISG - Use NIS Groups Database

NISG {ON|OFF {cmd}}

Initial value: OFF ypcat group Level: Global Available on: UNIX

By default, **FLIST** searches for group names of files scanning the /etc/group file.

When a NIS data base is in usage, the contents of /etc/group is irrelevant. With NIS ON, **FLIST** issues a ypcat group command to retrieve the list of groups.

When cmd is provided, **FLIST** will use cmd instead of ypcat group.

Without any argument, NISG displays the current setting.

Examples: nisg off nisg on nisg on ypcat -d domain2 group nisg

See Also: <u>NIS</u>

NUMber / NUMBER_Screen - Display File Line Numbers

NUMber ON OFF Initial value: ON Level: File and View

NUMBER_Screen ON | OFF

Initial value: ON Level: View

SEDIT maintains a separate NUMBER setting for each file and each view of this file defined with the <u>SCREEN</u> command.

The NUMBER_SCREEN command updates the default NUMBER setting of the current view, which is applied to every newly loaded file.

The NUMBER command applies to the current file on the current view.

When NUMBER is ON, the prefix area displays the corresponding file line number.

When NUMBER is OFF, the prefix area displays equal signs (====).

See Also: PREFIX

PENDing - Update the Pending List

PENDing	ON BLOCH OFF	string	
Query PENDing	$\{BLOCK\}$	$\{OLDNAME\}$	name *

Level: File

SEDIT manages the prefix macros and commands which have not yet been executed within 3 pending lists:

- The immediate pending list, which records the single prefix macros, such as A or D.
- The block pending list, which records the double prefix macros, such as DD or MM.
- The error pending list, which records invalid prefix commands.

PENDING applies to the current line.

PENDING ON str adds str to the immediate pending list.

PENDING BLOCK str adds str to the block pending list.

PENDING ERROR str adds str to the error pending list.

PENDING OFF removes any pending prefix command or macro related to the current line.

QUERY PENDING displays information about the pending lists.

BLOCK indicates that only the block pending list is to be checked.

OLDNAME indicates that the specified name is the original name of the prefix command or macro.

name is the name of the prefix command or macro. When OLDNAME is not specified, name is assumed to be a synonym defined by the <u>PREFIX</u> SYNONYM command.

When name is specified as *, information about all pending prefix commands and macros will be displayed. The information is displayed in the following form:

Line n:'name', Oldname', OP1='op1', OP2='op2', OP3='op3'

See Also: PREFIX

PGDown - Scroll Down

PGDown	{	Ν	* }				scrolls	down	Ν	screens:	the	last	line	displayed
							become	es the f	irst	line displ	ayed	N tir	nes.	

Scope: Display

PGDOWN 0 makes the first line in the file the current line.

PGDOWN * makes the end of file the current line.

When the current line is the end of file, and when <u>MODE</u> SCROLL WRAP is in effect, PGDOWN makes the first line to be the current line.

This command is mapped to the S-F8 key by default.

Return Codes:	0	Normal
	1	End Of File Reached
	5	Invalid Operand

See Also: MODE

PGUp - Scroll up

PGUp	{N	* }	scrolls up N screens: the first line displayed becomes
			the last line displayed N times.

Scope: Display

PGUP 0 makes the last file line the current line.

PGUP * makes the top of file the current line.

When the current line is the top of file, and when <u>MODE</u> SCROLL WRAP is in effect, PGUP makes the last line to be the current line.

This command is mapped to the S-F7 key by default.

Return Codes:	0	Normal
	1	Top Of File Reached
	5	Invalid Operand

See Also: MODE

POINT - Assign a Symbolic Name

```
Point {.symb {OFF}}
Point * {OFF}
```

Level: File

POINT is used to assign a symbolic name to the current line. This symbolic name can be used as a general target operand within the commands supporting targets, such as <u>LOCATE</u> or <u>CHANGE</u>.

POINT . symb assigns the name . symb to the current line.

POINT . symb OFF removes the symbolic name . symb without changing the current line.

POINT * displays all the symbolic names.

POINT * OFF removes all the symbolic names.

POINT without operands displays the current line's symbolic name, or a white string when no symbolic name has been assigned to that line.

A symbolic name may also be assigned by typing . symb in the corresponding prefix area.

Notes: The <u>COMPILE</u> command creates symbolic names which do not start with a period. The <u>NEXTERROR</u> command uses these symbolic names to set the cursor on the line with the error, even when the file has been edited by adding or removing lines.

It is possible to assign several names to the line.

The prefix area displays the first assigned symbolic name instead of the line number. The COLOR command allows the user to choose the color for displaying symbolic names.

Examples:	p.start1	assigns .start1 to the current line.
	p*off	removes all the symbolic names.
	point *	displays all the symbolic names.

See Also: COLOR, COMPILE, CLEARERRORS, NEXTERROR, LOCATE

POWerinput - Set Power Input Mode

POWerinput {ON | OFf } {Previous | Noprevious } {Move | NOMove } {Ft xxx }

Initial value: OFF PREVIOUS MOVE *Level:* File

When POWERINPUT is ON and when the cursor reaches the right column defined with the MARGINS column, or the data field end of line, a new line is automatically created. If POWERINPUT is ON MOVE, the last word of the cursor line is moved to the new line at the left column defined with the MARGINS command, and the cursor is moved to the end of this word. Then, the current line number is increased by one. When POWERINPUT is ON, the <u>AUTOEXP</u> feature is disabled.

Inserting a character within a line will have the same effect when the last line character spills after the right column defined with the MARGINS command or the end of field.

When POWERINPUT is ON PREVIOUS, **SEDIT** checks the lines before the cursor's line, searching for the start of the paragraph. A paragraph ends with a . : ; ? or ! punctuation sign, or is followed by an empty line. **SEDIT** moves as many words as possible from the beginning of the cursor's line to the end of the previous line up to the right margin column. If the keyboard is in INSERT mode, **SEDIT** searches the following lines to find the end of the paragraph in order to properly insert the word at the cursor location.

When POWERINPUT is ON NOPREVIOUS, **SEDIT** does not move words to the end of the previous line nor does it search for the end of the current paragraph.

When POWERINPUT is ON NOMOVE, **SEDIT** does not move the word at the cursor's location. **SEDIT** creates a new line, and moves the cursor at the left column defined with the MARGINS command.

If Ft xxx is specified, this setting will become the default for every new file with a xxx filetype.

If Ft is *, this will become the default for every file.

If Ft is a period, it will select files with no filetype. This setting is also applied to the current file, unless its filetype does not match Ft.

POWERINPUT without arguments displays the current power input mode.

Examples

Assuming the following commands:

MARGINS 5 50 POWERINPUT ON PREVIOUS MOVE

```
00009
00010 When POWERINPUT is ON and when the cursor
00011 reaches the data field end of line, a
00012 new line is automatically created, the last word of the
|...^...1...+...2...+...3...+...4...+...$...+...6
00013 cursor line is moved to the new line, and th
00014 cursor is moved to the end of this
00015
```

Typing an "e" will produce the following result:

00009	
00010	When POWERINPUT is ON and when the cursor
00011	reaches the data field end of line, a new
00012	line is automatically created, the last word
00013	of the cursor line is moved to the new line,
	[*] 1+2+3+4+\$+6
00014	and the
00015	cursor $\overline{i}s$ moved to the end of this
00016	

The POWERINPUT ON NOPREVIOUS NOMOVE mode is suited for source files similar to **COBOL** files, when typing over the column 72 requires the creation of an empty new line, and the cursor to be moved on this new line column 7.

Assuming the following commands:

```
MARGINS 7 72
POWERINPUT ON NOPREVIOUS NOMOVE
VERIFY 7 72
```

00000

```
^..1...+...2...+...3...+...4...+...5...+...6...+...7.$
00001 0x"202020205768656E20504F574552494E505554206973204F4E20616E642077
00002 -
```

Typing a "0" will produce the following result:

```
00000

^..1...+...2...+...3...+...4...+...5...+...6...+...7.$

00001 0x"202020205768656E20504F574552494E505554206973204F4E20616E6420770

00002

00003 -
```

Using the reprofile.sedit Facility

When a reprofile macro has been loaded at initialization by using the <u>HASH</u> command described on page 281, reprofile will be used every time a new file is loaded. This permits the reprofile macro to set up a different **SEDIT** environment for specific files.

To set up the MARGINS and POWERINPUT according to specific files, the user could write the following reprofile.sedit macro:

```
signal on novalue
'extract/name'
select
when ft(name.1) = '.txt' then
{ 'margins 1 70'
    'powerinput on previous move'
    'verify 1 *'
}
when ft(name.1) = '.cobol' then
{ 'margins 7 72'
    'powerinput on noprevious nomove'
    'verify 7 72'
}
otherwise nop
end
```

See Also: <u>AUTOEXP</u>, <u>MARGINS</u>

PREfix/ PREFIX_Screen - Change Prefix Mode

PREfix ON | OFF | Nulls {Left | Right} Initial value: ON LEFT Level: File and View

```
PREFIX_Screen ON|OFF|Nulls {Left | Right}
Initial value: ON LEFT
Level: View
```

SEDIT maintains a separate PREFIX setting for each file and each view of this file defined with the <u>SCREEN</u> command.

The PREFIX_SCREEN command updates the default PREFIX setting of the current view, which is applied to every newly loaded file.

The PREFIX command applies to the current file on the current view.

With PREFIX ON, **SEDIT** displays a five-character prefix area for each file line on the screen, which may be before that line (PREFIX ON LEFT), or after that line (PREFIX ON RIGHT). PREFIX NULLS is identical to PREFIX ON.

Prefix commands can be entered in the prefix area.

When the mouse is in the prefix area, buttons M1 and M2 are used to scroll the file.

When no prefix area is displayed, the user can scroll with the mouse by positioning the mouse cursor on the first logical screen line. See the "Using the mouse" section for more information about scrolling.

PREfix Synonym newname oldname

defines a newname synonym to the oldname prefix macro.

PREfix Synonym * | newname

PREFIX SYNONYM * displays all the defined newnames/oldnames values.

PREFIX SYNONYM oldname displays the defined newname/oldname value. When no newname synonym is defined, PREFIX SYNONYM oldname displays:

oldname oldname

See Also: <u>NUMBER</u>

PREServe - Settings Preservation

PREServe

PRESERVE is meant to be used within an **SEDIT** macro to save several settings until a subsequent <u>RESTORE</u> command is issued.

The following global settings are saved:

AUTOEXPAND	MODE
AUTOINDENT	SEP
AUTOSAVE	SPAN
ARBCHAR	STAY
COLOR	STREAM
CTAGS	SYNONYM ¹
HEX	VARBLANK
IMPCMSCP	WRAP
LIMIT	
LINEND	
MACRO	

The following file related settings are saved:

CASE	TRUNC
FD	VERIFY
FN	ZONE
FT	
LRECL	
PREFIX	
RELOAD	
RW	
TABSET	

File related settings are always restored to the file which was the current file at the time the PRESERVE command was issued.

1. Only the $\texttt{ON}\,|\,\texttt{OFF}$ setting is saved.

The following screen-related settings are saved:

CMDLINE ZONE_SCREEN CURLINE DISPLAY NUMBER PREFIX_SCREEN SCALE SCOPE SHADOW TABLINE VERIFY_SCREEN

The RESTORE command applies the screen-related settings to the current screen.

See Also: <u>RESTORE</u>, <u>SCREEN</u>

PREVWord - Cursor Moving to Previous Word

PREVWord

moves the cursor to the previous word.

Available on: OPENLOOK, MOTIF and WINDOWS

When the cursor is located on a data field, PREVWORD scans to the left of the cursor position. If PREVWORD finds the start of a word, the cursor is moved onto that position. When the start of the line is reached without a match, the process is repeated on the previous lines.

PREVWORD is mapped to the Control-Left-Arrow (C-R10) key when not running in ASCII terminal mode.

See Also: <u>NEXTWORD</u>

PRINTFile (UNIX) - Print a File Hardcopy

Scope:	Display				
PRINTFile	$\{\underline{ON} OFF ONEJ OFFEJ$	{printer	daemon	width	height}}

PRINTFILE prints the contents of the current file. PRINTFILE uses the internal **SEDIT** image of the file.

When running **SEDIT** in character mode, the six parameters must be specified.

When the four last parameters are not specified, **SEDIT** displays the following dialog box:

Printer: <u>1p</u>	Width: <u>132</u>
Daemon: <u>1</u> p	Height: 60
<u> </u>	(CANCEL)

on	print line numbers. This is the default value.
onej	print line numbers and start a new page whenever an "eject" string is found. The "eject" string must be followed and preceded with a blank or tabulation character to be recognized.
off	do not print line numbers.
offej	do not print line numbers and start a new page whenever an "eject" string is found.
printer	the printer to be used.
daemon	the command to be used to print. Typically lp or lpr.
width	the number of columns of the printer.
height	the number of lines by page.

When **SEDIT** is running in batch mode, the PRINTER, DAEMON, WIDTH and HEIGHT parameters are not optional.

See Also: ALL, PRINTSCREEN

PRINTFile (WINDOWS) - Print a File Hardcopy

Scope:	Display		
PRINTFile	$\{\underline{ON} \text{OFF} \text{ONEJ} \text{OFFEJ}$	{width	{height}}}
Batch Mode:	Not Available		

PRINTFILE prints the contents of the current file. PRINTFILE uses the internal **SEDIT** image of the file.

SEDIT displays the standard WINDOWS dialog box.

on	print line numbers. This is the default value.
onej	print line numbers and start a new page whenever an "eject" string is found. The "eject" string must be followed and preceded with a blank or tabulation character to be recognized.
off	do not print line numbers.
offej	do not print line numbers and start a new page whenever an "eject" string is found.
width	the number of columns of the printer. When not specified, SEDIT uses the default value provided by the system.
height	the number of lines by page. When not specified, SEDIT uses the default value provided by the system.

See Also: <u>ALL</u>, <u>PRINTSCREEN</u>

PRINTScreen (UNIX) - Print a Screen Hardcopy

PRINTScreen {printer {daemon}}Initial value:lp lpron BSD systemslp lpon System V systems

Scope: Global Batch Mode: Not Available

When printer is not specified, PRINTSCREEN prints a hardcopy of the screen.

When printer is specified, it becomes the default printer for both the PRINTSCREEN facility and for TREE. No printing occurs.

When daemon is also specified, it becomes the default **UNIX** command used to print. No printing occurs.

When not running in ASCII terminal mode, this command is mapped to the meta-L3 key on Sun Workstations, to the Compose-F13 key on DECstations and to the Shift-Control-Escape key on other workstations.

These keys are not available when running in ASCII terminal mode, so the user must either enter the PRINTSCREEN command in the command field, or assign it to any available function key.

See Also: **PRINTFILE**

PRINTScreen (WINDOWS) - Print a Screen Hardcopy

PRINTScreen prints a hardcopy of the screen. Batch Mode: Not Available

See Also: **PRINTFILE**

PRompt - Prompt user

PRompt string prompts the user with the message string.

Batch Mode: Not Available

string will appear in an alert box, with the two buttons "Continue" and "Cancel". If the user chooses "Continue", the return code will be 0. Otherwise, it will be 1.

It is possible to display up to 4 lines by using the "n" separator within string.

Example: prompt Do you really want\nto exit?

PUT - Save Data

PUT {target {fn {ft {fd}}} inserts lines from the currently edited file.
Scope: Display

target defines the number of lines to be inserted, starting from the current line. target may be one of the following:

:N	Up to but not including the Nth line.
N or +N	N lines.
+* or *	The end of file.
.symb	The line which has been assigned the .symb symbolic name by using the POINT command, or a .symb prefix command.
string expression	Defines a group of characters to be located.

The general format of a string expression is the following:

{+|-}{~}/string1{/{&}|{|}{~}/string2}

See the <u>LOCATE</u> command on page 300 for a precise string expression definition.

If target is omitted, a value of 1 is assumed.

When <u>MODE</u> GET NOSTAY is in effect, the target line becomes the current line.

When fn ft fd are omitted, the lines are saved into a temporary buffer used by the <u>GET</u> command, or the G prefix command, allowing the user to copy data.

fn specifies the filename part of the file into which lines will be inserted. When specified as =, the current file filename will be used. When specified as a period (.), no filename will be used.

If fn starts with "~", "/", "./" or "../", and ft are fd are not specified, fn will be considered as a full **UNIX** or **WINDOWS** name.

ft specifies the filetype (such as c for a foo.c file) part of the file into which lines will be inserted. When omitted or specified as =, the current file filetype will be used. When specified as a period (.), no extension will be used.

fd specifies the directory part of the file into which lines will be inserted. When omitted or specified as =, the current file directory will be used.

When the specified file exists, the lines are added to the end of that file. Otherwise, **SEDIT** displays the following message:

Creating new file: "xxxxxxx"

Examples: If line 10 is the current line, and foo.c is the current file:

P 5	will save lines 10 through 14.
P :20	will save lines 10 through 19.
P*	will save up to the end of the file.
P;main;==~/	pro
	will insert the lines up the main string into
	the ~/pro/foo.c file. Note that you must
	not use the / as the string target main
	delimiter, because it appears into the ~/pro
	filename.
P1 = . =	will insert one line in the foo file.
P* ~/pro/a	will insert lines into the $\sim/pro/a$ file.

See Also: <u>Get</u>, <u>mode</u>, <u>putd</u>

PUTD - Save Data

PUTD {target {fn {ft {fd}}} inserts lines from the currently edited file. Scope: Display

PUTD executes a PUT command, and then deletes the lines which have been saved.

See Also: <u>GET</u>, <u>MODE</u>, <u>PUT</u>

PURge - Clear Macros

PURge {macroname | *} removes from storage the macro macroname.

If you specify *, all the macros will be cleared.

Without parameters, PURGE will prompt the user for a confirmation before removing all the macros.

PWD/W - Display Current Directory

PWD or Wdisplays the current directory in the message field.Note that this directory is displayed at the window top border as well.

Query - Query About Editing Options

Query setting

Within **SEDIT**, using a command without parameters displays its setting. For example, typing <u>VERIFY</u> displays the verify setting.

Within the IBM **XEDIT** editor, you *must* use the QUERY command for that purpose, typing for example QUERY VERIFY.

The **SEDIT** QUERY command allows the prefix QUERY as well, in order to maintain strict compatibility with **XEDIT**.

QUIT / AQUIT / PQUIT / QQuit - Abandon File

AQUIT $\{N\}$

abandons the file being edited if it has not been modified since last stored. If the file has been modified, AQUIT will ask for an F1 key confirmation. If this command is called by a button, the prompt will be displayed in an alert box.

When **SEDIT** runs in batch mode, AQUIT performs as PQUIT.

PQUIT {N}

abandons the file being edited if it has not been modified since last stored. Otherwise, it does not quit the modified file, and issues the following message:

File has been changed; type QQUIT to quit anyway

In addition, PQUIT clears the **S/REXX** stack.

```
QUIT \{N\} or QQuit \{N\}
```

unconditionally abandons the file being edited.

By default, **SEDIT** defines the following synonym:

synonym quit 4 aquit

Therefore, using QUIT will in fact call the AQUIT command. Use COMMAND QUIT or QQUIT to override this synonym and issue the command QUIT.

The optional N value specifies the QUIT return code, overriding the default return code as described below.

Return Codes:	0	Normal
	1	Only one file was edited
	5	Invalid parameter
	12	File has been changed (PQUIT only)
	Ν	The number specified as operand

RChange (XEDIT MODE) - Regular Expression Change

RChange /regex/string{/{target {N|*} {P}}} XEDRChange

changes the regular expression regex with string.

Scope: Display

When <u>MODE</u> COMMAND XEDIT is in effect, RCHANGE calls the XEDIT mode XEDRCHANGE command. PDFRCHANGE may be used to call the ISPF/PDF mode CHANGE command.

/ may be replaced with any delimiting character that does not appear in the character strings involved in the replacement.

A regular expression is a character string used to describe, in an extended way, a string to be matched. It uses special characters, called meta characters to describe the match to be done. See the \underline{R} command on page 363 for a complete description of regular expressions.

target defines the number of lines to be scanned for a match. Lines are changed starting with the current line, up to but not including the target line. target may be one of the following:

:N	Up to but not including the Nth line.
N or +N	N lines.
+* or *	The end of file.
.symb	The line which has been assigned the .symb symbolic name by using the POINT command, or a .symb prefix command.
string expression	Defines a group of characters to be located.

The general format of a string expression is the following:

{+|-}{~}/string1{/{&}|{|}{~}/string2}

See the **LOCATE** command on page 300 for a precise string expression definition.

When target is omitted, all lines between the current line and the end of file will be scanned. However, if MODE CHANGE ONE is in effect, only the first line will be changed.

N is the number of occurrences of regex to be changed on each line.

If omitted, all occurrences of regex will be changed. However, if <u>MODE</u> CHANGE ONE is in effect, only the first occurrence will be changed.

If specified as *, all occurrences of regex will be changed.

P is the relative number of the first occurrence of string to be changed in each line. Its default value is 1.

When regex is omitted, string is inserted in the column which has a value defined by the first <u>ZONE</u> command operand (initially 1).

When ARBCHAR is ON, all occurrences of the arbitrary character in string will be changed with the string matching regex.

Examples:	rc/[0-9]/?/	will turn every number into a ?
	arbchar on @ rc/[a-z]/(@)/**	will enclose every lowercase alphabetical character within parenthesis.

If CASE CIGNORE is in effect, **SEDIT** will not consider capitalization when changing strings.

Example: case ci rc/Old/new/ will change old with new.

- Note: The <u>ZONE</u> command allows the user to choose the starting and ending columns to be scanned.
- $\underbrace{See Also: \underline{ARBCHAR}, \underline{CASE}, \underline{CHANGE}, \underline{CN}, \underline{HEX}, \underline{LOCATE}, \underline{MODE}, \underline{R/}, \underline{SCHANGE}, \underline{SCN}, \underline{SRCHANGE}, \underline{STAY}, \underline{ZONE}}$

RChange (ISPF MODE) - Repeat Last Change

RChange

PDFRChange

RCHANGE repeats the last ISPF/PDF PDFCHANGE command described on page 173.

When <u>MODE</u> COMMAND ISPF is in effect, RCHANGE calls the ISPF mode PDFRCHANGE command. XEDCHANGE may be used to call the XEDIT mode RCHANGE command.

READ - Place Terminal Information in the STACK

READ <u>Cmdline</u> |{Tag|<u>Notag</u>} All {Number} | Nochange {Number} | Batch Mode: Not Available

READ waits for a user action. It is intended to be called from an **S/REXX** macro, placing information in the REXX stack. READ does not perform any operation when the stack is not empty.

The operands are the following:

Cmdline	only the command input area is to be stacked. This is the default.
All	all lines changed on the screen are to be stacked. In addition, the
	file currently edited will be updated with these changes.
Nochange	all lines changed on the screen are to be stacked. The file currently edited will not be updated with these changes.
Number	the stacked information relative to changed lines will be prefixed by the corresponding file number.
Тад	a tag identifying the origin of the line will be added at the beginning of each stacked line.
Notag	no tags are added. This is the default.

Using READ CMDLINE

If a string str was entered on the command line:

- Using the Enter or Return key will stack str.
- Using a function key, such as F1, L2, R6 or ^a will stack the definition of that key, or nothing when this key is not defined. str will be ignored. **SEDIT** function keys are equivalent to **XEDIT** 'ONLY' keys.

If nothing was entered on the command line:

- Using the Enter or Return key will stack nothing.
- Using a function key will stack the definition of that key, or nothing when this key is not defined.
Using READ ALL Or READ NOCHANGE

Each modified field is stacked as a separate line. The stack will contain:

- The definition of the function key pressed, when this key is defined. The 1) Enter key definition is always ignored within SEDIT.
- The lines, prefix and input reserved areas changed on the screen. 2)
- 3) The command line, when not empty.

Using the TAG Operand

With the TAG operand, each stacked line is preceded by a string tag, which identifies the modified field:

CMD	identifies the command line.
FIL	identifies a file line.
PFK	identifies a top function key, such as F1 or PF12.
PFR	identifies a right function key, such as R2.
PFL	identifies a left function key, such as L3.
PRF	identifies a prefix area.
CTL	identifies a control key, such as ^a.
RES	identifies a reserved input field.
MOU	identifies the use of a mouse button.
CLI	identifies the use of the left mouse button on a sensitive field. When READ
	is waiting for a user action, the file data fields and the reserved fields are
	mouse sensitive: they display in reverse video when selected with the left
	mouse button, and make READ return when the mouse button is released.

The tag is followed by additional information, and by the str modified field content:

CMD str str is the string entered in the command line.

FIL n1 n2 $\{n3\}$ str

n1 n2 are the line and column number of the beginning of the field on the screen. n3 is the corresponding file line number. n3 is returned only when the NUMBER option has been specified.

PFK n str, PFR n str, PFL n str n is the number of the function key that was pressed. str is the key definition. Function keys are stacked LIFO.

CTL n str n is the ASCII value of the key that was pressed. For example, if ^a was entered, n value is a. str is the key definition. Control keys are stacked LIFO.

RES n1 n2 str n1 n2 are the line and column number of the reserved field on the screen. str is the field content.

MOU n n is the number of the mouse button that was pressed.

CLI n1 n2 $\{n3\}$

n1 n2 are the line and column number of the beginning of the field on the screen. n3 is the corresponding file line number, or 0 when clicking over a field which is not a file data field. n3 is returned only when the NUMBER option has been specified.

See Also: <u>CTLCHAR</u>, <u>MODE</u>, <u>READSCREN</u>, <u>RESERVED</u>

READScreen - Read User Action

READScreen

Batch Mode: Not Available

READSCREEN waits for a user action, allowing input only in the command field when called from an external macro. When called from an **S/REXX** macro, READSCREEN also allows input in the data fields.

When issued from a external macro, READSCREEN creates the following environment variables:

RDS_ACTION	the action keystroke, such as "return" or "F2".
RDS_CMD	the command line content.
RDS_MOUL	when the user clicks on a data field, this variable is set to the corresponding line number. Otherwise, it is set to -1.
RDS_MOUC	the corresponding column line number, or -1.
RDS_CUL	the cursor file line number, or -1 when the cursor is not on a data field.
RDS_CUC	the corresponding column line number, or -1.

Note: The created environment variables will be defined in the **SEDIT** main process. Since external macros run on different processes, the user cannot call the READSCREEN command within an external macro, and use directly the environment variables in the same macro. The user must use the EXTRACT ENVIRON command instead.

When issued from an S/REXX macro, READSCREEN creates REXX variables instead of creating environment variables. In addition, all modified lines and prefix fields are recorded in the following variables:

rds_num.0	the number of modified data fields.
rds_num.i	the corresponding file line number.
rds_cnt.i	the corresponding line content modified by the user.
rds_num_pre.0	the number of modified prefix fields.
rds_num_pre.i	the corresponding file line number.
rds_cnt_pre.i	the corresponding prefix content modified by the user.

When reserved fields have been created with the RESERVED command, READSCREEN creates also the following variables:

rds_res.0	the number of modified reserved data fields.
rds_res.i	the corresponding field content: the first word is the
	screen line number, the second word is the screen
	column number, and the following is the data typed in
	the field.

The current file is not modified. It is the responsibility of the calling macro to acknowledge the modifications, by using for example the REPLACE command, or to ignore them.

RECYCLE - Use the Recycle Bin

Initial value:ONLevel:GlobalRECycle {ON | OFF}sets ON or OFF the recycle bin facility.

On **WINDOWS** systems, when RECYCLE is ON, removing files from FLIST, or files and directories from TREE, moves then into the recycle bin.

RECYCLE without arguments displays the RECYCLE status.

REDo - Cancel Last Undo

REDo

cancels the last undo operation.

The redo memory is reset every time the file is modified by the user.

This command is mapped to the S-L4 key on Sun workstations, and to the S-F11 key on other workstations.

REFRESH - Screen Update

REFRESH {Clear} updates the display.

Batch Mode: Not Available

REFRESH is intended to be used within external macros in order to update the display.

When running in ASCII terminal mode, the clear option allows you to clear the screen before updating it. In this mode, "REFRESH CLEAR" is mapped to the r key.

RELEase - Removes a Directory From the PATH

RELEase {dir1 {dir2 ...}}

RELEASE removes from the path directories accessed with the <u>ACCESS</u> command.

If the diri directory is not accessed, or is the current directory, RELEASE silently ignores it.

RELEASE * removes all the directories from the path, except the current directory and, on **UNIX** systems, the following set of standard directories:

/usr/bin /bin /usr/lib /etc /usr/etc /usr/ucb

RELEASE without arguments scans the path, and removes nonexistent directories.

See Also: <u>ACCESS</u>, <u>SHOWPATH</u>

RELoad - Automatic Reload Feature

RELoad ON OFF {*}

sets the automatic reload feature ON or OFF.

Initial value: ON Level: File

When RELOAD is set to ON, **SEDIT** checks all the currently loaded files under the following circumstances:

- When **SEDIT** loses the keyboard focus, and then receives it again.
- When the user switches from one file to another.
- When the user loads a new file.

If **SEDIT** determines that a file has been externally modified, **SEDIT** saves the previous image of the file that it had loaded into memory (after appending to its name the % character), and then reloads the newly modified file.

A file is determined to be modified when its time stamp is older than the time stamp **SEDIT** memorized when loading that file. With mounted file systems, especially between a **UNIX** system and a **WINDOWS** system when using a CIFS **UNIX** client like the SharityTM software, there may be a discrepancy between the time stamp memorized by **SEDIT**, and the actual time stamp on the **WINDOWS** file system. The <u>STAMPDELAY</u> command allows **SEDIT** to ignore a given amount of discrepancy between time stamps in order to avoid spurious reloads.

When * is specified, the supplied reload status will be used for every new file.

RELOAD OFF * disables the reload facility for every newly loaded file.

See Also: <u>STAMPDELAY</u>

REPEat - Repeat a Command

REPEat	{target}	repeats the last entered command.
Scope:	Display	
target	defines the nun	hber of times the current line pointer will be moved.
۱N		Up to the Nth line.
N or	+N	N lines.
-N		Up N lines.
+* 0	r *	The end of file.
_*		The top of file.
.syı	mb	The line which has been assigned the .symb symbolic name by using the POINT command, or a .symb prefix command.
string	g expression	Defines a group of characters to be located.

The general format of a string expression is the following:

{+|-}{~}/string1{/{&}|{|}{~}/string2}

See the <u>LOCATE</u> command on page 300 for a precise string expression definition.

If target is omitted, a value of 1 is assumed.

When target is in a forward direction, REPEAT is equivalent to:

next 1 =

When target is in a backward direction, REPEAT is equivalent to:

up 1 =

REPEATS ends when the specified target is reached, or when the executed command returns a non-zero value, or when the top or bottom of file is reached.

Examples: repeat repeats the last command on the next line. repeat/main repeats the last command until finding a main string.

See Also: $\underline{?}$, $\underline{=}$

REPEATDelay - Set Auto-repeat Time-out

REPEATDelay {key1 key2 mouse1 mouse2} Initial values: 120 30 30 30 (UNIX) 400 50 60 60 (WINDOWS)

REPEATDELAY without arguments displays the current values.

When the user depresses a function key, such as F1 or R9, **SEDIT** performs the command assigned to that key, and then waits for key1 milliseconds. If that key has not been released during this interval, **SEDIT** performs the command again. Then, the command will be performed again every key2 milliseconds until the key is released.

mouse1 and mouse2 control in the same way the auto-repeat time-out associated with the mouse buttons when they are used to scroll the file, as described page 53.

REPEATDELAY is ignored when **SEDIT** is in ASCII terminal mode.

Note: On some platforms, there is a keyboard native auto-repeat feature which takes precedence over the **SEDIT** auto-repeat feature.

Replace (XEDIT MODE) - Replace Current Line

Replace text replaces the current line with text. XEDReplace

When <u>MODE</u> COMMAND XEDIT is in effect, REPLACE calls the XEDIT mode XEDREPLACE command. PDFREPLACE may be used to call the ISPF/PDF mode REPLACE command.

Replace (ISPF MODE)- Replace Data

Replace {file} {range} PDFReplace

Batch Mode: Not Available

When <u>MODE</u> COMMAND ISPF is in effect, REPLACE calls the ISPF mode PDFREPLACE command. XEDREPLACE may be used to call the XEDIT mode REPLACE command.

REPLACE saves the data being edited into a UNIX file.

file A file which may exist.

When file is omitted, **SEDIT** displays the following fullscreen panel:

```
Replace file ===>
Press Enter to replace, F3 or ^c to cancel
```

range Two labels that identify the lines to be saved. A label may be created by typing a .xxxx string on a prefix zone, or by using the XEDIT POINT command described on page 331. A label may also be one of the ISPF/PDF predefined labels:

.zfor.zfirst	the first line.
.zlor.zlast	the last line.
.zcsr	the cursor line

When a range is not specified, the user must enter either a C, CC, M or a MM prefix command in a prefix zone to specify the lines to be copied. Specifying a prefix origin can be done either before or after using the CREATE command.

Examples: r ~/foo .a .zl replace .a .b replace

See Also: <u>CREATE</u>, <u>FILE</u>, <u>SAVE</u>

RESERved - Reserve a Specified Line on the Screen

RESERved $M\{+n|-n\}$ {color} {exthi} {PSs} High {text} {+|-} n Off Off

Level: File

RESERVED reserves a given line of the logical screen, specifying the color, extended highlighting, and visibility of that line.

The operands are the following:

$M\{+n -n\}$	M stands for the screens, with a	ne middle of the screen, rounded up for odd-sized an optional offset to that position.
{+}n	specifies n lin	es from the top of the screen.
-n	specifies n lin	es from the bottom of the screen.
OFF	frees a previou	usly reserved line.
color	the color to be addition, <i>col</i>	e used, as described by the COLOR command. In <i>or</i> may be:
	White	same as BLACK
	Turquoise	same as MAGENTA
exthi	may be:	
	BLink	Maintained for XEDIT compatibility, but not supported within SEDIT .
	REVvideo	Displays in reverse video.
	Underline	Underlines the displayed characters.
	None	No extended highlighting. This is the default.
High Nohigh	specifies that t specifies that t is the default.	the string text is to be displayed in bold. he string text is not to be displayed in bold. This
PSs	maintained for SEDIT .	r XEDIT compatibility, but not supported within
text	is the text to defined by the	be displayed. It may imbed control characters CTLCHAR command.

Example: ctlchar @ escape ctlchar & noprotect red revvideo nohigh reserved m+1 noh Enter your name: @& allows the user to define an input red field displayed in reverse video.

Without operands, RESERVED displays the line numbers reserved.

Usage Notes

• On 3270 devices, a control character occupies one blank space. Thus, a command such as reserved m+1 noh Enter your name:@&John would display:



This limitation is implemented for strict **XEDIT** compatibility. However, it is possible to remove it by using the MODE RESERVED NOSKIP command, which would allow the user to display:



- RESERVED +N, RESERVED M { + | }N and RESERVED -N are treated as different lines, even if they fall on the same line. In order to be removed, a reserved line must be specified in the same way it was specified when it was reserved.
- Reserved lines are file specific. To reserve lines every time a new file is loaded, the RESERVED command must be used within the reprofile.ex or reprofile.sedit macro.reprofile is executed every time a new file is loaded, while profile is only executed at initialization.
- The SETP command allocates permanently one or more lines of the screen, and is more suitable for displaying non-file related function keys information. SETP without arguments frees the previously allocated line.

See Also: <u>CTLCHAR</u>, <u>MODE</u>, <u>READ</u>, <u>SETP</u>

RESet - Reset the Data Display

RESet {COmmand} {ERror} {EXcluded} {X} {Label}

RESET clears line-related conditions.

COmmand removes all pending prefix commands.

ERror removes the line symbolic names assigned by the <u>COMPILE</u> command.

EXcluded or **X** redisplays any excluded line.

Label removes . xxxx labels

When <u>MODE</u> COMMAND ISPF is in effect, RESET without argument is the same as RESET COMMAND ERROR EXCLUDED.

When MODE COMMAND XEDIT is in effect, RESET without argument is the same as RESET COMMAND.

See Also: <u>All</u>, <u>Clearerrors</u>, <u>Point</u>

RESTore - Settings Retrieval

RESTore

RESTORE retrieves the settings saved by the PRESERVE command.

See the PRESERVE command for a list of the settings affected by the RESTORE command.

See Also: PRESERVE

RFlist - Call Directory Editor

RFlist { FN {FT {FM}}} will call the directory editor.

Batch Mode: Not Available

RFLIST uses regular expressions to match files. See The Directory Editor FLIST on page 453 for further explanations.

See Also: <u>DACCESS</u>, <u>DFLIST</u>, <u>FFLIST</u>, <u>FLIST</u>

RFINd - Repeat Last Find

RFINd

RFIND repeats the last ISPF/PDF PDFFIND command described on page 262.

RIght - Scroll Right

RIght $\{N\}$ is used to alter the columns that are to be displayed.

"startc" is the first column.

"endc" is the last column.

If N is omitted a value of 1 is assumed.

If N is 0, the original setting will be restored.

In all other cases, "startc" and "endc" will be increased by N, shifting the data to the left by N positions

The command "RIGHT 40" is mapped to the C-F8 key by default.

See Also: LEFT, VERIFY

RIGHTAdjust - Right-adjusting Text

RIGHTAdjust {target}

All

Scope:

This command is mapped to the Shift-Control-R (^R) key by default.

RIGHTADJUST reformats a portion of the current file defined by the target operand. RIGHTADJUST positions the last non-blank character at the right margin defined with the <u>MARGINS</u> command.

target may be one of the following:

All	All the file is formatted.
Sel	Right-adjusts the selected lines. If the selection is rectangular, RIGHTADJUST right-adjusts the contents of the selected area, the text outside the selection not being modified.
:N	Up to but not including the line N.
+N	Down N lines.
-N	Up N lines.
+* or *	Down to the end of file.
_ *	Up to the top of file.
.symb	Up or Down to the line which has been assigned the .symb symbolic name by using the POINT command, or a .symb prefix command.
string expression	Defines a group of characters to be located.

The general format of a string expression is the following:

 $\{+|-\}\{-\}/string1\{/\{\&\}|\{|\}\{-\}/string2 \dots\}$

See the **LOCATE** command on page 300 for a precise string expression definition.

When target is not specified, RIGHTADJUST formats the line corresponding to the cursor location. When the cursor is not located upon a line of the current file, RIGHTADJUST reformats the current line.

Examples:	RIGHTADJUST	
	RIGHTADJUST	all
	RIGHTADJUST	sel
	RIGHTADJUST	/str/

See Also: <u>CENTER</u>, <u>FLOW</u>, <u>FORMAT</u>, <u>LEFTADJUST</u>, <u>LOCATE</u>, <u>MARGINS</u>, POWERINPUT

RW - Enable Read/Write Mode

RW { ON | OFF } Initial value: ON Level: File enables or disables the save and file commands.

When RW is OFF, the associated file cannot be saved. This is the default when loading a file using the HELP command.

See Also: <u>FILE</u>, <u>SAVE</u>

<u>R/ - Regular Expression Search</u>

R/regex{/}

searches for the first string matching the regular expression regex starting from the current line and proceeding in descending order.

Scope: Display

The cursor will be moved to the beginning of the string.

The last / is optional, unless the string ends with a / or a space.

A regular expression is a character string used to describe, in an extended way, a string to be matched. It uses special characters, called meta characters to describe the match to be done.

The meta characters are the following:

^	matches only at the beginning of a line.
\$	matches only at the end of a line.
\<	matches only at the beginning of a word.
\>	matches only at the end of a word.
	matches any single character.
[]	matches any character in a character class.
\setminus (delimits the start of a subexpression. It is available for VI compatibility,
	but has no special meaning.
\setminus)	delimits the end of a subexpression. It is available for VI compatibility,
	but has no special meaning.
*	repeats the preceding 0 or more times.

If you want to use a meta character as an ordinary character, you must precede it with a backslash $(\)$ character.

Examples:

r/**^**The

matches the string "The" only at the beginning of a line.

r/The\$

matches the string "The" only at the end of a line.

r/\<i\>

matches the string "i" in "i=3" but not in "if (k = 2)".

r/The....is

matches the string "The" followed by any 7 characters followed by the string "is". "The color is" will be matched. "The moon is" will not.

r/[A-Z][a-z]

[A-Z]	means any character from A to Z.
[a-z]	means any character from a to z.

The whole expression above matches any alphabetical string starting with a capital letter.

The string "The" will be matched. "L12" will not

Note that the meta characters are not treated specially when enclosed in brackets:

r/[.]

matches the string ".". Without brackets, the user should type:

Page 364

r/ackslash.

for the same match.

r/[0-9][0-9]*\.[0-9][0-9]*

[0-9]	means at least one character between 0 and 9.
[0-9]*	means 0 or more characters between 0 and 9.
\backslash .	means a period. The period must be preceded with a $\$, otherwise it
	would mean any character.

The whole expression above matches numbers like "12.32". It does not match ".32" or "12.".

Notes: The <u>ZONE</u> command allows the user to choose the starting and ending columns to be scanned.

When <u>MODE</u> LOCATE NOSTAY is in effect (the **SEDIT** default), these columns are also restricted by the VERIFY column definition; the user can only scan the visible part of the file. The cursor will be moved to the beginning of the target. A subsequent search will start at the cursor location.

When MODE LOCATE STAY is in effect (the **XEDIT** behavior), the cursor stays in the command line, the search is not restricted by the <u>VERIFY</u> setting, and the next search will start on the next (or previous) line.

When <u>WRAP</u> is set to ON, **SEDIT** continues the search up to the line preceding the current line within the R/ command. The search is continued following the current line within the R-/ command.

When WRAP is set to OFF, the search ends at the end (of top) of file. The EXTRACT/<u>RMATCH</u>/ command can be used within a macro to retrieve the matched string.

See Also: <u>ALL</u>, <u>CASE</u>, <u>COMPILE</u>, <u>EXTRACT</u>, <u>MODE</u>, <u>RCHANGE</u>, <u>R-/</u>, <u>VERIFY</u>, <u>WRAP</u>, <u>ZONE</u>, \angle , $-\angle$, \angle , $-\angle$

Page 365

<u>R-/ - Regular Expression Search</u>

R-/regex{/}

searches for the first string matching the regular expression regex starting from the current line and proceeding in ascending order.

Scope: Display

The cursor will be moved to the beginning of the string.

The last / is optional, unless the string ends with a / or a space.

See the R/ command on page 363 for a complete regular expression syntax description.

See Also: ALL, CASE, COMPILE, MODE, R/, VERIFY, ZONE, /, -/, \land , $-\land$

SABER_End - End Connection with Saber-C

SABER_End

terminates a connection with the Saber-C 3.x software¹.

This command makes **SEDIT** stop listening on the socket opened with the SABER_INIT command.

Note that **SEDIT** will notice if the Saber process to which it is connected ends, and automatically execute a SABER_END command without notifying the user.

The SABER_XXX commands are intended to be used with the Saber-C or CodeCenter 3.x release.

Please see the CENTER_XXX commands when running CodeCenter 4.x.

See Also: <u>CENTER END</u>, <u>CENTER INIT</u>, <u>CENTER SEND</u>, <u>LISTEN</u>, <u>SABER INIT</u>, <u>SABER SEND</u>

^{1.} Saber-C and CodeCenter are trademarks of CenterLine Software, Inc.

SABER_Init - Initialize Connection with Saber-C

SABER_Init

starts a connection with the Saber-C 3.x software¹.

Saber-C 3.01 and 3.1 listens for commands on a socket whose number is described in the files "/tmp/saber.socket.nnn" or "/tmp/sabsocketnnn", where nnn is the Saber-C process number.

If **SEDIT** finds that only one Saber-C process is running, it will establish the connection with it immediately. If more than one Saber-C process is running, SEDIT will display a fullscreen panel showing all the Saber-C process numbers, and the user will have to click with the mouse on the process to be communicated with to using the SABER_Send command.

The SABER_XXX commands are intended to be used with the Saber-C or CodeCenter 3.x release.

Please see the CENTER_XXX commands when running CodeCenter 4.x.

See Also: <u>CENTER END</u>, <u>CENTER INIT</u>, <u>CENTER SEND</u>, <u>LISTEN</u>, <u>SABER END</u>, <u>SABER SEND</u>

^{1.} Saber-C and CodeCenter are trademarks of CenterLine Software, Inc.

SABER_Send - Send Command to Saber-C

```
SABER_Send cmd
```

sends cmd to the Saber-C¹ process which has been recognized by the SABER_INIT command.

If no connection has been established with a Saber-C process, SEDIT executes a SABER_INIT command. Then, **SEDIT** sends cmd to that process, and listens on the socket opened. If Saber-C returns a string, **SEDIT** prints it in the window it was started from.

Note that the user can continue to use **SEDIT** normally, even if Saber-C does not answer.

The user may insert the following lines in the file "sedit.menu" in order to be able to send commands using the mouse:

```
"SABER" MENU
      "load " MENU
                      ".c" saber send load $fn.c
                      ".o" saber_send load $fn.o
      "load " END
      "unload" saber_send unload $fn
      "swap " saber_send swap $fn
      "stop " MENU
                 "stop in" saber send stop in $fn
                "stop at" Saber_stopat
      "stop " END
      "ini
             ....
               saber_init
      "list "
               saber_send list $fn
      "read " MENU
               "ON " listen 1999
                "OFF " listen off
      "read " END
      "end
             " saber_end
"SABER" END
```

^{1.} Saber-C and CodeCenter are trademarks of CenterLine Software, Inc.

Saber_stopat is the "\$xhome/xmac/Saber_stopat.ex" macro, and sets a stop in the current file at the cursor location:

```
#! /bin/csh -f
#
# Saber_stopat: sets a stop at the cursor line
#
set cursor = 'extract cursor'
if ( $cursor[4] == -1 ) then
    sends 'emsg .... Saber_stopat: invalid cursor position'
    exit 0
endif
set fname = 'extract fname'
set ftype = 'extract ftype'
set a = 'saber_send stop "'"$fname[2]""$ftype[2]"'":'$cursor[4]
sends "$a"
```

The SABER_XXX commands are intended to be used with the Saber-C or CodeCenter 3.x release.

Please see the CENTER_XXX commands when running CodeCenter 4.x.

See Also: <u>CENTER END</u>, <u>CENTER INIT</u>, <u>CENTER SEND</u>, <u>LISTEN</u>, <u>SABER END</u>, <u>SABER INIT</u>

SAve / SSave / KSAve/ DOSSave - Save File

SAve / SSave / KSAve / DOSSAve {fn {ft {fd}}}

These commands transform the unchanged source file into a backup file by appending a "%" to its name, and create a new file from the edited memory image, and continue the editing session. When SAVECLEARUNDO is set to ON (the default), the undo memory is reset.

When **SEDIT** is not running in batch mode, if the file name has been changed during the editing session so that it is identical to that of an existing file, or if the file has been modified by another user, SAVE will ask for a confirmation to overwrite the existing file. SSAVE will not. When **SEDIT** is running in batch mode, SAVE does not overwrite the existing file.

The KSAVE command performs the same function as the SAVE command, but leaves unchanged the saved file timestamp. This may be useful, for example, when the modified file is an include file. Using KSAVE will prevent a following make command from recompiling every file which relies on the saved file.

The DOSSAVE command performs the same function as the SAVE command, but adds a ^M character at the end of each line, and a ^Z character at the end of the file, thus making the file compatible with Personal Computers using the DOS operating system.

Under APL, **SEDIT** will first create a "./APLOBJ" directory and then try to save the current object in this directory. This save may fail if the object name contains APL characters not allowed in a **UNIX** or **WINDOWS** name.

If fn is specified, the filename of the file will be changed before saving.

If ft is specified, the filetype of the file will be changed before saving.

If fd is specified, the filedirectory of the file will be changed before saving.

Warning: When KEEPBLANKS is set to OFF, **SEDIT** removes all trailing blanks in every line before saving a file. Do not save a file (such as a "*.o" file) where trailing blanks are part of the data.

See Also: <u>BACKUP</u>, <u>KEEPBLANKS</u>, <u>DY</u> SAVE, <u>FILE</u>, <u>RW</u>, <u>VERIFY</u> SAVE, <u>SAVECLEARUNDO</u>

SAVECLEARUNDO - Set Clear Undo Status

SAVEClearundo {ON | OFF}

Initial value: ON Level: Global

When SAVECLEARUNDO is ON, the undo memory is reset every time the file is saved.

SCALe / SCALE_Screen - Set Scale Line

SCALE ON | OFF {line} Initial value: OFF 3 Level: File and View

```
SCALE_Screen ON|OFF {line}
Initial value: OFF 3
Level: View
```

SEDIT maintains a separate SCALE setting for each file and each view of this file defined with the <u>SCREEN</u> command.

The SCALE_SCREEN command updates the default SCALE setting of the current view, which is applied to every newly loaded file.

The SCALE command applies to the current file on the current view. SCALE selects the physical line on which the scale line is to be displayed.

With SCALE ON in effect, **SEDIT** displays a scale line in the input field area, which shows column indications according to the verify setting. It indicates where every fifth column is located. The left and right zone columns are indicated by < and >. The column pointer is indicated with a |. If the tabline is set on the same location as the scale line, the tab information will also appear on the scale line.

The scale line displays also a \uparrow character at the left margin position, a @ character at the first line indent position and a \$ character at the right margin position.

Clicking with the first mouse button on the scale line changes the first <u>VERIFY</u> setting to the corresponding column. This allows to scroll the file display to the right up to this column.

line can be specified in three ways:

n +n	selects the line n of the view to display the current lin the first line is line 1.	
-n		selects the line n from the bottom of the view, where the last line is line -1.
M+n M-n		selects the line n lines above or below the middle line of the view.
Examples:	SCALE SCALE SCALE SCALE	ON 2 ON -3 ON M OFF M+2

See Also: <u>CLOCATE</u>, <u>MARGINS</u>, <u>TABLINE</u>, <u>VERIFY</u>

SChange - Selective String Change

```
SChange /string1/string2{/{target {N|*} {P}}}
changes string1 with string2 asking for
confirmation at each occurrence.
```

```
Scope: Display
Batch Mode: Not Available
```

/ may be any delimiting character that does not appear in the character strings involved in the replacement.

target defines the number of lines to be scanned for a match. Lines are changed starting with the current line, up to but not including the target line. target may be one of the following:

:N	Up to but not including the Nth line.
N or +N	N lines.
+* or *	The end of file.
.symb	The line which has been assigned the .symb symbolic name by using the POINT command, or a .symb prefix command.
string expression	Defines a group of characters to be located.

The general format of a string expression is the following:

 $\{+|-\}\{-\}/string1\{/\{\&\}|\{|\}\{-\}/string2 \dots\}$

See the **LOCATE** command on page 300 for a precise string expression definition.

When target is omitted, all lines between the current line and the end of the file will be scanned. However, if <u>MODE</u> CHANGE ONE is in effect, only the first line will be changed.

N is the number of occurrences of string1 to be changed on each line.

If omitted, all occurrences of string1 will be changed. However, if MODE CHANGE ONE is in effect, only the first occurrence will be changed.

If specified as *, all occurrences of string1 will be changed.

P is the relative number of the first occurrence of string1 to be changed in each line. Its default value is 1.

When string1 is omitted, string2 is inserted in the column which value is defined by the first <u>ZONE</u> command operand (initially 1).

When <u>HEX</u> ON is in effect, the string*i* operands may be entered as hexadecimal values.

Every time string1 is found, **SEDIT** will pause.

Pressing the F12 key will make the change and the command will resume execution.

Pressing F1 will terminate the command.

Pressing Control-F12 will make all of the requested changes asked for without pausing again.

Pressing any other key will proceed to the next occurrence of string1 without processing a change.

During a pause, the last window line will indicate the above key's definition. All fields will be turned into output fields, preventing any typing in them, and the "undo" feature will be disabled.

Examples:	sc /i=2/i=3/	will turn "i=2" to "i=3"
	sc .a=b/3.a=c/3.	will turn "a=b/3" to "a=c/3"
	sc ./**/	will delete all "/**/" strings
	sc/te//:100 1 2	will delete the second "te" occurrence in
		each line until line 100
	sc //string	will insert string in the first zone column
	sc /x'31'/x'32'	with HEX ON in effect, changes all "1" with
		"2".
	sc/k/i//if	will turn "k" in "i" until the first line
		containing the "if" string.

If CASE CIGNORE is in effect, **SEDIT** will not consider capitalization when changing strings.

Example: case ci sch/Old/new/ will change old with new.

Notes: The ZONE command allows the user to choose the starting and ending columns to be scanned.

The SCKEYS command allows the user to modify the confirmation keys.

See Also: <u>ARBCHAR</u>, <u>CASE</u>, <u>CHANGE</u>, <u>CN</u>, <u>HEX</u>, <u>LOCATE</u>, <u>MODE</u>, <u>SCKEYS</u>, <u>SCN</u>, <u>SRCHANGE</u>, <u>STAY</u>, <u>ZONE</u>

SCKeys - Selective Change Confirmation Keys

SCKeys {key_quit key_do} Initial values: 1 12 Level: Global

SCKEYS modifies the confirmation keys used by the SCHANGE, SRCHANGE and SCN commands.

key_quit The top function key used to stop the changes.

key_do The top function key used to confirm a change.

SCKEYS without arguments displays the current values.

Example: sckeys 3 4

See Also: <u>SCHANGE</u>, <u>SRCHANGE</u>, <u>SCN</u>

SCN - Selective Name String Change

```
SCN /string1/string2{/{target {N|*} {P}}}
```

changes name string1 with string2, asking for confirmation at each occurrence of string1.

```
Scope: Display
Batch Mode: Not Available
```

A name is a string which is preceded or followed by an invalid C variable character. This command is very useful in modifying a variable.

/ may be any delimiting character that does not appear in the character strings involved in the replacement.

target defines the number of lines to be scanned for a match. Lines are changed starting with the current line, up to but not including the target line. target may be one of the following:

:N	Up to but not including the Nth line.
N or +N	N lines.
+* or *	The end of file.
.symb	The line which has been assigned the .symb symbolic name by using the POINT command, or a .symb prefix command.
string expression	Defines a group of characters to be located.

The general format of a string expression is the following:

```
{+|-}{~}/string1{/{&}|{|}{~}/string2 .... }
```

See the <u>LOCATE</u> command on page 300 for a precise string expression definition.

When target is omitted, all lines between the current line and the end of file will be scanned. However, if <u>MODE</u> CHANGE ONE is in effect, only the first line will be changed.

N is the number of occurrences of string1 to be changed on each line.

If omitted, all occurrences of string1 will be treated. However, if MODE CHANGE ONE is in effect, only the first occurrence will be changed.

If specified as *, all occurrences of string1 will be treated.

P is the relative number of the first occurrence of string1 to be changed in each line. Its default value is 1.

When string1 is omitted, string2 is inserted in the column which has a value defined by the first <u>ZONE</u> command operand (initially 1).

When <u>HEX</u> ON is in effect, the string*i* operands may be entered as hexadecimal values.

Every time string1 is found, **SEDIT** will pause.

Pressing the F12 key will make the change and the command will resume execution.

Pressing F1 will terminate the command.

Page 375

Pressing Control-F12 will make all the changes without pausing.

Pressing any other key will pass to the next occurrence of string1 without processing a change.

During a pause, the last window line will indicate the above key's definition. All fields will be turned into output fields, preventing any typing in them, and the "undo" feature will be disabled.

Example: scn /i/j/ will turn name "i" in "j" but will leave unchanged string "if".

If CASE CIGNORE is in effect, **SEDIT** will not consider capitalization when changing strings.

Example: case ci scn/Old/new/ will change old with new.

Notes: The ZONE command allows the user to choose the starting and ending columns to be scanned.

The SCKEYS command allows the user to modify the confirmation keys.

See Also: <u>ARBCHAR</u>, <u>CASE</u>, <u>CHANGE</u>, <u>CN</u>, <u>HEX</u>, <u>LOCATE</u>, <u>MODE</u>, <u>SCHANGE</u>, <u>SCKEYS</u>, <u>STAY</u>, <u>ZONE</u>

SCOpe - Set Selective Editing Scope

SCOpe {All	Display}	selects the selective editing scope.
Initial value: Level:	DISPLAY View	

Each line in the file has a number associated with it, called its selection level, which is set to zero by default and may be modified by the commands ALL and SELECT, and by the prefix commands X and S. When a line selection level does not fall in the DISPLAY range, it will not be displayed.

With SCOPE DISPLAY (the default) most **SEDIT** commands and prefix commands will not apply to the excluded lines. With SCOPE ALL, **SEDIT** commands will apply to all lines.

With no argument, SCOPE will display the current setting.

See Also: <u>All</u>, <u>DISPLAY</u>, <u>SELECT</u>, <u>SHADOW</u>

SCReen - Split Screen

 SCReen
 N
 {Horizontal | Vertical}

 Size
 11 {12 {13 ...}}

 Lines
 11 {12 {13 ...}}

 Width
 c1 {c2 {c3 ...}}

 Columns
 c1 {c2 {c3 ...}}

 Define
 111 cc1 y1 x1 {112 cc2 y3 x2 {....}}

Batch Mode: Not Available

SCREEN N or SCREEN N HORIZONTAL creates N horizontally arranged identical screens.

SCREEN N VERTICAL

creates N vertically arranged identical screens.

SCREEN SIZE or SCREEN LINES

creates horizontally arranged screens, where li is the number of lines in each screen. The last screen will extend to the **SEDIT** window bottom.

SCREEN WIDTH or SCREEN COLUMNS

creates vertically arranged screens, where ci is the number of columns in each screen. The last screen will extend to the **SEDIT** window right side.

SCREEN DEFINE

creates screens according to the specified layout:

- 11i is the number of lines.
- cci is the number of columns.
- yi is the line number of the screen upper-left corner.
- xi is the column number of the screen upper-left corner.

Examples:

screen 2 vcreates 2 identical vertical screens.screen s 12 15 8creates 3 horizontal screens.screen w 39 49creates 2 vertical screensscreen d 16 38 1 1 16 40 1 39 8 78 17 1creates 3 screens with the following layout:



See Also: <u>C_SCRH</u>, <u>C_SCRJ</u>, <u>C_SCRV</u>

SCROllbar - Set Scrollbar

SCROllbar	ON OFF	enables or disables scrollbar usage.
Initial value:	ON	
Level:	Global	
Available on:	UNIX	
Batch Mode:	Not Available	

When SCROLLBAR is ON, and when running the **MOTIF** or OpenLook **SEDIT** version, a vertical scrollbar is displayed on the main window. This scrollbar allows the user to scroll through current file.

When the screen has been split, the scrollbar scrolls through the file which contains the cursor.

See Also: <u>C SCRH</u>, <u>C SCRJ</u>, <u>C SCRV</u>, <u>SCREEN</u>

SELect - Set Selection Level

SELect $\{+ $	-}N {target}
Initial value:	0
Level:	File
Scope:	Display

Each line in the file has a number associated with it, called its selection level, which is set to zero by default and may be modified by the commands ALL and SELECT, and by the prefix commands X and S. When a line selection level does not fall in the DISPLAY range, it will not be displayed.

sets the selection level of lines in the current file.

With SCOPE DISPLAY (by default) most **SEDIT** commands and prefix commands will not apply to the excluded lines. With SCOPE ALL, commands will apply to all lines.

With SHADOW ON, **SEDIT** will display a shadow line to represent each group of excluded lines. With SHADOW OFF, **SEDIT** will not display these lines at all.

The first argument is the value to set to the lines described by the second argument:

- N will set the value to N.
- +N will add N to the current selection level.
- -N will substract N to the current selection level.

target describes the file area to be modified:

All	will set the selection level for all lines in the file.
Sel	will set the selection level for all lines selected with the mouse.
:N	Up to but not including the Nth line.
N or +N	N lines.
-N	Up N lines.
+* or *	The end of file.
_ *	The top of file.
.symb	The line which has been assigned the .symb symbolic name by using the POINT command, or a .symb prefix command.
string expression	Defines a group of characters to be located.

The general format of a string expression is the following:

$\{+|-\}\{-\}/string1\{/\{\&\}|\{|\}\{-\}/string2 \dots\}$

See the <u>LOCATE</u> command on page 300 for a precise string expression definition. If target is omitted, a value of 1 is assumed.

See Also: ALL, DISPLAY, SCOPE, SELECTALL, SHADOW, STAY, VISIBLE

SELECTall - Set Selection Level on All Lines

SELECTAll	$\{N1 \{N2\{\}\}\}$	sets the selection level of all lines in the current file.
Initial value:	0	
Level:	File	
Scope:	Display	

Each line in the file has a number associated with it, called its selection level, which is set to zero by default and may be modified by the commands ALL and SELECT, and by the prefix commands X and S. When a line selection level does not fall in the DISPLAY range, it will not be displayed.

SELECTALL uses the Ni arguments to set the selection level of all the lines. If there are less Ni arguments than lines in the file, SELECTALL uses the Ni arguments cycliquelly.

Example: selecta 1 0 hides every other line.

See Also: ALL, DISPLAY, SCOPE, SELECT, SHADOW, STAY, VISIBLE

SEP - Separator Change

SEP ON|OFF {value}

enables or disables the character separator when passing commands.

Initial value: line-feed Level: Global

value is an optional parameter specifying the separator between commands. It is originally set to line-feed.

line-feed is assigned to the following keys, depending on the workstation in use:

SUN Type 4 keyboard	Control-line-feed
SUN Type 5 keyboard	Control-AltGraph
IBM RS/6000	Control-Right-Alt
SiliconGraphics	Control-Right-Alt
DecStations	Control-PF3
DecStations with PC keyboards	Control-Right-Alt
HP	Control-Select
HP with PC keyboards	Control-Right-Alt
ASCII terminals	Control-l
Windows systems	Control-Right-Alt

The LINEND command is a synonym to the SEP command.

Examples:

sep on ; sets the separator to ";".
top;c /i/j/ changes every "i" to "j" from the beginning of
the file.

See Also: LINEND

SEt - Set Function Keys

Batch Mode: Not Available

First Mode:

SET		PFk { {keyword} string}
	<pre> {modifier}</pre>	Fk
	<pre> {modifier}</pre>	Rk
	<pre> {modifier}</pre>	SymbName
	<pre> {modifier}</pre>	Lk
	<pre> {modifier}</pre>	enter
		^cc
		M-cc
SET	?	

The first mode is used to assign a function key to a string which is executed as a command when this key is pressed.

When used without string, it will clear the key definition.

modifier may be one of the following:

S-	specifies that the Shift key must be held down.
C-	specifies that the Control key must be held down.
m–	specifies that the Meta key must be held down.
	The Meta key is labelled Left or Right on old Sun type 3
	keyboards, and \diamond on the Sun type 4 or type 5 keyboards.
	On DECstations, the meta key is the Compose key.
	On HP keyboards, the meta key is the Left Extend Char key.
	On most other keyboards, the meta key is the left Alt key.
s+c-	specifies that the Shift and the Control keys must be held down
	down.
s+m-	specifies that the Shift and the Meta keys must be held down.
m+c-	specifies that the Meta and the Control keys must be held
	down.
s+m+c-	specifies that the Shift, Control and Meta keys must be
	held down

Note: when specifying several modifiers, the order is irrelevant. set s+c-fl is the same as set c+s-fl.
SymbName may be one of the following:

UpArrow	specifies the up arrow key. UpArrow is internally changed to R8.
DownArrow	specifies the down arrow key. DownArrow is internally changed to R14.
LeftArrow	specifies the left arrow key. LeftArrow is internally changed to R10.
RightArrow	specifies the right arrow key. RightArrow is internally changed to R12.
Home	specifies the key labelled Home on PC-like keyboards. The corresponding Ri value depends on the platform.
End	specifies the key labelled End on PC-like keyboards. The corresponding Ri value depends on the platform. End is not available with DEC/COMPAQ/HP ALPHA TRUE64 keyboards.
PrintScreen	specifies the key labelled PrintScreen on PC-like keyboards. PrintScreen is internally changed to R1.
ScrollLock	specifies the key labelled ScrollLock on PC-like keyboards. ScrollLock is internally changed to R2.
Pause	specifies the key labelled Pause on PC-like keyboards. Pause is internally changed to R3.

Note: SymbName is not case sensitive. uparrow is the same as UpArrow.

With the SET command, the separator defined with the <u>SEP</u> or <u>LINEND</u> command is disabled, which allows the user to program several commands on the same key.

PFk means a 3270 equivalent PF key function.

PF1 – PF9 are mapped to F1 – F9 top keys.

PF10 - PF12 are mapped to R1 - R3 Sun right keys with the old Sun 9 top keys keyboard, and to F10 - F12 top keys with the other keyboards. The user must use the KEYBOARD . 1 command in its profile.sedit or PROFILE.sedit file to specify the old keyboard.

PF13 – PF24 are the same as PF1 – PF12 with the shift key held down.

PF25 – PF36 are the same as PF1 – PF12 with the control key held down.

PF37 – PF48 are the same as PF1 – PF12 with the meta key held down.

R1 – R15 are Sun right keys.

L1 – L10 are Sun left keys. L11 is the Sun HELP key.

The Left function keys are the following keys:

•	L1	Stop
•	L2	Again
•	L3	Props
•	L4	Undo
•	L5	Front
•	L6	Copy
•	L7	Open
•	L8	Paste
•	L9	Find
•	L10	Cut
•	L11	Help

On IBM, SiliconGraphics and HP PC-like keyboards, and on **WINDOWS** systems, the right keys are mapped in the following way:

•	R1	Print Screen
•	R2	Scroll Lock
•	R3	Pause
•	R4	Insert
•	R5	Home
•	R6	Page Up
•	R7	End
•	R8	Up Arrow
•	R9	Page Down
•	R10	Left Arrow
•	R12	Right Arrow
•	R14	Down Arrow

With the following physical layout:

R1	R2	R3	
R4	R5	R6	
	R7	R9	

On HP keyboards, the right and left keys are mapped in the following way:

•	L1	Reset
•	L2	Stop
•	L3	Menu
•	L4	User
•	L6	Print
•	R1	Clear
•	R2	Clear Display
•	R3	Insert Line
•	R4	Delete Line
•	R5	Insert Char
•	R6	Delete Char
•	R7	R
•	R9	Prev
•	R11	Next
•	R13	Numerical Pad Tab Key

With the following physical layout:

L1 L2	F1 F2 F3 F4	L3 L4	F5 F6 F7 F8	R1 R2
				R3 R4
				R5 R6
				R7 R9
				R11
L6				

•	R4	Find
•	R5	Insert Here
•	R6	Select
•	R7	Previous screen
•	R9	Next screen
•	L1	PF1
•	L2	PF2
•	L3	PF3
•	L4	PF4

On DECstation keyboards, the mapping is the following

With the following physical layout:



The user can specify a shift, control or meta condition by adding a "S-", "C-" or "M-" prefix to the Rk or Lk definition.

- ^cc sets "Control-cc", where cc is any character. However, when running in ASCII terminal mode, the user can only use characters ranging from 'a' to 'z', with the exceptions described below.
- M-cc sets "Meta-cc", where cc is any character. This facility is not supported on ASCII terminals.
- ? or no argument at all displays the key setting in a fullscreen manner.

The user can edit them directly. Once edited, the user must first depress the Enter or Return key to validate the changes, and then return to the editor by depressing the F1 key.

Depressing the F2 key adds a setkey.sedit file in the editing ring, containing all the key definitions and all the other editor settings.

When running in ASCII terminal mode, the following restrictions apply:

- It is not possible to know the "shift", "control" and "meta" key state. Therefore, it is not possible to assign a specific command to function keys when holding down these modifier keys. For example, "set s-f1 flquit" will not make SEDIT call the "flquit" command when hitting "shift-f1". For the same reason, "set ^A command" will not be recognized. Only "set ^a command" will be.
- The following "^cc" keys cannot be changed:
 - ^t enters the tab character (instead of ^tab).
 - ^i enters the next-field 3270 command.
 - ^j enters the up-field 3270 command.
 - ^f enters the down-field 3270 command.
 - ^h enters a backspace.
 - ^l enters the line-feed separator character.
 - ^m is equivalent to the Return or Enter key.
- "set M-cc" is not supported.

Examples: set pf15 cn /i/il/

set s-f3 cn /i/il/

set m-r4 ∖i

```
set ^q /i.del (.means "line-feed" separator)
Control-q will search and delete the next line containing "i"
character. Note that an error condition (like not finding "i") will stop the
process.
```

set ^Q QQUIT Shift-Control-q	will quit the current file, even if modified.
set c-r12 c_endl	Control-Right-Arrow moves the cursor to the end of the line.
set s-r8 top	Shift-Up-Arrow selects the first line as the current line.
set s-uparrow top	is the same as set s-r8 top
set m-r14 bot	Meta-Down-Arrow selects the last line as the current line.
set m-a s set all	Meta-a selects all of the current file.

Note: When the ENTER key is defined, by using the SET ENTER command, the auto-indentation is disabled. See the AUTOI command on page 155 for more details.

Second Mode:

SF

ET 	HOME IHOME PREV_FIELD INS CAPS APL DOWN_FIELD	 {S-} {C-} {M-} {S-} {C-} {M-} {S-} {C-} {M-} {S-} {C-} {M-} {S-} {C-} {M-}	PFk Fk Rk Lk SymbName ALT LF
İ	DOWN_FIELD		\mathbf{LF}
	UP_FIELD FOF		ESCAPE
I	101		66

The second mode is used to modify the 3270 simulation keys.

SymbName is described on page 385.

ALT is the key labelled Alt on Sun keyboards, the right Extend Char key on HP keyboards, and the right Control key on other workstations.

LF is the key labelled Line Feed on Sun keyboards, the Select key on HP keyboards, and the right Alt key on other workstations.

ESCAPE is the Esc key.

^cc sets "Control-cc", where cc is any character between 'a' and 'z'.

For a Sun workstation, the original setting is:

HOME	Rб
IHOME	R9
PREV_FIELD	R7
INS	R11
CAPS	R13
APL	R15
DOWN_FIELD	ALT
UP_FIELD	\mathbf{LF}
EOF	LЗ

See The 3270 Screen Interface on page 41 for a full 3270 functions description.

Note: with non-US keyboards, it is necessary to remove the default right ALT key "down_field" assignment. This is achieved by adding in the profile the "set down_field" command after the architecture dependent "set_xxx" keyboard setting macro has been called. On IBM stations for example, the keyboard setting macro is "set_ibm".

Examples:	set APL	disables the R15 APL key
	set HOME R6	sets the 3270 HOME command to key R6
	set HOME set R6 CURSOR HOME	sets the SEDIT CURSOR HOME command to
		R6

Third Mode:

SET BACKSPACE ^h | ^?

Depending on the ASCII terminal in use, the BackSpace key may send either the ^h or the ^? character.

By default, **SEDIT** recognizes the ^h character as the BackSpace character, and ^? as the Delete character.

Issuing the "SET BACKSPACE ^?" command reverses its behavior.

If a terminal such as this is in use, edit the "/home/xed/profile.sedit" macro, and add the following bold-faced line:

```
if version = 'curses' then
do
    if $TERM = 'MyTerminal' then 'set backspace ^?'
```

```
SET SERVER serv
```

When running the **MOTIF** version, this command allows the user to start **SEDIT** on a particular workstation (for example an IBM workstation), and to display it on another one (for example a DEC workstation) using the -display hostname:0 option, letting **SEDIT** know about the peculiarities of the remote server.

serv may be one of the following:

Display Workstation	serv value
Sun Sparc	sun
PC with Solaris X86	i86pc
SiliconGraphics	sgi
Ultrix DecStation	dec
Digital Unix TRUE64 DecStation	alpha
Digital Unix TRUE64 DecStation with a PC key- board	alphapc
IBM RS/6000	ibm
Hewlett Packard	hp
Hewlett Packard with a PC keyboard	hppc
PC with Linux	linux
PC with SCO	SCO
PC with Unixware	unixware

Display Workstation	serv value
Siemens	siemens

SET NBKEYS nb_left nb_top nb_right

This command makes **SEDIT** aware of the real number of left, top and right keys, so it can handle the shift, control and meta modifiers properly.

The macros /home/xed/xmac/set_xxxx use these 3 SET commands, so the user should never have to worry about them. Just use set_dec to display on a DEC/COMPAQ/HP, set_ibm to display on an IBM, and so on.

Fourth Mode:

Within the IBM **XEDIT** editor, the SET command allows the user to set various editing modes, such as the verify mode, by typing, for example, "set verify 1 3" instead of "verify 1 3".

The **SEDIT** SET command allows the prefix SET as well in order to maintain strict compatibility with **XEDIT**.

See Also: <u>METAKEY</u>, <u>XTESTCHARS</u>

SETEnv - Set Environment Variable

SETEnv var {expr} sets the environment variable var to the value expr.

Without expr, SETENV sets the environment variable var to an empty (null) value.

See Also: <u>UNSETENV</u>

SETP - Set Display String

SETP {string} will display string at the last window line every time **SEDIT** pauses.

Batch Mode: Not Available

This command is intended to be used in the "profile.sedit" macro when the original key setting is modified.

If string contains the "\n" line separator, it will be split into several lines according to the number of separators.

When string is omitted, the last window line is returned to the editor.

Examples: setp "1:Q 2:Ne 3:S 4:Sp" displays one help line.

setp "1:Q 2:Ne 3:S 4:Sp\n6:cu 7:U 8:D 9:? 10:H"
displays two help lines.

setp frees the last window line.

SHAdow - Set Selective Editing Display Mode

SHAdow {ON | OFF} Initial value: ON Level: View sets the way **SEDIT** displays excluded lines.

Each line in the file has a number associated with it, called its selection level which is set to zero by default and may be modified by the commands ALL and SELECT, and by the prefix commands X and S. When a line selection level does not fall in the DISPLAY range, it will not be displayed.

With SHADOW ON, **SEDIT** will display a shadow line to represent each group of excluded lines. With SHADOW OFF, **SEDIT** will not display these lines.

With no argument, SHADOW will display the current setting.

See Also: <u>All</u>, <u>DISPLAY</u>, <u>SELECT</u>, <u>SCOPE</u>

SHBlank - Show Last Trailing Blank

SHBlank ON OFF disables or enables the last trailing blank display.

Initial value: ON Level: Global

By default, **SEDIT** removes all trailing blanks in every line when loading a file, when editing a line and when saving a file. The KEEPBLANKS, BINARY, XKB and XBIN commands allow the user to edit a file without removing trailing blanks.

When SHBLANK is ON, and when not working in character mode, **SEDIT** flags the last trailing blank position displaying a thin vertical bar after that blank.

Note: KEEPBLANKS ON is not sufficient to preserve binary files integrity. Use BINARY ON or XBIN instead.

See Also: AUTOBIN, BINARY, KEEPBLANKS, XBIN, XKB

SHEll command to the operating system for execution.

If command ends with a "&", command will be placed in the background¹. Otherwise, command will execute in the foreground, and **SEDIT** will wait until command ends.

When running in the foreground, command can be interrupted by typing ^c.

On **UNIX** systems, the command is processed by the /bin/sh default shell.

On **WINDOWS** systems, the command is processed directly by the operating system. SHELL is a synonym to the WINDOWS command.

Example: shell lpr \$name & will print the current UNIX file.

See Also: <u>IMPCMSCP</u>, <u>WINDOWS</u>, <u>XSHELL</u>

^{1.} This facility is not available on ASCII terminals, since the command output would overwrite the **SEDIT** screen.

SHift - Shift Lines

```
SHift Left|Right {cols {target}}
Scope: Display
```

SHIFT allows the user to shift data to the left, or to the right. SHIFT affects text from the left zone column.

cols specifies the number of columns the data is to be shifted. When omitted, a value of 1 is assumed.

target defines the number of lines to be shifted. Lines are shifted starting with the current line, up to but not including the target line. target may be one of the following:

:N	Up to but not including the Nth line.
N or +N	N lines.
-N	Up N lines.
+* or *	The end of file.
_ *	The top of file.
.symb	The line which has been assigned the .symb symbolic name by using the POINT command, or a .symb prefix command.
string expression	Defines a group of characters to be located.

The general format of a string expression is the following:

 $\{+|-\}\{-\}/string1\{/\{\&\}|\{|\}\{-\}/string2 \dots\}$

See the <u>LOCATE</u> command on page 300 for a precise string expression definition. If target is omitted, a value of 1 is assumed.

The <, <<, > and >> prefix commands may be used for the same purpose.

Examples: shift 1 shifts one line. sh r 3 /main shifts all lines up to the line containing the main string.

See Also: <u>STAY</u>, <u>ZONE</u>

SHOw - Global Selective Line Editing

SHOw { target }

selects the hidden lines containing the target specified.

Scope: Display

SHOW scans the lines previously hidden by the ALL or the EXCLUDE commands, showing all the lines matching the target operand.

See the ALL command for a description of the target operand.

See Also: <u>ALL</u>, <u>EXCLUDE</u>

SHOWCdpath - Displays the Accessed Directories

SHOWCdpath

SHOWCDPATH displays the directories in the cdpath.

SHOWCDPATH could display for example:

/home/ml/ | /home/ /usr/ | /home/xed/

See Also: <u>DACCESS</u>, <u>DRELEASE</u>

SHOWHistory - Show History

SHOWHistory

Shows history.

SHOWHISTORY displays the commands memorized in the history buffer.

This command is mapped to the M-F9 key by default.

See Also: XSHOWHISTORY, HISTORY, ?, ?I

SHOWPath - Displays the Accessed Directories

SHOWPath

SHOWPATH displays the directories in the path, together with their filemodes.

SHOWPATH could display for example:

```
a : /home | b : /usr/ucb | c : /usr/bin | d : /usr/lib
e : /etc | f : /usr/etc
```

See Also: <u>ACCESS</u>, <u>FLIST</u>, <u>RELEASE</u>

SOrt - Sort a File

```
SOrt target {{Ascending|Descending} n1 m1} .....
sorts the current file.
```

Scope: DISPLAY

target indicates what lines will be sorted. It can be entered in the following ways:

•	∶n	will sort from the current line up to but not including th	ne line n.
---	----	--	------------

- n will sort n lines starting at the current line.
- * will sort all the lines starting at the current line
- All will sort the entire file. This is the default if no target is specified.
- Sel will sort the selected lines. If the selection is rectangular, the columns to be sorted will be that of the selection, the only extra parameter allowed being ASCENDING or DESCENDING.

The columns to be sorted will be determined by the {ni mi} pairs. If omitted, the current zone setting will used. If mi is an asterisk ("*"), the right zone column will be used. There can be any number of sort fields.

The sort fields may be preceded with ASCENDING or DESCENDING which indicates the order in which to sort the field, and all subsequent fields, until another ASCENDING or DESCENDING parameter is encountered.

The default is sorting in ascending order.

Examples:	sort							
	sort	*	а	1	12	d	18	*
	sort	S	d	13	*			

If CASE SIGNORE is in effect, **SEDIT** will not consider capitalization when the SORT command is applied.

Example: case si sort *

will sort the current file ignoring capitalization.

will sort all the file.

See Also: <u>ALL</u>, <u>CASE</u>

SORTRing - Sort the Ring

SORTRing

sorts the ring.

The files in the ring are normally displayed in the order they have been loaded. SORTRING displays the files in alphabetical order.

SOS - Screen Operation Simulation

SOS Alarm BAckspace CLEAR INSert ON|OFf|Toggle string INPut LINEAdd LINEDel TABB {N} TABCmd {N} TABCMDB TABCMDF $\{N\}$ TABF $\{N\}$

Batch Mode: Not Available

SOS Alarm

sounds the terminal bell the next time the screen is refreshed.

SOS BAckspace

moves the cursor as the BACKSPACE key would do.

SOS CLEAR

clears and redraws the screen. This is a synonym for the REFRESH CLEAR command.

- SOS INSert ON | OFF | TOGGLE sets the INSERT mode ON or OFF immediately. SOS TOGGLE will toggle the INSERT mode only when all characters entered with a previous SOS INPUT command have been processed.
- SOS INPut string inserts string at the cursor location.
- SOS LINEAdd adds a line below the cursor location. This is a synonym for the C_LINEADD command.
- SOS LINEDel

deletes the line at the cursor location. This is a synonym for the C_LINEDEL command.

SOS TABB $\{N\}$

moves the cursor as if the PREV_FIELD key had been depressed N times. If not specified, N assumes the value of one.

SOS TABCmd

sets the cursor at the command field for the screen in which it currently resides.

SOS TABCMDB $\{N\}$

sets the cursor to the N previously encountered command field. Useful to switch to a different screen within a macro and pass a command into that screen. If not specified, N assumes the value of one.

SOS TABCMDF $\{N\}$

sets the cursor to the N following encountered command field. Useful to switch to a different screen within a macro and pass a command to that screen. If not specified, N assumes the value of one.

SOS TABF $\{N\}$

moves the cursor as if the NEXT_FIELD key had been depressed N times. If not specified, N assumes the value of one.

See Also: <u>C_LINEADD</u>, <u>C_LINEDEL</u>, <u>REFRESH</u>

Page 402

SPAN - Multiple Lines Search

```
SPAN ON|OFF {Blank|Noblank {N|*}}
Initial value: OFF BLANK 2
Level: File
```

SPAN ON specifies that during a search, N lines are to be concatenated, allowing **SEDIT** to find a string starting on one line, and ending on the following lines.

SPAN OFF specifies that a character string must be included on the same line in order to be found.

When a truncation column has been specified with the <u>TRUNC</u> command, lines are padded with blanks in order to match the truncation length. Otherwise, trailing blanks are deleted before concatenation.

BLANK specifies that one more additional blank character is inserted between consecutive lines.

NOBLANK specifies that no additional blank character is inserted between consecutive lines.

N specifies the number of lines that a string can span. If specified as *, the rest of the file is searched.

When the searched columns are restricted with the \underline{ZONE} command, only the portion of lines defined by the \underline{ZONE} values are concatenated.

Return Codes:0Normal5Invalid Operand

See Also: LOCATE, ZONE

SPELL - Spelling Checker

SPELL

checks the current file for spelling errors.

Scope: ALL Available on: UNIX Batch Mode: Not Available

SPELL looks for the sedit_spell script file first in the current directory, then in the home directory and finally in the installation directory.

This script looks for an sedit.dictionary private dictionary in the same set of directories, and then calls the **UNIX** SPELL command, using this private dictionary when found.

Then, **SEDIT** highlights in reverse video the first misspelled word, and places the cursor on it.

The user may then type the correction. Remember that typing on selected characters deletes them and sets the keyboard in insert mode.

After correction, the user may use the SPELL_NEXT command to look for the next misspelled word, or the SPELL_ADD command to add this word to the private dictionary.

The **SEDIT** main menu "SPELL" item creates 3 buttons with the 3 spelling commands.

See Also: <u>SPELL ADD</u>, <u>SPELL NEXT</u>

<u>SPELL_Add - Update Private Dictionary</u>

SPELL_Add {ff}

adds the current misspelled word to a private dictionary.

Available on: UNIX Batch Mode: Not Available

SPELL_ADD looks for the ff file first in the current directory, then in the home directory and finally in the installation directory.

If ff is not specified, it will be set to sedit.dictionary.

Then, the current misspelled word will be added to the ff file, and ff will be sorted for a proper subsequent use with the SPELL command¹.

See Also: <u>SPELL</u>, <u>SPELL NEXT</u>

^{1.} Some UNIX SPELL commands (SiliconGraphics for instance) do not allow private dictionary use.

SPELL_Next - Search for Next Misspelled Word

SPELL_Next

displays the next misspelled word in reverse video and sets the cursor on it.

Available on: UNIX Batch Mode: Not Available

The user may then type the correction. Remember that typing on selected characters deletes them and sets the keyboard in insert mode.

See Also: SPELL, SPELL ADD

SPLTJOIN - Split/Join Lines

SPLTJOIN {<u>Stay</u>|Nostay}

when the cursor is before the last non-blank character, the line will be split, with indentation if the auto-indent feature is on. When the cursor is after the last non-blank character, the next line will be joined to the current location.

Scope: Display

If NOSTAY is specified, the cursor is moved to the new line with proper indentation. Otherwise, the cursor remains at the same location.

See Also: <u>AUTOI</u>, <u>C SPLIT</u>

SRChange - Selective Regular Expression Change

SRChange	$/regex/string{/{target {N *} {P}}}$		
	changes the regular expression regex with string asking for confirmation at each occurrence.		
Scope: Batch Mode:	Display Not Available		

/ may be replaced with any delimiting character that does not appear in the character strings involved in the replacement.

A regular expression is a character string used to describe, in an extended way, a string to be matched. It uses special characters, called meta characters to describe the match to be done. See the \underline{R} command on page 363 for a complete description of regular expressions.

target defines the number of lines to be scanned for a match. Lines are changed starting with the current line, up to but not including the target line. target may be one of the following:

:N	Up to but not including the Nth line.
N or +N	N lines.
+* or *	The end of file.
.symb	The line which has been assigned the .symb symbolic name by using the POINT command, or a .symb prefix command.
string expression	Defines a group of characters to be located.

The general format of a string expression is the following:

{+|-}{~}/string1{/{&}|{|}{~}/string2}

See the **LOCATE** command on page 300 for a precise string expression definition.

When target is omitted, all lines between the current line and the end of file will be scanned. However, if MODE CHANGE ONE is in effect, only the first line will be changed.

N is the number of occurrences of regex to be changed on each line.

If omitted, all occurrences of regex will be changed. However, if <u>MODE</u> CHANGE ONE is in effect, only the first occurrence will be changed.

If specified as *, all occurrences of regex will be changed.

P is the relative number of the first occurrence of string to be changed in each line. Its default value is 1.

When regex is omitted, string is inserted in the column which value is defined by the first <u>ZONE</u> command operand (initially 1).

Every time regex is found, **SEDIT** will pause.

Pressing the F12 key will make the change and the command will resume execution.

Pressing F1 will terminate the command.

Pressing Control-F12 will make all of the requested changes asked for without pausing again.

Pressing any other key will proceed to the next occurrence of regex without processing a change.

During a pause, the last window line will indicate the above key's definition. All fields will be turned into output fields, preventing any typing in them, and the "undo" feature will be disabled.

When ARBCHAR is ON, all occurrences of the arbitrary character in string will be changed with the string matching regex.

Examples:	<pre>src/[0-9]/?/</pre>	will turn every number into a ?		
	arbchar on @			
	src/[a-z]/(@)/**	will enclose every lowercase alphabetical		
		character within parenthesis.		

If CASE CIGNORE is in effect, **SEDIT** will not consider capitalization when changing strings.

Notes: The <u>ZONE</u> command allows the user to choose the starting and ending columns to be scanned.

The <u>SCKEYS</u> command allows the user to modify the confirmation keys.

See Also: <u>ARBCHAR</u>, <u>CASE</u>, <u>CHANGE</u>, <u>CN</u>, <u>HEX</u>, <u>LOCATE</u>, <u>MODE</u>, <u>RCHANGE</u>, <u>SCHANGE</u>, <u>SCKEYS</u>, <u>SCN</u>, <u>STAY</u>, <u>ZONE</u>

STAck - Stack Lines

STAck {target {col {len|*}}}
Scope: Display

STACK allows the user to place the lines starting at the current line up to the line specified by target in the S/REXX stack. **S/REXX** can retrieve these lines by using the PARSE PULL instruction.

target defines the number of lines to be stacked. Lines are stacked starting with the current line, up to but not including the target line. target may be one of the following:

:N	Up to but not including the Nth line.
N or +N	N lines.
-N	Up N lines.
+* or *	The end of file.
_ *	The top of file.
.symb	The line which has been assigned the .symb symbolic name by using the POINT command, or a .symb prefix command.
string expression	Defines a group of characters to be located.

The general format of a string expression is the following:

 $\{+|-\}\{-\}/string1\{/\{\&\}|\{|\}\{-\}/string2 \dots\}$

See the **LOCATE** command on page 300 for a precise string expression definition.

If target is omitted, a value of 1 is assumed.

cols specifies the starting column to be stacked. When omitted, a value of 1 is assumed.

len specifies the number of columns to be stacked. When specified as *, or when not specified, the line will be stacked up to the last non-blank character.

In any case, the last stacked column is less or equal to the truncation column defined by the LRECL command.

Example: stack*5 20

See Also: LRECL

STAMpdelay - Discrepancy Reload Setting

STAMpdelay	root time	sets the allowed discrepancy for the auto-reload feature.
STAMpdelay	Off	removes all time stamp delays.
STAMpdelay		displays the current time stamp delays.
Initial value: Level:	Not Set Global	

When RELOAD is set to ON, **SEDIT** checks all the currently loaded files under the following circumstances:

- When **SEDIT** loses the keyboard focus, and then receives it again.
- When the user switches from one file to another.
- When the user loads a new file.

If **SEDIT** determines that a file has been externally modified, **SEDIT** saves the previous image of the file that it had loaded into memory (after appending to its name the % character), and then reloads the newly modified file.

A file is determined to be modified when its time stamp is older than the time stamp **SEDIT** memorized when loading that file. With mounted file systems, especially between a **UNIX** system and a **WINDOWS** system when using a CIFS **UNIX** client like the SharityTM software, there may be a discrepancy between the time stamp memorized by **SEDIT**, and the actual time stamp on the **WINDOWS** file system. The STAMPDELAY command allows **SEDIT** to ignore a given amount of discrepancy between time stamps in order to avoid spurious reloads.

Examples: stampdelay /home.nt 8 stampdelay /home.nt4 8 SEDIT will accept an 8 seconds time stamp discrepancy before reloading any file starting with /home.nt or /home.nt4.

See Also: <u>RELOAD</u>

STATUS (Macro) - Displays All Settings

STATUS {filename} displays all the current settings, or creates a filename.sedit macro.

filename.sedit is an automatically generated macro which can be used to restore all the current settings.

See Also: <u>SET</u>

STAY - Current Line Move

STAY ON | OFF Initial value: OFF

When STAY is OFF, the current line becomes the Top Of File, or the End Of File, when a target search does not succeed after one of the following commands: <u>FIND</u>, <u>NFIND</u>, <u>FINDUP</u>, <u>NFINDUP</u> and <u>LOCATE</u>.

In addition, the last line examined or acted upon becomes the new current line for the following commands: <u>CHANGE</u>, <u>CN</u>, <u>SCHANGE</u>, <u>SCN</u>, <u>COUNT</u>, <u>LOWERCAS</u>, <u>UPPERCAS</u>, <u>SELECT</u> and <u>SHIFT</u>.

When STAY is ON, the pointer does not move.

STop - Set APL stop

STOP ON ALL OFF {FILE | SEL }

changes the stop setting for an APL function or operator.

Scope: Display

The first argument has the following meaning:

- ON will set a stop for every non-comment line.
- ALL will set a stop for every line.
- OFF will remove every stop.

The second optional argument has the following meaning:

•	FILE	will apply the changes to the entire function or operator. This is the default if omitted.
•	SEL	will apply the changes to the selected lines. See Using the Mouse on UNIX systems on page 123 for more details about making a linear or rectangular selection.
Example	es:	"stop on" will set a stop for every non-comment line. "stop all file" will set a stop for every line. "stop off sel" will remove every stop on the selected lines.

The prefix command field will be underlined when the stop is on.

STReam - Set Stream Status

STReam {ON | OFF}

When STREAM is ON, the entire file is searched for a column target in a <u>CDELETE</u> or a <u>CLOCATE</u> command.

When STREAM is OFF, only the current line is searched.

Without argument, STREAM displays the current status.

See Also: <u>CDELETE</u>, <u>CLOCATE</u>

SWitch - Switch Between Files

SWitch

allows the user to switch from one file to another in a circular sequence.

When the user switches to a file using the mouse or the command <u>XEDIT</u>, the file vacated acquires the highest priority so that the next SWITCH command returns the user to the file just vacated.

This command is mapped to the F5 key by default.

When the user is editing multiple files, using F5 and Shift-F5 will toggle between two of them without visiting others.

See Also: <u>ISWITCH</u>, <u>XEDIT</u>

SYNonym - Set a Synonym

SYNonym ON | OFf SYNonym {LINEND cc} alias {N} cmd SYNonym CLEAR alias Query SYNonym name Query SYNonym * *Initial value:* ON synonym quit 4 command aquit

When SYNONYM is ON, **SEDIT** looks for the aliases defined by the second SYNONYM command format, where:

LINEND CC	specifies that the cc character acts as the command separator.
alias	is the synonym to the cmd command. cmd cannot be another synonym itself.
N	is the minimum alias abbreviation.
cmd	is the command to be entered when alias is used.
CLEAR	suppresses the alias definition. CLEAR must be entered in capital letters.

QUERY SYNONYM name displays the name synonym, its minimum abbreviation and everything else that was specified to specify that synonym. If name was not defined, only name is displayed.

QUERY SYNONYM * displays the same information for every defined synonym.

Examples:	syn linend ; deltop 4 top;del syn remove 3 del syn fx f * x
	syn CLEAR deltop
	q syn deltop displays:
	SYNONYM LINEND ; deltop delt top;del

A synonym can be overridden by using the COMMAND command.

See Also: <u>COMMAND</u>

SYNTax - Set Syntax Coloring

SYNTax ON	OFF	GON	GOFF
-----------	-----	-----	------

- SYNTax filename
- Initial value: ON GON Level: File and Global
 - SYNTAX GON | GOFF enables or disables syntax coloring on a global level.
 - SYNTAX ON | OFF enables or disables syntax coloring for the current file. Syntax coloring will be performed for a given file when both SYNTAX GON and SYNTAX ON for that file are in effect.
 - SYNTAX filename reads the filename file.

filename describes the way syntax coloring must be performed, and to which file. filename may contain the following items:

filetype ft1 {ft2 {ft3}}}

specifies that the syntax description applies to any file with a fti extension.

firstline w1 {w2 {w3}}}
specifies that the syntax description applies to any file which first line contains
any of the wi words.

- end specifies the end of a filetype of firstline bloc.
- string color stringtype

color specifies the color used to display strings. See the COLOR command on page 182 for a list of available colors.

stringtype may be one of the following:

c a C like string. Embedded quotes within a string must be prefixed with a backslash. A backslash must also be prefixed with a backslash.

Example: "abcde\"fgh\\ijk"

- rexx a REXX like string. Embedded quotes must be doubled. Example: "abcde" "fgh\ijk"
- fortran a FORTRAN like string. Embedded quotes within a C string must be prefixed with a backslash or doubled. A backslash must also be prefixed with a backslash. Example: "abcde\"fgh\\ijk""lmn"
- cobol a COBOL like string. Embedded quotes must be doubled. Example: "abcde" "fgh\ijk"

```
comment color commenttype
```

comment specifies the color used to display comments. See the COLOR command on page 182 for a list of available colors.

commenttype may be one of the following:

- C C and C++ like comments, delimited with /* and */, or starting with // until the end of the line.
- rexx
 REXX like comments, delimited with /* and */. Unlike C, the

 REXX language allows for nested comments, such as:

 /*
 /*
 */

S/REXX and **SEDIT** also treat a line starting with a # as a comment.

fortran FORTRAN like comments. A line starting with a d, D, c, C, * or a ! is a comment line. The end of line after a ! character found outside a string is also a

> comment. In addition, some FORTRAN compilers allow the use of the C preprocessor. Therefore, blocs delimited with /* and */ are also comments.

- sh **UNIX** shells like comments. The end of line after a # character found outside a string is a comment.
- latex LATEX like comments. The end of line after a % character is a comment.
- cobol COBOL like comments. A character other than a blank or a minus (-) on column 7 indicates a comment statement.
- keyword color kw1 {kw2 {kw3}}}
 specifies the color used to display the words kwi.

case ignore respect

case ignore specifies that the keywords are not case sensitive. case respect specifies that the keywords are case sensitive.

match color1 {color2 {color3}}}
specifies the colors used to match the {}, () and [] delimiters.

```
cpp color1 {color2 {color3 ....}}}
```

specifies the colors used to match the C preprocessor #if, #ifdef and #ifndef constructs with their #else and #endif counterpart.

Note: The colors used to display strings and comments must no be used within a keyword, match or cpp definition.

On **UNIX** systems, the /home/xed/syntax/reverse file is an example intended to be used when displaying in reverse video mode:

```
*
   C and C++ files
filetype c c++ h
  comment steelblue c
  string forestgreen c
  case respect
 keyword coral struct union auto extern register typedef
static sizeof break continue default entry goto if else for
do while switch case int char float double long short
unsigned enum void volatile return
 match maroon lemonchiffon red orchid deeppink lightcyan
rosybrown
            lightseagreen cyan
                                    sienna
                                             springgreen
lightgoldenrod sienna
      maroon lemonchiffon red orchid deeppink lightcyan
  CDD
rosybrown
            lightseagreen cyan
                                    sienna
                                             springgreen
lightgoldenrod sienna
end
*
* C-SHELL scripts
firstline csh sh ksh tcsh
  comment steelblue sh
  string forestgreen c
  case ignore
 keyword coral if then else do forever endif foreach end
case esac echo set
  match
          red
                blue maroon
                                lemonchiffon
                                               lightcyan
lightgoldenrod lightgoldenrodyellow lightseagreen orchid
rosybrown sienna springgreen
end
```

Note that some single long lines, such as the keyword lines, are displayed wrapped.

<u>S_COpy - Copy a Selection</u>

S_COpy {Replace | Add {str}} copies the selection or the str string into the internal buffer.

Without argument, the selection is copied into the internal buffer. See Copying the Selected Characters on page 124 for more details.

Replace str

The str string overlays the internal buffer.

Add str

The str string is added as a new line into the internal buffer.

 S_COPY is mapped to the L6 key on Sun workstations, and to the F3 key on other workstations.

On **WINDOWS** systems, S_COPY is mapped to ^c.

<u>S_CUt - Cut a Selection</u>

S_CUt

removes the selected characters.

See Deleting the Selected Characters on page 123 for more details.

This command is mapped to the L10 key on Sun workstations, and to the F2 key on other workstations.

On **WINDOWS** systems, S_CUT is mapped to ^x.

<u>S_Find - Find a Selection</u>

S_Find

searches for selected characters.

See Searching for Selected Characters on page 125 for more details.

This command is mapped to the L9, S-L9 and C-L9 keys on Sun workstations, and to the F1 key on other workstations.

If there is no current selection, S_FIND remembers the last selection.

On WINDOWS systems, S_FIND is mapped to F1.

See Also: CASE

<u>S_Help - Shows Help About a Selected Item</u>

S_Help starts editing the help file selected with the mouse. If the selection is one character wide, it will be expanded to the word. This command is mapped to the ^H key by default.

S_Lower - Translate Into Lowercase

S_Lower

translates the characters selected with the mouse into lowercase.

Scope: Display

This command is mapped to the *`l key by default*.

See Also: LOWERCAS

S_LShift - Shift Left from Selection

S_LShift {cols}

S_LShift considers the current selection. The text from the column where the selection starts will be moved to the left.

cols specifies the number of columns the data is to be shifted. When omitted, a value of 1 is assumed.

This command is mapped to the M-F7 key by default.

See Also: SHIFT, S RSHIFT

S_MAN - Display Selected UNIX Reference Manual Pages

S_MAN

displays the **UNIX** reference manual pages in the same format as the **UNIX** man command, according to the current selection.

If the selection is one character wide, it will be expanded to the word. If there is no current selection, the first word at or before the cursor position will be chosen.

S_MAN creates a new file word.man in the editing ring, where word is the selected or expanded word with spaces replaced by the _ underscore character.

If word.man already exists, it will be overridden.

This command is mapped to the X (Shift-Control-x) key by default.

See Also: MAN

S_Paste - Retrieve a Selection

S_Paste	{Insert Overlay} {Clipboard Shelf Primary} {line column}
	retrieves previously saved characters.
INSERT	specifies that the characters retrieved will be inserted on the screen. This is the default when no keyword is specified, and when the S_PASTE command is assigned to a non-shifted key, such as L8 or F4.
OVERLAY	specifies that the characters retrieved will overlay the characters on the screen. This is the default when no keyword is specified, and when the S_PASTE command is assigned to a shifted key, such as S-L8 or S-F4.
SHELF	specifies that the characters retrieved will be the characters saved by the S_COPY command into the <i>SHELF</i> . The <i>SHELF</i> is the standard cut and paste buffer used by OpenLook applications. This is the default when no keyword is specified, and when the S_PASTE command is assigned to a non-controlled key, such as L8 or F4.
CLIPBOARI	is a synonym to SHELF. The CLIPBOARD terminology is used with WINDOWS applications.
PRIMARY	specifies that the characters retrieved will be the characters currently selected with the mouse. This is the standard cut and paste buffer used by MOTIF applications. This is the default when no keyword is specified, and when the S_PASTE command is assigned to a controlled key, such as C-L8 or C-F4.
LINE COLU	JMN when LINE and COLUMN are not specified, S_PASTE inserts or overlays data at the cursor location. When LINE and COLUMN are specified, S_PASTE inserts or overlays data at the specified line and column.

See Copying the Selected Characters on page 124 for more details.

Examples: s_paste s_paste 3 80 s_paste c o 12 79

This command is mapped to the L8 key on Sun workstations, and to the F4 key on other **UNIX** workstations.

On **WINDOWS** systems, S_PASTE CLIPBOARD is mapped to the ^v key.
S_RShift - Shift Right from Selection

```
S_RShift {cols}
```

S_RShift considers the current selection. The text from the column where the selection starts will be moved to the right.

cols specifies the number of columns the data is to be shifted. When omitted, a value of 1 is assumed.

This command is mapped to the M-F8 key by default.

See Also: SHIFT, S LSHIFT

S_Set - Set Selection

| Of

S_Set is intended to be used within macros to set the primary selection. The character selected will be highlighted in reverse video. The parameters are the following:

Linear

The selection is a linear selection.

Rectangular

The selection is a rectangular selection.

Pending

The selection is a pending delete selection.

Nopending

The selection is not a pending delete selection.

line1

The first selection line relative to the file.

col1

The starting selection column.

line2

The last selection line.

col2

The last selection column. -1 or * means the complete line, including the virtual invisible "n" newline character.

All

All of the file will be selected.

Off

The current selection is cancelled.

See Using the Mouse on UNIX systems on page 123 or Using the Mouse on WINDOWS Systems on page 127 for more details about selections.

Examples:	s_set	all		
	s_set	l n 1	. 2	58
	s_set	l p 2	2 5	12 -1
	s_set	off		

<u>S_Upper - Translate into Uppercase</u>

S_Upper	{All Word}	translates the characters selected with the mouse into uppercase.
Scope:	Display	
All	specifies that the default w	all the selected characters are to be translated. ALL is hen no argument is specified.
Word	specifies that translated.	only the first character of each selected word is to be

S_UPPER ALL is mapped to the ^u key by default, and S_UPPER WORD is mapped to ^U (Shift+Control+u).

See Also: <u>UPPERCAS</u>

<u>S_Xed - Edit a Selected File</u>

S_Xed

starts editing the file selected with the mouse.

If the selection is one character wide, it will be expanded to the word and the currently edited file filetype will be appended to it.

On **UNIX** systems, S_XED is mapped to the ^x key.

On **WINDOWS** systems, S_XED is mapped to the ^X key.

TABExp - Expand Tabulations

TABExp {All | Notf} {File | Sel} {N}

expands the tabulations into spaces.

Scope: Display

The first optional argument has the following meaning:

- All will expand every tabulation with spaces. This is the default if omitted.
- Notf will expand every tabulation with spaces. However, the first tabulation will be kept. This feature is useful with files such as FORTRAN files where the first tabulation has a special meaning.

The second optional argument has the following meaning:

- File will apply the changes to the entire file. This is the default if omitted.
- Sel will apply the changes to the selected lines.

See Using the Mouse on UNIX systems on page 123 or Using the Mouse on WINDOWS Systems on page 127 for more details about making a linear or rectangular selection.

The third optional argument is the number of spaces required for an indentation. The default value is 8.

Examples: "tabe" will expand all tabulations for every line.

"tabe n s" will expand the selected lines keeping the first tabulation.

TABLine / TABLINE_Screen - Set Tabline

TABLine ON|OFF {line} Initial value: OFF 4 Level: File and View

TABLINE_Screen ON|OFF {line} Initial value: OFF 4 Level: View

SEDIT maintains a separate TABLINE setting for each file and each view of this file defined with the SCREEN command.

The TABLINE_SCREEN command updates the default TABLINE setting of the current view, which is applied to every newly loaded file.

The TABLINE command applies to the current file on the current view.

TABLINE selects the physical line to display the tabline.

With TABLINE ON in effect, **SEDIT** displays a tabline in the input field area, which shows the position of each tab column set by the TABSET command. If the tabline is set on the same location as the scale line, the tab information will also appear on the scale line.

line can be specified in three ways:

n +n			selects the line n of the view to display the current line, where the first line is line 1.
-n			selects the line n from the bottom of the view, where the last line is line -1.
M+n M-n			selects the line n lines above or below the middle line of the view.
Examples:	TABL TABL TABL TABL	ON ON ON OF E	2 -3 M F M+2

See Also: <u>SCALE</u>, <u>TABSET</u>

TABSet - Set Tabulations

TABSet n1 {n2 n3 ...} {Ft string} TABSet Incr n {Ft string} TABSet None

sets the tab columns.

Initial value: None Level: File

Usually, the TAB and R7 keys are used to switch from one input field to another. Using the TABSET command, the user may define fixed positions in the input DATA fields. Then, hitting the TAB or the R7 key will move the cursor from one tab position to the following or preceding one.

With the first form of the TABSET command, the user enters a list of tab columns. If Ft string is specified, this setting will become the default for every new file with a string filetype.

If Ft is *, this will become the default for every file.

If FT is a period, it will select files with no filetype. This setting is also applied to the current file, unless its filetype does not match Ft.

With the second form of the TABSET command, the user specifies an increment n and **SEDIT** sets tabs in column 1 and every n columns thereafter.

TABSET NONE will cancel all tab columns in every file.

Examples:	tabs 1 6 72 ft f	will set 3 tab columns for every * . f new file
	tabs i 8 ft *	will set a tab column every 8 spaces for every file.
	tabs n	will cancel all tab columns.
	tabs 1 12 20 ft .	will set 3 tab columns for every file with
	tabs 1 9 17	will set 3 tab columns for the current file only.

TOolbar - Set Toolbar

TOolbar	$\{ON OFf Switch\}$	
Initial value: Level:	OFF Global	
Available on: Batch Mode:	WINDOWS Not Available	

TOOLBAR ON displays the following toolbar:



which perform the following actions:

QUIT	abandons the file being edited if it has not been modified since last stored.
NEW	creates a blank new file in memory.
OPEN	displays the OPEN FILE dialog box.
SAVE	saves the current file.
FILE	saves and then abandons the current file.
CUT	removes the selected characters.
СОРҮ	copies the selection into the clipboard.
PASTE	retrieves previously saved characters.
PASTE OVERLAY	retrieves previously saved characters in overlay mode.
UPPER	translates the characters selected with the mouse into uppercase.
LOWER	translates the characters selected with the mouse into lowercase.
SHIFT LEFT	shifts to the left, according to the selection.
SHIFT RIGHT	shifts to the right, according to the selection.
PRINT	prints the contents of the current file, after displaying the PRINT dialog box.
UNDO	cancels the last file modification.
REDO	cancels the last undo operation.
FIND	searches for selected characters.
FIND UP	searches backward for selected characters
TOOLBAR OFF	removes the toolbar.
TOOLBAR SWITCH	toggles ON and OFF the toolbar.
TOOLBAR	without arguments displays the current toolbar status.

TOP - Top of File

TOP

selects the first line as the current line.

Scope: Display

This command is mapped to the Sun S-R2 (S-Scroll-Lock on other workstations) key.

TRAce - Set APL Trace

TRACE ON ALL OFF {FILE SEL}

changes trace setting for an APL function or operator.

Scope: Display

The first argument has the following meaning:

- ON will set a trace for every non-comment line.
- ALL will set a trace for every line.
- OFF will remove every trace.

The second optional argument has the following meaning:

•	FILE	will apply the changes to the entire function or operator. This is the default if omitted.
•	SEL	will apply the changes to the selected lines. See Using the Mouse on UNIX systems on page 123 or Using the Mouse on WINDOWS Systems on page 127 for more details about making a linear or rectangular selection.
Example	es:	"trace on" will set a trace for every non-comment line. "trace all file" will set a trace for every line. "trace off sel" will remove every trace on the selected lines.

The data field will be underlined when the trace is on.

Tree {dir} calls the tree editor.

Batch Mode: Not Available

This command is mapped to the **`**r key by default.

See The Tree Editor on page 475 for further explanations.

TREEScanlevel - Set TREE Scanning Level

TREEScanlevel {N}
Initial value: 0

When TREESCANLEVEL is set to 0 (the default), all the subdirectories belonging to the same filesystem as the top level filesystem are scanned.

Once the scan is over, **SEDIT** saves the result in a file named sedit.treemap in order to avoid initialization delay at the next call. If the directory layout is modified outside **SEDIT**, **TREE** is not automatically updated.

When TREESCANLEVEL is set to a positive value N, **TREE** ignores any sedit.treemap already existing. **TREE** rescans the disk at every call, to a depth of N subdirectories. Initialization time will be longer than TREESCANLEVEL equal 0, but the display is always accurate.

See Also: TREE

TRUnc - Set Truncation Column

```
TRUnc * |N \{FT string\} sets the truncation column.
```

Initial value: * Level: File

* specifies that no truncation is to take place.

N specifies the column at which truncation occurs.

If FT string is specified, this setting will become the default for every new file with a string filetype.

If FT is *, this will be the default for any file.

If FT is a period, it will concern files with no filetype. This setting is also applied to the current file, unless its filetype does not match FT.

Examples:	trunc	80	ft	f	will set the truncation column for FORTRAN files.
	trunc	*			
	trunc	92	ft	•	

See Also: LRECL

UNButton - Remove Button

UNButton {button}

removes button "button", or all buttons if "button" is omitted.

Available on: UNIX Batch Mode: Not Available

UNDo - Cancel Last File Modification

UNDo $\{ALL | N\}$

UNDO cancels the last file modification.

UNDO ALL cancels all the modifications.

UNDO 3 cancels the last 3 file modifications.

When SAVECLEARUNDO is set to ON (the default), the undo memory is reset every time the file is saved.

UNDO is mapped to the L4 key on Sun workstations, and to the F11 key on other workstations.

See Also: <u>REDO</u>, <u>SAVECLEARUNDO</u>

UNSetenv - Remove Environment Variable

UNSetenv var

removes variable var from the environment.

See Also: <u>SETENV</u>

UP- Scroll Up

Up $\{N \mid *\}$ scrolls up N lines.

Scope: Display

If N is omitted, a value of 1 is assumed. UP * makes the Top Of File the current line.

Return Codes:	0	Normal
	1	Top Of File Reached
	5	Invalid Operand

UPPercas - Translate Into Uppercase

UPPercas {target}

Scope: Display

target defines the number of lines to be translated into uppercase. Lines are translated starting with the current line, up to but not including the target line. target may be one of the following:

:N	Up to but not including the Nth line.
N or +N	N lines.
-N	Up N lines.
+* or *	The end of file.
_ *	The top of file.
.symb	The line which has been assigned the .symb symbolic name by using the POINT command, or a .symb prefix command.
string expression	Defines a group of characters to be located.

The general format of a string expression is the following:

{+|-}{~}/string1{/{&}|{|}{~}/string2 }

See the <u>LOCATE</u> command on page 300 for a precise string expression definition. If target is omitted, a value of 1 is assumed.

Examples:	upp	translates one line.
	upp:5	translates all lines up to line 4.
	uppercas*	translates the rest of the file.

See Also: <u>STAY</u>, <u>S UPPER</u>

VARblank - Ignore Successive Blanks

VARblank ON OFF

Initial value: OFF *Level:* FILE

When VARBLANK is set to ON, the number of blanks between strings does not matter in searching for a target.

Without parameters, VARBLANK displays its setting.

Example: /the mouse/ matches "the mouse"

Verify / VERIFY_Screen - Set Columns

Verify {{ON|OFF} {{Hex} start1 {end1}} {{Hex} start2 {end2}} {....}}
VERIFY defines the columns that are to be displayed on the current file on the current screen.

Initial value: 1 2147483647 Level: File and View

```
\label{eq:VERIFY_Screen} $$ {ON|OFF} { {Hex} start1 {end1} } { {Hex} start2 {end2} } { \dots } $$ {\dots } $} $$
```

VERIFY_SCREEN defines the default columns that are to be displayed for every newly loaded file on the current screen.

Initial value: 1 2147483647 Level: View

SEDIT maintains a separate VERIFY setting for each file and each view of this file defined with the <u>SCREEN</u> command.

The VERIFY_SCREEN command updates the default VERIFY setting of the current view, which is applied to every newly loaded file.

The VERIFY command applies to the current file on the current view.

ON and OFF have no special meaning within **SEDIT**. They are retained for XEDIT compatibility.

starti is the first column.

endi is the last column.

Hex displays the data in hexadecimal notation.

With no parameters at all, VERIFY displays the current setting.

If end1 is omitted, it will be set in such a way that the length to be displayed matches the data field length. This particular setting is useful with vertically split screens.

The commands "left 0" or "right 0" restore the original setting.

If start1 is negative, the length to be displayed will match the data field length every time a new view is created by splitting or unsplitting the screen, or when resizing the main window. In addition, it will enable the **SEDIT** fullshift feature described below.

When displaying data in hexadecimal notation, SEDIT does not allow the newline "OA" character to be typed in.

Examples:	" v 1 74" will set display columns from 1 to 74.
	"v" will display the setting "1 74".
	" $v -1$ " will enable the automatch feature when splitting the screen,
	and will enable the fullshift mode.
	"v" will display the setting "-1 74"
	"v 1" will set the setting to "1 74" if the screen is 80 columns wide,
	and cancel the automatch feature.
	"v 1 20 h 1 20" will display the columns from 1 to 20 in both ASCII
	and hexadecimal notation.
	"verify_s 1 79" sets the default VERIFY for every newly loaded file.

The FULLSHIFT Mode

When displaying a subset of the file columns, by using for example the v 1 command, the characters located outside of the screen are not affected by the Delete, Backspace or ERASE END OF FIELD keys.

When in fullshift mode, the invisible characters located on the right of the screen are erased by the ERASE END OF FIELD key, and shifted to the left by the Delete key, and by the Backspace key when in INSERT mode.

See Also: <u>LEFT</u>, <u>RIGHT</u>, SCALE, <u>C SCRH</u>, <u>C SCRJ</u>, <u>C SCRV</u>, <u>SCREEN</u>, <u>VERIFY SAVE</u>

VERIFY_Save / VERIFY_SSave / VERIFY_KSave

VERIFY_SAve / VERIFY_SSave / VERIFY_KSAve {fn {ft {fd}}}

These commands transform the unchanged source file into a backup file by appending a "%" to its name, and create a new file using the edited memory image and the VERIFY settings.

If the file name has been changed during the editing session so that it is identical to the name of an existing file, or if the file has been modified by another user, VERIFY_SAVE will ask for a confirmation before overwriting the existing file. VERIFY_SAVE will not.

The VERIFY_KSAVE command performs the same function as the VERIFY_SAVE command, but leaves the saved file timestamp unchanged. This may be useful, for example, when the modified file is an include file. Using VERIFY_KSAVE will prevent a following make command from recompiling every file which relies on the saved file.

If fn is specified, the filename of the file will be changed before saving.

If ft is specified, the filetype of the file will be changed before saving.

If fd is specified, the filedirectory of the file will be changed before saving.

VERIFY_SAVE does not heed the TRUNC, LRECL and KEEPBLANKS settings. If the second value of a pair of VERIFY column is *, VERIFY_SAVE will save from the first column up to the length of the line.

Example:	xed testfile verify 20 30 1 10 70 90
	verify_save testfile cols
	saves the columns 20 to 30, 1 to 10 and 70 to 90 in the testfile.cols file.
Warning:	Using VERIFY_SAVE without argument will overwrite the current file with a possibly truncated version of this file.

See Also: <u>VERIFY</u>

VIsible - Count Visible Lines

VIsible

Each line in the file has a number associated with it, called its selection level, which is set to zero by default. It may be modified by the commands ALL and SELECT, and by the prefix commands X and S. When a line selection level does not fall in the DISPLAY range, it will not be displayed.

VISIBLE displays the number of visible lines.

See Also: <u>All</u>, <u>DISPLAY</u>, <u>DY ALL</u>, <u>EXCLUDE</u>, <u>R/</u>, <u>SCOPE</u>, <u>SELECT</u>, <u>SHADOW</u>, <u>SHOW</u>

WIndows - Execute a WINDOWS Command

WIndows command transmits the string command to the operating system for execution.

If command ends with a "&", command will be placed in the background¹. Otherwise, command will execute in the foreground, and **SEDIT** will wait until command ends.

When running in the foreground, command can be interrupted by typing ^c.

On **WINDOWS** systems, the command is processed directly by the operating system. WINDOWS is a synonym to the SHELL command.

On UNIX systems, the command is processed by the /bin/sh default shell.

Examples: wi nmake&

starts the nmake program in the background.

See Also: <u>IMPCMSCP</u>, <u>MESSAGESDIR</u>, <u>SHELL</u>, <u>XSHELL</u>

^{1.} This facility is not available on **UNIX** ASCII terminals, since the command output would overwrite the **SEDIT** screen.

WRap - Wrap Around Feature

WRap ON OFF

sets the wrap around feature ON or OFF.

Initial value: ON Level: Global

When WRAP is set to ON, **SEDIT** continues the search up to the line preceding the current line within the / and R/ commands. The search is continued following the current line within the -/ and R-/ commands.

Within the CDELETE and CLOCATE commands, the search is continued up to the character preceding (or following) the column pointer.

When WRAP is set to OFF, the search ends at the end (of top) of file.

See Also: <u>CDELETE</u>, <u>CLOCATE</u>, <u>R/</u>, <u>R-/</u>, <u>/</u>, <u>-/</u>

XBin - Edit Binary Files

XBin {name {name2 {...}}}

starts editing the specified files in binary mode.

By default, **SEDIT** removes all trailing blanks in every line when loading a file, when editing a line and when saving a file. **SEDIT** also searches for the **WINDOWS** control characters ^M and ^Z, and automatically removes then from display setting the loaded file FILECONV to WINDOWS.

Trailing blanks are generally meaningless within text files, but may be essential within binary files. When BINARY is set to ON, **SEDIT** does not remove trailing blanks setting KEEPBLANKS to 1, does not check for the **WINDOWS** control characters and always sets the loaded file FILECONV to UNIX.

In addition, when not running in character mode, when SHBLANK is set to ON (the default), and when the last character in a line is a blank, **SEDIT** displays a thin vertical bar just after that last blank character.

See Also: AUTOBIN, FILECONV, BINARY, KEEPBLANKS, SHBLANK, XKB

XEDit - Edit New Files

XEDit {name {name2 {...}}} starts editing the specified files.

When name *i* is omitted, XEDIT switches from one edited file to another in a circular sequence.

If name *i* contains blanks, it must be surrounded with quotes or double quotes. If a file name contains a quote or a double quote, the quote must be escaped with a backslash.

If name *i* does not start with a directory indicator, like "/", "./", "~/" or "\" on **WINDOWS**, name *i* will first search in the current directory.

If not found, it will be searched for in the directories described by the environment variable XPATH, or PATH, or accessed with the <u>ACCESS</u> command.

There are some short-cuts to make editing another file easier.

When the user is editing a certain type of file, for example "test.c", and the user wants to edit another file of the same type, for example "test1.c", "x test1" may be typed instead of "xed test1.c".

Note "x test1.f" can be typed to override this "x" feature.

XED is required only if the user does not want to append any filetype.

There are also several abbreviations for the most frequent types of files:

"xc	test"	<===>	"xed	test.c"
"xf	test"	<===>	"xed	test.f"
"xp	test"	<===>	"xed	test.p"
"xh	test"	<===>	"xed	test.h"
"xt	test"	<===>	"xed	test.txt"
"xm	test"	<===>	"xed	test.mem"
"xx	test"	<===>	"xed	test.x"
"xi'	ı	<===>	"xed	.dbxinit"
"xe	test"	<===>	"xed	test.ex"
"xs	test"	<===>	"xed	test.sedit"

Notes: It is possible to limit the size of files to be edited by using the LIMIT command. Use XBIN to edit a binary file.

Use XBLANK to preserve and dsiplay trailing blanks.

Examples:	xed test.c x foo	now, edits foo.c
	x "a b" c d	edits 3 files. The first file name is "a b". Quotes are necessary.
	xed a\"b xed 'a"b'	edits the a "b file. does the same.

See Also: <u>ACCESS</u>, <u>FOLLOW</u>, <u>ISWITCH</u>, <u>LIMIT</u>, <u>SWITCH</u>, <u>XBIN</u>, <u>XKB</u>

XF - Edit an APL Object

{LINE} XF 'NAME' starts editing object 'NAME' at line 'LINE'

XF is an APL function supplied within the /home/xed/XF workspace able to edit any kind of APL object, but \Box OR object representation. The only restriction relates to the character \Box AV[0] which cannot be edited.

In the case of a nested array, or of an object with rank greater than two, the user will receive a two dimensional display representation, but the user will not be allowed to issue the "file" command to fix it in the active workspace.

The function XF maintains the date/time of the last modification in a variable named TSOBJ, and **SEDIT** displays this information in the first screen line.

LINE will become the current line. If omitted, it will assume the value of 0 for a function or an operator, and 1 for any other object.

As a shortcut, the command may be entered in the following way:

XF 'NAME' 3 instead of 3 XF 'NAME'

This may be useful if the string " XF ' " is assigned to some Fi key.

On Sun workstations, this can be done by inserting the "mapi F2 xf'" string in the " \sim /.ttyswrc" file before starting the APL shelltool.

When the state indicator is not empty, typing "XF''" will edit the currently stopped function.

XCSHell - Execute a Shell Command

XCSHell command

transmits the string command to the C-shell csh for execution, and displays the result within **SEDIT**.

Available on: UNIX Batch Mode: Not Available

XCSHELL creates a nnn.xshell file, where nnn is a number between 1 and the value set with the XSHELLMAX command (10 by default) chosen not to overwrite a previously created file when possible. The name of the last created file can be retrieved with the EXTRACT/<u>XSHELL</u> command.nnn.xshell exists only in the editing ring. The SAVE or FILE command must be used to save it to disk.

Example: xcsh ls -Ftla ~/foo

See Also: EXTRACT, MESSAGESDIR, SHELL, XSHELL, XSHELLMAX, XKSHELL

XKB - Edit Files with Trailing Blanks

```
XKB {name {name2 {...}}}
```

starts editing the specified files in KEEPBLANKS ON mode.

By default, **SEDIT** removes all trailing blanks in every line when loading a file, when editing a line and when saving a file.

Trailing blanks are generally meaningless within text files, but may be essential within data files. When KEEPBLANKS is set to ON, **SEDIT** does not remove trailing blanks setting KEEPBLANKS to 1.

In addition, when not running in character mode, when SHBLANK is set to ON (the default), and when the last character in a line is a blank, **SEDIT** displays a thin vertical bar just after that last blank character.

Notes: XKB is not sufficient to preserve binary files integrity. Use BINARY ON or XBIN instead.

See Also: <u>AUTOBIN, BINARY, KEEPBLANKS, SHBLANK, XBIN</u>

XKSHell - Execute a Shell Command

transmits the string command to the Korn shell ksh for execution, and displays the result within **SEDIT**.

Available on: UNIX Batch Mode: Not Available

XKSHELL creates a nnn.xshell file, where nnn is a number between 1 and the value set with the XSHELLMAX command (10 by default) chosen not to overwrite a previously created file when possible. The name of the last created file can be retrieved with the EXTRACT/<u>XSHELL</u> command.nnn.xshell exists only in the editing ring. The SAVE or FILE command must be used to save it to disk.

Example: xksh ls -Ftla ~/foo

See Also: EXTRACT, MESSAGESDIR, SHELL, XCSHELL, XSHELL, XSHELLMAX

XSHell - Execute a Shell Command

XSHell command

Batch Mode: Not Available

On **UNIX** systems, XSHELL transmits the string command to the Bourne shell sh for execution, and displays the result within **SEDIT**.

On **WINDOWS** systems, XSHELL executes the command directly.

XSHELL creates a nnn.xshell file, where nnn is a number between 1 and the value set with the XSHELLMAX command (10 by default) chosen not to overwrite a previously created file when possible. The name of the last created file can be retrieved with the EXTRACT/<u>XSHELL</u> command.nnn.xshell exists only in the editing ring. The SAVE or FILE command must be used to save it to disk.

Example: xsh ls -Ftla /usr/john/foo

Note: The Bourne shell does not allow the use of the ~ home directory meta character.

See Also: EXTRACT, MESSAGESDIR, SHELL, XCSHELL, XKSHELL, XSHELLMAX

XSHELLMax - Set Displayed XSHELL Files Limit

XSHELLMax {max}

sets the maximum number of nn.xshell displayed files.

Initial value: 10 Level: Global

The various XSHELL commands create a nnn.xshell file, where nnn is a number between 1 and max.

See Also: MESSAGESDIR, XCSHELL, XKSHELL, XSHELL

XSHOwhistory - Show History In Fullscreen Mode

XSHOwhistory

Shows history in fullscreen mode.

Batch Mode: Not Available

XSHOWHISTORY displays the commands memorized in the history buffer in fullscreen mode.

Clicking on a command with the first mouse button brings it in the command line. Shift-clicking with the first mouse button or clicking with the middle mouse button executes the command.

Moving the cursor in front of a command, using for example the TAB key, and pressing Enter or Return brings it in the command line.

This command is mapped to the Control-F9 key by default.

See Also: SHOWHISTORY, HISTORY, ?, ?I

XTESTChars - Set the Font Testing Mode

XTESTChars ON | OFF

Initial value:OFFLevel:GlobalAvailable on:UNIX

When XTESTCHARS is ON, **SEDIT** checks the width and the height of the character to be displayed. When either of these values is 0, **SEDIT** displays a quotation mark (?) instead of displaying the character. This allows the user to use X Windows fonts in which some characters are not defined.

However, on many X11 servers, the character size information is often wrong, misleading **SEDIT** to display quotation marks for valid characters.

When XTESTCHARS is OFF, **SEDIT** systematically displays quotation marks for characters with a decimal value of less than 32, and does not check the size information for characters above that value.

The set server xxxx command sets XTESTCHARS OFF.

Since the set_xxx keyboard macros used in the profile.sedit initialization file call the set server command, it is necessary to put the XTESTCHARS command behind these macros.

Example:

when arch = 'sun4' | arch = 'sun3' | arch = 'sparc' then do
 'set_sun_t5'
 if \$DISPLAY = "NCD:0" then 'xtestchars off'

This profile modification calls the XTESTCHARS command when a SUN is displaying on an X terminal which DISPLAY is NCD:0.

See Also: <u>SET SERVER</u>

Zone / ZONE_Screen - Set Zone

```
Zone {zone1 {zone2}}
Initial value: 1 2147483647
Level: File and View
```

```
ZONE_Screen {zone1 {zone2}}
Initial value: 1 2147483647
Level: View
```

SEDIT maintains a separate ZONE setting for each file and each view of this file defined with the <u>SCREEN</u> command.

The ZONE_SCREEN command updates the default ZONE setting of the current view, which is applied to every newly loaded file.

The ZONE command applies to the current file on the current view.

ZONE sets the zone to be searched by the commands "R/", "R-/", "/", "-/", "\", "-\", "CHANGE", "CN".

zone1 is the starting left column.

zone2 is the ending right column. When omitted, it assumes the value of 2147483647.

Without any argument, ZONE displays the current setting.

<u>\ - Locate a Name String</u>

 $\{string}{/}$

will search for the name string starting at the current line in descending order.

Scope: Display

The cursor will be moved to the beginning of the string.

The last / is optional, unless the string ends with a / or a space.

If string is omitted, $\$ remembers the string passed at the previous invocation.

Examples: \i will find "i" in "a=i" but not in "a=ij" \test/ \ searches again for the test name. \a=b/c/ \//

Note: The "zone" command allows the user to choose the starting and ending columns to be scanned.

These columns are also restricted by the <u>VERIFY</u> columns definition: the user can only scan the visible part of the file.

See Also: <u>ARBCHAR</u>, <u>CASE</u>, <u>MODE</u>, <u>VERIFY</u>, <u>ZONE</u>

-\ - Locate a Name String

 $- \{ string \} \{ / \}$

will search for the name string starting at the current line in ascending order.

Scope: Display

The cursor will be moved to the beginning of the string.

The last / is optional, unless the string ends with a / or a space.

If string is omitted, - remembers the string passed at the previous invocation.

Note: The "zone" command allows the user to choose the starting and ending columns to be scanned. These columns are also restricted by the <u>VERIFY</u> columns definition: the user can only scan the visible part of the file.

See Also: <u>ARBCHAR</u>, <u>CASE</u>, <u>MODE</u>, <u>VERIFY</u>, <u>ZONE</u>

? - Display Last Command

?

displays the last N commands in a circular sequence.

This command is mapped to the F9 key by default.

The length N of the history buffer can be changed with the <u>HISTORY</u> command described on page 287.

When <u>CMDLINE</u> is OFF, using the ? command restores the command line in order to let the user enter a command. Once the command is processed, the command line is removed.

When the command line contains one character, ? will only display the commands starting with this character.

See Also: <u>CMDLINE</u>, <u>HISTORY</u>, <u>SHOWHISTORY</u>, <u>XSHOWHISTORY</u>

<u><u><u>?I</u> - Display Last Command</u></u>

?I

displays the last N commands in a reversed circular way.

This command is mapped to the S-F9 key by default.

The length N of the history buffer can be changed with the HISTORY command described on page 287.

When CMDLINE is OFF, using the ?I command restores the command line in order to let the user pass a command. Once the command is processed, the command line is removed.

When the command line contains one character, ? I will only display the commands starting with this character.

See Also: <u>CMDLINE</u>, <u>HISTORY</u>, <u>SHOWHISTORY</u>, <u>XSHOWHISTORY</u>

= - Repeat Last Command

repeats the last command without displaying it.
 set = string the next time = is used, string will be executed.
 = is mapped to the F12 key by default.
 When cmd is specified, cmd is executed before the = action is taken.
 Example: add adds a line.
 =: 3 adds a line after the line 3.

<u># - Comments</u>

#

starts a comment line; useful in macro files.

SEDIT Text Formatting Facilities

Margins

The miscellaneous text formatting commands use the margins set with the <u>MARGINS</u> command described on page 307.

MARGINS 2 72 +4

sets the left margin to 2 and the right margin to 72. The first line of every paragraph will begin on column 6.

The margin settings are file specific. The default margin values are set to 1 72 +0.

In order to modify the default margins, the user may use the reprofile.ex or reprofile.sedit initialization macro which is executed every time a file is loaded.

For example, to set the default margins to 2 75 +3 for every *.doc document, the user could use the following **S/REXX** reprofile.sedit macro:

```
'extract /ftype'
if ftype.1 = '.doc' then 'margins 2 75 +3'
```

Formatting Text

The <u>FORMAT</u> command described on page 273 specifies the way the <u>FLOW</u> command described on page 269 identifies and formats paragraphs.

FLOW is assigned by default to the Shift-Control-F (^F) key.

When pressing ^F, the first word of the paragraph is placed at the paragraph indent column, and the rest of the paragraph is placed to fit the left and right margins. If specified with the FORMAT command, the text will be justified.

The <u>CENTER</u> command described on page 166 centers a line of text between the left and right margins.

The <u>LEFTADJUST</u> (^L) command described on page 296 positions a line of text at the left margin.

The <u>RIGHTADJUST</u> (^R) command described on page 362 positions a line of text at the right margin.

Wordwrap Feature

When <u>POWERINPUT</u> is ON and the cursor reaches the end of a line, a new line is automatically created, the last word of the cursor line is moved to the new line and the cursor is moved to the end of this word. Then, the current line number is increased by one.

TEXT FORMATTING

The Directory Editor FLIST

What Is It For?

The directory editor **FLIST** is a fullscreen file browser which allows the user to pass various commands directly against files.

Throughout this chapter, the file naming convention is the following:

For any file such as "/usr/ml/test.f":

- "/usr/m1" is called filedirectory.
- "test" is called filename.
- "f" is called filetype.

In **FLIST**, all files are referenced by passing an individual filename (FN), a filetype (FT) and a filedirectory (FD).

The format of the 4 FLIST commands is:

{	FN	{	\mathbf{FT}	{	FD	}	}	}
{	FN	{	\mathbf{FT}	{	FD	}	}	}
{	FN	{	\mathbf{FT}	{	FD	}	}	}
{	FN	{	FΤ	{	FD	}	}	}
	{ { { {	<pre>{ FN { FN { FN { FN } FN }</pre>	<pre>{ FN { } } } }</pre>	<pre>{ FN { FT { FN { FT } FN { FT } FN { FT } FN { FT }</pre>		<pre>{ FN { FT { FD } { FN { FT { FD } { FN { FT { FD } } }</pre>	<pre>{ FN { FT { FD } { FN { FT { FD } { FN { FT { FD } { FN { FT { FD } } }</pre>	$ \left\{ \begin{array}{cccc} FN & \left\{ \begin{array}{cccc} FT & \left\{ \begin{array}{cccc} FD \end{array} \right\} \\ \left\{ \begin{array}{cccc} FN & \left\{ \begin{array}{cccc} FT & \left\{ \begin{array}{cccc} FD \end{array} \right\} \\ \left\{ \begin{array}{cccc} FN & \left\{ \begin{array}{cccc} FT & \left\{ \begin{array}{cccc} FD \end{array} \right\} \\ \left\{ \begin{array}{cccc} FN \end{array} \right\} \\ \left\{ \begin{array}{cccc} FN & \left\{ \begin{array}{cccc} FT & \left\{ \begin{array}{cccc} FD \end{array} \right\} \\ FD \end{array} \right\} \\ \end{array} \right\} \end{array} \right\} $

where:

FN is the filename of all files to be displayed.

If an asterisk ("*") is entered here, all file-names will be selected.

A single period (".") will select files with no filename.

FT is the filetype of all files to be displayed.

If FT is omitted or if an asterisk ("*") is entered here, all file-types will be selected.

A single period (".") will select files with no filetype.

FLIST considers the following special meta characters:

- * matches any set of characters.
- ? matches any (one) character.

RFLIST considers the following special meta characters:

^	matches only at the beginning of a line.
\$	matches only at the end of a line.
\<	matches only at the beginning of a word.
\>	matches only at the end of a word.
	matches any single character.
[]	matches any character in a character class.

- $\$ delimits the start of a subexpression. It is available for $\forall I$ compatibility, but has no special meaning.
- $\$ delimits the end of a subexpression. It is available for VI compatibility, but has no special meaning.
- * repeats the preceding 0 or more times.

If you want to use a meta character as an ordinary character, you must precede it with a backslash $(\)$ character.

DFLIST displays only directories.

FFLIST displays only non-directories.

FD is the filedirectory of the files to be displayed.

If FD is a string of 1 or 2 alphabetical characters, such as "a" or "za", it represents an abbreviation for the directories currently accessed via the PATH or XPATH environment variable. The user may override this feature by typing "Shift-Return" instead of "Return".

The order of the file-directories is alphabetical:

"a" means the first one.

"b" the second one.

etc...

The first directory will always be the current directory, regardless of its position in the **UNIX** path.

If FD starts with a directory indicator, such as "/", "./", " \sim /", it will be treated like a standard directory. Otherwise, **SEDIT** will search first in the current directory and then through the directories in the cdpath accessed with the DACCESS command.

If FD is more than 2 alphabetical characters, FLIST will treat it as a directory-name.

If FD contains blanks, it must be surrounded with quotes or double quotes. If a directory contains a quote or a double quote, the quote must be escaped with a backslash.

Examples: Assume a cdpath and a home directory as "/usr/ml".

			will scan all the files in the current directory.
*	*	a	will do the same.
*	*	~	will do the same.
•	*		will scan for all files with no filename in the
		current	directory.
*	h	~/dir1	will scan for every "/usr/ml/dirl/*.h" file.
*	h	dir1	is a short-cut to do the same.
*	*	*	will scan all the files in all PATH directories.
te	est	;* f	will scan all the test*.f files in the current
		directo	ry.
*	ل ا ۲	* a	(followed by "Shift-Return") will scan the
			directory "/home/m1/a"
	* * * te	* * * * * h * h test	* * a * * ~ . * current * h ~/dirl * h dirl * * * test* f directo * * a

<u>Using "Control-F"</u>

If no directory editor session is active, entering "Control-F" is equivalent to the FLIST command.

Once the directory editor is started, "Control-F" will switch between the file and the directory editor.

Large Files support

A large file is a file larger than 2,147,483,647 bytes. **SEDIT** supports large files and **FLIST** displays correctly large files length on the operating systems displayed when typing HELP LARGEFILES.

Getting Started

Type f in the command field, and then hit the "Return" key.

The screen will look like this:

Level 0 40 Files			1 OF 40			
-rw-rw-rw- test	.f	а		1207	16/02/88 01:19	
-rw-rw-rw- test	.f	а		457	06/02/88 13:31	
-rw-rw-rw- include	.h	а		11111	11/01/88 18:44	
-rw-rw-rw- command	 *	а		9870	16/04/87 21:44	
a : /usr/m1						
b : /usr/m1/cmd						
c : /usr/bin						
d : /usr/etc						
e : /etc						
1:/SN 3:END 4:XE	ED 5:SW	ITCH	6:/SB 7:U 8:D 9:/S	SD 10:/ST	11:-> 12:CAN	

The format used is similar to the "ls -l" UNIX command.

The first line indicates the current level. Each time the user calls the directory editor, a new level is created.

Key F3 cancels the current level, and key F12 cancels all levels and returns to the file editor.

The second line is the message field.

The next four lines (in this short example) are the work area; they show the selected files in a reversed time order. Also displayed are the permission indicators, the filename, the filetype, the filedirectory abbreviation, the input field filled with tabulations ("....."), the file length, and the time of the last modification.

The next five lines indicate the directory abbreviations corresponding to the PATH environment variable. In this example, in the ".cshrc" file, the user may have:

set path = (/usr/m1 /usr/m1/cmd /usr/bin /usr/etc /etc)

Note that the current directory is always the first to appear.

A cd command passed to the file editor will cancel all directory editor levels.
Displaying Owner/Group/Timestamp

When **FLIST** is running, typing ^h (Control-h) displays the file related time-stamps:

Level 0 40 Files				1 OF 4	40
-rw-rw-rw- test -rw-rw-rw- test1 -rw-rw-rw- include	.f .f .h	a a a		1207 457 11111	16/02/88 01:19 06/02/88 13:31 11/01/88 18:44
-rw-rw-rw- command* a : /usr/m1 b : /usr/m1/cmd		a		9870	16/04/87 21:44
1:/SN 3:END 4:XED 5	5:SWI7	ГСН	6:/SB 7:U 8:D 9:/SD	10:/ST	11:-> 12:CAN

Typing ^o (Control-o) displays the file related owners:

Level 0 40 Files				1 OF	40
-rw-rw-rw- test -rw-rw-rw- test1 -rw-rw-rw- include -rw-rw-rw- command* a : /usr/m1 b : /usr/m1/cmd	.f .f .h	a a a		1207 457 11111 9870	O: john O: root O: bin O: root
1:/SN 3:END 4:XED	5:SWI	ГСН	6:/SB 7:U 8:D 9:/SD	0 10:/ST	11:-> 12:CAN

Typing ^g (Control-g) displays the file related groups (**UNIX** only):

Level 0 40 Files				1 OF	40
-rw-rw-rw- test -rw-rw-rw- test1 -rw-rw-rw- include -rw-rw-rw- command* a : /usr/m1 b : /usr/m1/cmd	.f .f .h	a a a		1207 457 11111 9870	G: team1 G: operator G: wheel G: wheel
1:/SN 3:END 4:XED	5:SWI	ГСН	6:/SB 7:U 8:D 9:/SD	10:/ST	11:-> 12:CAN

Using the Function Keys

The principal function key definitions are referenced on the last line of the window.

Level 0 40 Files	1 OF 40
-rw-rw-rw- test.f-rw-rw-rw- test1.f-rw-rw-rw- include.f-rw-rw-rw- command*a : /usr/m1 b : /usr/m1/cmd 1:/SN 3:END 4:XED 5:SY	a 1207 G: users a 457 G: root n a 11111 G: operator a 9870 G: wheel WITCH 6:/SB 7:U 8:D 9:/SD 10:/ST 11:-> 12:CAN
Fl	SORT BY NAME files will be displayed sorted by their filename. files with no filename, like .dbxinit, will be displayed first.
Shift-F1	SORT BY NAME in reversed order.
F2	generates an SEDIT file with the same content displayed within FLIST .
Shift-F2	generates an SEDIT file with the full names of the files displayed within FLIST .
F3	END will terminate the current directory editor level. If this level is the last one, it will return to the file editor.
F4	XED opens for editing the file pointed by the cursor.
F5	SWITCH switches between different directory editor levels. Shift-F5 does the same as above in reversed order. This key has the same behavior in XED and FLIST.
F6	SORT BY SIZE files will be displayed in the decreasing order of their sizes.
Shift-F6	SORT BY SIZE in reversed order
F7	UP if the mouse is in the work area, the user can scroll up the files. If it is in the directory indicator area, the user can scroll up the directory indicator display.
F8	DOWN if the mouse is in the work area, the user can scroll down the files. If it is in the directory indicator area, the user can scroll down the directory indicator display.

F9	SORT BY DATE the files will be displayed beginning with the latest. This is the initial default.
Shift-F9	SORT BY DATE in reversed order.
F10	SORT BY FILETYPE files will be displayed in a filetype alphabetical order. files with no filetype, like "module", will be displayed first.
Shift-F10	SORT BY FILETYPE in reversed order.
F11	EXTENSION this key is used when data is longer than the input zone. A screen similar to the following will be displayed:

Level 0 40 Files				1 OF -	40
-rw-rw-rw- test	.f	а			
-rw-rw-rw- test	.f	а		457	06/02/88 13:31
-rw-rw-rw- include	.h	а		11111	11/01/88 18:44
-rw-rw-rw- command*		a		9870	16/04/87 21:44
a : /usr/m1					
b : /usr/m1/cmd					
c : /usr/bin					
d : /usr/etc					
e : /etc					
1:/SN 3:END 4:XED 5:	SWIT	CH	6:/SB 7:U 8:D 9:/SD	10:/ST 11	:-> 12:CAN

Shift-F11	will scroll up to the first file.
F12	CANCEL will cancel all directory editor levels and return to the file editor.
Shift-F12	will scroll up to the last file.
HOME	On WINDOWS systems, moves the cursor to the start of the input field. On UNIX systems, moves the cursor to the first input field.When the 3270 HOME simulation is cleared with a command such as 'set home' in the profile, the HOME key moves the cursor to the start of the input field.
Control-HOME	will scroll up to the first file.
END	On WINDOWS systems, moves the cursor to the end of the typed command. On UNIX systems, moves the cursor to the last input field. When the 3270 IHOME simulation is cleared with a command such as 'set ihome' in the profile, the END key moves the cursor to the start of the typed command.

Control-END	will scroll up to the last file.				
Control-m ¹	generates an SEDIT file with the same contents displayed within FLIST .				
Control-M ¹	generates an SEDIT file with the full names of the files displayed within FLIST .				
Control-n	will initiate a new directory editor level scanning for all files with the filename indicated by the cursor. The user may do the same by typing "f /n *".				
Control-t	will initiate a new directory editor level scanning for all files with the filetype indicated by the cursor. The user may do the same by typing "f * /t".				
Control-f	will switch to the file editor.				
Control-x	does the same as above.				
Control-r	will switch to the tree editor. See The Tree Editor on page 475 for further explanations.				
Control-y	will scroll up to the first file.				
Control-u	will scroll down to the last file.				
Control-v	will scroll up the directory indicator display.				
Control-b	will scroll down the directory indicator display.				
Control-w	clears the input fields in the work area.				
Control-e	initiates a scan, without creating a new level. It can be used to refresh the display when the corresponding directory has been modified outside SEDIT .				
Control-a	toggles ON and OFF the display of the file related permissions.				
Control-h	displays the file related time-stamps.				
Control-o	displays the file related owners.				
Control-g	displays the file related groups.				

^{1.} Not in ASCII terminal mode.

Using the Buttons

If the following statement:

'FBUTTON ON'

is included in the profile.sedit initialization macro, **FLIST** displays the following set of menu buttons:



Clicking with the third mouse button on UNIX systems displays a menu.

Clicking with the left mouse button directly executes the first menu item.

On **WINDOWS** systems, the left mouse button displays the menu.

<u>The Sort menu</u>



The New menu



The End menu

Return	Returns to the caller, either XED or TREE .
End Level	Will terminate the current directory editor level. If this
	is the last level, it will return to the file editor.
End All Levels	Will cancel all directory editor levels and return to the
	file editor.

The simple buttons



Mouse Editing a File

Clicking with the leftmost mouse button on the filename part of a file will start editing this file.

On WINDOWS systems, clicking on an * . exe file executes this file.

Switching Permissions Display

When **FLIST** is running, typing ^a (Control-a) switches the permissions display mode.

-	-		-	
Level 0 40 Files			10	F 40
<pre>-rw-rw-rw- test -rw-rw-rw- test1 -rw-rw-rw- include -rw-rw-rw- command* a : /usr/m1 b : /usr/m1/cmd c : /usr/bin </pre>	.f a .f a .h a a		1207 457 11111 9870	16/02/88 01:19 06/02/88 13:31 11/01/88 18:44 16/04/87 21:44
d : /usr/etc e : /etc 1:/SN 3:END 4:XED	5:SWITC	'H 6:/SB 7:U	8:D 9:/SD 10:/ST	11:-> 12:CAN

By default, the **FLIST** directory editor displays the file related permissions:

Level 0	40 Files			1 OF	5 40
test	.f	а		1207	16/02/88 01:19
test1	.f	а		457	06/02/88 13:31
include	.h	а		11111	11/01/88 18:44
command*		а		9870	16/04/87 21:44
a : /usr/m]	1				
b : /usr/m	1/cmd				
c : /usr/bir	n				
d : /usr/etc	e				
e : /etc					
1:/SN 3:E	END 4:XE	D 5:SW	TCH 6:/SB 7:U 8:D 9:/SD) 10:/ST	11:-> 12:CAN

Typing ^a will switch the display to:

This allows more space for displaying long file names.

The permissions display mode may also be changed by using the FLATH **SEDIT** command.

Passing Commands

The Built-in Commands

The built-in commands are commands which are specific to the directory editor. Their syntax is quite different from that of the corresponding **UNIX** commands.

Once executed, they are flagged by a "*" character when successful or by a "?" when they fail. The user may type a command, scroll using the mouse or the function keys, type another command and then execute them by pressing the return key. If the user changes the sort order before executing these pending commands, they will be commented out with a "#" character.

* # or ?	starting commands are comments and will not be executed.
?	alone redisplays the last command.
Bottom	will scroll up to the last file.
F, RF, DF, FF	commands are similar to the *FLIST commands passed in the file editor, with some exceptions:

• The implicit directory is not the current directory but the filedirectory of the file it is applied to. For example:

Level 0	40 Files				1 OF	40
-rw-rw-rw- -rw-rw-rw- a : /usr/m b : /usr/m	test include command* 1 1/cmd	.f .h	b b b	f * * ./dup 	457 11111 9870	06/02/88 13:31 11/01/88 18:44 16/04/87 21:44

initiates a new directory editor level searching all the "/usr/ml/cmd/dup/*.*" files.

• The user may type /n which means "same filename" /twhich means "same filetype"

Level 0	40 Files				1 OF 4	40
-rw-rw-rw- -rw-rw-rw- a : /usr/m b : /usr/m	test include command* 1 1/cmd	.f .h	b b b	f /n * 	457 11111 9870	06/02/88 13:31 11/01/88 18:44 16/04/87 21:44

initiates a new directory editor level searching all the "/usr/m1/cmd/test.*" files.

Cp or Copy

command is an IBM CMS-style copyfile command. It applies directly to the file indicated by the cursor.

Its syntax is Cp FN FT FD {(Rep {Oldd} } }

FN is the filename of the newly created file.

FT is its filetype.

FD is its filedirectory.

The user may use = to indicate that the component is the same as that of the matching file.

Rep is an optional indicator which allows the user to overwrite an existing file. If the user does not specify it, **SEDIT** will not allow the file to be overwritten.

Oldd is an optional indicator which allows the user to preserve the source file modification time.

Usage note: CP without arguments brings the filename, filetype and the = sign on the corresponding command line, allowing easy editing.

Level 0	40 Files				1 OF	40
-rw-rw-rw- -rw-rw-rw- -rw-rw-rw- a : /usr/m b : /usr/m	test1 include command* 1 1/cmd	.f .h	b b b	cp = oldf a (r 	457 11111 9870	06/02/88 13:31 11/01/88 18:44 16/04/87 21:44

will copy /usr/m1/cmd/test1.f to /usr/m1/test1.oldf.

Level 0	40 Files				1 OF -	40
-rw-rw-rw- -rw-rw-rw- -rw-rw-rw- a : /usr/m b : /usr/m	test1 include command* 1 1/cmd	.f .h	b b b	cp = = ./dup	457 11111 9870	06/02/88 13:31 11/01/88 18:44 16/04/87 21:44

will copy /usr/ml/cmd/test1.f to /usr/ml/cmd/dup/test1.f.

Diff			passes the matching the name built with diff command.	g complete h the argu	UNIX filename and ments to the UNIX
Level 0 40 Files				1 OF	40
-rw-rw-rw- test	.f	b	d = oldf =	457	06/02/88 13:31
-rw-rw-rw- include	.h	b		11111	11/01/88 18:44
-rw-rw-rw- test a : /usr/m1 b : /usr/m1/cmd	oldf	b		9870	16/04/87 21:44

executes the UNIX

diff /usr/ml/cmd/test.f /usr/ml/cmd/test.oldf

command, and displays the result within SEDIT.

Usage note: DIFF without arguments brings the filename, filetype and the = sign on the corresponding command line, allowing easy editing.

Mv or Ren

command is an IBM CMS-style movefile command. It applies directly to the file indicated by the cursor.

its syntax is Mv FN FT FD {(Rep {Oldd} }

Level 0	40 Files				1 OF -	40
-rw-rw-rw- -rw-rw-rw- -rw-rw-rw- a : /usr/m b : /usr/m	test1 include command* 1 1/cmd	.f .h	b b b	mv = = ./dup	457 11111 9870	06/02/88 13:31 11/01/88 18:44 16/04/87 21:44

will move /usr/ml/cmd/test1.f to /usr/ml/cmd/dup/test1.f.

If the user replaces a displayed file using the MV command, that file will be displayed in blue, its length will be replaced with a "xxxxxx" string, and its first letter by a " | ".

Level 0	40 Files				1 OF 4	40
-rw-rw-rw- -rw-rw-rw- -rw-rw-rw-	test1 test2 command*	.f .f	b b b	mv test2 = = (r	457 11111 9870	06/02/88 13:31 11/01/88 18:44 16/04/87 21:44
b : /usr/m	1/cmd					
	I					

gives:

Level 0 40 Files			1 OF	40
-rw-rw-rw- test2 -rw-rw-rw- est2 -rw-rw-rw- commar a : /usr/m1 b : /usr/m1/cmd	.f .f nd*	b b b	 457 xxxxx 9870	06/02/88 14:06 11/01/88 18:44 16/04/87 21:44

Every directory editor level will be updated.

Usage note: MV without arguments brings the filename, filetype and the = sign on the corresponding command line, allowing easy editing.

RM or E

command is used with no argument to delete the matching file.

Once a file has been erased, it is displayed in blue and its length is replaced with a "xxxxxxx" string.

Level 0 40 Files 1 OF 40	40
-rw-rw-test1 .f b rm 457 -rw-rw-rw-test2 .f b 11111	06/02/88 13:31 11/01/88 18:44
-rw-rw-rw- command* b	16/04/87 21:44

gives:

Level 0	40 Files				1 OF	40
-rw-rw-rw- -rw-rw-rw- a : /usr/m b : /usr/m	test1 test2 command* 1 1/cmd	.f .f	b b b	*rm 	xxxxx 11111 9870	06/02/88 13:31 11/01/88 18:44 16/04/87 21:44

Notes: Since ISPF users generally use the "e" command to start editing a file, when "mode prefix ispf" is on, the user cannot use the "e" command to delete a file. Only the "rm" command can be used for that purpose.

On **WINDOWS** systems, when RECYCLE is ON, removing files moves then into the recycle bin.

Тор	will scroll up to the first file.
Xed	starts editing the matching file.

This command allows the user to start editing several files at once. If the user wants to edit only one file, the F4 function key may be used.

XBin	starts editing the matching file in binary mode. See the <u>BINARY</u> command on page 158 for more information.
XKb	starts editing the matching file with KEEPBLANKS set to ON. See the <u>KEEPBLANKS</u> command on page 290 for more information.
WIPE	wipes the selected file. WIPE is in fact the wipe.flist macro, and uses the WIPE() S/REXX buil-in described page 608.

=

repeats the preceding command

Level 0	40 Files				1 OF -	40
-rw-rw-rw- -rw-rw-rw- -rw-rw-rw- a : /usr/m b : /usr/m	test1 test2 test3 test4 1 1/cmd	.f .f .f .f	b b b	cp = oldf = (rep = =	457 11111 9870 9870	06/02/88 13:31 11/01/88 18:44 16/04/87 21:44 16/04/87 21:44

will copy these four files and give:

Level 0	40 Files				1 OF 4	0
-rw-rw-rw-	test1	.f	b	*cp = oldf = (rep	457	06/02/88 13:31
-rw-rw-rw-	test2	.f	b	*cp = oldf = (rep	11111	11/01/88 18:44
-rw-rw-rw-	test3	.f	b	*cp = oldf = (rep	9870	16/04/87 21:44
-rw-rw-rw-	test4	.f	b	*cp = oldf = (rep	9870	16/04/87 21:44
-rw-rw-rw-	test1	.oldf	b		457	06/02/88 13:31
-rw-rw-rw-	test2	.oldf	b		11111	11/01/88 18:44
-rw-rw-rw-	test3	.oldf	b		9870	16/04/87 21:44
-rw-rw-rw-	test4	.oldf	b		9870	16/04/87 21:44
a : /usr/m1						
b : /usr/m1	/cmd					

The Non-built-in Commands

When the user passes a command other than a built-in command, that command is passed directly to the shell followed by the matching complete **UNIX** or **WINDOWS** filename.

Note that this command may be interrupted by typing ^c at any time.

Level 0	40 Files				1 OF 4	40
-rw-rw-rw-	private	.f f	a b	chmod o-w	457	06/02/88 13:31 11/01/88 18:44
	command*	.1	b b	•••••	0870	16/04/87 21:44
 -rw-rw-rw- command* b a : /usr/m1 b : /usr/m1/cmd c : /usr/lib/fonts/fixedwidthfonts 			nts	 	3870	10/04/87 21.44

will modify the permissions for the UNIX file /usr/ml/private.f.

Overriding a Built-in Command

If the user validates a command by typing "Control-return" instead of "Return", there will be no checking for built-in commands. This is useful if the user wants to pass a synonym of a built-in command to the shell.

This facility is not available when **SEDIT** runs in character mode.

Using S/REXX Macros Within FLIST

An **S/REXX** macro command is a file with an flist filetype which is called from the **FLIST** environment.

In order to make a macro file available for such usage, the user must first enter (for example in the profile.sedit initialization file) the "HASH {dir1 {dir2} {...}}" command described on page 281.

The default profile load all the macros located in the {install-dir}/xmac directory.

xmac contains the following utime.flist sample macro:

```
/*
* utime: MACRO sample used within FLIST
*
*
   Usage example:
*
   -rw-rw-r-- restart.x a utime 1/1/1998 12:03:13
*
*
   utime will be called as
*
*
    call utime "{a directory}/restart.x", "1/1/1998 12:03:13"
*
*/
signal on novalue
option mixed setenv
parse arg file, args
if args = '' then return 0
parse var args jj'/'mm'/'yy hh':'mi':'ss
if hh = '' then hh = 0
if mi = '' then mi = 0
if ss = '' then ss = 0
rep = utime(file, jj, mm, yy, hh, mi, ss)
if rep = 0 then return 0
'msg utime: Unable to change "'file'" timestamp.'
'msg reason: 'rep
return 1
```

Typing the macro name (utime) in one of the FLIST input fields calls the macro with 2 arguments. The first argument is the complete file name (including the directory part), and the second is the optional string entered after the macro name.

When the macro return 0, **FLIST** remains active. When the macro returns 1, **FLIST** returns to the file editor.

In this example, utime parses the entered date and then uses the **S/REXX** utime() built-in to modify the time stamp of the corresponding file.

When FMACRO is OFF (the default), **FLIST** looks for built-in commands first before looking for macros.

When FMACRO is ON, **FLIST** looks for macros first before looking for built-in commands. FMACRO ON allows to override built-in **FLIST** commands such as the cp command.

The $\underline{FLFILES}()$ built-in described on page 559 can be used to retrieve the names of the files displayed in the current **FLIST** level.

The Tree Editor

Getting Started

The tree editor **TREE** allows the user to graphically visualize the directory layout.

The format of the **TREE** command is:

Tree {dir}where dir is the directory to start the scan. If
omitted, the scan will start at the home directory.

When <u>TREESCANLEVEL</u> is set to 0 (the default), all the subdirectories belonging to the same filesystem as the dir filesystem are scanned.

Once the scan is over, **SEDIT** saves the result in a file named sedit.treemap in order to avoid initialization delay at the next call. If the directory layout is modified outside **SEDIT**, **TREE** is not automatically updated.

When TREESCANLEVEL is set to a positive value N, **TREE** ignores any sedit.treemap already existing. **TREE** rescans the disk at every call, to a depth of N subdirectories. Initialization time will be longer than TREESCANLEVEL equal 0, but the display is always accurate.

To modify the TREESCANLEVEL during an SEDIT session, issue for example the following command in the SEDIT command field:

====> TREES 1

To set the default TREESCANLEVEL, add for example in the user's profile.sedit initialization macro file:

'TREES 1'



Assume the user types t /usr, the screen will then look like this:

Using the Mouse

Note: On **WINDOWS** systems with a 2 button mouse, the rightmost button acts as the third M3 button on a 3 button mouse. M1 is the leftmost button, and M2, the center button on a 3 button mouse is not available.

When selecting a directory with the leftmost mouse button, a new directory editor level is started on this directory.

To return to the tree editor, the user just has to type ^r.

When the user selects a directory with the center mouse button, this directory becomes the current directory. Note that the current directory appears in blue on color displays, and bold-faced on monochrome displays. On **WINDOWS** systems with a 2 button mouse, use the Shift-Left button instead.

When changing the current directory, all the directory editor levels will be lost.

When the user selects a directory with the rightmost mouse button, the following menu pops up:

DOWN
HIDE
RENAME
MKDIR
CLONE
MOVE
СОРУ
EMPTY
RM -R
WIPE

- **DOWN** restarts the tree editor upon the selected directory. If the selected directory is the current tree root, the string **DOWN** will be replaced by the string **UP**, and choosing that item will restart the tree editor on the current tree root parent.
- **HIDE** undisplays all the selected directory subdirectories. If the user clicks again over that directory, the string **HIDE** will be replaced with the string **SHOW**, allowing a redisplay of the hidden directories.
- **RENAME** pops up a dialog box asking for a new name for the selected directory.
- **MKDIR** pops up a dialog box asking for a new subdirectory name.
- **CLONE** pops up a dialog box asking for a new directory name. A new directory identical to the selected one, including all sub-directories, will be created using the new name.
- MOVE highlights the selected directory and changes the mouse pointer adding a small M to it. Then the user will have to choose a destination directory by clicking over it with M1 or M2. To cancel the operation, just click out of any directory box.

- **COPY** highlights the selected directory and changes the mouse pointer adding a small C to it. Then the user will have to choose a destination directory by clicking over it with M1 or M2. To cancel the operation, just click out of any directory box.
- EMPTY pops up a dialog box asking confirmation and then deletes all files in the selected directory. On WINDOWS systems, when RECYCLE is ON, files will be moved to the recycle bin.
- **REMOVE** pops up a dialog box asking confirmation and them removes the whole selected directory, after removing all its files if necessary. On **WINDOWS** systems, when RECYCLE is ON, files will be moved individually to the recycle bin.
- **RM R** pops up a dialog box asking confirmation and then removes the selected directory, and all its subdirectories. On **WINDOWS** systems, when RECYCLE is ON, the designated directory will be moved globally to the recycle bin.
- WIPE pops up a dialog box asking confirmation and then wipes all files in the selected directory. See The WIPE S/REXX routine page 608 for more information.

Note that, unlike the **UNIX** "cp –R" command, **SEDIT** respects symbolic links while copying directories. **MOVE** and **COPY** will also work across file systems.

WARNING: deleting files cannot be undone. Be very careful when using the **EMPTY** and **REMOVE** facilities.

Using the Buttons

The DONE button, or the F1 key will terminate the tree editor and return to the caller, either XED or FLIST.

The SCAN button or the F10 key will again scan the directories, updating the display if any changes are found since the last scan. Note that once the scan is over, **SEDIT** saves the result in a file named sedit.treemap in order to avoid initialization delay at the next call.

SCAN automatically hides subdirectories belonging to file systems other than the initial dir file system.

The SCAN ALL button or the F11 key will scan the directories without hiding subdirectories belonging to other files systems.

The RET button or the F3 key will return to the caller. A subsequent call to TREE without argument will cause the tree editor to resume where it was left off.

The XED button or the x key will return to the file editor. A subsequent call to TREE without argument will resume the tree editor at the point the user left it.

The FLIST button or the ^f key will return to the directory editor. A subsequent call to TREE without argument will resume the tree editor at the point the user left it.

On **UNIX** systems, the button PRINT will pop up a menu asking the user for the following items:

- Printer the name of the printer to be used.
- Width the number of columns the printer features. Use the Tab key

or the left mouse button to toggle between these two items.

• Line drawing set	APL if the printer uses the DYALOG APL line drawing set. PC8 if the printer uses the IBM PC8 character set. None if the printer does not feature any line drawing set.
	The button CANCEL, or depressing the L1 key ¹ will cancel the print. The button OK, or depressing the Return key will start the print.

Using the Function Keys

TREE supports the following function keys:

F1	terminates the tree editor and returns to the caller, either XED or FLIST.
F3	returns to the caller. A subsequent call to TREE without argument will resume the tree editor at the point the user left it.
F7	scrolls up one page.
F8	scrolls down one page.
F10	scans the directories, updating the display if any changes are found since the last scan.
F11	scans the directories without hiding subdirectories belonging to other files systems.
Home	scrolls up to the first directory.
End	scrolls down to the last directory.
PageUp	scrolls up one page.
PageDown	scrolls down one page.
Control-f	returns to the directory editor. A subsequent call to TREE without argument will cause the tree editor to resume where it was left off.
Control-e	scrolls down to the last directory.
Control-h	scrolls up to the first directory.
Control-p	pops up the print dialog box.

^{1.} Sun only

Control-s	asks for a search string and scrolls to the first directory matching this string. Within the search string, a * character means any set of characters, and a ? character means any character.			
	Examples:	<pre>se* matches sedit and select. ?edit matches xedit and sedit, but not regedit.</pre>		
	Notes:	When GLOBALCASE is set to IGNORE (the default on WINDOWS systems), the matching is case insensitive. On Sun keyboards, the FIND key can also be used for the same purpose. Entering an empty string searches for the last entered string.		
Control-x	returns to the file editor. A subsequent call to TREE without argument will cause the tree editor to resume where it was left off.			

Changing the Default Printer on UNIX Systems

On **UNIX** systems, the <u>PRINTSCREEN</u> command described page 340 changes the default TREE printer and printing daemon.

Getting started

Running SEDIT With CodeCenter

SEDIT may run as an EDIT session for the **CodeCenter**¹ 4.x software².

To set up communication between **SEDIT** and **CodeCenter**, uncomment the following lines in the file {instal-dir-SEDIT}/sedit.menu:

```
"CENTER" MENU
              "load " MENU
                           ".c" c_load center
                           ".o" c_load center o
              "load " END
              "unload" c_unload center
              "swap " MENU
                        "--> c " c_swap center c
                         "--> o " c_swap center o
              "swap " END
              "stop " MENU
                     "stop in" c_stop center
                     "stop at" c_stopat center
              "stop " END
              "ini " center_ini
              "list " c_list center
              "xref " saber_xref center
              "run " center_send run
              "build " center_send build
              "end " center_end
"CENTER" END
```

Then type the following **SEDIT** command:

====> menu \$xhome/sedit.menu

^{1.} CodeCenter and Saber-C are trademarks of CenterLine Software, Inc.

^{2.} CodeCenter is not supported on all platforms and operating systems.

This will create the following menu items:



The menu items have the following meaning:



You may also uncomment the following line in the profile.sedit file:

```
/*

'set ^s ONLY c_stopat center'

'set ^S ONLY c_split'

'mbutton Center center.bu'

'hash $xhome/xmac/center'

*/
```

which gives:

```
'set ^s ONLY c_stopat center'
'set ^S ONLY c_split'
'mbutton Center center.bu'
'hash $xhome/xmac/center'
```

Typing ^s (Control-s) will set a stop at the cursor location.

Note: these commands applies to **CodeCenter** 4.x. If you are using **Saber-C** (or **CodeCenter**) 3.x, please type the following **SEDIT** command:

====> HELP SABER

CodeCenter

Using S/REXX

Starting S/REXX on UNIX Systems

To execute an **S/REXX** program, the user must first create a text file containing the **S/REXX** source program by using a text editor, such as **SEDIT**. Once the program is created, there are two ways to execute it.

Explicit Execution

Assuming the user has created a file called fname, the user must type the following command:

% /home/xed/srexx fname

The % sign is the **UNIX** prompt and is not part of the command.

If the /home/xed directory has been installed in the current path, the user may simply type:

% srexx fname

Note that srexx searches fname in the directories described in the PATH environment variable.

Automatic Execution

The first line of the source program must contain the following entry:

#! /home/xed/srexx

The program must be set for execution permission with the following command:

% chmod a+x fname

Then, the user can start the program by typing:

% fname

Note: when using **SEDIT** to create an automatic **S/REXX** program, the **SEDIT** save function will recognize the first line "#!" statement and automatically set up the execution authorizations.

Starting S/REXX on WINDOWS Systems

To execute an **S/REXX** program, the user must first create a text file containing the **S/REXX** source program by using a text editor. Once the program is created, there are three ways to execute it.

Explicit Execution

Assuming the user has created a file called fname, the user must type the following command in a DOS window:

"C:\Program Files\SEDIT\srexx" fname

If the C:\Program Files\SEDIT directory has been installed in the current path, the user may simply type:

srexx fname

Note that srexx searches fname in the directories described in the PATH environment variable.

Choosing between srexx.exe and wsrexx.exe

srexx.exe is a console application, meant to be used from a **DOS** window. Error messages will be displayed on the **DOS** window it was started from. When starting srexx.exe using a **WINDOWS** icon, a **DOS** console is displayed at initialisation.

wsrexx.exe is a **WINDOWS** graphical application. Error messages will be displayed on a dialog box. A **DOS** console will be displayed only when using a standard input-output rexx instruction, such as the SAY instruction. The CLOSE_CONS() built-in can be used to close such a console.

Automatic Execution

Unlike UNIX systems, WINDOWS NT does not provide a way to associate a text script to a specific interpreter. We suggest the user create a c:\myprogs\fname.bat file for every c:\myprogs\fname S/REXX program with the following content:

```
"C:\Program Files\SEDIT\srexx" c:\myprogs\fname
```

Assuming that the c:\myprogs directory is in the current path, the user may then type:

fname

to start the fname **S/REXX** program.

Note: Use double quotes when the installation directory contains blank characters. c:\Program Files\SEDIT\srexx fname without quotes would fail.

Using anysrexx.exe

An alternative method is to use the anysrexx.exe or anywsrexx.exe programs. First, you must add the **SEDIT-S/REXX** installation directory in your PATH environment variable. On NT systems, click on the System icon in the Control Panel, click on the Environment tab and add:

;C:\Program Files\SEDIT

at the end of the contents of the Path variable:

	2			System Properties ? 🗙
i	Control P File Edit Vi	anel iew <u>H</u> elp	000/19294	Startup/Shutdown Hardware Profiles User Profiles ter General Performance Environment
	Mouse	اللي المجاني (MS Licensing	Multimedia	System Variables:
Re	PC Card (PCMCIA)	Ports	printers	Value Value OS Windows_NT Os2LibPath C:\WTSRV\system32\os2\dll; Path C:\WTSRV\system32\c:\WTSRV;C:\WTRE PATHEXT .COM;EXE;BAT;:CMD;VBS;;VBE;JS;JSE; PROCESSOR RR
	Recherche accélérée	Regional Settings	SCSI Adapter:	User Variables for m2: Variable Value TEMP C:\TEMP TMP C:\TEMP
	Provides system	System minformation an	Tape Devices d changes envi	⊻ariable: Path
Wi	ndows NT V	Mware A	,crobat	Value: ot%;C:\NTRESKIT;C:\NTRESKIT\Perl;c:\Program Files\SEDIT Set Delete

On non-NT Windows systems, you must edit the autoexec.bat file to modify the path. Then, issue the command:

copy "C:\Program Files\SEDIT\anysrexx.exe" fname.exe

fname.exe will look in the path for srexx.exe, and start it passing to it fname as first argument. If fname.exe is copied from anywsrexx.exe, it will use wsrexx.exe instead.

Using the WINDOWS NT 3.51 File Manager

The **WINDOWS** file manager allows the association of files with a specific extension to a specific application.

We suggest the user give a .srx extension to all **S/REXX** programs which must be started with the file manager. Any other extension not in use by the system, such as the .bat extension, can be used though.

Using the File/Associate menu, display the Associate dialog box. Click on the Browse button, and select the C:\Program Files\SEDIT\srexx.exe file name.



Click on the OK button in the Browse and Associate dialog boxes. Now, double clicking on any *.srx file will start **S/REXX** upon that file.

Using the WINDOWS NT 4.0 and WINDOWS 95/98 Explorer

We suggest the user give a .srx extension to all **S/REXX** programs which must be started with the file manager. Any other extension not in use by the system, such as the .bat extension, can be used though.

Then, double click on a .srx **S/REXX** file, and the **WINDOWS** Explorer will ask for the application name to associate with such a file.

Compiling a Program

To prepare a non-modifiable version of the test source program, issue the following command:

```
ccsr -o test_user test
```

This creates a test_user program, which on **UNIX** systems may be run directly by typing its name. On **WINDOWS** systems, the explicit execution mode described on page 488 must be used to start test_user.

When simply typing ccsr test, ccsr creates a test.sr output file.

S/REXX Implementation

S/REXX complies with the REXX 4.0 language as defined in Cowlishaw's book "The REXX Language", with the sole following restriction:

S/REXX uses the workstation floating point coprocessor for numeric computation. This limits the NUMERIC DIGITS setting to a maximum of 15.

When NUMERIC DIGITS is higher than 9, usual coprocessor rounding errors will occur.

Since **UNIX** commands never return a negative value when they fail, the default TRACE setting is TRACE ERROR instead of TRACE NORMAL.

S/REXX Extensions

Static Scoping

Usual REXX implementations rely on dynamic scoping. This means that the source program is examined one line at a time, and its translation relies only on the previously interpreted lines.

For efficiency considerations, **S/REXX** has been built more as a compiler than an interpreter. The whole program is analyzed and compiled before execution starts. This makes **S/REXX** run faster than a purely interpreted language, and allows the programmer to detect syntax errors as soon as the program is loaded.

Detection of syntax errors by the programmer eliminates the discovery by end users of syntax errors in code paths not previously executed.

Dynamic Memory Allocation

S/REXX uses dynamic memory allocation for all its internal buffers.

This means there is no internal limitation of any kind.

In particular:

- The number of lines or REXX clauses within a single program are not limited.
- The complexity of an expression and the number of nested parenthesis are not limited.
- The number of created variables, the length of a symbol describing a variable and the length of the contents of a variable are not limited.
- The number of recursive subprograms calls is not limited.
- The number of arguments passed to a subroutine is not limited.

The only limitations are the system limitations:

- The amount of virtual memory available.
- The size of the C stack. The usual stack size will allow tens of thousands of nested parenthesis and thousands of recursive calls. The system administrator should be able to increase the C stack size if needed.

The Operators Extensions

The following operators may be typed in the following way:

NOT	~ \ ^
NOT EQUAL	\= /= ~= ^= <> ><
STRICTLY NOT EQUAL	\== /== ~== ^ ==
GREATER OR EQUAL	>= /< \< ~< ^<
STRICTLY GREATER OR EQUAL	>>= /<< \<< ^<<
LOWER OR EQUAL	<= /> \> ~> ^>
STRICTLY LOWER OR EQUAL	<<= />> \>> ^>> ^>>

Important Note for Mainframe Users

Mainframe keyboards often do not offer the | character. Therefore, IBM REXX considers ! as being the OR operator, and !! as being the concatenation operator.

The REXX language definition specifies that the ! character may be used within variables.

Therefore, "aa!!bb" is treated by **S/REXX** as a variable whose name is "aa!!bb", and "a ! b" as the concatenation of 3 variables: "a||' '||!||' '||b"

When porting an IBM REXX procedure to **S/REXX**, the user will have to replace all ! with |.
Logical Operators

When evaluating an expression such as:

```
expr1 & expr2
```

If expr1 evaluates to 0, expr2 will not be evaluated, and expr1 & expr2 will evaluate to 0.

This feature allows the user to write statements such as:

```
say 'Enter a positive number'
pull rep .
if datatype(rep) = 'NUM' & rep > 0 then call do_something rep
else say 'Invalid number'
```

If the user types an invalid number, such as ".qa1212", the expression rep > 0 will not be evaluated. Many REXX implementations would evaluate it anyway, thus leading to an interpretation error.

Similarly, when evaluating:

expr1 | expr2

If expr1 evaluates to 1, expr2 will not be evaluated, and expr1 | expr2 will evaluate to 1.

Dynamic Loading on UNIX Systems

Modern programming languages, such as C or FORTRAN 77, allow the user to build a collection of general utility routines and incorporate them into different programs when needed.

These utility routines can share global variables with the main program by using external variables in C and common blocks in FORTRAN.

S/REXX supports dynamic loading, allowing the use of external source routines.

For example, consider the following routine:

```
#! /home/xed/srexx
say 'Enter a positive number'
pull rep .
if test_nump(rep) then call do_something rep
else say 'Invalid number'
```

When encountering the test_nump() statement, **S/REXX** will proceed in the following way:

S/REXX searches for an internal routine named test_nump. An internal routine is a sequence of REXX instructions inside the same source file, which start at the label test_nump.
 If the word test_nump is enclosed with guotes this start is huppeded.

If the word test_nump is enclosed with quotes, this step is bypassed.

- 2) If test_nump is not found, **S/REXX** searches for a built-in routine, such as the date() routine, which is defined as part of the language.
- 3) If test_nump is not found, other REXX implementations will stop and issue an error message. Some implementations will try to load an external program named test_nump, but by creating a different process (UNIX) or a different work area (VM/CMS), thus making it impossible to exchange global variables between the main program and the subroutine test_nump.

S/REXX will look for a file test_nump in the directories described by the PATH environment variable, and if found, will dynamically append it to the end of the main file, making it available as an internal routine.

To hide dynamically loaded subroutine variables, the user may use the procedure {expose} instruction.

For example, assume the user's PATH is the following:

.:/bin:/usr/bin:/etc:/usr/ucb:/user/john/srexx_macs

We will assume the user stores all his **S/REXX** routines in the directory /user/john/srexx_macs.

If /user/john/srexx_macs/test_nump is the following:

```
#! /home/xed/srexx
if datatype(rep) = 'NUM' & rep > 0 then return 1
else return 0
```

The main program will be updated in the following way:

```
#! /home/xed/srexx
say 'Enter a positive number'
pull rep .
if test_nump(rep) then call do_something rep
else say 'Invalid number'
exit
test_nump:
if datatype(rep) = 'NUM' & rep > 0 then return 1
else return 0
```

Note that to be recognized as an **S/REXX** subroutine, the first line of the file must start with the characters #! followed by a sentence including the word srexx.

An external routine may also be called by using its absolute pathname. An absolute pathname is a string enclosed in quotes, starting with / . or \sim .

Examples:

```
call "/user/john/srexx_macs/test_nump" rep
call "~/test_nump" rep
call "./test_nump" rep
```

Notes: since most **UNIX** filenames are typed in lower case, an external subroutine will be searched for in lower case, unless explicitly typed in upper case and enclosed in quotes.

OPTION NOLOAD prevents S/REXX from loading external routines.

Using EXIT inside a dynamically loaded procedure is the same as using EXIT within an internal procedure. The current REXX program is terminated. Use RETURN to return to the caller.

Unlike with **S/REXX** 2.10, the PATH environment variable is parsed at every external routine invocation. Therefore, It is possible to add the directory containing the external macros within an **S/REXX** program.

```
option setenv mixed
$PATH = $PATH||':/users/john/srexx_macs'
if test_nump(rep) then call do_something rep
else say 'Invalid number'
```

Using OPTION NOLOAD

Consider the following example:

```
#! /home/xed/srexx
OPTION NOLOAD
say 'Enter a positive number'
pull rep .
if test_nump(rep) then call do_something rep
else say 'Invalid number'
```

When encountering the test_nump() statement, **S/REXX** will proceed in the following way:

First, S/REXX searches for an internal routine named test_nump. An internal routine is a sequence of REXX instructions inside the same source file, which start at the label test_nump.
 If the word test_nump is enclosed with quotes this stap is hupessed

If the word test_nump is enclosed with quotes, this step is bypassed.

2) If test_nump is not found, **S/REXX** searches for a built-in routine, such as the date() routine, which is defined as part of the language.

3) If test_nump is not found, **S/REXX** will look for a file test_nump in the directories described by the PATH environment variable, and if found, will pass it to the default environment.

Note that to be recognized as an **S/REXX** external subroutine, the first line of the file must start with the characters #! followed by a sentence including the word srexx.

An external routine may also be called by using its absolute pathname. An absolute pathname is a string enclosed in quotes, starting with / . or \sim .

Examples:

```
call "/user/john/srexx_macs/test_nump" rep
call "~/test_nump" rep
call "./test_nump" rep
```

Notes: since most **UNIX** filenames are typed in lower case, an external subroutine will be searched for in lower case, unless explicitly typed in upper case and enclosed in quotes.

Using EXIT inside an external routine terminates only the external routine. An external routine can only return a number to the caller.

Setting Default Options for UNIX or WINDOWS REXX Programs

When an **S/REXX** programs starts, **S/REXX** searches for a .srexxrc file in the user's home directory. If not found, **S/REXX** searches .srexxrc in the **S/REXX** installation directory.

If .srexrc is found, **S/REXX** executes all the REXX statements included in this file before executing the actual program.

This allows the user to change the default options.

Consider, for example, the following /home/xed/.srexxrc file:

```
OPTION NOLOAD
TRACE NORMAL
```

The default **S/REXX** settings related to external routines and TRACE command will be identical to the **IBM** REXX settings.

Note: the ccsr compiler reads the .srexxrc file at the compile time. The compiled file will not reread the .srexxrc file when executed.

Setting Default Options for SEDIT REXX Macros

When an **S/REXX SEDIT** macro starts, **S/REXX** searches for an sedit.srexxrc file in the user's home directory. If not found, **S/REXX** searches sedit.srexxrc in the **S/REXX** installation directory.

If sedit.srexrc is found, **S/REXX** executes all the REXX statements included in this file before executing the actual program.

Dynamic Loading on WINDOWS Systems

Modern programming languages, such as C or FORTRAN 77, allow the user to build a collection of general utility routines and incorporate them into different programs when needed.

These utility routines can share global variables with the main program by using external variables in C and common blocks in FORTRAN.

S/REXX supports dynamic loading, allowing the use of external source routines.

For example, consider the following routine:

```
say 'Enter a positive number'
pull rep .
if test_nump(rep) then call do_something rep
else say 'Invalid number'
```

When encountering the test_nump() statement, **S/REXX** will proceed in the following way:

1) **S/REXX** searches for an internal routine named test_nump. An internal routine is a sequence of REXX instructions inside the same source file, which start at the label test_nump.

If the word test_nump is enclosed with quotes, this step is bypassed.

- 2) If test_nump is not found, **S/REXX** searches for a built-in routine, such as the date() routine, which is defined as part of the language.
- 3) If test_nump is not found, other REXX implementations will stop and issue an error message. Some implementations will try to load an external program named test_nump, but by creating a different process (UNIX) or a different work area (VM/CMS), thus making it impossible to exchange global variables between the main program and the subroutine test_nump.

S/REXX will look for a file test_nump in the directories described by the PATH environment variable. If test_nump exists, its first line must start with the characters #! followed by a sentence including the word srexx.

If test_nump does not exists, or is not appropriate, **S/REXX** searches for a test_nump.srx file, which does not need to start with a specific sentence.

When found, **S/REXX** will dynamically append test_nump (or test_nump.srx) to the end of the main file, making it available as an internal routine.

To hide dynamically loaded subroutine variables, the user may use the procedure {expose} instruction.

For example, assume the user's PATH is the following:

```
.;c:\john\srexx_macs;c:\nt
```

We will assume the user stores all their **S/REXX** routines in the directory c:\john\srexx_macs.

If c:\john\srexx_macs\test_nump is the following:

```
#! srexx
if datatype(rep) = 'NUM' & rep > 0 then return 1
else return 0
```

The main program will be updated in the following way:

```
say 'Enter a positive number'
pull rep .

if test_nump(rep) then call do_something rep
else say 'Invalid number'

exit
test_nump:
if datatype(rep) = 'NUM' & rep > 0 then return 1
else return 0
```

An external routine may also be called by using its absolute pathname. An absolute pathname is a string enclosed in quotes, starting with $x \colon \langle . \rangle$. $\langle . \rangle$ or \sim .

Examples:

```
call "c:\john\srexx_macs\test_nump" rep
call ".\test_nump" rep
```

Notes: OPTION NOLOAD prevents S/REXX from loading external routines.

Using EXIT inside a dynamically loaded procedure is the same as using EXIT within an internal procedure. The current REXX program is terminated. Use RETURN to return to the caller.

Unlike with **S/REXX** 2.10, the PATH environment variable is parsed at every external routine invocation. Therefore, It is possible to add the directory containing the external macros within an **S/REXX** program.

```
option setenv mixed
$PATH = $PATH||';c:\john\srexx_macs'
if test_nump(rep) then call do_something rep
else say 'Invalid number'
```

Setting Default Options for WINDOWS REXX Programs

When an **S/REXX** programs starts, **S/REXX** searches for a HOME environment variable. If found, **S/REXX** searches for [a .srexxrc file in the directory described by this HOME environment variable.

If HOME does not exist, **S/REXX** searches for a .srexxrc file in the C:\ directory.

If .srexxrc is not found in the C:\ directory, S/REXX searches .srexxrc in the S/REXX installation directory.

If .srexrc is found, **S/REXX** executes all the REXX statements included in this file before executing the actual program. This allows the user to change the default options.

For example, consider for example the following C:\Program Files\SEDIT\.srexxrc file:

```
OPTION NOLOAD
TRACE NORMAL
```

The default **S/REXX** settings related to external routines and TRACE command will be identical to the **IBM** REXX settings.

Note: the ccsr compiler reads the .srexxrc file at the compile time. The compiled file will not reread the .srexxrc file when executed.

Extended PROCEDURE EXPOSE

In order to allow external routines to be used either stand-alone or as dynamically loaded routines, the PROCEDURE {EXPOSE} statement can be found anywhere and any number of times.

If found within a main program, it will be ignored.

If found twice in an internal routine, the EXPOSE statement will be used to update the exposed variable list. The second PROCEDURE statement will be ignored.

Example:

```
#! /home/xed/srexx
procedure expose a
                                /* This is ignored */
arg a .
call manage_arg a
/*
 * Do some processing with the variable whose name is the contents
 *
   of A
 */
exit
manage_arg:procedure
arg var_name . /* var_name is hidden: it will not affect the caller */
/*
 * Make the variable whose name is the contents of VAR_NAME available
 * to the caller
 */
interpret 'procedure expose 'var_name
/* Do something */
return
```

Extended LEAVE and ITERATE

The LEAVE and ITERATE instructions may be used within an INTERPRET clause.

Example:

```
do i = 1 to 5
   if i = 3 then interpret 'leave 'var_name
   /* ..... */
end
```

Using Backquotes

Within a REXX expression, it is possible to retrieve the result of a **UNIX** or **WINDOWS** command by surrounding it with backquotes.

Example:

```
a = '"hostname"' /* Puts the workstation hostname in the A variable */
```

Note that commands must be enclosed with single or double quotes, in order to prevent the usual REXX variable substitution.

Using { and }

For a better legibility, the user may use the "{" character instead of "DO ;", and "}" instead of "END".

Example:

```
if a < 0 then
{ 'Prompt Invalid line number'
exit 2
}
else
{</pre>
```

Using Bracket Indexing

S/REXX allows the user to set or to retrieve substrings by using bracket indexing.

The following syntax is supported for an assignment:

SYMBOL = expr The usual REXX assignment.

```
SYMBOL[expr1] = expr
```

The string resulting from the expr evaluation overlays SYMBOL at the expr1 column. SYMBOL is padded with blanks when expr1 is greater than its length.

```
SYMBOL[expr1:expr2] = expr
```

The string resulting from the expr evaluation overlays SYMBOL at the expr1 column, until the expr2 column. SYMBOL is padded with blanks when expr1 is greater than its length.

When expr is longer than expr2-expr1+1, expr is truncated.

When expr is shorter then expr2-expr1+1, expr is used from left to right in a cyclical way.

```
SYMBOL[expr1:] = expr
```

```
Is equivalent to SYMBOL[expr1:lenght(SYMBOL)] = expr
```

If expr1 is greater than the SYMBOL length, an empty string is returned.

```
SYMBOL[:expr2] = expr
```

```
Is equivalent to SYMBOL[1:expr2] = expr
```

The following syntax is supported for a REXX expression:

```
SYMBOL[expr1] or (expr)[expr1]
```

The character located at the exprl column. When exprl is greater than the SYMBOL or expr length, a space is returned.

```
SYMBOL[expr1:expr2] or (expr)[expr1:expr2]
```

The characters located between the expr1 and expr2 columns. Spaces are returned for indexes located above the SYMBOL or expr length

```
SYMBOL[expr1:] or (expr)[expr1:]
Is the same as
SYMBOL[expr1:length(SYMBOL], or expr[expr1:length(SYMBOL].
```

SYMBOL[:expr2] or (expr)[:expr2]
Is the same as
SYMBOL[1:expr2], or expr[1:expr2].

Examples:

```
a = '12345';a[2] = 'bcd'
                                                       * /
                          /* displays "1bcd5"
say a
a = '12345678';a[2:6] = 'BC'
                          /* displays "1BCBCB78"
                                                       */
say a
a = '12345678';
say a[2]
                          /* displays "2"
                                                       */
                         /* displays "345"
                                                       */
say a[3:5]
                         /* displays "123"
say a[:3]
                                                       */
                          /* displays "8
                                           */
say a[8:12]
a = '1234'; b = 'abcd'
say (a||b)[4:5]
                          /* displays "4a"
                                                       */
```

Using S/REXX within SEDIT

When running S/REXX within SEDIT in a windowing environment such as OPEN WINDOWS or MOTIF, all input and output operations are redirected to the window SEDIT was started from.

In order to allow the input operations to execute properly, **SEDIT** must run in the foreground.

Starting **SEDIT** in the background with a command like "xed &" or "sedit" will make **SEDIT** hang every time a TRACE ? or a PULL instruction is executed.

S/REXX New or Extended Instructions

This chapter describes new or extended instructions not described in Cowlishaw's book, "The REXX Language".

ADDRESS (UNIX) - Set Destination of Commands

ADDRESS 	env {exprc} {VALUE} exprv
The env des	stination may be one of the following:
UNIX	The Bourne Shell sh. This is the default when S/REXX runs standalone.
SH	Same as UNIX.
WINDOWS	Same as UNIX.
CSH	The C Shell csh.
TCSH	The tcsh shell.
KSH	The Korn Shell ksh.
EXEC	S/REXX attempts to execute directly the string passed to the EXEC environment without using any UNIX shell. The PATH is not searched and the usual shell redirection ">" and pipe " " characters are not treated specifically. Shell meta characters like "*" are also passed without expansion.
SEDIT	Available only in SEDIT macros. This is the default when S/REXX runs under SEDIT .
Examples:	

```
ADDRESS CSH

'ls ~/.cshrc' /* ~ would not work with ADDRESS SH */

/*

* To list a file actually named "*"

*/

ADDRESS EXEC

'/bin/ls -Ftla *' /* 'ls' would not work */
```

ADDRESS (WINDOWS) - Set Destination of Commands

ADDRESS	env {ex	prc}
	$ \{VALUE\}$	exprv

On WINDOWS systems, the env destination may be one of the following:

WINDOWS The default **WINDOWS** command interpreter. This is the default when **S/REXX** runs standalone.

First, the WINDOWS environment checks if the passed command is one of the following DOS commands:

ASSOC CLS COPY DIR DEL ERASE FTYPE MD MOVE RD REN RENAME START TIME TYPE VER VERIFY VOL

and starts a DOS interpreter instance to execute them. Note that using equivalent built-ins such as DEL(), COPY(), MKDIR(), RENAME() or RMDIR() within S/REXX is much faster than using a DOS command

For any other command, **S/REXX** searches in every directory in the path first for an expr.exe file, then for an expr.com file and finally for an expr.bat file.

- UNIX Same as WINDOWS.
- SEDIT Available only in **SEDIT** macros. This is the default when **S/REXX** runs under **SEDIT**.

Using UNIX Shells on WINDOWS

It is possible to install UNIX-like shells on WINDOWS systems.

S/REXX ADDRESS supports the SH, CSH, TCSH and KSH keywords to address such shells. **S/REXX** will use an environment variable with the same name to find a shell.

For example, if the user has installed the Hamilton C-SHELL in c:\hamilton\bin, the user may create a CSH environment variable in the following way:

```
option mixed setenv

$CSH = 'c:\hamilton\bin\csh.exe -FXC'

ADDRESS CSH

'ls -Ftl +a ~'
```

CD - Change Directory

CD {dir} makes dir the current directory.

The user may use the ~ . UNIX directory meta characters to specify a location.

Examples:	CD	makes the home directory current.
	CD '~'	has the same effect.
	CD '~/foo'	if the home directory is /users/john, makes
		/users/john/foo the current directory.
	CD ''	if the current directory is /users/john, makes
		/users the current directory.

Note: the **UNIX** directory meta characters must be enclosed in quotes.

On **WINDOWS** systems, the HOME environment variable is usually not defined. In this case, the " $\sim/$ " or " \sim \" directory shortcut is translated into "C:\".

DESBUF - Clear Stack

DESBUF is not part of the **S/REXX** language, but for VM/CMS compatibility it is implemented as an extension of the **UNIX** or **WINDOWS** environment. Therefore, it is recommended to enclose it in quotes in order to prevent the normal **S/REXX** variable substitution.

DESBUF format is:

DESBUF

clears the program stack buffer.

See Also: DROPBUF, MAKEBUF, SENTRIES

DO - Controlled Loop

The DO instruction offers the following extension:

```
DO name IN expr;
END {symbol};
```

The variable name will be assigned to every word of the REXX expression expr. A word is a set of characters surrounded by any number of blanks, tabulations or n end of line character.

Examples:

```
DO a IN 'word1 word2 word3'
say a
end a
```

displays:

word1 word2 word3

The following routine:

```
DO a IN '"ls"'
if state(a, 'd') then sayx 'du -s 'a
end a
```

shows the size of all the subdirectories.

DROPBUF - Remove Stack

DROPBUF is not part of the **S/REXX** language, but for VM/CMS compatibility it is implemented as an extension of the **UNIX** or **WINDOWS** environment. Therefore, it is recommended to enclose it in quotes in order to prevent the normal **S/REXX** variable substitution.

DROPBUF format is:

DROPBUF $\{n\}$ removes the specified stack buffer.

n specifies the number of the first stack buffer to be removed. DROPBUF will remove all stack buffers which number is greater than n.

When n is not specified, the most recently created buffer is removed.

See Also: <u>DESBUF</u>, <u>MAKEBUF</u>, <u>SENTRIES</u>

EXECIO - Input/Output Operations

EXECIO is not part of the **S/REXX** language, but for VM/CMS compatibility it is implemented as an extension of the **UNIX** or **WINDOWS** environment. Therefore, it is recommended to enclose it in quotes in order to prevent the normal **S/REXX** variable substitution.

EXECIO format is:

EXECIO	lines 	DISKR 	fn ft {fo	d {linenum}}	$\{(\{\texttt{FINIs}\}$	A	В}
	* *	DISKW	fn ft fd {recfm {I	{linenum lrecl}}}	$\{(\{\texttt{FINIs}\}$	В	C D}
		 diski 	fn ft fd {recfm {]	{linenum lrecl}}}	$\{(\{FINIs\}$	В	C D}
		 DISKD	fn ft fd	{linenum}	$\{(\texttt{FINIs}\}$		
		PRINT	printer		$\{(\{FINIs\}$	В	CD}

Options formats:

- (A) {Find /string/} {Zone n1 n2} {FIFO|LIFO} {SKip}
 {LOcate /string/}
 {Avoid /string/}
- (B) {Margins n1 n2} {STRIP} {NOTYPE {STEm xxx} ${VAR vvv}$
- (C) $\{CAse U | \underline{M}\}$
- (D) {STring xxx}

where:

lines	is the number of processed lines. lines must be any non-negative integer.
	With the VAR option, lines must be 1.

An asterisk * indicates that the operation is to terminate when a 0-length line is read during an output operation, or when an end-of-file condition is detected during an input operation.

When lines is specified as zero (0), no I/O operation takes place other than closing the file or printer when the FINIS option is specified.

For a DISKW or PRINT operation, if the STEM operand has not been specified and the lines operand exceeds the number of lines available on the program stack, **S/REXX** waits for user input at the terminal the **S/REXX** program was started from. If lines has been specified as a *, reading an empty line terminates the operation.

- DISKR reads lines from a disk file to the stack or **S/REXX** variables.
- DISKW writes lines from the stack, **S/REXX** variables or command line to a disk file. When using the DISKW function to write in the middle of a file, for example to write a string at line 10 of a 2000 line file, **S/REXX** does not truncate the file at line 10. Instead, it checks the string length, compares it to the original line 10 length, and moves the remainder of the file either to the left (shortening the file) or to the right, depending on whether the new line is shorter (left) or longer (right) than the original line. With large files, this process may take a while.
- DISKI inserts lines from the stack, **S/REXX** variables or command line to a disk file *before* the specified line. The remainder of the file is moved to the right. With large files, this process may take a while.
- DISKD removes the specified lines. The line pointer remains unchanged.

PRINT (UNIX)

writes lines from the stack, **S/REXX** variables or command line to the printer defined by the printer operand. **S/REXX** keeps these lines in memory until the FINIS operand is used to close the printer. Several printers may be opened simultaneously.

PRINT (WINDOWS)

writes lines from the stack, **S/REXX** variables or command line to the printer named printer. When printer is specified as an *, the default printer is used. printer can be specified within quotes. **S/REXX** keeps these lines in memory until the FINIS operand is used to close the printer. Only one printer may be opened at a time. The default printer can be changed with the dy_printer built-in function.

- recfm is implemented for VM/CMS compatibility. It must be V or F. When F is specified, the default lrecl is 80.
- lrecl specifies the length of each updated line of the file. When the data is larger than this length, it is truncated. When the data is shorter, it is padded with blanks.

fn is the filename part of the file. A period (.) may be used if no filename is required.

When fd is specified as a period (.), fn may be the full UNIX or WINDOWS pathname, including the file-directory and filetype parts. This allows the user to use a UNIX or WINDOWS like way to describe a file, such as:

```
execio 1 diskw ~/foo.c . .(
```

instead of the VM/CMS way, such as:

```
execio 1 diskw foo c ~(
```

- ft is the filetype part of the file. A period (.) may be used if no filetype is required.
- fd is the directory part of the file. When fd is not specified or specified as an asterisk (*) during an input operation, all the directories described in the PATH environment variable are searched.
- linenum is the absolute line number where a file operation is to begin. When not specified, or specified as 0, reading begins at the first line, and writing at the last line for the first operation. Subsequent operations will resume at the line where the previous operation ended.
- FINIS causes the specified file or printer to be closed.A subsequent DISKR operation will return the first line in the file.A subsequent DISKW operation will append data at the end of the file.A subsequent PRINT operation will start a new print job.

Option A

- FInd writes 2 strings to the stack LIFO (last-in first-out) by default, or FIFO (first-in first-out) when the FIFO option is specified:
 - 1) the contents of the first matched line.
 - 2) the relative and absolute line numbers of the first line that begins with the string specified between delimiters. The delimiter is the first non-blank character found after the FIND keyword. It does not need to be a /.

The ZONE option allows the user to search for a string starting at the specified n1 column. n2-n1 must be greater than the length of string.

When used with the STEM xxx option, FIND will update the xxx*n* variables in the following way:

	1)	xxx0 is set to 2.		
	2)	xxx1 is filled with the first line that matches the condition.		
	3)	xxx2 is filled with the relative and absolute line numbers. The relative line number is the number of lines scanned before the match occurs.		
LOcate	is lik (or zo	e the FIND option, except the string may occur any place within a line one portion of that line).		
Avoid	is lik that l	s like the LOCATE option, except the search is for a line (or zone portion of hat line) that does not contain the specified characters.		
Zone	restri opera	cts the portion of the lines searched during a FIND, LOCATE or AVOID ation.		
	speci	fied as *, the search is performed through the end of the line.		
FIFO	the li excep	nes are written to the stack in first-in first-out order. This is the default, of for the FIND, LOCATE or AVOID operations.		
LIFO	the li the F	nes are written to the stack in last-in first-out order. This is the default for IND, LOCATE or AVOID operations.		
SKIP	preve	ents a read operation from writing to the stack.		

Option B

Margins	specifies that only columns n1 through n2 (inclusive) are to be processed. If
	n2 is specified as *, the process is performed through the end of the line.

- STRIP removes the trailing blanks from any output lines or lines returned.
- NOTYPE suppresses the display of any **S/REXX** messages when an I/O error occurs.
- STEm xxx the variables xxxn will be used to supply input data for output-type operations. They will be the destination for output for the input-type operations. xxx1 is the first used or created variable, xxx2 the second, and so on. xxx0 will be set to the number of lines returned for the input-type operations.
- VAR vvv the variable vvv will be used to supply input data for output-type operations. It will be the destination for output for the input-type operations. When VAR is specified, lines must be specified as 1.

Option C

Case	U	the data read is translated to uppercase.
Case	М	the data read is not translated. This is the default.

Option D

STRING supplies output data explicitly. Any characters following the STRING keyword are treated as string data. Therefore, STRING must be the final option on the command line.

The EXECIO return codes have the following meanings:

0	Success.
2	End of file condition on DISKR operation.
3	No match when using a FIND/LOCATE/AVOID option.
24	Bad parameter list.
28	File not found.
29	Invalid printer (WINDOWS only)
101	I/O error.
2008	Invalid STEM or VAR operand.

Notes: On **WINDOWS** systems, the HOME environment variable is usually not defined. In this case, the "~/" or "~\" directory shortcut is translated into "C:\".

If fn, ft or fd contains blanks, they must be surrounded with quotes or double quotes.

```
Examples:
```

```
'execio 2 diskr foo c ../usr/john 5(stem ff.'
places lines 5 and 6 of the ../usr/john/foo.c file into the ff.1 and ff.2 variables.
ff.0 is set to 2.
```

```
'execio 1 diskr foo c ../usr/john'
```

since the .../usr/john/foo.c file was not closed by the previous EXECIO call, the next line (line 7) is placed into the stack.

'execio 2 diskw foo . ~ 7 f 90(finis stem ff.'

writes the contents of ff. 1 and ff. 2 into the \sim/foo file, starting at line 7, and padding those lines with blanks up to 90 columns. The \sim/foo file is closed at EXECIO termination. Note the use of the period (.) placeholder to specify that the file does not have any filetype.

'execio * diskr . cshrc ~(find \$setenv\$ stem ff.'

scans the \sim /.cshrc file, looking for the setenv string. Note the use of the period (.) placeholder to specify that the file does not have any filename.

```
'execio 1 diskw foo c ~(string /* NOTREACHED */'
adds the string /* NOTREACHED */ at the end of the file ~/foo.c
```

'execio * diskr "c:\Program Files\SEDIT profile.sedit" . .(stem ff.'
reads the "c:\Program Files\SEDIT\profile.sedit" file.

'execio * PRINT "LASERJET IIISI" (stem ff.'

on **WINDOWS**, prints on the "LASERJET IIISI" printer. Quotes are mandatory when the name of the printer contains blanks.

```
'execio * PRINT * (stem ff.'
```

on WINDOWS, prints on the default printer.

GLOBALV - Share Variables

GLOBALV is not part of the **S/REXX** language, but for VM/CMS compatibility it is implemented as an extension of the **UNIX**, **WINDOWS** or **SEDIT** environment. Therefore, it is recommended to enclose it in quotes in order to prevent the normal **S/REXX** variable substitution.

When OPTION NOGLOBALV is in effect, the initial processing relative to the GLOBALV command does not take place, and GLOBALV will not be recognized as an extension to the **UNIX**, **WINDOWS** or **SEDIT**environment.

GLOBALV format is:

```
globalv init
        {select {grp}}
       {select {grp}} set name1 {val1 name2{....}}
       {select {grp}} sets name1 {val1 name2{....}}
       {select {grp}} setp name1 {val1 name2{....}}
       {select {grp}} setl name {val}
       {select {grp}} setls name {val}
        {select {grp}} setsl name {val}
        {select {grp}} setlp name {val}
        {select {grp}} setpl name {val}
        {select {grp}}
                       list
                             {name1 {name2 ...}}
        {select {grp}} stack {name1 {name2 ...}}
        {select {grp}} put
                             name1 {name2 {...}}
                             name1 {name2 {...}}
        {select {grp}} puts
        {select {grp}}
                             name1 {name2 {...}}
                       putp
        {select {grp}} get
                             {name1 {name2 ...}}
        {select {grp}} purge
        grplist
       grpstack
```

An S/REXX script, called the parent, can start several other S/REXX scripts, either by using the UNIX or WINDOWS environment, or the CALL command when OPTION NOLOAD is in effect.

The GLOBALV command lets an **S/REXX** script and its descendants share a common set of values, and also retain them for subsequent use by other parents.

GLOBALV maintains groups of variables in the GLOBALDIR/srexx.globalv directory. By default, GLOBALDIR is the home ~ directory on UNIX, and the C: directory on WINDOWS.

GLOBADIR can be changed by creating a GLOBALVHOME environment variable. That can be done at the start of the parent **S/REXX** script:

call setenv "GLOBALVDIR", "/tmp"

GLOBALV supports use of more than one group. This allows for grouping distinct variables that are either related or often used together.

Variables defined for the current parent **S/REXX** script are retained in the GLOBALDIR/srexx.globalv/storage.xxxx directory, where xxxx is unique to the parent script. Those required longer than a single parent existence are retained in the GLOBALDIR/srexx.globalv/session and GLOBALDIR/srexx.globalv/lasting files.

These two files and a third file (GLOBALDIR/srexx.globalv/initial) are the source from which GLOBALV creates and initializes the variable or variables in the storage.xxxx file. The initial file is normally created by the user as an alternative way of defining a large number of initial variables.

init allocates and initializes global variable or variables in the storage.xxxx file from the variables stored in the lasting, session, and initial files. Variables defined in the session file override identical variables defined in the lasting file, which override identical variables defined in the initial file.

GLOBALV INIT is performed automatically if not explicitly requested before other GLOBALV requests.

select {grp}

identifies the global variable group that is the subject of this or subsequent calls. If no function is specified, GLOBALV sets the default group for subsequent calls. The default is set to the grp group or to unnamed if grp is not specified. A GLOBALV SELECT command that does specify a function affects only the group specified in the command. It has no effect on setting or resetting the default group.

SET, SETS, SETP name1 {{val1 name2{....}}

assigns the vali values to the name i variables. SET fields are delimited by blanks and the values cannot contain any blanks. (Use the SETL command for such values.) If vali is not specified, the value is assumed to be an empty string. SET adds the assignments in the selected or default global variable group in storage. SETS adds or replaces the assignments in the selected or default group and appends it to the session file. SETP adds or replaces the assignments in the selected or default group and appends it to the lasting file. SETL, SETLS, SETSL, SETLP, SETPL name {val}

assigns the specified literal val value, which may contain blanks, to the name variable. The first blank following the name delimits the name from the value field and is not part of the value. All characters following this blank (including any other blanks) are part of the value. If val is not specified, the value is assumed to be an empty string.

SETL adds the assignment in the selected or default global variable group in storage. SETLS adds the assignment in the selected or default group and appends it to the session file. SETSL is the same as SETLS. SETLP adds the assignment in the selected or default group and appends it to the lasting file. SETPL is the same as SETLP.

LIST

displays a list of the specified variable name or names, from the selected or default group, and their associated values. If no name is specified, all variables in the selected or default group are listed.

STACK

places the values associated with the specified variable name or names, from the selected or default group, LIFO in the program stack. The variable named first in the command is the first retrieved from the stack. If a variable is not found in the group, an empty string is stacked. The command has no effect if the variable name is omitted.

PUT, PUTS, PUTP

PUT assigns the value of the **S/REXX** variable specified in name as a global value in the selected or default global variable group. PUTS does the same, and appends the value to the session file. PUTP does the same, but appends the value to the lasting file.

Usage note: to be compatible with its VM/CMS implementation, the various PUT commands do not perform a complete stem substitution. For example:

GET

assigns values from the specified or default global variable group to the specified **S/REXX** variable names. If no names are specified, GET does nothing.

Usage note: to be compatible with its VM/CMS implementation, GET does not perform a complete stem substitution. See the example above.

PURGE

clears the variables from the selected group in storage.xxxx. Used without SELECT, PURGE clears all variables in all groups.

GRPLIST

displays a list of all groups.

GRPSTACK

stacks LIFO the names of all groups. An empty string delimiter indicates the end of the stacked names.

The GLOBALV return codes have the following meanings:

0	Success.
1000024	No Function Specified on GLOBALV command.
1100000	I/O Error reading GLOBALV type files.
1500000	Invalid HOME or GLOBALVHOME.
1501000	I/O Error on initial.
1502000	I/O Error on lasting.
1503000	I/O Error on session.
1504000	I/O Error on storage.
1000004	Invalid argument.
1505000	Unable to lock file.

Examples:

```
'globalv select grp1 set var1 val_var1 var2 val_var2 var3'
```

places the 'val_vari' strings into the grp1 group vari variables. The previous default group is not changed.

```
'globalv select grp1'
```

sets grp1 as the default group.

'globalv get var2'

retrieves into the **S/REXX** var2 variable the previously saved val_var2 value.

LOWER - Lower Case Translation

LOWER {varlist}

translates the contents of the variables described by varlist into lowercase.

It is not an error to include a non-initialized variable into varlist.

Example: lower a b

MAKEBUF - Create Stack

MAKEBUF is not part of the **S/REXX** language, but for VM/CMS compatibility it is implemented as an extension of the **UNIX** or **WINDOWS** environment. Therefore, it is recommended to enclose it in quotes in order to prevent the normal **S/REXX** variable substitution.

MAKEBUF format is:

MAKEBUF

creates a new stack buffer.

After MAKEBUF is executed, the rc variable contains the number of the newly created stack buffer.

Note: To prevent an error message from being displayed when the MAKEBUF command is executed, issue a TRACE OFF command first.

See Also: <u>DESBUF</u>, <u>DROPBUF</u>, <u>SENTRIES</u>

OPTION - Set Various Options

The OPTION instruction offers the following syntax:

OPTION MIXED | UPPER | LOWER SETENV | UNSETENV LOAD | NOLOAD GLOBALV | NOGLOBALV

Initial value: UPPER UNSETENV LOAD GLOBALV

By default, the REXX language is case insensitive. All variables, labels and subroutines are translated into uppercase before usage. Uninitialized variables return their name in upper-case.

When OPTION LOWER is in effect, all variables, labels and subroutines are translated into lowercase before usage. Uninitialized variables return their name in lower case.

When OPTION MIXED is in effect, capitalization is respected. For example, Var and var are two different variables.

When OPTION SETENV is in effect, variables starting with a dollar (\$) sign are treated as **UNIX** or **WINDOWS** environment variables. In addition, \$?var returns 1 (true) when the var environment variable exists.

Example:

```
OPTION MIXED SETENV
$PATH = '.:'$PATH
Aa = 'MyProg'
aa = 'param1'
call Proc Aa, aa
exit
Proc:procedure
parse arg v1, v2
v1 v2   /* Executes "MyProg param1", using a search  */
return  /* path starting with the "." current directory */
```

Although Proc is a procedure, \$PATH, being an environment variable, has the same value in Proc as in the main program.

OPTION NOLOAD prevents S/REXX from loading dynamically external routines.

When OPTION NOGLOBALV is in effect, the initial processing relative to the GLOBALV command does not take place, and GLOBALV will not be recognized as an extension to the **UNIX**, **WINDOWS** or **SEDIT** environment.

Notes: the OPTION statement is processed only at the initial program scanning. Once the program is started, OPTION is ignored. Its settings cannot be changed during execution.

S/REXX programs written in MIXED, LOWER or SETENV mode may be incompatible with usual REXX implementation.

Within **SEDIT**, OPTION GLOBALV | NOGLOBALV is taken in account only within the first **S/REXX** macro called, typically the profile.

PARSE - Parsing

For IBM compatibility, S/REXX has added the following extensions to the PARSE verb:

```
PARSE {UPPER} EXTERNAL {template}
is a synonym of the PARSE {UPPER} LINEIN {template} instruction.
```

PARSE {UPPER} NUMERIC {template}

The current numeric controls DIGITS FUZZ FORM are parsed with template.

Example:

/* di receives 9 */ /* fu receives 0 */ /* fo receives SCIENTIFIC */

parse numeric di fu fo

SAYN - Terminal Output

```
SAYN {expr} displays expr without appending a newline character at the end.
```

This instruction is similar to the SAY instruction. However, it allows the user to type a reply on the same line expr has been displayed.

Example:

sayn "Do you really want to exit ? "
pull rep .

will lead to the following dialog:

```
Do you really want to exit ? no
```

SAYX - Displayed Execution

SAYX {expr}

displays expr before passing it to the default environment.

SAYX expr is equivalent to the statement SAY expr followed by the statement expr.

SENTRIES - Query Stack

SENTRIES is not part of the **S/REXX** language, but for VM/CMS compatibility it is implemented as an extension of the **UNIX** or **WINDOWS** environment. Therefore, it is recommended to enclose it in quotes in order to prevent the normal **S/REXX** variable substitution.

SENTRIES format is:

SENTRIES

sets the rc variable to the number of entries in the current stack buffer.

Notes: To prevent an error message from being displayed when the SENTRIES command is executed, issue a TRACE OFF command before. Using the QUEUED() built-in function is a more efficient way to query the stack.

See Also: <u>DESBUF</u>, <u>DROPBUF</u>, <u>MAKEBUF</u>

TRACE - Debug Setting

S/REXX adds the following extensions to the TRACE verb:

TRACE !

inhibits command mode execution.

Commands passed to external environments such as UNIX, WINDOWS or SEDIT will be displayed, but not executed.

As each command is displayed, the RC REXX variable is set to 0.

Note that commands entered manually in interactive debug mode are always executed.

Using the TRACE ! command a second time switches ON the command execution.

Example: TRACE ?!i switches interactive debug mode ON, inhibits command execution, and displays intermediate results.

Warning: When running S/REXX within SEDIT in a windowing environment such as OPEN WINDOWS or MOTIF, all input and output operations are redirected to the window SEDIT was started from. In order to allow the input operations to execute properly, SEDIT *must run in the foreground*.

Starting **SEDIT** in the background with a command like "xed &" or "sedit" will make **SEDIT** hang every time a TRACE ? or a PULL instruction is executed.

When running **S/REXX** within **SEDIT** on **WINDOWS**, all input and output operations are redirected to a console window created by **S/REXX**. This console window can be removed by the Special-Close Console menubar item.

TRACE x starts the RXD graphical debugger.

See Using the RXD Debugger on page 653 for more information.

Extended TRACE output

S/REXX displays more information during a TRACE output.

Consider the following example:

```
trace i
a = 2
str = "This is a"
id = 1
tab.a = substr(str||" string", id+1, 2)
```

```
5 *-* a = 2
      "2"
 >L>
6 *-* str = "This is a"
 >L> "This is a"
7 * - * id = 1
      "1"
 >L>
8 *-* tab.a = substr(str || " string",id + 1,2)
 >V>
       "This is a"
       " string"
 >L>
 >0> "This is a string"
     "1"
 >V>
      "1"
 >L>
      "2"
 >0>
       "2"
 >L>
 >F> "hi"
```

S/REXX will display:

```
5 *-* a = 2
>>> A <--- "2"
6 *-* str = "This is a"
>>> STR <-- "This is a"
7 *-* id = 1
>>> ID <-- "1"
8 *-* tab.a = substr(str||" string", id+1, 2)
>C> TAB.A --> "TAB.2"
>V> STR --> "This is a"
>O> "This is a" || " string" --> "This is a string"
>V> ID --> "1"
>O> "1" + "1" --> "2"
>F> SUBSTR() --> "hi"
>>> TAB.2 <-- "hi"</pre>
```

UPPER - Upper Case Translation

UPPER {varlist}

translates the contents of the variables described by varlist into uppercase.

It is not an error to include a non-initialized variable into varlist.

Example: upper a b
S/REXX New or Extended Built-in Functions

This chapter describes modified or new built-in functions not described in Cowlishaw's book "The REXX Language".

ACOS - Arc Cosine

ACOS(arg) returns the radian arc cosine value of the argument arg in the range 0 to π .

ARCH - Get Hardware Information

ARCH() returns a hardware dependent string described in Appendix B: Hardware String on page 677.

ARG - Returns Argument String

In addition to the standard arg() REXX features, arg(0) returns the name of the currently executed **S/REXX** program.

ASIN - Arc Sine

ASIN(arg) returns the radian arc sine value of the argument arg in the range $-\pi/2$ to $\pi/2$.

ATAN - Arc Tangent

ATAN(arg) returns the radian arc tangent value of the argument arg in the range $-\pi/2$ to $\pi/2.$

CHANGE - Change String

CHANGE(str, old, new) changes the old string with the new string within str, and returns the modified string.

CHARIN - Read Character Input Stream

In addition to the standard CHARIN() REXX features, CHARIN(, 1, NN) returns NN characters read from the standard input without displaying them.

```
Example: sayn 'Enter a 3 characters password: '
pass = charin(,1,3)
say
say 'The password is :"'pass'"'
sayn 'Enter a 3 characters password: '
pass = charin(,,3)
say
say 'The password is :"'pass'"'
```

When reading the standard input, CHARIN() sets the special RC REXX variable to 0 in case of success, and to the 'EOF' uppercase string when the standard input is no longer available. In that case, CHARIN() returns an empty string. This allows the use of an **S/REXX** program as a standard input filter.

Consider the following test program:

```
#! /home/xed/srexx
do forever
  val = charin()
  if rc = 'EOF' then exit
  say '"'upper(val)'"'
end
```

Typing (using an UNIX shell):

echo abc | test

would display:

"A" "B" "C" "

CHDIR - Change Directory

CHDIR(dir) makes dir the current directory.

The user may use the \sim .. directory meta characters to specify a location.

Examples: call chdir makes the home directory the current directory. call chdir '~' has the same effect. call chdir '~/foo' if the home directory is /users/john, makes/users/john/foo the current directory. call chdir '../foo' if the current directory is /users/john, makes/users/foo the current directory.

Notes: The directory meta characters must be enclosed in quotes. The CD instruction requires less typing for the same purpose. On **WINDOWS** systems, the HOME environment variable is usually not defined. In this case, the "~/" or "~\" directory shortcut is translated into "C:\".

CLEAR or CLS - Clear the Screen

CLEAR() and CLS() clear the screen when possible.

These functions return 0 in case of success, or an error message in case of failure.

CLOSE_CONS - Close a Console

CLOSE_CONS()

CLOSE_CONS is specific to the wsrexx.exe WINDOWS S/REXX version.

CLOSE_CONS closes the console opened by OPEN_CONS().

CONCAT - Concatenate Files

CONCAT(org,	dest)		
CONCAT appends the files described by the org string to the dest file.			
org	is a string which identifies the filenames of the files to be used as data input.		
dest	CONCAT read each input file in sequence, and appends their content to the dest file. If dest does not exists, it will be created first.		
Example:	call concat "file1 c:\file2", "e:\result"		

COS - Cosine

COS(ang) returns the cosine value of the radian argument ang.

CP or COPY - Copy Files

CP(string) COPY(string	J)
string	is a string which supports 3 formats:
"file1 file	2"
	CP copies the contents of file1 onto file2.
"file1 file	Each filename is copied to the indicated directory; the basename of the copy corresponds to that of the original. The destination directory must already exist for the copy to succeed.
"directory_	org directory_des" The directory directory_des must not exist. The directory_org directory is recursively copied to directory_des.
On UNIX syste	ms, CP preserves symbolic links.

CP sets up two variables:

- RC is set to 0 in the case of a success, or to 1 in the case of a failure, on any file to copy.
- RESULT is set to an empty string in the case of a success, or to a string with an error message indicating the cause of the failure.

Examples: call cp "test.srx test2.srx" call cp "test1 test2 test3 .\backup" call cp "c:\prog c:\prog.back"

CPUID - Workstation CPU Identifier

CPUID({'n'})

CPUID() returns the cpu identifier as an integer. CPUID('n') returns the cpu identifier in native form, which is hardware dependent. For example, on SUNs stations, CPUID('n') returns an hexadecimal number.

CSH - Pass UNIX Command

CSH(cmd{, stem}) executes the UNIX command cmd using the C shell csh.

When stem is not provided, the cmd output will be placed in the stack. The user will be able to read it using the parse pull command.

The queued () function may be used to return the number of lines in the stack.

When stem is provided, it must be a valid REXX name. It will be filled with the cmd output.

Example: call csh "df", tab tab.0 will contain the number of lines sent back by df. tab.1, tab.2, ... will contain the df output line by line.

See also the EXEC(), UNIX(), KSH() and TCSH() functions.

CUSERID, USERID - Get Userid

CUSERID(parm) returns the character login name of the user.

On UNIX systems, parm may be one of the following:

Login	returns the original login name, ignoring the use of the su UNIX command. This is the default when parm is omitted.
Real	returns the effective login name, which can be modified by the use of the su UNIX command.
Example:	if userid('r') ~= 'root' then

Example:	ιİ	user	ıd	('r')	~=	'ro	oot'	then
	{	say	ΊΙ	need	to	be	root	. .'
		exit	3					
	}							

CVTAILS - Get Active Stems Tails

CWD("str") returns the tails of the all stem variables derived from str.

CWD, GETCWD, GETWD - Get Current Directory

CWD() returns the current directory.

C2O - Character to Octal

C2O(str)

C2O converts the encoding of the str string to its 3-digit octal representation. If str is a null string, a null string is returned.

Examples: say C2O('123') /* Displays 061062063 */ say '"'C2O('')'"' /* Displays "" */

DATE - Get Current Date

DATE ('J') returns the date in the YYDDD format.

Example: say date('j') /* 92012 Perhaps */

DATE(nn) where nn is a whole number returns the date in YYYY/MM/DD format, considering that nn is the number of days elapsed since the base date 1 Jan 0001. This reverts the behavior of the DATE('b') function.

Example: date('b')+7) /* Same day next week date */

DATE('L') returns the date in the dd Month yyyy format.

DATE (parm, "dd/mm/yyyy") returns the value coresponding to the dd/mm/yyyy date instead of using the current day date.

DATE ('e4') returns the date in the dd/mm/yyyy format.

DEL or RM - Delete Files

DEL(ff)
RM(ff)

 $\tt RM($) and $\tt DEL($) remove the ff files, and returns the full path names of the deleted files.

ff may include the \sim .. **UNIX** or **WINDOWS** file meta characters. If a filename contains blanks, it must be surrounded with quotes or double quotes.

When RM fails, it sets the rc variable to a non-zero value, and returns an error message, such as:

RM() error: File does not exist

Examples: say rm("~/foo ~/test")
 could print: /user/john/foo /usr/john/test
 call rm '"/user/file with blanks"'
 call del "'c:\Program Files\log'"

DIR or LS - List Files

LS({pat{, stem{, case}}}) DIR({pat{, stem{, case}}})

LS searches for the files matching the pat pattern string.

The RESULT variable will be set to the number of matches.

pat	describes the files to match. pat may start with a directory indicator such as "/home" or "c:\Program Files\". Within pat, a "*" character matches any string and a "?" character matches any character.
stem	when stem is provided, it must be a valid REXX name. RESULT and stem.0 will contain the number of matching filenames. stem.1, stem.2, will contain the matching filenames. When stem is not provided, the matching filenames will be queued.
case	when case is not provided, it defaults to 'i' on WINDOWS systems, and to 'r' on UNIX systems. When case is set to 'i', LS ignores the capitalization when matching filenames. When case is set to 'r', LS respects the capitalization.
Example:	call ls 'c:\test*.f'
	<pre>call dir 'test???.bat', tab, 'i' do i = 1 to tab.0 say tab.i /* Could print test001.bat*/ end i</pre>

DY_ASCL - Add a Set of Strings to a Scrolled List

DY_ASCL(har	ndle, nt_scl, stem, {l_stem}, {pos})
handle	is the number returned by the DY_END() function.
nt_scl	is the number returned by the DY_SCL() function.
stem	is a valid REXX symbol. The derived stem values (stem.1, stem.2, etc) will be used to fill the list.
l_stem	is the length of the list of strings. When not provided, $stem.0$ will be used instead.
pos	is the position to insert the strings. When not provided, or when set to 0, the strings will be added at the end of the list.

DY_BEEP - Sound the Alarm

CALL DY_BEEP

DY_BUTTON - Make a Dialog Button Item

nn = DY_BUTTON(x, y, str{, Rb, Gb, Bb, Rf, Gf, Bf})

nn	is the item number. When the user clicks on the button, the dialog box callback, as defined by the DY_END() function, is called with
	its second argument set to the string Bnn (such as B1, B2, etc).
х	is the item column position. When x is set to 1, the item is displayed on the left of the dialog box.
У	is the dialog box line position. When y is set to 1, the item is displayed on the top of the dialog box.
str	is the string displayed within the button.
Rb, Gb, Bb	are the optional background color RGB values. These are integers between 0 and 255. The default MOTIF background color can be set with the dialog*button*background X11 resource.
Rf, Gf, Bf	are the optional foreground color RGB values. These are integers between 0 and 255. The default MOTIF foreground color can be set with the dialog*button*foreground X11 resource.
Note:	Individually colored items are not supported by the xsrexx OpenLook S/REXX version.

DY_BUTTON_COLOR - Change a Button Dialog Item Color

DY_BUTTON_C	OLOR(handle, nn, Rb, Gb, Bb, Rf, Gf, Bf})		
handle	is the number returned by the DY_END() function.		
nn	is the item number returned by the $DY_BUTTON()$ function.		
Rb, Gb, Bb	are the background color RGB values. These are integers between 0 and 255. The default MOTIF background color can be set with the dialog*button*background X11 resource.		
Rf, Gf, Bf	are the foreground color RGB values. These are integers between 0 and 255. The default MOTIF foreground color can be set with the dialog*button*foreground X11 resource.		
Note:	Individually colored items are not supported by the xsrexx OpenLook S/REXX version.		

DY_CH - Make a Choice Dialog Item

nt_ch	is the item number to be used by the DY_VCH() function. is the optional global label to be displayed.
	is the optional global label to be displayed.
txt	
x_txt	is the global label column position. When x_txt is set to 1, the label is displayed on the left of the dialog box.
y_txt	is the global label line position. When y_txt is set to 1, the label is displayed on the top of the dialog box.
txt <i>i</i>	is the label of the sub-item i.
Example:	<pre>call dy_start() nt_ch = dy_ch("Host:", 2, 1, "host0", "host1") hnd = dy_end("#", 0, 0, 25, 6, "n") dy_map(hnd)</pre>

displays:

9	/usr	
Host:	∑ host0	

DY_CH_COLOR - Change a Choice Dialog Item Color

DY_CH_COLOF	R(handle, nt_ch, Rb, Gb, Bb, Rf, Gf, Bf})
handle	is the number returned by the DY_END() function.
nt_ch	is the item number returned by the DY_CH() function.
Rb, Gb, Bb	are the background color RGB values. These are integers between 0 and 255. The default MOTIF background color can be set with the dialog*choice*background X11 resource.
Rf, Gf, Bf	are the foreground color RGB values. These are integers between 0 and 255. The default MOTIF foreground color can be set with the dialog*choice*foreground X11 resource.
Note:	Individually colored items are not supported by the xsrexx OpenLook S/REXX version.

DY_DESTROY - Destroy a Dialog Box

DY_DESTROY(handle) destroys the dialog box handle.

handle is the number returned by the DY_END() function.

 $\tt DY_DESTROY()$ must not be called inside the REXX subroutine callback defined by the dy_start() function call.

DY_DSCL - Remove a Set of Strings from a Scrolled List

DY_DSCL(har	ndle, nt_scl, pos, nb)
handle	is the number returned by the $\mathtt{DY_END}($) function.
nt_scl	is the number returned by the $\mathtt{DY_SCL}(\)$ function.
pos	is the position of the first string to be removed.
nb	is the number of strings to remove.

DY_END - End a Dialog Box

handle = DY_END("callback", x, y, ww, hh, "Grab" | "Ngrab" {, Rb, Gb, Bb})

DY_END terminates the dialog box started with DY_START.

- handle is the dialog box number to be used with the various DY_XXX() functions.
- callback when used in an SEDIT macro, callback is the SEDIT macro called at every user action. See S/REXX Dialog Management within SEDIT on page 613 for more details.

when used in a stand-alone REXX program, callback is the name of a subroutine to be called at every user action. See S/REXX Dialog Management on page 609 for more details.

callback receives two three arguments:

	handle reason	the dialog bo B <i>i</i> F <i>i</i> L <i>i</i> R <i>i</i> ^ <i>CC</i> return focus	bx handle. Button <i>i</i> . Top function key <i>i</i> . Left function key <i>i</i> . Right function key <i>i</i> . Control + <i>cc</i> character. Return or Enter key. The mouse entered the dialog box.
		SCi	Simple click on row scb of scrolled list <i>i</i> .
	scb	DSCi	Double click on row scb of scrolled list <i>i</i> . The row when clicking on a scrolled list.
x	is the dialog b is horizontally	ox column po centered reg	Siftion. When x is set to 0, the dialog box arding the SEDIT window position.
У	is the dialog box line position. When y is set to 0, the dialog box is vertically centered regarding the SEDIT window position.		
WW	is the dialog b	ox width.	
hh	is the dialog b	ox height.	
Grab	creates a transient dialog box. The user must enter a reply before being able to use SEDIT again. The dialog box is unmapped when the reply is entered.		
Nograb	creates a non- user unmaps i	transient dial t explicitly.	og box. The box stays mapped until the
Rb, Gb, Bb	are the backgr and 255. The dialog*bac	ound color R default MO ckground X	GB values. These are integers between 0 TIF background color can be set with the K11 resource.

DY_FOCUS - Give a Dialog Input Item the Keyboard Focus

DY_	_FOCUS	(handle,	nn)
-----	--------	----------	-----

- handle is the number returned by the DY_END() function.
- nn is the number returned by the DY_INPUT() function.

DY_FONT - Set the Dialog Font

DY_FONT(fontname)

DY_FONT makes the various dialog items use the fontname font.

On Windows, the syntax of fontname is "Name%Modifier%Height%Width".

Notes: When not specified, Modifier defaults to Regular, Height to 9 and Width to 15. If a font does not support the specified size, S/REXX will chose the closest. The modifier is localization specific. Bold used with an English version of Windows will have to be replaced with Gras with a French one.
Example: call dy font "Courier new%Regular%9%15"

DY_HEADER - Set the Dialog Box Header

DY_HEADER(handle, str)

- handle is the number returned by the DY_END() function.
- str is the string to be displayed on top of the dialog box.

DY_INPUT - Make a Dialog Input Item

nn = DY_INP	$UT(x, y, len, {str}{, Rb, Gb, Bb, Rf, Gf, Bf})$
nn	is the item number to be used by the $\tt DY_VINPUT()$ and the $\tt DY_SINPUT()$ functions.
x	is the item column position. When x is set to 1, the item is displayed on the left of the dialog box.
У	is the dialog box line position. When y is set to 1, the item is displayed on the top of the dialog box.
len	is the item length.
str	when specified, initializes the input item.
Rb, Gb, Bb	are the optional background color RGB values. These are integers between 0 and 255. The default MOTIF background color can be set with the dialog*input*background X11 resource.
Rf, Gf, Bf	are the optional foreground color RGB values. These are integers between 0 and 255. The default MOTIF foreground color can be set with the dialog*input*foreground X11 resource.
Note:	Individually colored items are not supported by the xsrexx OpenLook S/REXX version.

DY_INPUT_COLOR - Change an Input Dialog Item Color

DY_INPUT_CC	DLOR(handle, nn, Rb, Gb, Bb, Rf, Gf, Bf})
handle	is the number returned by the DY_END() function.
nn	is the item number returned by the $\mathtt{DY_INPUT}(\)$ function.
Rb, Gb, Bb	are the background color RGB values. These are integers between 0 and 255. The default MOTIF background color can be set with the dialog*input*background X11 resource.
Rf, Gf, Bf	are the foreground color RGB values. These are integers between 0 and 255. The default MOTIF foreground color can be set with the dialog*input*foreground X11 resource.
Note:	Individually colored items are not supported by the xsrexx OpenLook S/REXX version.

DY_LABEL - Make a Dialog Label Item

nn = DY_LABEL(x, y, str{, Rb, Gb, Bb, Rf, Gf, Bf})

- x is the item column position. When x is set to 1, the item is displayed on the left of the dialog box.
- y is the dialog box line position. When y is set to 1, the item is displayed on the top of the dialog box.
- str is the string displayed.
- Rb, Gb, Bb are the optional background color RGB values. These are integers between 0 and 255. The default **MOTIF** background color can be set with the dialog*label*background X11 resource.
- Rf, Gf, Bf are the optional foreground color RGB values. These are integers between 0 and 255. The default **MOTIF** foreground color can be set with the dialog*label*foreground X11 resource.
- Note: Individually colored items are not supported by the xsrexx OpenLook S/REXX version.

DY_LABEL_COLOR - Change a Label Dialog Item Color

DY_LABEL_COLOR(handle, nn, Rb, Gb, Bb, Rf, Gf, Bf})

- handle is the number returned by the DY_END() function.
- nn is the item number returned by the DY_LABEL() function.
- Rb, Gb, Bb are the background color RGB values. These are integers between 0 and 255. The default **MOTIF** background color can be set with the dialog*label*background X11 resource.
- Rf, Gf, Bf are the foreground color RGB values. These are integers between 0 and 255. The default **MOTIF** foreground color can be set with the dialog*label*foreground X11 resource.
- Note: Individually colored items are not supported by the xsrexx OpenLook S/REXX version.

DY_MAP - Map a Dialog Box

DY_MAP(handle) makes the handle dialog box visible.

handle is the number returned by the DY_END() function.

DY_OPEN (UNIX) - Displays the Contents of a Directory

DY_OPEN displays the following dialog box:



rc	is the return code. It will be set to 0 when the requested directory has been successfully scanned.
x	is the dialog box column position. When x is set to 0, the dialog box is horizontally centered regarding the screen when S/REXX is used as a UNIX script, or centered regarding the SEDIT window position when S/REXX is used as an SEDIT macro.
У	is the dialog box line position. When y is set to 0, the dialog box is vertically centered regarding the screen when S/REXX is used as a UNIX script, or centered regarding the SEDIT window position when S/REXX is used as an SEDIT macro.
ht	is the height of the file and directories scrolling lists.
stem	must be a valid S/REXX variable name. stem.0 will contain the number of selected files. stem.1, stem.2, etc, will contain the names of the selected files.
dir	is the initial directory to be scanned. When omitted, the current directory will be scanned.

- filt_f is the filter used to select which files are to be displayed. When omitted, it defaults to *, which means any file. When the regular expression switch is off, * means any set of characters. a*df* would for example match a_123.dfte. Several filters can be specified by using a; separator. Example: *.c;*.h
- filt_d is the filter used to select which directories are to be displayed.
- label is the label to be displayed on the top of the dialog box.
- lg_reg when set to 1, toggles on the regular expression search. When omitted, or set to 0, toggles off the regular expression search.
- Rb, Gb, Bb are the background color RGB values. These are integers between 0 and 255. The default **MOTIF** background color can be set with the dialog*background X11 resource.

A regular expression is a character string used to describe, in an extended way, a string to be matched. It uses special characters, called meta characters to describe the match to be done.

The meta characters are the following:

^	matches only at the beginning of a line.
\$	matches only at the end of a line.
\<	matches only at the beginning of a word.
\>	matches only at the end of a word.
	matches any single character.
[]	matches any character in a character class.
\(delimits the start of a subexpression. It is available for ∇I compatibility, but has no special meaning.
\)	delimits the end of a subexpression. It is available for VI compatibility, but has no special meaning.
*	repeats the preceding 0 or more times.

If you want to use a meta character as an ordinary character, you must precede it with a backslash $(\)$ character.

Examples:

^af

matches the string "af" only at the beginning of a line.

af\$

matches the string "af" only at the end of a line.

dc....is

matches the string "dc" followed by any 7 characters followed by the string "is".

[A-Z][a-z]

[A-Z] means any character from A to Z.

[a-z] means any character from a to z.

The whole expression above matches any alphabetical string starting with a capital letter.

The string "File001" will be matched. "F001" will not.

Note that the meta characters are not treated when enclosed in brackets:

[.\$]

matches the string ". \$". Without brackets, the user should type:

(\.\\$

for the same match.

Supported User Actions

The user can perform the following actions:

- Clicking once with the left mouse button on a displayed file selects this file, and displays its name in the file input zone.
- With the **MOTIF** version, holding the Shift key down while clicking extends the selection to several contiguous files. Holding the Control key down extends the selection to another, possibly non-contiguous, file.
- Double clicking on a file makes DY_OPEN return. stem will contain the name of all the selected files.
- Clicking once with the left mouse button upon a displayed directory selects this directory, and displays its name in the directory input zone.
- Double clicking on a displayed directory initiates a scan of the directory.
- Using the Return or Enter key when the keyboard focus is in the File input zone makes DY_OPEN return. stem will contain the name of the file displayed in that File input zone.
- Using the Return or Enter key when the keyboard focus is in the Directory input zone initiates a scan of the directory displayed in that zone. When this directory name does not start with a / or a ~, it will be considered as a subdirectory of the previously scanned directory.
- Using the Return or Enter key when the keyboard focus is in the File or Directory filter zone initiates a new scan of the previously scanned directory.
- Clicking on the OPEN button makes DY_OPEN return. stem will contain the name of all the selected files.
- Clicking on the CANCEL button makes DY_OPEN return. stem.0 will contain the 0 string.

• Clicking on the SCAN button initiates a new scan of the previously scanned directory.

The following /home/xed/xmac/dy_open.sedit macro is used by the **SEDIT** text editor to open new files:

```
* dy_open: opens a set of new files
    Syntax: DY_OPEN {dir}, {filt-file}, {filt-dir}, {lg_reg}
 *
    dir: The directory to scan, or //last to open the last directory
 *
            scanned
 */
signal on novalue
option mixed setenv
parse arg dir, ff, fd, reg
if dir = '' then dir = cwd()
else
 if dir = '//last' then
  { if $?last_dy_open_scanned then dir = $last_dy_open_scanned
                                   dir = '.'
    else
  }
if ff = '' then ff = '*'
if fd = '' then fd = '*'
if reg = '' then reg = 0
trace off
call dy_open 0, 0, 10, sfi, dir, ff, fd, "xed - dir:"cwd(), reg
if result = 0 then
 { do i = 1 to sfi.0
    'xed 'sfi.i
   end i
   if sfi.0 ~= 0 then $last_dy_open_scanned = fd(sfi.1)
 }
else 'prompt Unable to scan 'dir
```

DY_OPEN (WINDOWS) - Displays the Contents of a Directory

DY_OPEN displays the standard **WINDOWS** dialog box.

rc	is the return code. It will be set to 0 when the requested directory has been successfully scanned.
x	unused.
У	unused.
ht	unused.
stem	must be a valid S/REXX variable name. stem. 0 will contain the number of selected files. stem. 1, stem. 2, etc, will contain the names of the selected files.
dir	is the initial directory to be scanned. When omitted, the current directory will be scanned.
filt_f	 is the filter used to select which files are to be displayed. When omitted, it defaults to *, which means any file. Several filters can be specified by using a ; separator. Example: *.c;*.h
filt_d	unused.
label	is the label to be displayed on the top of the dialog box.
lg_reg	unused.

DY_PRINTER - Set the Default Printer

rr = DY_PRINTER()

On **WINDOWS** systems, DY_PRINTER displays the standard PRINT dialog box. The settings entered by the user will be used the next time this dialog box is displayed, or by the EXECIO command when printing.

rr is set to 1 when the user clicks on the OK button, and to 0 otherwise.

DY_PSCL - Set the First Displayed String¹

DY_PSCL(handle, nt_scl, pos)

- handle is the number returned by the DY_END() function.
- nt_scl is the number returned by the DY_SCL() function.
- pos is the rank of the string to be displayed on top of the scrolled list. The first string is the string number 1.

^{1.} DY_PSCL is not supported by the OpenLook xsrexx version.

DY_REFRESH - Redraw the Dialog Box

call DY_REFRESH

When an **S/REXX** macro is busy doing some processing, DY_REFRESH() can be used periodically to redraw all the currently displayed dialog boxes.

DY_RSCL - Replace a String in a Scrolled List

DY_RSCL(har	ndle, nt_scl, pos, string)
handle	is the number returned by the DY_END() function.
nt_scl	is the number returned by the DY_SCL() function.
pos	is the rank of the string to be replaced. The first string is the string number 1.
string	is the new string.

DY_SCH - Set a Choice Value

DY_SCH(hand	lle, nc, i)
handle	is the number returned by the $\mathtt{DY_END}($) function.
nc	is the number returned by the $\mathtt{DY_CH}(\)$ function.
i	is the index of the sub-item to be displayed.

DY_SINPUT - Set a Dialog Input Item Value

)

handle	is the number returned by the $\mathtt{DY_END}($) function.
n	is the number returned by the $\mathtt{DY_INPUT}($) function.
str	is the string to be displayed.

DY_SCL - Make a Scrolled List Dialog Item

nt_scl = D)	<pre>{_SCL(x, y, la, ht, stem, {l_stem}, {type} {, Rb, Gb, Bb, Rf, Gf, Bf})</pre>
nt_scl	is the item number, to be used by the various $\mathtt{DY_xSCL}(\)$ functions.
x	is the column position. When x is set to 1, the list is displayed starting on the left of the dialog box.
У	is the line position. When y is set to 1, the list is displayed starting on the top of the dialog box.
la	is the width of the list.
ht	is the number of lines displayed by the list.
stem	is a valid REXX symbol. The derived stem values (stem.1, stem.2, etc) will be used to fill the list.
l_stem	is the length of the list. When not provided, stem.0 is the default.
type	when type is the "Multiple" string, the list will permit multiple selections. This is the default when type is not specified. When type is the "Single" string, only one line can be selected.
Rb, Gb, Bb	the optional background color RGB values. These are integers between 0 and 255. The default MOTIF background color can be set with the dialog*list*background X11 resource.
Rf, Gf, Bf	the optional foreground color RGB values. These are integers between 0 and 255. The default MOTIF foreground color can be set with the dialog*list*foreground X11 resource.
Notes:	Individually colored items are not supported by the xsrexx OpenLook S/REXX version. The callback will receive different values when clicking or double clicking on an item. See the DY_END description on page 539 for more information. Double clicking on an item within a GRAB dialog box unmaps the dialog box. Simple clicking does not.

Example: the file {install-dir}/demo/demo_dy/dy_scl shows the use of every DY_xSCL function:

```
option mixed setenv
call dy_start()
$dismiss = dy_button(1, 1, "DISMISS")
call csh 'ls ~', tab
$handle_scl1 = dy_scl(2, 4, 11, 10, tab, /* tab.0 */, 'm')
$transfer = dy_button(26, 4, "TRANFER")
         = dy_button(26, 6, "DELETE")
= dy_button(26, 8, "TOP")
= dy_button(26, 10, "REPLACE")
$del
$top
$rep
$set
            = dy_button(26, 12, "SET")
$add
            = dy_button(26, 14, "ADD")
$handle_scl2 = dy_scl(39, 4, 11, 10)
$handle_dy = dy_end("dy_ex_cb", -25, -10, 67, 17.5, "n")
call dy_map $handle_dy
say
say '... Returned from dy_map(1)'
say
call dy_map $handle_dy
say
say '... Returned from dy_map(2)'
say
return
dy_ex_cb:procedure
parse arg handle reason
say 'dy_ex_cb: 'reason
select
  when reason = 'F1' ,
       reason = 'B'$dismiss then
        { call dy_unmap(handle)
           call dy_destroy(handle)
           exit 0
        }
```

```
when reason = 'B'$transfer then
    { call do_it
     return 0
    }
 when reason = 'B'$del then
    { call dy_vscl handle, $handle_scl1, num
     if num.0 ~= 0 then call dy_dscl handle, $handle_scl1, num.1,
     num.0
     return 0
    }
 when reason = 'B'$top then
    { call dy vscl handle, $handle scl1, num
     if num.0 ~= 0 then call dy_pscl handle, $handle_scl1, num.1
     return 0
    }
 when reason = 'B'$rep then
    { call dy_vscl handle, $handle_scl1, num
     if num.0 ~= 0 then call dy_rscl handle, $handle_scl1, num.1,
      "New String"
     return 0
    }
 when reason = 'B'$set then
    { call dy_sscl handle, $handle_scl1, 2, 1
     return 0
    }
 when reason = 'B'$add then
    { strings.1 = 'Last'
     call dy ascl(handle, $handle scl1, strings, 1, 0)
     call dy_ascl(handle, $handle_scl2, strings, 1, 0)
     return 0
    }
 when reason = 'focus' then
    { say '.... Focus'
     return 0
    }
 otherwise return 0
end
do_it:procedure expose handle
 say '-----'
 l_num = dy_vscl(handle, $handle_scl1, num)
 do i = 1 to num.0
   say num.i
 end
 say
```

```
l_num = dy_vscl(handle, $handle_scl1, num, strings)
do i = 1 to num.0
   say num.i strings.i
end
call dy_ascl(handle, $handle_scl2, strings, strings.0, 0)
return
```

On UNIX systems, typing:

```
% cd /home/xed/demo/demo_dy
% ./dy_scl
```

displays:



On WINDOWS systems, type:

```
C:\> chdir "\Program Files\SEDIT\demo\demo_dy"
C:\> "\Program Files\SEDIT\wsrexx" dy_scl
```

DY_SCL_COLOR - Change a Scrolled List Dialog Item Color

DY_SCL_COLOR(handle, nt_scl, Rb, Gb, Bb, Rf, Gf, Bf})

- handle is the number returned by the DY_END() function.
- nt_scl is the item number returned by the DY_SCL() function.
- Rb, Gb, Bb are the background color RGB values. These are integers between 0 and 255. The default **MOTIF** background color can be set with the dialog*list*background X11 resource.
- Rf, Gf, Bf are the foreground color RGB values. These are integers between 0 and 255. The default **MOTIF** foreground color can be set with the dialog*list*foreground X11 resource.

Note: Individually colored items are not supported by the xsrexx OpenLook S/REXX version.

DY_SLABEL - Set a Dialog Label Item Value

DY_SLABEL(handle, n, str)

handle	is the number returned by the $\mathtt{DY_END}($) function.
n	is the number returned by the $\mathtt{DY_LABEL}($) function.
str	is the string to be displayed.

DY_SSCL - Select or Unselect a String Within a Scrolled List

DY_	SSCL	(handle,	nt_	_scl,	pos,	{set	}))
-----	------	----------	-----	-------	------	------	-----	---

handle	is the number returned by the DY_END() function.
nt_scl	is the number returned by the $DY_SCL()$ function.
pos	is the rank of the string to be selected or unselected. The first string is the string number 1
set	when set to 1, or when not specified, the string is selected. When set to 0, the string is unselected.

DY_START - Start a Dialog Box

DY_START() must be called before using the DY_INPUY(), DU_LABEL(), DY_BUTON() and DY_TG() functions.

DY_STG - Set a Dialog Toggle Value

DY_STG(hand	lle, nt_g, nt, val)
handle	is the number returned by the DY_END() function.
nt_g	is the number returned by the DY_TG() function.
nt	is the rank of the sub-item to be set to val.
val	is 0 (false) or 1 (true). The OpenLook version only responds to a 1 value.

DY_TG - Make a Dialog Toggle

nt_g = DY_	IG({txt}, x_txt, y_txt,
	x1, y1, txt1, set1{,
	$x2, y2, txt2, set2\{$
nt_g	is the item number to be used by the $\mbox{DY_VTG}(\)$ and the $\mbox{DY_STG}(\)$ functions.
txt	is the optional global label to be displayed.
x_txt	is the global label column position. When x_txt is set to 1, the label is displayed on the left of the dialog box.
y_txt	is the global label line position. When y_{txt} is set to 1, the label is displayed on the top of the dialog box.
xi	is the column position of the sub-item <i>i</i> .
yi	is the line position of the sub-item <i>i</i> . The SEDIT OpenLook version stacks sub-items vertically or horizontally. The MOTIF version respects precisely the (xi, yi) coordinates.
txt <i>i</i>	is the label of the sub-item i.
seti	either 1 (true) or 0 (false).
Example:	<pre>call dy_start() nt_g = dy_tg("toggle1:", 2, 1,</pre>
	dy_map(hnd)

displays:

🥥 /home/m1/sedit/obj/xxed		
toggle1:	string0	
	string1	
	string2	

DY_TG_COLOR - Change a Toggle Dialog Item Color

DY_TG_COLOF	R(handle, nt_g, Rb, Gb, Bb, Rf, Gf, Bf})
handle	is the number returned by the DY_END() function.
nt_g	is the item number returned by the $DY_TG()$ function.
Rb, Gb, Bb	are the background color RGB values. These are integers between 0 and 255. The default MOTIF background color can be set with the dialog*toggle*background X11 resource.
Rf, Gf, Bf	are the foreground color RGB values. These are integers between 0 and 255. The default MOTIF foreground color can be set with the dialog*toggle*foreground X11 resource.
Note:	Individually colored items are not supported by the xsrexx OpenLook S/REXX version.

DY_UNMAP - Unmap a Dialog Box

DY_UNMAP(handle) makes the handle dialog box invisible.

handle is the number returned by the DY_END() function.

DY_VINPUT - Get a Dialog Input Item Value

$str = DY_VI$	NPUT(handle, nn)
str	is the contents of the nn input item.
handle	is the number returned by the $DY_END()$ function.
nn	is the number returned by the $\mathtt{DY_INPUT}($) function.

DY_VCH - Get a Dialog Choice Value

$val = DY_V$	CH(handle, nt_ch)
val	is the value of the CHOICE dialog item.
handle	is the number returned by the $\mathtt{DY_END}($) function.
nt_ch	is the number returned by the DY_CH() function.

DY_VSCL - Retrieve a Scrolled List Ranks and Contents of the Selected Strings

l_num = DY_	_VSCL(handle, nt_scl, num, {cnt})
l_num	is the number of selected items.
handle	is the number returned by the DY_END() function.
nt_scl	is the number returned by the DY_SCL() function.
num	is a valid REXX symbol. The derived stem values (num.1, num.2, etc) will be filled with the rank of the selected items. num.0 will contain the number of selected items.
cnt	is a valid REXX symbol. The derived stem values (cnt.1, cnt.2, etc) will be filled with the selected items. cnt.0 will contain the number of selected items.

DY_VTG - Get a Dialog Toggle Item Value

val = DY_VTG(handle, nt_g, i)

val	is the logical value (0 or 1) of the sub-item i of the nt_g toggle item.
handle	is the number returned by the DY_END() function.
nt_g	is the number returned by the DY_TG() function.
i	is the sub-item number.

DY_WARP - Set Mouse Handling

old = DY_WARP({str})

str	when set to "ON", S/REXX moves the mouse onto a GRAB dialog
	box when it is displayed. When set to "OFF", the mouse position
	remains unchanged.

old is set to ON or OFF, according to the previous setting.

EXEC - Pass UNIX Command Directly

EXEC(cmd{, stem}) executes the UNIX command cmd directly.

S/REXX attempts to execute directly the cmd string passed without using any UNIX shell. The PATH is not searched and the usual shell redirection ">" and pipe " | " characters are not treated specifically. Shell meta characters like "*" are also passed without expansion.

On **WINDOWS** systems, EXEC() is identical to the WINDOWS() built-in function.

When stem is not provided, the cmd output will be placed in the stack. The user will be able to read it using the parse pull command.

The QUEUED() function may be used to return the number of lines in the stack.

When stem is provided, it must me a valid REXX name. It will be filled with the cmd output.

- Example: call exec "/bin/ls *", tab
 /* lists a file actually named * */
 tab.0 will contain the number of lines sent back by /bin/ls.
 tab.1, tab.2, ... will contain the ls output line by line.
 Note: EXEC() not supporting the meta characters, use CSH() or KSH() to pass
- a command such as call csh 'ls ~/foo*.c'

See also the UNIX(), CSH(), TCSH() and KSH() functions.

EXTERNALS - Pending Input

On **UNIX** systems, EXTERNALS () returns the number of characters available in the standard input stream.

On **WINDOWS** systems, EXTERNALS() returns 0 when the standard input is empty, and 1 otherwise.

FD - Get File-Directory

FD(fname) returns the fname directory part.

Example:	<pre>a = fd("/usr/john/foo.c")</pre>
	returns "/usr/john".

FILECONV - UNIX or WINDOWS File Conversion

FILECONV(string)

string "Unix" or "Windows"

When string is set to **UNIX** (the default on **UNIX** systems), **S/REXX** considers that a line in a file ends with a newline character.

When string is set to WINDOWS (the default on **WINDOWS** systems), **S/REXX** considers that a line in a file ends either with a newline character or with a ^M character followed by a newline character. In addition, a ^Z character encountered alone on a line will indicate an end of file condition.

When writing to a file, **S/REXX** will terminate every line with a ^M character before the newline character, and end the file with a ^Z character following the last newline character.

Using FILECONV('W') on **UNIX** systems permits the reading of **WINDOWS** files eliminating M and Z characters.

Using FILECONV('U') on **WINDOWS** systems permits the writing of files without M and Z characters, making them easier to share with **UNIX** systems.

Example: call fileconv 'u'

FLFILES - Get FLIST Files

call flfiles tab returns in the tab stem the full names of the files listed within the current **FLIST** level. tab. 0 contains the number of files returned, tab.i with i varying from 1 to tab.0 contains the file names.

FN - Get Filename

FN(fname) returns the fname filename part.

Example:	<pre>a = fn("/usr/john/foo.c")</pre>
	returns "foo".

FOLLOW - Follow Symbolic Links

FOLLOW(file) checks if any component of file is a symbolic link, and replaces it with the file to which the symbolic link points. The full pathname of the file will be returned. If file is recursively linked to itself, or if the file directory component does not exist, FOLLOW returns an empty string.

FOLLOW sets RC to zero in case of success. In case of error, FOLLOW returns an empty string and sets RC and to -1.

Example:	call chdir '/users/john'
	'ln -s ./somefile ./somefile.link'
	<pre>say follow('somefile.link')</pre>
	displays: /users/john/somefile

FORK - Spawn a New Process

FORK()

On **UNIX** systems, FORK () causes creation of a new process. The new process (child process) is an exact copy of the calling process (parent process). The child process inherits the variables and the programming state from its parent process. However, all opened files are closed within the child process, and the child process cannot process dialog boxes opened by the parent process. The child process of an **SEDIT** macro cannot pass commands to **SEDIT**.

Upon successful completion, FORK() returns a value of 0 to the child process and returns the process ID of the child process to the parent process. Otherwise, a value of -1 is returned to the parent process.

On WINDOWS systems, a value of -1 is always returned.

Example:

```
father = getpid()
a = fork()
if a = 0 then
 { say 'Son: 'getpid() '(Father is 'father')'
  do i = 1 to 5
    say '... Son'
    call sleep 1
  end
  say 'Son: exiting'
  exit
 }
else
 { say 'Father: 'getpid() '(son is 'a')'
  call usleep 500000
  say 'Father: waitpid(,"N") = 'waitpid(a, 'n')
  say 'Father: waiting'
  say 'Father: waitpid = 'waitpid(a)
  say 'Father: exiting'
 }
```

would display:

```
Father: 28159 (son is 28160)
Son: 28160 (Father is 28159)
... Son
Father: waitpid(,"N") = 0
Father: waiting
... Son
... Son
... Son
Son: exiting
Father: waitpid = 28160
Father: exiting
```

FT - Get Filetype

FT(fname) returns the fname filetype part.

Example:	<pre>a = ft("/usr/john/foo.c")</pre>
	returns ".c".

GETDISKSPACE - Get Free Disk Space

GETDISKSPACE({mount_point}) returns a string containing in kbytes the amount of disk space occupied by the mount_point file system, the amount of used and available space, and the percentage of the file system's total capacity used.

If mount_point is not specified, the root directory ("/" on UNIX systems, "c:" on WINDOWS systems) will be used. mount_point can be any directory on UNIX systems, and any drive letter ("c:") on WINDOWS systems.

An empty string is returned in case of error.

Example:	<pre>say '"'getdiskspace("/")'"' could display</pre>			
	"288119 158610 100698 61"			
Note:	GETDISKSPACE is not supported on Linux, SCO and SunOS systems.			

GETENV - Get Environment Variable

GETENV(var) returns the value of the var environment variable.

Example: a = getenv("PATH")

See also the SETENV() function.

GETFILE - Get File Content

rc = GETFILE({start}, {end}, {stem})

Within SEDIT, GETFILE retrieves the contents of the current file.

start	is the first file line to be retrieved. When omitted, $\verb+start$ defaults to 1.	
end	is the last file line to be retrieved.When omitted, end defaults to the lenght of the current file.	
stem.0	the number of retrieved lines.	
stem.i	the <i>ith</i> retrieved line content.	
rc	the number of retrieved lines.	
When stem is not provided, the GETFILE output will be placed in the stack.		
Example:	call getfile 12, 666, tab	

GETPID - Process Identifier

GETPID()

GETPID returns the current process number. Every process has a different process number. This number can be used to create a unique filename.

HOSTNAME - Workstation Hostname

HOSTNAME()

HOSTNAME returns the name of the workstation.

JUSTIFY - Justify String

JUSTIFY(string, len{, pad}) returns a string of length len.

The default pad value is the blank character.

string is first normalized. Multiple blanks are converted to single blanks, and leading and trailing blanks are removed.

If the length of the normalized string is greater than len, string is then truncated on the right and all trailing blanks are removed.

If the length of the normalized string is less than len, extra pad characters are then added evenly from left to right to provide the required length, and the blanks between words are replaced with the pad character.

Examples:

```
justify('ONE THREE TWO',11,'-'): 'ONE-THREE-T'
justify("", 9, "+"): '+++++++'
justify("The red shoe", 15): 'The red shoe'
justify("The red shoe", 15, "+"): 'The+++red++shoe'
```

KILL - Terminate a Process

KILL(pid{, sig})

On **UNIX** systems, KILL() sends to the process whose process ID (returned by the FORK() built-in function) is pid the signal sig. sig can be any number, or one of the usual **UNIX** signal strings:

SIGIOT	SIGTRAP
SIGKILL	SIGTSTP
SIGLOST	SIGTTIN
SIGPIPE	SIGTTOU
SIGPOLL	SIGURG
SIGPROF	SIGUSR1
SIGQUIT	SIGUSR2
SIGSEGV	SIGVTALRM
SIGSTOP	SIGWINCH
SIGSYS	SIGXCPU
SIGTERM	SIGXFSZ
	SIGIOT SIGKILL SIGLOST SIGPIPE SIGPOLL SIGPROF SIGQUIT SIGSEGV SIGSTOP SIGSYS SIGTERM

The sig default value is SIGKILL, which will terminate the pid process.

The first 3 letters of sig can be omitted: ALRM is the same as SIGALRM.

Upon successful completion, a value of 0 is returned. Otherwise, a value of -1 is returned.

On WINDOWS systems, KILL() always returns a value of -1.

KSH - Pass UNIX Command

KSH(cmd{, stem}) executes the UNIX command cmd using the Korn shell ksh.

When stem is not provided, the cmd output will be placed in the stack. The user will be able to read it using the parse pull command.

The queued () function may be used to return the number of lines in the stack.

When stem is provided, it must be a valid REXX name. It will be filled with the cmd output.

Example: call ksh "df", tab tab.0 will contain the number of lines sent back by df. tab.1, tab.2, ... will contain the df output line by line.

See also the EXEC(), UNIX(), CSH() and TCSH() functions.

LINEIN, LINEOUT - Input / Output

The **S/REXX** LINEIN() and LINEOUT() functions comply with the standard REXX LINEIN() and LINEOUT() functions as described in "The REXX Programming Language".

The following peculiarities must be noted:

The UNIX or WINDOWS file system does not know about lines, only about characters. The lines delimiter is implied by the presence of the "OA"x newline character on UNIX, and by the ^M character followed by the newline character on WINDOWS.

At the first LINEIN() or LINEOUT() invocation, **S/REXX** scans the entire file and memorizes the newline character positions, permitting an extremely fast line access on subsequent calls.

When using the LINEOUT() function to write in the middle of a file, for example to write a string at line10 of a 2000 line file, **S/REXX** does not truncate the file at line 10. Instead, it checks the string length, compares it to the original line 10 length, and moves the remainder of the file either to the left or to the right, depending on whether the new line is shorter (left) or longer (right) than the original line. With large files, this process may take a while.

The filename parameter may include the ~ .. file meta characters.

When reading the standard input, LINEIN() sets the special RC REXX variable to 0 in case of success, and to the 'EOF' uppercase string when the standard input is no longer available. In that case, LINEIN() returns an empty string. This allows the use of an **S/REXX** program as a standard input filter.

Consider the following test program:

```
#! /home/xed/srexx
do forever
  val = linein()
  if rc = 'EOF' then exit
  say upper(val)
end
```

Typing (using an UNIX shell):

echo abc | test

would display:

ABC
MKDIR - Make a Directory

MKDIR(dir) creates the dir directory, and returns the full dir pathname.

dir may include the ~ .. file meta characters.

When MKDIR fails, it sets the rc variable to a non-zero value, and returns an error message, such as:

MKDIR() error: File exists

Example: say mkdir("~/bin")

could print: /user/john/bin

MV or RENAME - Rename a File

RENAME(file1, file2)
MV(file1, file2)

RENAME renames the file or directory file1 to file2.

RENAME sets up two variables:

RC	is set to 0 in the case of a success, or to the error number returned by the system in the case of a failure.		
RESULT	is set to the full pathname of file2 in the case of a success, or to a string with an error message indicating the cause of the failure.		
Example:	call rename "myfile", "myfile.old"		
	RESULT may contain for example:		
	c:\userfiles\myfile.old		

OPEN_CONS - Open a Console

OPEN_CONS({title {,width{,height}})

OPEN_CONS is specific to the wsrexx.exe WINDOWS S/REXX version.

OPEN_CONS is used within the windowing wsrexx.exe version to open a standard I/O console, similar to a DOS console. S/REXX automatically calls OPEN_CONS when a SAY, SAYX, TRACE or PARSE PULL statement is issued and the console has not been opened before.

- title is a string to be displayed on top of the console.
- width is the width in characters unit of the console.
- height is the height in characters unit of the console.

Example: call open_cons "MyApp", 80, 25

PARG - Parse Argument

parg(argv, opt, tab) parses the argv argument string according to the options defined by the opt string, saving the result into the tab stem.

An option is a string starting with a minus sign. A parameter is a string following an option.

parg returns 0 when the argument string argv matches the options, 1 when the number of parameters following any option does not match the number of parameters defined by opt and 2 when an option is not defined.

Consider the following test program:

```
#! /home/xed/srexx
option mixed
opt = "-Wp 2 -help 0 -font 1"
parse arg argv
if parg(argv, opt, tab) ~= 0 then
 { say 'Invalid option.'
   exit 1
 }
do i = 1 to tab.0
 select
   when tab.i = 'help' then call help proc
    when tab.i = 'font' then
     { font = tab.font.1
       say 'Font set to "'font'"'
     }
    when tab.i = 'Wp' then
    \{ px = tab.Wp.1 \}
      py = tab.Wp.2
      say 'Position set to "'px py'"'
     }
  end
end i
str = tab.i
say 'Final string: "'str'"'
exit
help_proc:
  say "Help not yet available"
  exit 1
```

The "-Wp 2 -help 0 -font 1" opt string has the following meaning:

The -Wp option must be followed by 2 parameters. The -help option must be followed by no parameter. The -font option must be followed by 1 parameter.

tab.0 gives the number of recognized options passed to the program. If n is tab.0+1, tab.n gives the remaining argument string.

When the -Wp option is passed to the program, tab.Wp.1 and tab.Wp.2 give the two words following the -Wp option in the argv argument string.

Examples:

```
% test -Wp 345 123 str1 str2 str3
Position set to "345 123"
Final string: "str1 str2 str3"
% test -help
Help not yet available
% test -font cour.b.18
Font set to "cour.b.18"
Final string: ""
%
```

When option mixed is not in effect, all options are translated into uppercase. In this case, the test program would be:

```
#! /home/xed/srexx
opt = "-wp 2 -help 0 -font 1" /* Same as "-WP 2 -HELP 0 -FONT 1" */
parse arg argv
if parg(argv, opt, tab) ~= 0 then
 { say 'Invalid option.'
   exit 1
 }
do i = 1 to tab.0
  select
    when tab.i = 'HELP' then call help_proc
    when tab.i = 'FONT' then
     { font = tab.font.1
       say 'Font set to "'font'"'
     }
    when tab.i = 'WP'
                        then
     \{ px = tab.wp.1 \}
       py = tab.wp.2
       say 'Position set to "'px py'"'
     }
  end
end i
str = tab.i
say 'Final string: "'str'"'
exit
help_proc:
 say "Help not yet available"
  exit 1
```

QPID - Query Process Death

QPID(pid)

On **UNIX** systems, QPID() returns 1 if the pid process is dead and 0 when it is alive. pid is the process ID returned by the FORK() built-in command.

On **WINDOWS** systems, QPID() always returns -1.

REGISTRY_DEL - Delete REGISTRY Key Contents

On **WINDOWS** systems, REGISTRY_DEL() is used to delete the contents of a registry key, or the key itself.

WARNING: DISRUPTING THE WINDOWS REGISTRY CAN IRREPARABLY DAMAGE THE SYSTEM.

- rc = REGISTRY_DEL(hkey, where{, name})
- hkey is the key root location in the registry. hkey can be one of the following strings:

HKEY_CLASSES_ROOT HKEY_CURRENT_USER HKEY_LOCAL_MACHINE HKEY_USERS HKEY_CURRENT_CONFIG HKEY DYN DATA

- where is the location of the key in the hkey tree.
- name when provided, name is the name of the subkey to be removed. when not provided, the whole where key is removed. Note that on **WINDOWS NT** systems, where must be empty in order to be removed.
- rc is 0 when the call succeeds, or an error message.

Examples:

```
call registry_del("HKEY_LOCAL_MACHINE",,
    "SOFTWARE\test", "dms")
call registry_del("HKEY_LOCAL_MACHINE",,
    "SOFTWARE\test")
```

REGISTRY_GET - Retrieve REGISTRY Key Contents

On **WINDOWS** systems, REGISTRY_GET() is used to retrieve the contents of a registry key.

val = REGISTRY_GET(hkey, where, name)

hkey is the key root location in the registry. hkey can be one of the following strings:

HKEY_CLASSES_ROOT HKEY_CURRENT_USER HKEY_LOCAL_MACHINE HKEY_USERS HKEY_CURRENT_CONFIG HKEY_DYN_DATA

where is the location of the key in the hkey tree.

name	is the name of the subkey. If name is the " " empty string, the default value of the specified key location is retrieved.
val	is a string representing the contents of the key when the call succeds, or an error message starting with the "REGISTRY_GET Error:" string. REGISTRY_GET() returns the key value using a format similar to the WINDOWS NT Registry Editor when using the Export Registry File command.
	<code>REGISTRY_GET()</code> understands the following <code>WIN32</code> API type of keys:
	REG_BINARY: val is in the "hex:xx,xx,xx," format.
	REG_RESOURCE_LIST: val is in the "hex(8): xx , xx , xx ," format.
	REG_FULL_RESOURCE_DESCRIPTOR: val is in the "hex(9): xx , xx , xx ," format.
	REG_DWORD: val is in the "dword:xxxxxxx" format.
	REG_DWORD_BIG_ENDIAN: val is in the "hex(5): xx , xx , xx ," format.
	REG_LINK: val is in the "hex(6):xx, xx, xx," format.
	REG_MULTI_SZ: val is in the "hex(7):xx, xx, xx," format.
	REG_NONE: val is in the "hex(0):xx, xx, xx," format.
	REG_EXPAND_SZ: val is in the "hex(2): xx , xx , xx ," format.
	REG_RESOURCE_REQUIREMENTS_LIST: val is in the "hex(a): xx , xx , xx ," format.
	REG_SZ: val is a string.

Examples:

```
say registry_get("HKEY_LOCAL_MACHINE",,
    "HARDWARE\DESCRIPTION\System\CentralProcessor\0",,
    "~MHz")
```

could display:

dword:00000109

```
say registry_get("HKEY_LOCAL_MACHINE",,
    "SOFTWARE\Citrix\Client Management\ICA Client Update",,
    "Default Database")
```

could display:

hex(2):25,53,79,73,74,65

REGISTRY_KEYS - REGISTRY Subkeys Enumeration

On **WINDOWS** systems, REGISTRY_KEYS() is used to enumerate subkeys of the specified registry key.

rc = REGISTRY_KEYS(hkey, {where}, stem)

hkey is the key root location in the registry. hkey can be one of the following strings:

HKEY_CLASSES_ROOT HKEY_CURRENT_USER HKEY_LOCAL_MACHINE HKEY_USERS HKEY_CURRENT_CONFIG HKEY_DYN_DATA

- where is the location of the key in the hkey tree. When omitted, the whole hkey tree is enumerated.
- stem is the name of a valid REXX name.
- stem.0 will contain the number of enumerated subkeys.
- stem.i will contain the *ith* enumerated subkey.
- rc is the number of enumerated subkeys when the call succeeds, or an error message starting with the "REGISTRY_KEYS Error:" string.

Example:

```
call registry_keys("HKEY_LOCAL_MACHINE",,
    "SOFTWARE", tab)
do i = 1 to tab.0
    say tab.i
end
```

REGISTRY_SET - Set REGISTRY Key Contents

On **WINDOWS** systems, REGISTRY_SET() is used to set the contents of a registry key.

WARNING: DISRUPTING THE WINDOWS REGISTRY CAN IRREPARABLY DAMAGE THE SYSTEM.

- val = REGISTRY_SET(hkey, where, name, cnt)
- hkey is the key root location in the registry. hkey can be one of the following strings:

HKEY_CLASSES_ROOT HKEY_CURRENT_USER HKEY_LOCAL_MACHINE HKEY_USERS HKEY_CURRENT_CONFIG HKEY_DYN_DATA

- where is the location of the key in the hkey tree.
- name is the name of the subkey. If name is the " " empty string, the default value of the specified key location is set.
- cnt is a string representing the contents of the key. REGISTRY_SET() uses a format similar to the **WINDOWS NT** Registry Editor when using the Export Registry File command.

REGISTRY_SET() understands the following WIN32 API type of keys:

REG_BINARY: cnt is in the "hex:xx,xx,xx,..." format.

REG_RESOURCE_LIST: cnt is in the "hex(8):xx,xx,xx,...." format. REG_FULL_RESOURCE_DESCRIPTOR: cnt is in the "hex(9):xx,xx,xx,...." format.

REG_DWORD: cnt is in the "dword:xxxxxxx" format.

REG_DWORD_BIG_ENDIAN: cnt is in the "hex(5):xx,xx,xx,...." format.

REG_LINK: cnt is in the "hex(6):xx,xx,xx,...." format.

REG_MULTI_SZ:
cnt is in the "hex(7):xx,xx,xx,...." format.

REG_NONE: cnt is in the "hex(0):xx,xx,xx,...." format. REG_EXPAND_SZ: cnt is in the "hex(2):xx,xx,xx,...." format. REG_RESOURCE_REQUIREMENTS_LIST: cnt is in the "hex(a):xx,xx,xx,...." format. REG_SZ: cnt is a string not starting with hex:, dword: or hex(n):. val is 0 when REGISTRY_SET() succeeds, or an error message. Example: call registry_set("HKEY_LOCAL_MACHINE",,

```
"SOFTWARE\test", "dms", "hex(6):01,02,03")
```

REGISTRY_VALUES - REGISTRY Values Enumeration

On **WINDOWS** systems, REGISTRY_VALUES() is used to enumerate the values of the specified registry key.

```
rc = REGISTRY_VALUES(hkey, where, stem)
```

hkey is the key root location in the registry. hkey can be one of the following strings:

HKEY_CLASSES_ROOT HKEY_CURRENT_USER HKEY_LOCAL_MACHINE HKEY_USERS HKEY_CURRENT_CONFIG HKEY DYN DATA

- where is the location of the key in the hkey tree. When set to an empty string, the hkey values are enumerated.
- stem is the name of a valid REXX name.
- stem.0 will contain the number of enumerated values.
- stem.i will contain the *i*th enumerated values.
- rc is the number of enumerated values when the call succeeds, or an error message starting with the "REGISTRY_VALUES Error:" string.

Example:

```
call registry_values("HKEY_LOCAL_MACHINE",,
    "SOFTWARE\Program Groups", tab)
do i = 1 to tab.0
    say tab.i
end
```

RM / DEL / RECYCLE - Delete Files

DEL(ff) RM(ff) RECYCLE(ff)

 $\mathsf{RM}(\)$ and $\mathsf{DEL}(\)$ remove the ff files, and returns the full path names of the deleted files.

On **WINDOWS** systems, RECYCLE() moves the ff files or directories to the recycle bin.

ff may include the \sim .. **UNIX** or **WINDOWS** file meta characters. If a filename contains blanks, it must be surrounded with quotes or double quotes.

When RM fails, it sets the rc variable to a non-zero value, and returns an error message, such as:

RM() error: File does not exist

Examples: say rm("~/foo ~/test")
 could print: /user/john/foo /usr/john/test
 call rm '"/user/file with blanks"'
 call recycle "'c:\Program Files\log'"

RMDIR - Delete a Directory

RMDIR(dir{, "r"})

RMDIR removes the dir directory.

When the recursive "r" flag is not specified, dir must be empty.

When "r" is specified, RMDIR removes all of the dir files and subdirectories first.

RC	is set to 0 in case of success, or to 1 in case of failure.
RESULT	is set to the full pathname of dir in case of success, or to a string with an error message indicating the cause of the failure.

Examples: call rmdir "c:\foodir", "r" call rmdir "/home/foodir", "r"

SCRIPT - Record Session

SCRIPT({filename {, 'a'}})

When SCRIPT is called with a filename parameter, everything printed on the windows **S/REXX** was started from is written to filename. Unless the optional 'a' parameter is specified, the filename file is overwritten.

When SCRIPT is called without parameters, the recording stops.

Example: call script '~/logfile', 'a'
say 'This will be recorded'
address unix 'df' /* This will be recorded */

```
call script
say 'This will not be recorded'
```

Note: SCRIPT is not supported on Windows 95/98.

SERVICE_CREATE - Create a Service

On **WINDOWS NT** systems, SERVICE_CREATE() is an interface to the WIN32 CreateService function. SERVICE_CREATE() accepts arguments similar to the following CreateService arguments:

LPCTSTR	lpServiceName	//pointer to name of service to start
LPCTSTR	lpDisplayName	//pointer to display name
DWORD	dwDesiredAccess	//type of access to service
DWORD	dwServiceType	//type of service
DWORD	dwStartType	//when to start service
DWORD	dwErrorControl	//severity if service fails to start
LPCTSTR	lpBinaryPathName	//pointer to name of binary file
LPCTSTR	lpLoadOrderGroup	//pointer to name of load ordering group
LPCTSTR	lpDependencies	//pointer to array of dependency names
LPCTSTR	lpServiceStartName	//pointer to account name of service
LPCTSTR	lpPassword	<pre>//pointer to password for service account</pre>

See the Microsoft CreateService documentation for more information.

SERVICE_CREATE() returns 0 in case of success, or an explicit error message.

Example:

```
call service_create,
    'SEDIT-SREXX License Server',,
    'SEDIT-SREXX License Server',,
    'SERVICE_ALL_ACCESS',,
    'SERVICE_WIN32_OWN_PROCESS|SERVICE_INTERACTIVE_PROCESS',,
    'SERVICE_AUTO_START',,
    'SERVICE_ERROR_NORMAL',,
    'c:\Program Files\SEDIT\xserv.exe'
```

<u>SERVICE_DELETE - Delete a Service</u>

SERVICE_DELETE(name)

name the name of the service to be deleted.

On **WINDOWS NT** systems, SERVICE_DELETE() is an interface to the WIN32 DeleteService function.

See the Microsoft DeleteService documentation for more information.

SERVICE_DELETE() returns 0 in case of success, or an explicit error message.

SERVICE_STOP - Stop a Service

SERVICE_STOP(name)

name the name of the service to be stopped.

On **WINDOWS NT** systems, SERVICE_STOP() is an interface to the WIN32 ControlService function.

See the Microsoft ControlService documentation for more information.

SERVICE_STOP() returns 0 in case of success, or an explicit error message.

SERVICE_START - Start a Service

SERVICE_START(name)

name the name of the service to be started.

On **WINDOWS NT** systems, SERVICE_START() is an interface to the WIN32 StartService function.

See the Microsoft StartService documentation for more information.

SERVICE_START() returns 0 in case of success, or an explicit error message.

SERVICE_STATUS - Status of a Service

SERVICE_STATUS(name)

name the name of the service to be queried.

On **WINDOWS NT** systems, SERVICE_STATUS() is an interface to the WIN32 QueryServiceStatus function.

See the Microsoft QueryServiceStatus documentation for more information.

SERVICE_STATUS() returns an explicit error message in case of failure, or one of the following strings:

SERVICE_STOPPED SERVICE_START_PENDING SERVICE_STOP_PENDING SERVICE_RUNNING SERVICE_CONTINUE_PENDING SERVICE_PAUSE_PENDING SERVICE_PAUSED SERVICE_DOES_NOT_EXIST

SETENV, PUTENV - Set Environment Variable

SETENV(var, str) or PUTENV(var, str) assigns str to the var environment variable.

Example: call putenv "PATH", ".:/usr/bin:/bin"

See also the GETENV() function.

SIN - Sine

SIN(ang) returns the sine value of the radian argument ang.

SLEEP - Suspend Execution

SLEEP(sec) suspends execution for sec seconds.

SockAccept - Accept an Incoming Request

```
as = SockAccept(s{, 'stem.'}
as = accept(s{, 'stem.'}
accepts a connection request from a remote host.
              a positive value indicates succes. as can then be used with
as
              SockRecv() to retrieve the message sent by the remote host.
              is an optional stem variable where the address that is bound to the as
'stem.'
              socket is placed.
stem.family
              is always 'AF_INET' or 'PF_INET'.
stem.port
              the port number assigned to the socket.
              either 'INADDR_ANY' or the internet address in dotted format
stem.addr
              (nnn.nnn.nnn.nnn).
```

SockClose - Close a Socket

SockClose(s)
closesocket(s)
closes the s socket opened with the SockSocket() built-in.

SockBind - Bind a Socket

<pre>rc = SockBind(s, 'stem.') rc = bind(s, 'stem.') assigns a name to an unnamed socket.</pre>			
rc	0 when SockBind() succeds.		
S	specifies a socket.		
'stem.'	is a stem variable containing the address that is to be bound to socket.		
stem.family	must always be 'AF_INET' or 'PF_INET'.		
stem.port	the port number to be assigned to the socket. If port is set to 0, the the system will assign an available port. SockGetSockName() can be used to retrieve the port number assigned.		
stem.addr	either 'INADDR_ANY' or the internet address in dotted format (nnn.nnn.nnn.nnn). On hosts with more than one network interface (called multihomed hosts), a caller can select the interface with which it is to bind.		
SockBind() following error	sets the errno variable to 0 in case of success, or to one of the codes:		
EACCES	the requested address is protected and the current user has inadequate permission to access it.		
EADDRINUSE	the specified address is already in use.		
EADDRNOTAVA	XIL		
	the specified address is not available on the local machine.		
EBADF	s is not a valid descriptor.		
EINVAL	the socket is already bound to an address.		
ENOSR	there were insufficient STREAMS resources for the operation to complete.		
ENOTSOCK	s is a descriptor for a file, not a socket.		
Example:	<pre>addr_family = 'AF_INET' addr_port = 1256 addr_addr = 'INADDR_ANY' rc = SockBind(sock_in, 'addr_')</pre>		
Note:	Using a stem name such as 'addr.' may lead to unexpected results. If for example the port REXX variable is assigned the value of 12, addr.port will expand to addr.12, and the port value assigned to addr.port will be impossible to retrieve. Use a non-stemmed prefix such as addr_ to prevent this error.		

SockConnect - Connect a Socket

<pre>rc = SockConnect(s, 'stem.') rc = connect(s, 'stem.') connects a socket to a host.</pre>			
rc	0 when SockConnect() succeds.		
S	specifies a socket.		
'stem.'	is a stem variable containing the address of the remote socket to which a connection is to be attempted.		
stem.family	y must always be 'AF_INET' or 'PF_INET'.		
stem.port	the port number assigned to the remote socket.		
stem.addr	either 'INADDR_ANY' or the internet address in dotted format (nnn.nnn.nnn).		
SockConnect following error	t sets the errno variable to 0 in case of success, or to one of the codes:		
EACCES	search permission is denied for a component of the path prefix of the pathname in name.		
EADDRINUSE	the address is already in use.		
EADDRNOTAVA	AIL the specified address is not available on the remote machine.		
EAFNOSUPPOR	addresses in the specified address family cannot be used with this socket.		
EALREADY	the socket is non-blocking and a previous connection attempt has not yet been completed.		
EBADF	s is not a valid descriptor.		
ECONNREFUSI	ED the attempt to connect was forcefully rejected.		
EINPROGRESS	5		
	the socket is non-blocking and the connection cannot be completed immediately.		
EINTR	the connection attempt was interrupted before any data arrived by the delivery of a signal.		
EIO	an I/O error occurred while reading from or writing to the file system.		
EISCONN	the socket is already connected.		
ELOOP	too many symbolic links were encountered in translating the pathname in name.		
ENETUNREACH	the network is not reachable from this host.		

- ENOSR there were insufficient STREAMS resources available to complete the operation.
- ENXIO the server exited before the connection was complete.
- ETIMEDOUT connection establishment timed out without establishing a connection.

```
Example: addr_family = 'AF_INET'
addr_port = 1256
addr_addr = SockGetHostId()
rc = SockConnect(sock_out, 'addr_')
```

Note: Using a stem name such as 'addr.' may lead to unexpected results. If for example the port REXX variable is assigned the value of 12, addr.port will expand to addr.12, and the port value assigned to addr.port will be impossible to retrieve. Use a non-stemmed prefix such as addr_ to prevent this error.

SockDropFuncs - Compatibility Function

SockDropFuncs() is provided for compatibility purposes. SockDropFuncs does no perform any function.

SockGetHostByAddr - Search for Information for a Host

```
rc = SockGetHostByAddr(dotAddress, 'stem.'{, domain})
rc = gethostbyaddr(dotAddress, 'stem.'{, domain})
gets information about a specified host on the network using its dotted decimal
address.
```

- rc 1 when SockGetHostByAddr() succeds, 0 in case of failure.
- dotAddress a string specifying the dotted decimal address of the host.
- domain the domain value. SockGetHostByAddr() only supports the "AF_INET" value.
- 'stem.' is a stem variable containing the information about the host.
- stem.name the standard name of the host.
- stem.alias.0 number of aliases for this host.
- stem.alias.1 First alias for this host.
- stem.alias.n n'th alias for this host.

stem.addrtype

always "AF_INET".

stem.addr	the default dotted decimal address.
stem.addr.0	number of addresses for the name host.
stem.addr.1	first address for the name host.
stem.addr.n	n'th address for the name host.

SockGetHostByAddr() sets the h_errno variable to 0 in case of success, or to one of the following error codes:

```
HOST NOT FOUND
TRY AGAIN
NO RECOVERY
NO DATA
NO ADDRESS
Example:
            rc = SockGetHostByAddr('192.9.200.1', 'host.')
            say 'host.name = 'host.name
            say 'host.alias.0 = 'host.alias.0
            do i = 1 to host.alias.0
              say 'host.alias.'i' = 'host.alias.i
            end
            say 'host.addrtype = 'host.addrtype
            say 'host.addr = 'host.addr
```

```
say 'host.addr.0 = 'host.addr.0
do i = 1 to host.addr.0
  say 'host.addr.'i' = 'host.addr.i
end
```

SockGetHostByName - Search for Information for a Host

```
rc = SockGetHostByName(name, 'stem.')
rc = gethostbyname(name, 'stem.')
gets information about a specified host on the network using its name.
                 1 when SockGetHostByName() succeds, 0 in case of failure.
rc
                 a string specifying the name of the host.
name
'stem.'
                 is a stem variable containing the information about the host.
                 the standard name of the host.
stem.name
stem.alias.0 number of aliases for this host.
stem.alias.1 First alias for this host.
stem.alias.n n'th alias for this host.
stem.addrtype
                 always "AF_INET".
stem.addr
                 the default dotted decimal address.
stem.addr.0
                 number of addresses for the name host.
                 first address for the name host.
stem.addr.1
                 n'th address for the name host.
stem.addr.n
```

SockGetHostByName() sets the h_errno variable to 0 in case of success, or to one of the following error codes:

```
HOST NOT FOUND
TRY AGAIN
NO RECOVERY
NO DATA
NO ADDRESS
Example:
            rc = SockGetHostByName(hostname(), 'host.')
            say 'host.name = 'host.name
             say 'host.alias.0 = 'host.alias.0
             do i = 1 to host.alias.0
              say 'host.alias.'i' = 'host.alias.i
             end
             say 'host.addrtype = 'host.addrtype
             say 'host.addr = 'host.addr
             say 'host.addr.0 = 'host.addr.0
             do i = 1 to host.addr.0
               say 'host.addr.'i' = 'host.addr.i
             end
```

SockGetHostId - Get the Dot Address of the Host

```
dotAddress = SockGetHostId()
dotAddress = gethostid()
retrieves the dot address of the local host in nnn.nnn.nnn format.
```

SockGetPeerName - Get the Name of the Connected Peer

```
rc = SockGetPeerName(s, 'stem.')
rc = getpeername(s, 'stem.')
retrieves information about the peer connected to the socket s in the 'stem.' stem.
              0 when SockGetPeerName() succeds.
rc
              specifies a socket.
S
'stem.'
              is a stem variable containing the address that is bound to the s
              socket.
stem.family
              is always 'AF_INET' or 'PF_INET'.
              the port number assigned to the socket. If the socket is not bound to
stem.port
              an address, stem.port is set to 0.
              either 'INADDR ANY' or the internet address in dotted format
stem.addr
              (nnn.nnn.nnn.nnn).
SockGetPeerName() sets the errno variable to 0 in case of success, or to one
of the following error codes:
```

EBADF the argument s is not a valid file descriptor.

- ENOMEM there was insufficient memory available for the operation to complete.
- ENOSR there were insufficient STREAMS resources available for the operation to complete.

ENOTSOCK the argument s is not a socket.

ENOTCONN the socket s is not connected.

Example: SockGetPeerName(s, 'addr_') say addr_family /* displays 'AF_INET' */ say addr_port /* could display 1256 */ say addr_addr /* could display 'INADDR_ANY' or '192.9.200.1' */

Note: Using a stem name such as 'addr.' may lead to unexpected results. If for example the port REXX variable is assigned the value of 12, addr.port will expand to addr.12, and the port value assigned to addr.port will be impossible to retrieve. Use a non-stemmed prefix such as addr_ to prevent this error.

SockGetSockName - Get the Current Socket Name

```
rc = SockGetSockName(s, 'stem.')
rc = getsockname(s, 'stem.')
retrieves information about the s socket in the 'stem.' stem.
               0 when SockGetSockName() succeds.
rc
              specifies a socket.
s
'stem.'
              is a stem variable containing the address that is bound to the s
              socket.
stem.family
              is always 'AF_INET' or 'PF_INET'.
              the port number assigned to the socket. If the socket is not bound to
stem.port
               an address, stem.port is set to 0.
stem.addr
              either 'INADDR ANY' or the internet address in dotted format
               (nnn.nnn.nnn.nnn).
SockGetSockName() sets the errno variable to 0 in case of success, or to one
of the following error codes:
EBADF
               the argument s is not a valid file descriptor.
               there was insufficient memory available for the operation to
ENOMEM
               complete.
               there were insufficient STREAMS resources available for the
ENOSR
               operation to complete.
ENOTSOCK
              the argument s is not a socket.
```

Example:	SockGetSockName(s, 'addr_') say addr_family /* displays 'AF_INET' */ say addr_port /* could display 1256 */ say addr_addr /* could display 'INADDR_ANY' or '192.9.200.1' */
Note:	Using a stem name such as 'addr.' may lead to unexpected results. If for example the port REXX variable is assigned the value of 12, addr.port will expand to addr.12, and the port value assigned to addr.port will be impossible to retrieve. Use a non-stemmed prefix such as addr_ to prevent this error.

SockGetSockOpt - Get Socket Options

<pre>rc = SockGe rc = getsoc gets options asso</pre>	etSockOpt(s, level, optname, 'optval') ekopt(s, level, optname, 'optval') ociated with a socket.		
rc	0 when SockGetSockOpt() succeds.		
S	specifies a socket.		
level	the protocol level. SockGetSockOpt() supports only the "SOL_SOCKET" level.		
optname	on UNIX systems, optname can be:		
	SO_DEBUG SO_REUSEADDR SO_KEEPALIVE SO_DONTROUTE SO_LINGER SO_BROADCAST SO_OOBINLINE SO_SNDBUF SO_RCVBUF SO_TYPE SO_ERROR		
	On WINDOWS system, optname can be:		
	SO_DEBUG SO_REUSEADDR SO_KEEPALIVE SO_DONTROUTE SO_LINGER SO_BROADCAST SO_OOBINLINE SO_SNDBUF SO_RCVBUF SO_DONTLINGER		
'optval'	the name of an S/REXX variable enclosed in quotes. When optname is SO_LINGER, optval is filled with a string including 2 integers. The first integer is a boolean flag describing the linger status, and the second integer is the linger time.		
SockGetSockOpt() sets the errno variable to 0 in case of success, or to one of the following error codes:			
EBADF	the argument s is not a valid file descriptor.		
ENOMEM	there was insufficient memory available for the operation to complete.		
ENOPROTOOPI	the option is unknown at the level indicated		
ENOSR	there were insufficient STREAMS resources available for the operation to complete.		

ENOTSOCK the argument s is not a socket.

Example:

```
rc = SockGetSockOpt(sock_out, "SOL_SOCKET", "SO_REUSEADDR", 'lg')
if (lg = 1) then
```

SockInit - Compatibility Function

SockInit() is provided for compatibility purposes. SockInit() does not perform any function.

SockIoctl - Perform Special Operations on Socket

```
rc = SockIoctl(s, codeop, 'var')
rc = ioctl(s, codeop, 'var')
sets socket attribute. or retrieves information.
```

rc 0 when SockIoctl() succeds.

- s specifies a socket.
- codeop the ioctl command to perform. codeop can be 'FIONBIO' or 'FIONREAD'.
- FIONBIO sets or clears nonblocking input/output for the s socket. var must be an integer. When var contains the value of 0, input/output on the socket s are blocking. Otherwise, input/output on the socket s are nonblocking.
- FIONREAD Sockloctl() stores in var the number of bytes available for reading.
- 'var' a REXX variable.

SockIoctl() sets the errno variable to 0 in case of success, or to one of the following error codes:

- EINVAL request or codeop is not valid for this device.
- EIO some physical I/O error has occurred.
- ENOLINK s is on a remote machine and the link to that machine is no longer active.

SockListen - Listen for Incoming Requests

- rc = SockListen(s, backlog) rc = listen(s, backlog) completes the binding necessary for a socket to accept connections and creates a connection request queue for incoming requests.
- rc0 when SockListen() succeds.sspecifies a socket.backlogthe maximum length the queue of pending connections may grow to.

SockListen() sets the errno variable to 0 in case of success, or to one of the following error code:

EBADF the argument s is not a valid file descriptor.

SockLoadFuncs - Compatibility Function

SockLoadFuncs() is provided for compatibility purposes. SockLoadFuncs() does not perform any function.

SockPSock_Errno - Last Error Code

SockPSock_Errno({str}) prints the last error code set by a socket call. Subsequent successful socket calls do not reset this error code.

When str is provided and is not empty, SockPSock_Errno() prints first str followed by a colon and a space.

SockRecv - Receive Data

```
rc = SockRecv(s, 'var', len{, flag})
rc = recv(s, 'var', len{, flag})
receives data on a connected socket.
```

- rc -1 in case of failure or the length of the incoming data.
 s a connected socket. Generally, the return of the SockAccept()
 function.
 'var' the name of a REXX variable the data will be received into.
- len the maximum length of the data to be read.
- flag a blank delimited list of options: MSG_OOB reads any out-of-band data on the socket. MSG_PEEK peeks at the data present on the socket; the data is returned but not consumed, so that a subsequent receive operation sees the same data.

SockRecv() sets the errno variable to 0 in case of success, or to one of the following error codes:

- EINTR the operation was interrupted by delivery of a signal before any data was available to be received.
- EIO an I/O error occurred while reading from or writing to the file system.
- ENOMEM there was insufficient user memory available for the operation to complete.
- ENOSR there were insufficient STREAMS resources available for the operation to complete.

ENOTSOCK s is not a socket.

ESTALE a stale NFS file handle exists.

EWOULDBLOCK

the socket is marked non-blocking and the requested operation would block.

SockRecvFrom - Receive Data

rc = SockRecvFrom(s, 'var', len, {flag}, 'addr.')
rc = recvfrom(s, 'var', len, {flag}, 'addr.')
receives data on a socket whether it is in a connected state or not.

rc	-1 in case of	failure or the	length of the	incoming data.
				()

- s specifies a socket.
- 'var' the name of a REXX variable the data will be received into.
- len the maximum length of the data to be read.

flag a blank delimited list of options:

MSG_OOB reads any out-of-band data on the socket. MSG_PEEK peeks at the data present on the socket; the data is returned but not consumed, so that a subsequent receive operation sees the same data.

- 'addr.' when provided, the source address of the message is filled into the 'addr.' stem.
- addr.family is always 'AF_INET'.

addr.port the port number assigned to the socket.

addr.addr either 'INADDR_ANY' or the internet address in dotted format (nnn.nnn.nnn).

SockRecvFrom() sets the errno variable to 0 in case of success, or to one of the following error codes:

- EINTR the operation was interrupted by delivery of a signal before any data was available to be received.
- EIO an I/O error occurred while reading from or writing to the file system.
- ENOMEM there was insufficient user memory available for the operation to complete.
- ENOSR there were insufficient STREAMS resources available for the operation to complete.
- ENOTSOCK s is not a socket.

ESTALE a stale NFS file handle exists.

EWOULDBLOCK

the socket is marked non-blocking and the requested operation would block.

SockSelect - Monitor Sockets

```
rc = SockSelect('reads.', 'writes.', 'excepts.' {,tt})
rc = select('reads.', 'writes.', 'excepts.' {,tt})
monitors the activity of the specified sockets.
```

rc the number of ready sockets, or -1 in case of failure.

- 'reads.' the stem specifying the sockets to be checked for readability. When omitted, or specified as an empty string, no socket is checked for readability.
- reads.0 the number of sockets to be checked for readability.
- reads.n the n'th socket to be checked for readability.
- 'writes.' the stem specifying the sockets to be checked for readiness for writing. When omitted, or specified as an empty string, no socket is checked for readiness for writing.
- writes.0 the number of sockets to be checked for readiness for writing.
- writes.n the n'th socket to be checked for readiness for writing.
- 'excepts.' the stem specifying the sockets to be checked for exceptional pending conditions (out-of-band data in the receive buffer). When omitted, or specified as an empty string, no socket is checked for exceptional pending conditions.
- excepts.0 the number of sockets to be checked for exceptional pending conditions.
- excepts.n the n'th socket to be checked for exceptional pending conditions.
- tt the timeout amount in seconds before SockSelect() returns when no socket is ready. When tt is set to 0, SockSelect() does not wait before returning. If no timeout value is passed, or if tt is an empty string (""), SockSelect() does not return until one socket becomes ready.

SockSelect() sets the errno variable to 0 in case of success, or to one of the following error codes:

- EBADF the argument s is not a valid file descriptor.
- EINTR a signal was delivered before any of the selected events occurred, or the time limit expired.

Example: sock_in = SockSocket("AF_INET", "SOCK_STREAM", 0)
sock_out = SockSocket("AF_INET", "SOCK_STREAM", 0)
do forever
 reads.0 = 1
 reads.1 = sock_in
 writes.0 = 1
 writes.1 = sock_out
 excepts.0 = 2
 excepts.1 = sock_in
 excepts.2 = sock_out
 call SockSelect 'reads.', 'writes.', 'excepts.', 1.5
 do i = 1 to reads.0

```
say reads.i 'is ready for reading'
end
do i = 1 to writes.0
    say writes.i 'is ready for writing'
end
do i = 1 to excepts.0
    say excepts.i 'is exceptional'
end
end
```

SockSend - Send Data

```
rc = SockSend(s, data{, flags})
rc = send(s, 'data'{, flags})
sends data on a connected socket.
```

rc -1 in case of failure or the number of bytes sent.

data the data to be sent.

flags is an optional blank delimited list of options:

MSG_OOB

Sends out-of-band data on sockets that support SOCK_STREAM communication.

MSG_DONTROUTE

The SO_DONTROUTE option is turned on for the duration of the operation. This is usually used only by diagnostic or routing programs.

SockSend() sets the errno variable to 0 in case of success, or to one of the following error codes:

- EBADF s is an invalid file descriptor.
- EINTR the operation was interrupted by delivery of a signal before any data could be buffered to be sent.
- EMSGSIZE the socket requires that message be sent atomically, and the message was too long.
- ENOMEM there was insufficient memory available to complete the operation.
- ENOSR there were insufficient STREAMS resources available for the operation to complete.
- ENOTSOCK s is not a socket.

EWOULDBLOCK

the socket is marked non-blocking and the requested operation would block.

SockSendTo - Send Data

```
rc = SockSendTo(s, data, {flags}, 'addr')
rc = sendto(s, 'data', {flags}, 'addr')
sends data on a socket whether it is in a connected state or not.
```

rc -1 in case of failure or the number of bytes sent.

data the data to be sent.

flags is an optional blank delimited list of options:

MSG_OOB

Sends out-of-band data on sockets that support SOCK_STREAM communication.

MSG_DONTROUTE

The SO_DONTROUTE option is turned on for the duration of the operation. This is usually used only by diagnostic or routing programs.

- 'addr' the name of a REXX variable containing the destination address.
- addr.family must always be 'AF_INET' or 'PF_INET'.

addr.port the port number assigned to the socket.

addr.addr either 'INADDR_ANY' or the internet address in dotted format (nnn.nnn.nnn).

SockSendTo() sets the errno variable to 0 in case of success, or to one of the following error codes:

- EBADF s is an invalid file descriptor.
- EINTR the operation was interrupted by delivery of a signal before any data could be buffered to be sent.
- EMSGSIZE the socket requires that the message be sent atomically, and the message was too long.
- ENOMEM there was insufficient memory available to complete the operation.
- ENOSR there were insufficient STREAMS resources available for the operation to complete.
- ENOTSOCK s is not a socket.

EWOULDBLOCK

the socket is marked non-blocking and the requested operation would block.

SockSetSockOpt - Set Socket Options

```
rc = SockSetSockOpt(s, level, optname{, optval})
rc = setsockopt(s, level, optname{, optval})
sets options associated with a socket.
```

- rc 0 when SockSetSockOpt succeds.
- s specifies a socket.
- level the protocol level. SockSetSockOpt() supports only the "SOL_SOCKET" level.
- optname optname and any specified options optval are passed uninterpreted to the appropriate protocol module for interpretation.

On UNIX systems, optname can be:

SO_DEBUG SO_REUSEADDR SO_KEEPALIVE SO_DONTROUTE SO_LINGER SO_BROADCAST SO_OOBINLINE SO_SNDBUF SO_RCVBUF SO_TYPE SO_ERROR

On **WINDOWS** system, optname can be:

SO_DEBUG SO_REUSEADDR SO_KEEPALIVE SO_DONTROUTE SO_LINGER SO_BROADCAST SO_OOBINLINE SO_SNDBUF SO_RCVBUF SO_DONTLINGER

optval may be a string or a number.

When optname is SO_LINGER, optval must be a string including 2 integers. The first integer is a boolean flag enabling the linger feature, and the second integer is the linger time.

SockSetSockOpt() sets the errno variable to 0 in case of success, or to one of the following error codes:

- EBADF the argument s is not a valid file descriptor.
- ENOMEM there was insufficient memory available for the operation to complete.

ENOPROTOOPT

the option is unknown at the level indicated.

- ENOSR there were insufficient STREAMS resources available for the operation to complete.
- ENOTSOCK the argument s is not a socket.

Examples:

```
rc = SockSetSockOpt(sock_out, "SOL_SOCKET", "SO_REUSEADDR", 1)
rc = SockSetSockOpt(sock_out, "SOL_SOCKET", "SO_LINGER", "1 2")
```

SockShutDown - Close a Socket

SockShutDown(s, how)
shutdown(s, how)
shuts down all or part of a full duplex connection.

S	a socket.	
how	0	no more data can be received on the socket s.
	1	no more output to be allowed on the socket s.
	2	no more data can be sent or received on socket s

SockShutDown() sets the errno variable to 0 in case of success, or to one of the following error codes:

EBADF	s is not a valid file descriptor.
ENOMEM	there was insufficient user memory available for the operation to complete.
ENOSR	there were insufficient STREAMS resources available for the operation to complete.
ENOTCONN	the specified socket is not connected.
ENOTSOCK	s is not a socket.

SockSocket - Create a Socket

s = SockSocket(domain, type, protocol)

s = socket(domain, type, protocol)

creates an endpoint for communication and returns a socket descriptor representing the endpoint.

S	a returned socket.
5	a letuineu socket.

- domain specifies a communications domain within which communication
 will take place. SockSocket supports only the "AF_INET"
 (identical to "PF_INET") domain.
- type The socket has the indicated type, which specifies the communication semantics. type may be "SOCK_STREAM", "SOCK_DGRAM", or "SOCK_RAW"
- protocol is the protocol family which should be used. protocol may be "IPPROTO_UDP", "IPPROTO_TCP", or a whole number (generally 0).

SockSocket sets the errno variable to 0 in case of success, or to one of the following error codes:

- EACCES permission to create a socket of the specified type and/or protocol is denied.
- EMFILE the per-process descriptor table is full.
- ENOMEM insufficient user memory is available.

ENOSR There were insufficient STREAMS resources available to complete the operation.

EPROTONOSUPPORT

The protocol type or the specified protocol is not supported within this domain.

SockSoClose - Close a Socket

SockSoClose(s) closes the s socket opened with the SockSocket() built-in.

SockSock_Errno - Last Error Code

str = SockSock_Errno() returns the last error code set by a socket call.
Subsequent successful socket calls do not reset this error code.

SockVersion - Version Number of Socket Library

SockVersion() returns the version number of the S/REXX Socket library.

SORT - Sort a List

SORT(tab,	desc, start, end)
tab	is a valid REXX symbol. The derived stem values (tab.1, tab.2, etc) will be sorted accordingly to the desc string.
desc	is a string describing how to sort tab.
	desc is a list of paired columns, which may be preceded with Ascending, Descending, N or n, which indicates the order in which to sort the field and the type of field, and all subsequent fields, until another Ascending or Descending or N or n parameter is encountered. N indicates a numerical field to be sorted in ascending order.
	n indicates a numerical field to be sorted in descending order.
	Ascending, regardless of the case, indicates an alphanumeric field to be sorted in ascending order.
	Descending, regardless of the case, indicates an alphanumeric field to be sorted in descending order.
	An asterisk * as a second column indicates the end of the string to be sorted.
start	indicates the rank of the first stem to be sorted. When not specified, it defaults to 1.
end	indicates the rank of the last stem to be sorted. When not specified, it defaults to tab.0.
Example:	call sort list, "a 1 12 d 13 24 N 25 *", 2, 13

STATE / LSTATE - Query File State

 $\label{eq:state} \verb|STATE(fname{, option})| and \verb|LSTATE(fname{, option})| return 1 when the file fname matches option, and 0 otherwise.$

The LSTATE() function obtains file attributes similar to STATE(), except when the named file is a symbolic link; in that case LSTATE() returns information about the link, while STATE() returns information about the file the link references.

fname may include the ~ .. UNIX or WINDOWS file meta characters.

option may be one of the following letters, or the word corresponding to the letter:

"d"	"Directory"	matches a directory.
"e"	"Exists"	matches an existing file. This is the default when option is not supplied.
"f"	"File"	matches a plain file. Special files, like symbolic links or sockets, return 0.
"1"	"Link"	matches a symbolic link.
"0"	"Owned"	matches a file owned by the current user. Always returns 1 on WINDOWS systems.
"r"	"Read"	matches a file which can be read by the current user.
"s"	"Size"	returns the file size.
" w "	"Write"	matches a file which can be written by the current user.
"x"	"eXecute"	matches a file with execute permission. Always returns 1 on WINDOWS systems.
"z"	"Zero"	matches a zero length file.
"p"	"stamP"	returns a string in dd/mm/yyyy hh:mm:ss format indicating the time of last modification.
"n"	"owNer"	returns the name of the owner of the file.
"g"	"Group"	returns the name of the group of the file. Always returns an empty string on WINDOWS systems.
"У"	"sYstem"	returns a value which uniquely identifies the file system that contains the file.
Example	s: if state MyRoutin	e("~/MyFile") then call MyRoutine he will be called when ~/MyFile exists.
	owner =	<pre>state("MyFile", "n")</pre>
	owner =	<pre>state("MyFile", "owner")</pre>
Notes:	On WIND	DWS systems, fname may be surrounded with quotes.
	When the is set the RC F	nformation query succeeds, STATE() and LSTATE() REXX variable to 0.
When the query fails, STATE() and LSTATE() return 0, and set the RC REXX variable to a string describing the reason the query failed.		

STIME - Set System Time

stime(str) sets the system time according to the str string which must be in 'dd/mm/yyyy hh:mm:ss' format.stime returns 0 when the call succeeds.

Example: call stime '25/1/2001 12:03:24'

STREAM - Compatibility Function

stream() is a compatibility function, which always returns the ready string, and performs no action.

SUBDIRS - Find Subdirectories

SUBDIRS(root, {stem}, {rec})

root	is the root directory to be scanned for subdirectories.
------	---

stem when stem is not provided, the SUBDIRS output will be placed in the stack. The user will be able to read it using the parse pull command.

The queued() function may be used to return the number of lines in the stack.

When stem is provided, it must be a valid REXX name. It will be filled with the SUBDIRS output. stem. 0 will contain the number of subdirectories found.

rec when not specified, or specified as the "nr" string, only the first level subdirectories names are returned.

When specified as the "r" string, every subdirectory will be recursively scanned, and all the nested subdirectories names will be returned.

Example: call subdirs "~", tab, "r" do i = 1 to tab.0 say tab.i end

SysCls - Clear the Screen

SysCls() clears the screen when possible.

SysCls() returns 0 in case of success, or an error message in case of failure.

SysFileDelete - Delete File

SysFileDelete(file) removes the file file. file may include the ~ .. UNIX or WINDOWS file meta characters.

Notes: SysFileDelete()removes one file at a time. To remove several files with one call, use the RM() or the DEL() subroutine. RM() and DEL() need quotes when the name of the file to erase contains blanks. SysFileDelete() does not.

Return Codes:

0	File deleted successfully.
2	File not found.
3	Path not found.
4	Too many symbolic links were encountered in translating path.
5	Access denied or busy.
б	Components of path require hopping to multiple remote machines and the file system does not allow it.
7	Path points to a remote machine and the link to that machine is no longer active.
8	The length of the path argument is too long.
108	Read-only filesystem.
999	Unknown error.

SysFileSearch - Scan File

SysFileSearch(str, file, 'stem.'{, opt})
searches the file file to find all lines containing the str string. file may include
the ~ .. UNIX or WINDOWS file meta characters.

str	the string to match.
file	the file to search.
'stem.'	the name of a stem variable used to return the result of the search.
stem.0	the number of matching lines.
stem.i	the contents of a matching line. When opt contains the N option, stem.i contains the line number.
opt	an optional string containing one of the following one-character options:
	Nreturns the file line numbers.Cconducts a case-sensitive search.

By default, the search is case-insensitive without line numbers.

Return Codes:

- 3 Error opening file.
- 4 Error reading file.

Example:

```
call SysFileSearch 'spool', '/etc/passwd', 'stem.', 'n'
do i = 1 to stem.0
    say stem.i
end
could print:
7 lp:x:71:8:Line Printer Admin:/usr/spool/lp:
10 nuucp:x:9:9:uucp Admin:/var/spool/uucppublic
```

SysFileTree - Scan Directory

SysFileTree(filespec, 'stem.', {opt})
searches the directory described by filespec for matching files.

filespec can be one of the following:

a dir directory all the files in the dir directory matching opt will be returned. dir may include the ~ .. UNIX or WINDOWS file meta characters.

an expr search string

all files matching expr and opt in the current directory will be returned. When opt does not specify a regular expression search, expr can include the * and ? special meta characters. * matches any set of characters. ? matches any (one) character.

- dir/expr all files matching expr and opt in the dir directory will be returned.
- a null ("") string all files matching opt in the current directory will be returned.
- 'stem.' the name of a stem variable used to return the result of the search.
- stem.0 the number of matching files.
- stem.i a matching file.

opt	an optional	string	containing	one	of	the	following	one-character
	options:							

- F Search only for files.
- D Search only for directories
- B Search for both directories and files. This is the default.
- S Search subdirectories recursively.
- T Return the time and date in YY/MM/DD/HH/MM format.
- L Return the time and date in YYYY-MM-DD HH:MM:SS format.
- Return only the file name. The default is to return the string in the example below.
- I Ignore case. This is the default on **WINDOWS** systems.
- R Respect case. This is the default on **UNIX** systems.
- G filespec is a regular expression. See <u>page 363</u> for a regular expression definition. Note that on **WINDOWS** systems, the \ regular expression escape character cannot be used. Instead of using for example \. (meaning "."), use [.].

SysFileTree() returns 0 in case of success, or an explicit error message such as "Error Opening Directory xxxxx" in case of failure.

```
Examples:
```

```
call SysFileTree '/usr/include/*io*.h', 'stem.'
do i = 1 to stem.0
  say stem.i
end
could print:
04/24/96
          03:18
                         -rw-r--r-- /usr/include/aio.h
                   2317
          03:18
04/24/96
                   1025 -rw-r--r-- /usr/include/cpio.h
04/24/96
                          -rw-r--r-- /usr/include/stdio.h
          19:18
                  11868
call SysFileTree 'C:\WTSRV\[2-3][.]dll', 'stem.', 'g'
do i = 1 to stem.0
  say stem.i
end
could print:
04/29/96
                   21648 ---A- C:\WTSRV\ctl3dv2.dll
          12:13
08/24/98
          10:00
                   52224 ---A- C:\WTSRV\scnlib32.dll
06/11/97
                  104448 ---A- C:\WTSRV\TWAIN32.DLL
          00:06
08/23/98
                   77312 ---A- C:\WTSRV\TWAIN 32.DLL
          13:32
```

```
05/09/98 14:04 24336 ---A- C:\WTSRV\vmmreg32.dll
```

SysGetKey - Read Character Input Stream

SysGetKey() is a synonym of the CHARIN() built-in described page 530. SysGetKey() and CHARIN() do not need the Enter key to be pressed before returning.

SysMkDir - Delete a Directory

SysMkDir(dir) creates the specified directory.

dir may include the ~ .. UNIX or WINDOWS file meta characters.

Return Codes:

0	Success.
3	Path not found.
4	Too many symbolic links were encountered in translating path.
5	Access Denied.
6	Components of path require hopping to multiple remote machines and the file system does not allow it.
7	Path points to a remote machine and the link to that machine is no
-	longer active.
8	I/O error.
87	Already exists.
108	Read-only filesystem.
206	File name too long or no space left on device.
999	Unknown error.

SysRmDir - Delete a Directory

SysRmDir(dir)

SysRmDir() removes the dir directory. dir must be empty. See the RMDIR() built-in function to remove recursively non-empty directories.

dir may include the ~ .. UNIX or WINDOWS file meta characters.

Return Codes:

0	Success.
3	Path not found.
4	Too many symbolic links were encountered in translating path.
5	Access Denied.
б	Components of path require hopping to multiple remote machines and the file system does not allow it.
7	Path points to a remote machine and the link to that machine is no longer active.
8	I/O error
9	The directory to be removed is the mount point for a mounted file system.
10	The directory to be removed is the current directory.

108	Read-only filesystem.
206	File name too long or no space left on

Unknown error. 999

SysSearchPath - Search Files in Path

```
rf = SysSearchPath('PATH', file{, exec} {, 'stem.')
```

SysSearchPath() searches for the file file within the directories described by the environment variable PATH. The PATH directories are separated by a colon (': ') on UNIX systems, and by a semi-colon (';') on WINDOWS systems.

device

rf	the full file specification of the first file in the path matching file.
exec	0 (the default) or 1. On UNIX systems, when exec is set to 1, SysSearchPath() only finds files with at least one of the "user",
	"group" and "other" execute permission flags set to on.

- when specified, SysSearchPath() stores all the files matching 'stem.' file in the stem. variable.
- the number of matching files. stem.0
- a matching file. stem.i

Examples:

```
call SysSearchPath "PATH", 'csh', 1, "stem."
do i = 1 to stem.0
  say stem.i
end
say 'result = 'result
could print:
/usr/bin/csh
/bin/csh
result = /usr/bin/csh
```

SysSetPriority - Change the Priority

SysSetPriority(class, delta) changes the priority of the current process.

On UNIX systems:

class	the type of priority to change:	
	0 no changes.	
	1 the scheduling priority of the process.	
	2 the scheduling priority of the process group.	
	3 the scheduling priority of the user.	
delta	the delta (positive or negative) applied to the process priority process default priority is 0, and can vary between -20 and +20 the superuser can lower the priority. Lower priorities cause favorable scheduling.	ty. The). Only e more
On WINDOWS systems:

class	the type of	the type of priority to set:		
	0 1	no changes. IDLE_PRIORITY_CLASS: specify this class for a process whose threads run only when the system is idle. The threads of the process are preempted by the threads of any process running in a higher priority class. An example is a screen saver. The idle-priority class is inherited by child processes.		
	2	NORMAL_PRIORITY_CLASS: specify this class for a process with no special scheduling needs.		
	3	HIGH_PRIORITY_CLASS: specify this class for a process that performs time-critical tasks that must be executed immediately. The threads of the process preempt the threads of normal or idle priority class processes. Use extreme care when using the high-priority class, because a high-priority class application can use nearly all available CPU time.		
	4	REALTIME_PRIORITY_CLASS: specify this class for a process that has the highest possible priority. The threads of the process preempt the threads of all other processes, including operating system processes performing important tasks. For example, a real-time process that executes for more than a very brief interval can cause disk caches not to flush or cause the mouse to be unresponsive.		
delta	ignored			

delta ignored.

Return Codes:

0	Success.
1	Unable to get current priority.
2	Unable to set priority.
307	Invalid priority class.
Note:	SysSetPriority() is not supported on SCO systems.

SysSleep - Suspend Execution

 ${\tt SysSleep(sec)}$ suspends execution for sec seconds. See also the ${\tt SLEEP()}$ and ${\tt USLEEP()}$ built-ins.

SysTempFileName - Make a Unique File Name

SysTempFileName(filespec, {, filter})
returns a name for a file or directory which does not exists.

- filespec can be a tmp template for a filename, or a dir directory name followed by a tmp template for a file name. When dir is not provided or is invalid, it defaults to the /tmp directory on UNIX systems, and to the C:/temp directory on WINDOWS systems.
- filter the filter character used in tmp. Each filter character in tmp is replaced with a random numerical value. Then, tmp is appended a random 6 characters string.

SysTempFileName() returns an empty string in case of error.

Examples:

say SysTempFileName("/usr/test??", "?")
say SysTempFileName("?foo??", "?")
say SysTempFileName("", "?")

could print:

/usr/test48a002b4 /tmp/1foo95a002b4 /tmp/a002b4

SysVersion - Operating System Description

SysVersion() returns a string describing the operating system, such as:

```
AIX 2 3 000012627700
IRIX 5.3 11091812 IP22
OSF1 V4.0 464 alpha
HP-UX B.10.10 A 9000/710
SunOS 4.1.3_U1 2 sun4m
SunOS 5.5 Generic i86pc
SunOS 5.5.1 Generic_103640-14 sun4u
Windows NT 4.0 build 1381 Service Pack 3
Linux 2.0.32 #1 Wed Nov 19 00:46:45 EST 1997 i586
```

TAN - Tangent

TAN(ang) returns the tangent value of the radian argument ang.

TBADD - Insert Table Line

nb_line = TBADD(li{, arg1{, arg2 {...}}}) inserts a line after the line li in the currently opened table, filling it with the arguments provided.

When no argument is provided, the new line will be an empty line.

TBADD returns the table length.

Examples: nb_line = tbadd 12 call tbadd 12, "Item 1",,"Item 3"

See S/REXX ISPF-like Tables on page 619 for more information about the table functions.

TBCLOSE - Close Current Table

TBCLOSE closes the opened table currently. All modified data will be lost.

TBDEL - Delete Table Line

nb_line = TBDEL(li) deletes the line li in the currently opened table. TBDEL returns the table length.

TBDISPL - Display Table

TBDISPL(li, stem) displays the current table starting at line li, filling stem with the following information:

stem.0	The stem siz	The stem size (8 here).		
stem.1	A keyword indicating the user action:			
	return	the Return key.		
	Fi	The i top function key.		
	Li	The i left function key.		
	Ri	The i right function key.		
	Bi	The i mouse button.		
	^x	The Control-x action.		
stem.2	The cursor lin is not on a)M	The cursor line file related position, or 0 if the cursor is not on a)MODEL data field location.		
stem.3	The cursor co cursor is not c	olumn file related position, or 0 if the on a) MODEL data field location.		

stem.4	The mouse line file related position, or 0 if the mouse is not on a)MODEL data field location.
stem.5	The mouse column file related position, or 0 if the mouse is not on a)MODEL data field location.
stem.6	The last displayed line.
stem.7	The number of lines which can be displayed, according to the panel layout and the screen size.
stem.8	The number of lines in the current loaded table.

TBGET - Get Table Line

TBGET(li) updates the input variables described in the)MODEL section with the table data at line li.

TBOPEN - Open a Table

nb_line = TBOPEN(fi, pa{, sep} {, mode}) opens the fi file using the pa panel. The separator in use to parse the file will be sep, or the '09'x tabulation character by default.

When the optional mode parameter is the 'r' string, the table is opened in read-only mode. When mode is omitted, or set to the 'w' string, the table is opened in read-write mode.

TBOPEN returns the table length.

When no argument is provided, the new line will be an empty line.

Example: nb_line=tbopen '~/data','~/data.panel',';'

TBPUT - Update Table Line

TBPUT(li{, arg1{, arg2 {...}}}) updates the current table at line li with the arg*i* arguments, or with existing REXX variables whose names are described in the)MODEL section when $\arg i$ is not supplied.

Examples: call tbput 12, "Item 1",,"Item 3". call tbput 12

TBSAVE - Save Table

TBSAVE saves the current table content in the file described by the last TBOPEN call.

TCSH - Pass UNIX Command

TCSH(cmd{, stem}) executes the UNIX command cmd using the tcsh shell.

When stem is not provided, the cmd output will be placed in the stack. The user will be able to read it using the parse pull command.

The queued () function may be used to return the number of lines in the stack.

When stem is provided, it must be a valid REXX name. It will be filled with the cmd output.

Example: call tcsh "df", tab tab.0 will contain the number of lines sent back by df. tab.1, tab.2, ... will contain the df output line by line.

See also the EXEC(), UNIX(), CSH() and KSH() functions.

TEE - Pass UNIX Command

TEE(cmd{, stem}) executes the **UNIX** or **WINDOWS** command cmd, displaying intermediate results on the standard output.

The arguments are the same as for the UNIX() or WINDOWS() built-in function.

UNIX or SH - Pass UNIX Command

 $\texttt{UNIX(cmd}\{\mbox{, stem}\})$ executes the UNIX command cmd using the Bourne shell sh.

On **WINDOWS** systems, UNIX() is identical to the WINDOWS() built-in function.

When stem is not provided, the cmd output will be placed in the stack. The user will be able to read it using the parse pull command.

The queued () function may be used to return the number of lines in the stack.

When stem is provided, it must me a valid REXX name. It will be filled with the cmd output.

Example:	call unix "df", tab
	(or call sh "df", tab)
	tab.0 will contain the number of lines sent back by df.
	tab.1, tab.2, will contain the df output line by line.

Note: sh does not support the ~ meta character. Use csh() or ksh() to pass a command such as call csh 'ls ~/foo*.c'

See also the EXEC(), CSH(), TCSH() and KSH() functions.

UNSETENV - Remove Environment Variable

UNSETENV(var) removes the environment variable var.

Example: call unsetenv "PATH" /* Not recommended! Without PATH, most commands will fail */

See also the ${\tt SETENV}($) function.

USLEEP - Suspend Execution

USLEEP(usec) suspends execution for usec microseconds.

UTIME - Change File Timestamp

UTIME(file, jj, mm, yyyy, hh, mm, ss) sets the file timestamp accordingly to the jj/mm/yyyy hh:mm:ss date.

UTIME returns 0 in case of success, or an error message.

Example: call utime '~/.cshrc',12,1,2002,23,55,36
say state('~/.cshrc', 'stamp')
/* displays: 12/01/2002 23:55:36 */

VALUE - Set or Retrieve a Variable

VALUE(symb {, expr}) returns the value of the symb S/REXX variable.

When the expr expression is specified, expr will be assigned to symb.

If symb refers to an uninitialized variable, the default value of that variable is always returned, regardless of the NOVALUE condition which is never raised.

Examples: tr = 4 say value('tr') /* Displays "4" */ call value 'tab.'tr, 2**8 /* Sets tab.4 to 256 */

VERSION- Windowing Identifier

VERSION() returns the current windowing identifier:

xview	when running the Open Windows xsrexx version.
motif	when running the MOTIF msrexx version.
windows	when running the WINDOWS version.
a null string (" ")	when running the non-windowing srexx version.

WAITPID - Wait for a Process Termination

WAITPID(pid{, "N"})

On UNIX systems, WAITPID(pid) suspends the calling process until one of the specified children terminates; if a child process terminated prior to the call to WAITPID(), return is immediate. pid specifies a set of child processes for which status is requested.

If pid is equal to -1, status is requested for any child process.

If pid is greater than 0, it specifies the process ID (returned by the FORK() built-in function) of the child process for which status is requested.

If WAITPID() returns because the status of a child process is available, this function returns a value equal to the process ID of the child process for which status is reported.

The optional "N" parameter passed to WAITPID() specifies that WAITPID() must not suspend the calling process. A value of 0 is returned when none of the processes specified with the pid argument have terminated.

A value of -1 is returned in case of error.

On **WINDOWS** systems, WAITPID() always returns a value of -1.

WINDOWS - Pass WINDOWS Command

WINDOWS(cmd{, stem})

On WINDOWS systems, WINDOWS () executes the WINDOWS command cmd.

On UNIX systems, WINDOWS() is identical to the UNIX() built-in function.

When stem is not provided, the cmd output will be placed in the stack. The user will be able to read it using the parse pull command.

The queued () function may be used to return the number of lines in the stack.

When stem is provided, it must me a valid REXX name. It will be filled with the cmd output.

Example: call windows "dir", tab tab.0 will contain the number of lines sent back by dir. tab.1, tab.2, ... will contain the dir output line by line.

Note: When using the wsrexx.exe windowing version of S/REXX, calling DOS like commands such as dir will make a temporary console appear. To list files, the DIR() built-in function would be more effective.

WIPE - Wipe Files

WIPE(ff)

With modern methods of recovery for data stored on magnetic media, such as Magnetic Force Microscopy (MFM), simply overwriting a file with 0s, for example, is not sufficient to prevent unwanted access to that file. These methods can in fact be used to read the previous state of the portion of the disk which has been wiped with a unique simple pattern.

WIPE() overwrites the ff file with 40 different patterns selected to prevent the recovery of the initial state of that file, and then erases the file.

WIPE() returns the full path names of the deleted files.

ff may include the \sim .. UNIX or WINDOWS file meta characters. If a filename contains blanks, it must be surrounded with quotes or double quotes.

When WIPE fails, it sets the rc variable to a non-zero value, and returns an error message, such as:

RM() error: File does not exist

Examples: say wipe("~/foo ~/test") could print: /user/john/foo /usr/john/test

XHOME - Installation Directory

XHOME() returns the installation directory. Usually /home/xed on UNIX, and C:\Program Files\SEDIT on WINDOWS.

S/REXX Dialog Management

S/REXX permits the creation of OpenLook, MOTIF or WINDOWS dialog panels.

To create OpenLook panels, the S/REXX program must start with:

```
#! /home/xed/xsrexx
```

To create **MOTIF** panels, the **S/REXX** program must start with:

```
#! /home/xed/msrexx
```

When OpenLook is not supported, xsrexx is the same as msrexx, so in a UNIX multi-platform environment, always using xsrexx will present no problems.

To create **WINDOWS** panels, the **S/REXX** either **srexx**.exe or **wsrexx**.exe.

For example:

C:\> wsrexx myprog

OpenLook Specifics

Individually colored items are not supported by the xsrexx OpenLook S/REXX version. Scroll lists do not support multiple selections.

WINDOWS Specifics

Individually colored items are not supported by the wsrexx S/REXX version.

Dialog boxes do not emit a FOCUS message and do not respond to function keys.

DY_PSCL() does not perform any action.

Consider the following /home/xed/demo/demo_dy/dy_tar macro:

```
#! /home/xed/xsrexx
signal on novalue
option mixed setenv
call dy_start()
$quit = dy_button(1, 1, "Quit")
call dy_label 14, 1.3, 'From Directory:'
$dir = dy_input(30, 1.3, 28)
$tape = dy_tg('Tape Selection:', 14, 5, 32, 4.5, "nrst4", 1, 40, 4.5,,
              "nrst5", 0)
$start = dy_button(26.5, 10, "Start TAR")
$handle_dy_ex = dy_end("proc", 2, 3.5, 61, 12.5, "n")
call dy_map $handle_dy_ex
exit
proc:
 parse arg handle reason
  select
    when reason = 'F1' | reason = 'B'$quit | reason = '^c'
                                                              then
          { call dy_unmap(handle)
             exit 0
          }
    when reason = 'B'$start | reason = 'return' then
      { if do_it() = 0 then exit 0
      }
    otherwise return 0
  end
return
do_it:
  dir = dy_vinput(handle, $dir)
  if ~state(dir, 'd') then
   { call dy_start()
     call dy_label 2, 5, '"'dir'" is not a valid directory.'
    call dy button 26.5, 10, "Restart"
     $prompt = dy_end("foo", 2, 3.5, 61, 12.5, "g")
    call dy_map $prompt
    call dy_destroy $prompt
    return 1
   }
  select
    when 1 = dy_vtg(handle, $tape, 1) then tape = 'nrst4'
    when 1 = dy_vtg(handle, $tape, 2) then tape = 'nrst5'
  end
  cd dir
  say 'dy_tar could perform the following commands:'
  sav
  say '
        cd 'cwd()
  say ' tar -cvf /dev/'tape '.'
  say
return 0
foo:
return
```

Calling this macro by typing dy_exch will display the following dialog box:

Q	No Name
Quit	From Directory: _֎
	Tape Selection: nrst4 nrst5
	Start TAR

This macro asks for a directory name and a tape device, and will display (without executing them) the **UNIX** commands needed to *tar* the directory using the chosen tape device.

option mixed setenv

allows the user to create environment variables such as *\$tape*. These variables are shared with procedure subroutines.

```
call dy_start()
```

starts a dialog box.

```
$quit = dy_button(1, 1, "Quit")
```

creates the Quit button on column 1, line 1. The \$quit variable receives the button number for future use.

```
call dy_label 14, 1.3, 'From Directory:' creates the From Directory label.
```

\$dir = dy_input(30, 1.3, 28))

creates the input field in column 30, line 1.3. The \$dir variable receives the input field number for future use.

creates the Tape Selection toggle in column 14, line 5, setting it to the nrst4 value.

```
$handle_dy_ex = dy_end("proc", 2, 3.5, 61, 12.5, "n")
```

ends the current dialog box. The dialog box will be located at column 2, line 3.5, starting from the position where the dialog box is centered regarding the whole screen.

It will be 61 columns wide and 12.5 lines high. "n" means the dialog box will be persistent. The user will have to dismiss it explicitly by clicking the Quit button, or by selecting the dialog box window Quit (or Close if the **MOTIF** MWM window manager is running) item.

proc is the name of the **S/REXX** subroutine to be called every time the user issues an action within the dialog box.

```
call dy_map $handle_dy_ex
```

maps the dialog box. dy_map() will return on 2 cases: the user selects the dialog box window Quit (or Close if the **MOTIF** MWM window manager is running) item, or when the proc call back subroutine issues a dy_unmap() call.

```
select
```

```
when reason = 'F1' | reason = 'B'$quit | reason = '^c' then
   { call dy_unmap(handle)
      exit 0
   }
```

when the users clicks on the Quit button, or hits the Fl or ^c key, proc unmaps the dialog box and exits.

```
when reason = 'B'$start | reason = 'return' then
```

when the user clicks on the Start TAR button, proc call the do_it() subroutine.

```
dir = dy_vinput(handle, $dir)
```

reads the directory input field.

```
select
  when 1 = dy_vtg(handle, $tape, 1) then tape = 'nrst4'
  when 1 = dy_vtg(handle, $tape, 2) then tape = 'nrst5'
end
```

reads the tape select toggle.

S/REXX Dialog Management within SEDIT

Within SEDIT, S/REXX permits the creation of OpenLook or MOTIF dialog panels.

Consider the following /home/xed/demo/demo_dy/dy_exch.sedit macro:

```
option mixed setenv
'extract/zone/case/line/size/nbfile'
if nbfile.1 = 0 then
 { 'prompt Open a file first'
  exit 0
 }
if ~$?handle_dy_ex then
{ call dy_start()
   $dismiss_dy_ex = dy_button(1, 1, "DISMISS")
   call dy_label 14, 1.3, 'EXCHANGE THIS:'
   exc_dy_ex = dy_input(29, 1.3, 29)
   call dy_label 14, 3.3, ' WITH THIS:'
   $with_dy_ex = dy_input(29, 3.3, 29)
   call dy_label 5, 6, 'From Column:'
   $fromc_dy_ex = dy_input(18, 6, 10, zone.1)
   call dy_label 30, 6, 'To Column:'
   $toc_dy_ex = dy_input(42, 6, 10, zone.2)
   call dy_label 5, 8, ' From Line:'
   $froml_dy_ex = dy_input(18, 8, 10, line.1)
   call dy_label 30, 8, ' To Line:'
   $tol_dy_ex = dy_input(42, 8, 10, size.1)
   if case.2 = 'respect' then fl = 1
    else
                               fl = 0
   $case_dy_ex = dy_tg(,,,5, 11, "Consider Case", fl)
    $word_dy_ex = dy_tg(,,,30, 11, "Whole Word", 0)
   $do_dy_ex = dy_button(26.5, 15, "DO IT")
   $handle_dy_ex = dy_end("dy_ex_cb", 2, 3.5, 61, 17.5, "n")
 }
else 'dy_ex_set' /* sets the dialog box values */
call dy_map $handle_dy_ex
```

,			.,
DISMISS	EXCHANGE THIS:	*	
	WITH THIS:		
From Co	lumn: <u>1</u>	To Column:	2147483647
From I	.ine: <u>59</u>	To Line:	68
🖌 Cons	ider Case	_ Whole Wo	rd

Calling this macro by typing dy_exch will display the following dialog box:

This macro allows the user to enter a string str1 in the EXCHANGE THIS input field, and a second string str2 in the WITH THIS input field. Clicking on the DO IT button will make **SEDIT** change every string str1 with the string str2, and str2 with str1.

option mixed setenv

allows the user to create environment variables such as \$handle_dy_ex. These variables are retained between macro calls.

```
if ~$?handle_dy_ex then
```

allows the user to test if the \$handle_dy_ex variable exists. If not, this is the first time the macro is called, and the dialog box must be created.

call dy_start()

starts a dialog box.

```
$dismiss_dy_ex = dy_button(1, 1, "DISMISS")
```

creates the DISMISS button on column 1, line 1. The \$dismiss_dy_ex variable receives the button number for future use.

```
call dy_label 14, 1.3, 'EXCHANGE THIS:' creates the EXCHANGE THIS label.
```

```
$exc_dy_ex = dy_input(29, 1.3, 29)
```

creates the first input field in column 29, line 1.3. The exc_dy_ex variable receives the input field number for future use.

```
$case_dy_ex = dy_tg(,,,5, 11, "Consider Case", fl)
```

creates the Consider Case toggle in column 5, line 11, setting it to the fl value, which reflects the current CASE setting. The first 3 arguments are omitted, since this toggle does not need a global label.

```
$handle_dy_ex = dy_end("dy_ex_cb", 2, 3.5, 61, 17.5, "n")
```

ends the current dialog box. The dialog box will be located at column 2, line 3.5, starting from the position where the dialog box is centered regarding the **SEDIT** window.

It will be 61 columns wide and 17.5 lines high. "n" means the dialog box will be persistent. The user will have to dismiss it explicitly by clicking the DISMISS button, or by selecting the dialog box window Quit (or Close if the **MOTIF** MWM window manager is running) item.

 dy_ex_cb is the name of the S/REXX macro to be called every time the user issues an action within the dialog box.

else 'dy_ex_set'

when the dialog box has already been created, the user can call the dy_ex_set S/REXX macro to update the displayed values according to the current file.

call dy_map \$handle_dy_ex

maps the dialog box.

The /home/xed/demo/demo_dy/dy_ex_cb.sedit macro is the following:

```
'extract/nbfile'
parse arg handle reason
select
 when reason = 'F1' ,
       reason = 'B'$dismiss_dy_ex
                                     then
        { call dy_unmap(handle)
           exit 0
        }
 when reason = 'B'$do dy ex then
    { if nbfile.1 = 0 then
       { 'prompt Open a file first'
         exit 0
       }
      call do it
      exit 0
    }
```

```
when reason = 'focus' then
    { if nbfile.1 ~= 0 then 'dy_ex_set'
               /* sets the "dy_exch" dialog box values */
      exit 0
    }
  otherwise exit 0
end
do it:
col1 = dy_vinput(handle, $fromc_dy_ex)
col2 = dy_vinput(handle, $toc_dy_ex)
line1 = dy_vinput(handle, $froml_dy_ex)
line2 = dy_vinput(handle, $tol_dy_ex)
str1 = dy_vinput(handle, $exc_dy_ex)
str2 = dy_vinput(handle, $with_dy_ex)
/*
 * Testing full world
 */
 if dy_vtg(handle, $word_dy_ex, 1) then
 { cmd = 'command cn'
    ff = ' \setminus '
  }
 else
  { cmd = 'command change'
    ff = '/'
  }
call test str1, ff
call test str2, ff
'preserve'
':'line1
'zone 'coll col2
/*
 * We look for a character which does not belong to strl and str2
*/
'sep off'
'arbchar off'
do i = 47 to 255
   sep = d2c(i)
   if 0 = pos(sep, str1) & 0 = pos(sep, str2) then leave i
end i
if i = 256 then
 { 'prompt No possible separator.'
   'restore'
   exit 0
 }
/*
 * Testing case
 * /
 if dy_vtg(handle, $case_dy_ex, 1) then 'case r'
                                         'case i'
 else
lines = line2-line1+1
cmd||sep||str1||sep||'..ööööö..@@@@@..ööööö'||sep lines '*'
cmd||sep||str2||sep||str1||sep||lines '*'
cmd||sep||'..ööööö..@@@@@..öööööö'||sep||str2||sep lines '*'
```

```
'restore'
return
/*
 * We see if str can be found
 */
test:procedure
parse arg str, ff
'extract/line'
trace off
ff||str
if rc = 0 then
 { ':'line.1
  return
 }
'prompt String "'str'" not found.'
'msg'
exit 0
```

```
when reason = 'focus' then
    { if nbfile.1 ~= 0 then 'dy_ex_set'
```

when the mouse enters the dialog box window, this callback macro is called with the second argument reason set to the word focus.

In this case, the macro calls the dy_ex_set macro:

```
option mixed setenv
'extract/zone/case/line/size'
call dy_sinput $handle_dy_ex, $fromc_dy_ex, zone.1
call dy_sinput $handle_dy_ex, $toc_dy_ex, zone.2
call dy_sinput $handle_dy_ex, $froml_dy_ex, line.1
call dy_sinput $handle_dy_ex, $froml_dy_ex, size.1
if case.2 = 'respect' then fl = 1
else fl = 0
call dy_stg $handle_dy_ex, $case_dy_ex, 1, fl
```

dy_ex_set sets the Columns and Lines input field according to the current file zone setting, to the current line and to the file length.

The Consider Word toggle is set according to the CASE setting.

```
select
when reason = 'F1' | ,
    reason = 'B'$dismiss_dy_ex then
{ call dy_unmap(handle)
```

when the user clicks on the DISMISS button, or hits the F1 key, dy_ex_cb unmaps the dialog box. The dialog box still exists, but is invisible.

```
when reason = 'B'$do_dy_ex then
```

when the user clicks on the DO IT button, dy_ex_cb reads the various input fields, and executes the following **SEDIT** commands:

zone col1 col2	to restrict the search to the specified columns.			
case i	when the Consider Case toggle is OFF.			
:line1	to set the current line to the From Line field specified starting line.			
change/str1/??@@@@@	changes the first specified string to a string not likely to be found in the file.			
change/str2/str1/ lines *				
	changes the second specified string to the first string.			
change/??@@@@@@??/	str2 changes what was the first string to the second string.			

When the Whole Word toggle is ON, dy_ex_cb uses the CN command instead of the CHANGE command.

S/REXX ISPF-like Tables

When running as **SEDIT** macros, **S/REXX** programs have the ability to display data files in a formatted way called a table.

A data file has rows and columns. Every row is separated from the previous row by a newline character, as in ordinary text files.

Every column is separated by an arbitrary character within a line. The default separator is a tabulation. However, for better legibility within this manual, the *i* character will be used as a separator.

The directory /home/xed/demo/demo_table contains various table example files:

/home/xed/demo_table/test_tbl.data:

```
Line 1
Line 2;Item2;Item3;Item4;5;6;7;8
Line 3;Item2
Line 4;Item2;Item3
Line 6;Item2;Item3;Item4
Line 7;Item2;Item3;Item4
Line 8;Item2
Line 9;Item2;Item3;Item4
Line 10;Item2;Item3;Item4
Line 11;Item2;Item3;Item4
Line 12;Item2;Item3;Item4
Line 13;Item2;Item3;Item4
```

This file contains 14 lines. Line 1 is one column wide, line 3 is two columns wide, etc.

/home/xed/demo_table/test_tbl.panel:

```
)ATTR default(+% )
^ type(output) intens(high) color(black) Hightlight(reverse)
" type(output) intens(low) color(black) Hightlight(normal)
$ type(text) intens(low) color(red) Hightlight(normal)
@ type(input) intens(zero) color(red) Hightlight(underline)
& type(num) intens(low) color(red) Hightlight(underline)
)BODY expand(//)
%/-/ edit table /-/
2
$COMMAND ====> ZCMD
8
                   ^DATE $ ^TIME $
%
         VOLSER
+SEL
                                    UNIT
                                                  SIZE
+/-/
)model
_SEL
       + _VOLSER
                                _UNIT + _SIZE "trail $
                    +
)TRAIL expand(//)
Ŷ
$COMMAND ====>&ZCMDBOT
$/ /F1:Quit F3:Save/ /
) BUTTON
Quit
Save
Add
Del
Exit
```

This file describes the overall formatted screen layout by using 5 sections.

1) The)ATTR section

This section maps a single character to a specific screen field type.

The field attributes may be the following:

TYPE(param)	Text matches a read-only output field.	
	Output matches a read-only output field. It must	
	contain a valid REXX variable whose content will be used to update the field.	
	Input matches an input field.	
	Num matches an input field allowing only numerical characters.	
INTENS(param)	High matches double intensity display.	
	Low matches normal display.	
	Zero matches no display.	

COLOR(param)	specifies the field display color. See the SEDIT color command for a complete list of all available colors.	
HIGHLIGHT(param)	Normal matches no highlight.	
	Underline matches an underlined field.	
	Reverse matches a reverse video field.	

When specifying default(+%), the following default characters will be in use:

	+	%	_
ТҮРЕ	Text	Text	Input
INTENS	Low	Low	Low
COLOR	Black	Red	Red
HIGHTLIGHT	Normal	Normal	Normal

2) The)BODY section

This section describes a leading fixed part of the screen, which may be used to visually describe the MODEL section, or to create input fields where the user may type commands.

The expand (//) syntax forces **S/REXX** to expand the characters within the // separators to match the screen width.

For example, the "%/-/ edit table /-/" entry makes S/REXX display:

----- edit table -----

An input entry, such as "_ZCMD" must contain a valid **S/REXX** variable symbol. If the user fills the corresponding displayed field, the **S/REXX** variable (ZCMD in this example) will be updated in the following way:

ZCMD.0	0 when no data has been typed in.
	1 when data has been typed in.

ZCMD.1 The typed in data.

3) The)MODEL section

This section describes the screen layout used to display the data.

An input entry, such as "_SEL" must contain a valid S/REXX variable symbol. This variable will be updated by the TBGET() built-in function in the same way the)BODY variables are.

4) The)TRAIL section

This section describes a trailing fixed part of the screen, which may be used in the same way the) BODY section is.

5) The) BUTTON section

Each line of this section will be displayed as a button.

/home/xed/demo/demo_table/test_tbl.sedit:

```
parse arg trail
if trail = '' then trail = '+'
call tbclose
'extract/xhome'
file = xhome.1'/demo/demo_table/test_tbl.data'
panel = xhome.1'/demo/demo_table/test_tbl.panel'
line = 1
nb_line = tbopen(file, panel, ';')
/*
* Initial displayed values
* /
date
       = date('e')
      = time()
time
       = ''
zcmd
zcmdbot = '1.25'
do cntl = 1
 call tbdispl line, rr
 nb_line = rr.8
  if ZCMD ~= ''
                   then
   { ZCMD = lower(strip(ZCMD))
     select
       when ZCMD = 'top' then
        { line = 1
          iterate cntl
        }
       when ZCMD = 'bot' then
        { line = nb_line
          iterate cntl
        }
       when left(ZCMD, 1) = 'e' then
        { parse var ZCMD 'e' ltr
          if datatype(ltr, 'w') & ltr > 0 & ltr <= nb_line then
           { call tbget ltr
             size = ''
             unit = ''
            volser = ''
            sel = ''
            call tbput ltr
           }
          else 'prompt Invalid line number'
          iterate cntl
        }
       when left(ZCMD, 1) = 'r' then
        { parse var ZCMD 'r' ltr
          if datatype(ltr, 'w') & ltr > 0 & ltr <= nb_line then</pre>
           { call tbget ltr
             call tbput ltr, size, unit, volser, sel
           }
          else 'prompt Invalid line number'
          iterate cntl
        }
       when datatype(ZCMD, 'w') then
        \{ line = max(ZCMD, 1)
          line = min(line, nb_line)
          iterate cntl
        }
```

```
otherwise nop
    end
   }
  if ZCMDBOT ~= '' then say 'ZCMDBOT = 'ZCMDBOT
 do ll = line to rr.6
   call tbget ll
  end
  select
    when rr.1 = 'F1' | rr.1 = 'B1' then leave cntl
    when rr.1 = 'F8'
when rr.1 = 'F7'
                                    then line = rr.6
                                    then line = Max(1, 1+line - rr.7)
    when rr.1 = 'F3' | rr.1 = 'B2' then call tbsave
     when rr.1 = 'F15' then
      { call tbsave
       leave cntl
     }
     when rr.1 = 'B3' then nb_line = tbadd(line)
     when rr.1 = 'B4' then nb_line = tbdel(line)
     when rr.1 = 'B5' then
      { trace off
        'prompt Really Quit ?'
       trace e
       if rc = 0 then 'exit'
       else iterate cntl
      }
     when rr.1 = '^=' \& rr.2 \sim = 0 then
      { call tbget rr.2
       call tbadd rr.2, sel, volser, unit, size
       iterate cntl
      }
     when rr.1 = '^a' \& rr.2 \sim = 0 then
     { call tbadd rr.2
       iterate cntl
      }
     when rr.1 = '^d' \& rr.2 \sim = 0 then
      { call tbdel rr.2
       iterate cntl
      }
     otherwise nop
  end
end
call tbclose
```

This macro shows how to use the various built-in table functions.

call tbclose

closes a previously opened table.

```
nb_line = tbopen(file, panel, ';')
```

opens the "file" file using the "panel" panel. The separator in use to parse "file" will be the third ";" parameter.

tbopen returns the file number of lines.

```
call tbdispl line, rr
```

displays the table, starting at line "line", and waits for user action.

The following panel will be displayed:

zed 8 C - text_thLoedit, dir:/home/mt/sedit/shj/sed/demo/demo_table						
Quit Save Add Del Exit						
Π			edit	table		
	0010101					
	COLLING	ab ===== =				
		12/06/	215 1	2:45		
1	BEL	VOLSER		UNIT	SIZE	I
	Line	1				+
7	Line 3	1 2 Ttom?		Tton?	Itopi	
	Line	i Item?		LOADS	T Collina	I
1	Line	4 Item2		Iten3		+
		a tata		a c-anc		+
	Line #	5 Item2		Iten3	Iten4	+
	Line 7	7 Item2		Iten3		+
	Line 8	6 Item2				+
	Line i	9 Item2		Iten3	Iten4	+
	Line 1	10 Item2		Item3	Item4	+
	Line 1	11 Item2		Iten3	Iten4	*
	Line 1	12 Item2		Item3	Iten4	*
	Line I	13 Item2		Iten3	Item4	*
	riue :	14 10482		114h3	Trens	+
	COMMAN	RD ====> 1.25				
			F1:Quit	F3:Save		
1						

The "rr" stem will be used to return the following information:

rr.O	The rr size (8	8 here).	
rr.1	A keyword in	A keyword indicating the user action:	
	return	the Return key.	
	Fi	The i top function key.	
	Li	The i left function key.	
	Ri	The i right function key.	
	Bi	The i mouse button.	
	^x	The Control-x action.	
0			
	I bo ourcor lin	a tila raiotad nacition or () it th	

The cursor line file related position, or 0 if the cursor is not on a)MODEL data field location.

rr.3	The cursor column file related position, or 0 if the cursor is not on a)MODEL data field location.
rr.4	The mouse line file related position, or 0 if the mouse is not on a)MODEL data field location.
rr.5	The mouse column file related position, or 0 if the mouse is not on a)MODEL data field location.
rr.6	The last displayed line.
rr.7	The number of lines which can be displayed, according to the panel layout and the screen size.
rr.8	The number of lines of the current loaded table.

```
call tgbet ltr
```

updates the SEL, VOLSER, UNIT, and SIZE variables described in the)MODEL section, according to the modifications entered by the user.

```
call tbput ltr
```

uses the SEL, VOLSER, UNIT, and SIZE variables described in the)MODEL section to update the currently opened table.

```
call tbsave
```

saves the currently opened table content in the file described by the last tbopen call.

```
nb_line = tbadd(line)
```

adds an empty line after line "line", and updates nb_line with the total number of lines of the current table.

call tbadd rr.2, sel, volser, unit, size

adds a line after line "rr.2", using the contents of the variables sel, volser, unit and size.

nb_line = tbdel(line)

deletes line "line", and updates nb_line with the total number of lines in the current table.

This macro is designed to execute the following actions:

F1	Quit without saving the changes.
F3	Saves the current table.
F7	Scrolls up.
F8	Scrolls down.
^=	Duplicates the cursor line.
^a	Inserts 1 line at the cursor location.
^d	Deletes 1 line at the cursor location

The following commands may be entered in the ZCMD field:

Selects the first line as the current line.
Selects the last line as the current line.
Reverts the contents of the line i.
Makes the i line the current line.

In addition, the user may click on the following buttons:

Quit	Quit without saving the changes.
Save	Saves the current table.
Add	Inserts 1 line at the current line location.
Del	Deletes 1 line at the current line location.
Exit	Terminates the current SEDIT session.

The default **SEDIT** profile.sedit initialization file loads the test_tbl macro, so the user may start it by simply typing test_tbl in the command field.

S/REXX Programming Interface

This chapter describes how to imbed the **S/REXX** language into C applications, and how to add user-supplied built-in functions.

Creating a New Address Environment

The following routines are provided:

- env_rx initiates a host command environment.
- exit_rx cleans up before exiting.
- getval_rx gets an **S/REXX** variable.
- pull_rx extracts the first available External Data Queue item.
- push_rx adds a string on top of the External Data Queue.
- queue_rx adds a string to the External Data Queue.
- queued_rx queries the External Data Queue length.
- run_rx runs an **S/REXX** program from C.
- setval_rx sets an **S/REXX** variable.
- stop_rx stops the currently active S/REXX program.

To use these routines two files are required:

{install-dir}/lib/arch/libsr.o
{install-dir}/include/srexx.h

where arch is the hardware dependent string described in Appendix B: Hardware String on page 677.

A typical makefile on an IBM RS/6000 resembles the following:

```
ARCH = ibm
CCLIB = /home/xed/lib/$(ARCH)
CCPATH = /home/xed/include
CC = cc -0
demo1: demo1.c $(CCLIB)/libsr.o $(CCPATH)/srexx.h
        $(CC) -0 demo1 demo1.c $(CCLIB)/libsr.o -I$(CCPATH)
-lbsd -lc -lm
```

Note that the lbsd library is required on IBMs RS/6000 only.

All C examples described in this section are provided in the {install-dir}/home/demo_demo_sr directory.

ENV_RX - Initiate a Host Command Environment

```
void env_rx(name, fns, lg_def)
char *name;
int (*fns)();
int lg_def;
void env_rx2(name, fns, lg_def, parm)
char *name, *parm;
int (*fns)();
int lg_def;
```

The function fns will be called every time the **S/REXX** program will issue a command to the name environment. name is a NULL terminated string which will be translated into upper case by env_rx before use.

If the name environment already exists, it will be updated.

If fns is a NULL pointer, a previous name environment will be deleted.

If lg_def is set to 1, name will become the default environment.

env_rx2 can be used instead of env_rx to pass an arbitrary parm parameter to fns.

fns will receive a NULL terminated string containing the command and its length:

```
int fns(string, l_string, parm)
  char *string, *parm;
  int l_string;
```

parm is the arbitrary parameter passed to env_rx2. When env_rx has been used to create the host command environment, parm will be set to NULL.

Note that when it is first called, env_rx or env_rx2 will also create the standard **S/REXX UNIX** or **WINDOWS** environment.

Example:

A C demol.c program:

```
#include <stdio.h>
#include "srexx.h"
int call_back(string, len)
  char *string;
  int len;
{
    printf ("call_back: received '%s'\n", string);
    return(0);
}
main()
{
  int rc;
  env_rx("MyEnv", call_back, 0); /* MyEnv tranlated */
  rc = run_rx("r_demo1", "../..", NULL, NULL, NULL);
  exit_rx(rc); /* exit_rx() cleans up before exiting */
}
```

An r_demo1 S/REXX program called by the demo1 program:

address myenv 12**5.56

To compile and execute this program, issue the following commands:

```
C{foo}% cd {install-dir}/demo/demo_sr
C{demo_sr}% make demo1
cc -0 -o demo1 demo1.c ../../lib/sun4/libsr.o -I../../in-
clude -lc -lm
9.1u 1.4s 0:10 96% 0+900k 3+63io 0pf+0w
C{demo_sr}% demo1
call_back: received "1000570.58"
C{demo_sr}%
```

where {*install-dir*} is the actual S/REXX installation directory.

EXIT_RX - Cleans up and Exits

void exit_rx(rc)
 int rc;

 $exit_rx()$ performs the necesary clean up before exiting with the rc return code. In particular, $exit_rx()$ releases a floating license in use.

GETVAL_RX - Get an S/REXX Variable

```
void getval_rx(res, len, name, l_name)
  char **res, *name;
  int *len, l_name;
```

name is a string which must contain a valid **S/REXX** symbol name with a length of 1_name.

*res will be allocated with a NULL terminated string which is the contents of name. *len will receive the *res length.

It is the responsibility of the caller to free *res after usage.

Example:

A C demo2.c program:

```
#include <stdio.h>
#include "srexx.h"
int call_back(name, ll)
  char *name;
{
  char *res;
  int len;
  getval_rx(&res, &len, name, ll);
  printf ("call_back: %s = \"%s\"\n", name, res);
  free(res);
  return(0);
}
main()
{
  int rc;
  env_rx("MyEnv", call_back, 1);
  rc = run_rx("r_demo2", "/home/xed", NULL, NULL, NULL);
  exit_rx(rc); /* exit_rx() cleans up before exiting */
}
```

An r_demo2 S/REXX program called by the demo2 program:

```
i = "1"
j = 2
tab.i.j = 'This is tab.1.2'
"i"
"j"
"tab.i.j"
"tab.1.3"
```

To compile and execute this program, issue the following commands:

```
C{foo}% cd {install-dir}/demo/demo_sr
C{demo_sr}% make demo2
cc -0 -o demo2 demo2.c ../../lib/sun4/libsr.o -I../../in-
clude -lc -lm
6.4u 1.8s 0:10 79% 0+852k 94+61io 124pf+0w
C{demo_sr}% demo2
call_back: i = "1"
call_back: j = "2"
call_back: tab.i.j = "This is tab.1.2"
call_back: tab.1.3 = "TAB.1.3"
C{demo_sr}%
```

where {*install-dir*} is the actual **S/REXX** installation directory.

PULL_RX - Extract External Data Queue Item

```
void pull_rx(res, len)
  char **res;
  int *len;
```

*res will be allocated with a NULL terminated string holding the first external data queue (or stack) item content. *len will receive the *res length.

If the external data queue is empty, *res will be set to NULL.

It is the responsibility of the caller to free *res after usage.

Example:

A C demo3.c program:

```
#include <stdio.h>
int call_back(string, ll)
  char *string; /* ARGSUSED */
{
  char *res;
  int len;
  pull_rx(&res, &len);
  if (res)
   { printf ("call_back: \"%s\" was in the stack (length
= %d).\n", res, len);
      free(res);
    }
  else
      printf ("call_back: stack empty.\n");
  return(0);
}
main()
{
  int rc;
  env_rx("MyEnv", call_back, 1);
  rc = run rx("r demo3", "/home/xed", NULL, NULL, NULL);
  exit_rx(rc); /* exit_rx() cleans up before exiting */
}
```

```
''
queue ''
queue 'String 1'
queue 'String 2 '
queue 'String 3 '
''
''
''
''
''
```

To compile and execute this program, issue the following commands:

```
C{foo}% cd {install-dir}/demo/demo_sr
C{demo_sr}% make demo3
cc -0 -o demo3 demo3.c ../../lib/sun4/libsr.o -I../../in-
clude -lc -lm
8.9u 1.6s 0:11 94% 0+896k 2+67io 0pf+0w
C{demo_sr}% demo3
call_back: stack empty.
call_back: "" was in the stack (length = 0).
call_back: "String 1" was in the stack (length = 8).
call_back: "String 2 " was in the stack (length = 9).
call_back: "String 3 " was in the stack (length = 10).
call_back: stack empty.
C{demo_sr}%
```

where {*install-dir*} is the actual **S/REXX** installation directory.
PUSH_RX - Add a String on Top of the External Data Queue

```
void push_rx(str, len)
  char *str;
  int len;
```

The str string, whose length is given by len, is added on top the External Data Queue (or stack). str does not need to be a NULL terminated string.

Example: see the demo4.c example on page page 638.

QUEUE_RX - Add a String to the External Data Queue

```
void queue_rx(str, len)
  char *str;
  int len;
```

The str string, whose length is given by len, is added to the External Data Queue (or stack). str does not need to be a NULL terminated string.

Example:

A C demo4.c program:

```
#include <stdio.h>
int push(string, len)
  char *string;
  int len;
{ push_rx(string, len);
  printf ("push: \"%s\" has been pushed.\n", string);
  return(0);
}
int queue(string, len)
  char *string;
  int len;
{ queue_rx(string, len);
  printf ("queue: \"%s\" has been queued.\n", string);
  return(0);
}
main()
{ int rc;
  env_rx("push", push, 1);
  env_rx("queue", queue, 1);
  rc = run_rx("r_demo4", "/home/xed", NULL, NULL, NULL);
  exit_rx(rc); /* exit_rx() cleans up before exiting */
}
```

An r_demo4 S/REXX program called by the demo4 program:

```
address queue 'This will be queued'
address push 'This will be pushed'
parse pull a
say a
parse pull a
say a
```

To compile and execute this program, issue the following commands:

```
C{foo}% cd {install-dir}/demo/demo_sr
C{demo_sr}% make demo4
cc -0 -o demo4 demo4.c ../../lib/sun4/libsr.o -I../../in-
clude -lc -lm
9.1u 1.5s 0:11 95% 0+900k 1+68io 0pf+0w
C{demo_sr}% demo4
queue: "This will be queued" has been queued.
push: "This will be queued" has been pushed.
This will be pushed
This will be pushed
This will be queued
C{demo_sr}%
```

where {*install-dir*} is the actual **S/REXX** installation directory.

QUEUED_RX - Query External Data Queue Length

int queued_rx()

queued_rx returns the external data queue (or stack) length.

Example:

A C demo5.c program:

An r_demo5 S/REXX program called by the demo5 program:

```
''
queue '1'
queue '2'
queue '3'
''
pull .
pull .
pull .
jull .
```

To compile and execute this program, issue the following commands:

```
C{foo}% cd {install-dir}/demo/demo_sr
C{demo_sr}% make demo5
cc -0 -o demo5 demo5.c ../../lib/sun4/libsr.o -I../../in-
clude -lc -lm
8.8u 2.0s 0:13 82% 0+876k 44+71io 81pf+0w
C{demo_sr}% demo5
call_back: stack length = 0
call_back: stack length = 3
call_back: stack length = 0
C{demo_sr}%
```

where {*install-dir*} is the actual **S/REXX** installation directory.

RUN_RX - Run an S/REXX Program

```
#include "rexx.h"
int run_rx(args, inst, ss, ret_str, len_ret_str)
  char *args, *inst, **ret_str;
  SAV_COMP **ss;
  int *len_ret_str;
```

args is a NULL terminated string which starts with a filename related to an **S/REXX** program, optionally followed by the argument to be passed to this program.

inst is a NULL terminated string indicating the **S/REXX** installation directory, which must contain a passwds file with a valid password identifying the cpu on which run_rx will execute. If inst is NULL, run_rx will attempt to use a REXXHOME environment variable instead. In this case, before using run_rx, the user must issue a command such as "setenv REXXHOME /home/xed" (C-Shell) or

"export REXXHOME=/home/xed" (Korn Shell).

On **WINDOWS** systems, inst can optionally contain the name of the .exe module to be used when the REXX CALL clause is used with OPTION NOLOAD in effect:

define INST "C:\\Program Files\\SEDIT\\srexx.new.exe"
rc = run_rx(args, INST, NULL, NULL, NULL);

ss is a pointer to a structure which will be filled with the compiled form of the args **S/REXX** program, or a NULL pointer if this save is not to be performed.

If ss is not a NULL pointer, it must be set to zero before the first run_rx call. Subsequent run_rx calls will use the ss compiled form instead of compiling the args program every time, saving a substantial amount of time. Note that run_rx will notice if the args program has been externally modified between two successive calls, and automatically compile it again.

If ret_str is not a NULL pointer, ret_str will be filled with an allocated NULL terminated string containing the string passed to the **S/REXX** EXIT statement, if any. len_ret_str will contain the ret_str length.

It is the responsibility of the caller to free ***ret_str** after usage.

Example:

A C demo6.c program:

```
#include <stdio.h>
#include "srexx.h"
int call_back(string, len)
 char *string;
{ printf ("call_back: received \"%s\"\n", string);
 return(0);
}
void dsp(exit_value, len_exit_value, rc)
  char *exit value;
  int len_exit_value, rc;
{ if (exit_value)
   { printf ("demo6: exit_value = \"%s\", len = %d\n",
             exit_value, len_exit_value);
     free(exit_value);
   }
  printf ("demo6: return code = %d\n", rc);
}
main()
{ char *exit_value;
  SAV_COMP *compiled;
  int len_exit_value, rc;
  env_rx("MyEnv", call_back, 1);
  /*
   * Compiled form not saved
   */
  run_rx("r_demo6", "/home/xed", NULL, NULL, NULL);
  /*
   * Compiled form saved
   */
  compiled = NULL; /* **** MANDATORY **** */
  rc = run_rx("r_demo6", "/home/xed", &compiled,
             &exit_value, &len_exit_value);
  dsp(exit_value, len_exit_value, rc);
  /*
   * run_rx() will use the previous compiled form
   */
  rc = run_rx("r_demo6 1", "/home/xed", &compiled,
              &exit_value, &len_exit_value);
  dsp(exit_value, len_exit_value, rc);
  /*
   * run_rx() will recompile r_demo6 because we modify it
   */
  system("touch r_demo6");
  rc = run_rx("r_demo6 2", "/home/xed", &compiled,
              &exit_value, &len_exit_value);
  dsp(exit_value, len_exit_value, rc);
  rc = run_rx("r_demo6 3", "/home/xed", &compiled,
               &exit_value, &len_exit_value);
  dsp(exit_value, len_exit_value, rc);
  exit_rx(rc); /* exit_rx() cleans up before exiting */
}
```

An r_demo6 S/REXX program called by the demo6 program:

To compile and execute this program, issue the following commands:

```
C{foo}% cd {install-dir}/demo/demo_sr
C{demo_sr}% make demo6
cc -O -o demo6 demo6.c ../../lib/sun4/libsr.o -I../../include -lc -lm
9.1u 1.6s 0:12 84% 0+880k 49+67io 82pf+0w
C{demo_sr}% demo6
************************************
demo6: called with "" argument.
call_back: received "Sent to the MYENV callback routine"
*****
demo6: called with "" argument.
call_back: received "Sent to the MYENV callback routine"
demo6: return code = 0
demo6: called with "1" argument.
call_back: received "Sent to the MYENV callback routine"
demo6: return code = 0
*****
demo6: called with "2" argument.
call_back: received "Sent to the MYENV callback routine"
demo6: exit value = "12.029856", len = 9
demo6: return code = 12
demo6: called with "3" argument.
call_back: received "Sent to the MYENV callback routine"
demo6: exit_value = "Exit String", len = 11
demo6: return code = 1165519220
C{demo_sr}%
```

where {*install-dir*} is the actual S/REXX installation directory.

<u>SETVAL_RX - Set an S/REXX Variable.</u>

```
void setval_rx(symb, l_symb, str, l_str)
  char *symb, *str;
  int l_symb, l_str;
```

symb is a character string which must contain a valid S/REXX name. 1_symb is its length. str is a character string to be assigned to symb. 1_str is its length.

Example:

A C demo7.c program:

```
#include <stdio.h>
int call_back(string, len)
    char *string;
{
    printf ("call_back: received \"%s\"\n", string);
    setval_rx(string, len, "Value assigned", 14);
    return(0);
}
main()
{
    int rc;
    env_rx("MyEnv", call_back, 1);
    rc = run_rx("r_demo7", "../..", NULL, NULL, NULL);
    exit_rx(rc); /* exit_rx() cleans up before exiting */
}
```

An r_demo7 S/REXX program called by the demo7 program:

```
say 'val = 'val
'val'
say 'val = 'val
```

To compile and execute this program, issue the following commands:

```
C{foo}% cd {install-dir}/demo/demo_sr
C{demo_sr}% make demo7
cc -0 -o demo7 demo7.c ../../lib/sun4/libsr.o -I../../in-
clude -lc -lm
9.1u 1.4s 0:11 95% 0+904k 12+58io 12pf+0w
C{demo_sr}% demo7
val = VAL
call_back: received "val"
val = Value assigned
C{demo_sr}%
```

where {*install-dir*} is the actual **S/REXX** installation directory.

STOP_RX - Stop an S/REXX Program.

```
void stop_rx(str, l_str, rc)
  char *str;
  int l_str, rc;
```

stop_rx will make **S/REXX** behave as if the statement "EXIT STR" had been entered. run_rx will return to its caller with a rc return code. 1_str is str length. str may be NULL, which will simulate a simple "EXIT" statement.

Example:

A C demo8.c program:

```
#include <stdio.h>
int call back(string, len)
  char *string;
  int len;
{
  printf ("call_back: received \"%s\"\n", string);
  stop_rx(string, len, 12);
  return(0);
}
main()
{
  char *exit_value;
  int len_exit_value, rc;
  env_rx("MyEnv", call_back, 1);
  rc = run_rx("r_demo8", "/home/xed", NULL, &exit_value,
               &len_exit_value);
   if (exit_value)
    printf ("demo8: exit_value = \"%s\"\n", exit_value);
   exit_rx(rc); /* exit_rx() cleans up before exiting */
}
```

An r_demo8 S/REXX program called by the demo7 program:

```
say 'demo8 started'
'exiting'
say 'Not displayed'
```

To compile and execute this program, issue the following commands:

```
C{foo}% cd {install-dir}/demo/demo_sr
C{demo_sr}% make demo8
cc -0 -0 demo8 demo8.c ../../lib/sun4/libsr.o -I../../in-
clude -lc -lm
6.6u 1.5s 0:08 95% 0+868k 3+62io 0pf+0w
C{demo_sr}% demo8
demo8 started
call_back: received "exiting"
demo8: exit_value = "exiting"
C{demo_sr}%
```

where {*install-dir*} is the actual **S/REXX** installation directory.

Adding Built-in Functions

It is possible to add built-in functions by modifying and compiling the rx_add_on.c example supplied in the {install-dir}/demo/demo_built directory.

A typical makefile on an IBM RS/6000 is shown below:

Note that the lbsd library is required on IBMs RS/6000 only.

This makefile creates a srexx2 module, which incorporates two new built-in functions described in the rx_add_on.c file.

rx_add_on must start with the following statements:

These statements defines NB new built-in functions. They will be named left2 and pi2. The C functions bu_left2() and bu_pi2() will be called by the **S/REXX** interpreter when the left2 and pi2 built-in functions will be used.

pi2(N) returns the first N π decimals.

left2 is a simple copy of the standard left function. It demonstrates the use of various internal subroutines:

```
rx_nbfa(args, its, nb_its)
LEX *args;
ITEM ***its;
int *nb_its;
```

The first call within a built-in function must be rx_nbfa , which computes the supplied arguments.

The number of arguments passed to the routine will be stored in *nb_its. The actual arguments will be stored in the ITEM array *its.

The following is an example of an ITEM structure:

```
typedef struct str
{ char *str;
    int len;
} STR;

typedef struct item
{ enum { IT_DB, IT_STR } type;
    union
        { STR str;
            double db;
        } val;
        int prec;
    } ITEM;
```

It may be either a string STR structure, or a double.

The it2str function allows the user to convert an ITEM value into a string, regardless of its initial content:

```
void it2str(it, v_it, l_it, ind)
ITEM *it;
char **v_it;
int *l_it, ind;
```

it2str uses 10 static internal buffers to store the data. ind indicates which buffer is to be used, and may be the constant values ST1, ST2, ... ST10 defined in the srexx.h include file.

For example:

```
it2str(its[0], &arg1, &len1, ST1);
```

stores the its[0] content in character format into arg1.

The functions malloc_a(), realloc_a() and strdupa() must be used in replacement for the standard C library functions malloc(), realloc() and strdup(). They cleanly abort the srexx process when no more memory is available.

The rx_round function rounds a double value to a specified value:

```
double rx_round(val, nd)
  double val;
  int nd;
```

The rx_bu_err function cleanly aborts any built-in function which receives an erroneous argument:

```
void rx_bu_err(args, its, nb_its, ierr, mes)
  LEX *args;
  ITEM **its;
  int ierr;
  char *mes;
```

its are the arguments computed by the rx_nbfa function. mes is an error message to be displayed. When no message is to be displayed, mes may be replaced by the NULL statement.

free_it allows the user to free the storage allocated by the rx_nbfa function:

```
for (i=0; i<nb_its; i++) free_it(&its[i]);
free(its);</pre>
```

Using the RXD Debugger

rxd is a graphical debugger which is licensed separately.

Entering RXD Explicitly

To enter rxd explicitly on **UNIX** systems, type:

```
/home/xed/rxd test1 args
```

This starts rxd, which will run the test1 S/REXX program, passing to it the args optional arguments.

To enter rxd explicitly on **WINDOWS** systems, type:

```
cd c:\Program Files\SEDIT
rxd test1 args
```

or use the S/REXX Debugger icon located in the SEDIT folder.

No modification of the program is necessary to start the debugger.

Entering RXD Implicitly

To enter rxd implicitly, add the following statement within the S/REXX program to debug:

trace x

This method is the only way to debug an SEDIT macro.

rxd will initiate and display the following window:



The I/O area is used by the REXX process to display its output, and permits the user to enter a string to be sent to the REXX process (a response to a PULL statement for example).

This input is modifiable using the editing keys, until it is sent to the REXX process by hitting the Return or Enter key. Therefore, it is not possible to use the REXX charin() function to read one character at a time.

The command area is used to enter the following rxd commands:

alias new old	new will be a synonym to the old command.
alias new "old	"allows the user to specify a synonym ending with a ";". For example: alias cwd "say cwd();"
alias	displays all the defined synonyms.
down	moves down the call stack one level.
cont	continues execution.
delete numline	removes a stop at line numline.
delete all	removes all the stops.
kill	terminates the REXX process.
list proc	displays in the source area the proc procedure.
next	continues execution, and pauses at the next statement within the same stack level. This enables subroutines to be skipped over.
print var	prints the variable var.
print expr	<pre>executes the interpret say expr statement within the REXX process, and displays the result in the I/O window. Within the expr statement, two variables are defined to access the selection: .sel becomes the current selection. .selw becomes the REXX variable containing the selection. For example, to print tab.1, select one letter in the word tab and click on the print button, which is assigned to the command print .selw.</pre>
run {args}	when args is not specified, run terminates the current REXX process, and restarts it with the arguments used for the previous run. When specified, args are the new process arguments.
rerun {args}	is similar to the run command. When args is omitted, no argument is passed to the REXX process.
sav_stat file	saves the stops location in the specified file.
source file	reads the specified file, and executes every line.
set	set function keys. See using the 'using the set command' section.
status	displays the stops.
step	continues execution, and pauses at the next statement.
stepout	continues execution, and pauses after exiting the current

	subroutine.
stop at line	sets a stop at the specified line.
stop in proc	sets a stop at the beginning of the proc procedure. proc does not need to be loaded.
unalias new	removes the new synonym.
up	moves up the call stack one level.
upcmd n	shrinks n lines the command line subwindow.
upsource n	shrinks n lines the source subwindow.
where	displays the call stack.
expr;	sends the expr expression to the REXX process to be interpreted.
^C	typing Control-c interrupts the REXX process. An empty DO loop or a parse pull statement cannot be interrupted.

The I/O and command areas can be edited using the following keys:

Arrow UP	progressively displays the previous commands in a reverse chronological sequence.						
Arrow DOWN	progressively displays the previous commands in a chronological sequence.						
Arrow LEFT	moves the cursor to the left.						
Arrow RIGHT	moves the cursor to the right.						
Insert or ^i	switches insert and replace mode.						
Home or ^h	moves the cursor to the start of the line.						
End or ^e	moves the cursor to the end of the line.						
Escape or L3	erases the characters following the cursor.						
F3 or L6	saves the selection into an internal buffer named the shelf.						
F4 or L8	pastes the shelf content at the cursor location.						
Mouse 2	pastes the current selection at the cursor location.						

Setting Stops

When the mouse enters the stop area, the mouse cursor shape becomes circular.

Clicking with the first mouse button sets a stop at the specified line location. Clicking on a line where a stop is displayed removes the stop.

Customizing RXD

When initializing, rxd searches for a .rxdinit file in the current directory, the user's home directory and the **S/REXX** installation directory.

This file may contain the following elements:

back_command xx xx xx

The command subwindow background color, where xx xx xx corresponds to the RED/GREEN/BLUE value, which is a number in the range 0 to 255.

windows ht1 ht2 ht3

On UNIX systems, the relative sizes of the source window, the I/O window and the command window. For example, windows 50 35 15 specifies that the source window occupies 50% of the total windows height, the I/O windows occupies 35%, and the command window the remaining

15%.

On **WINDOWS** systems, the relative sizes are memorized when rxd exits, and the memorized values are used the next time rxd is started.

back_source xx xx xx

The source subwindow background color.

back_panel xx xx xx

The button subwindow background color.

back_io xx xx xx

The I/O subwindow background color.

back_prefix xx xx xx

The color in use to display the line numbers.

back_current xx xx xx

The color to display the line where the REXX process is stopped.

back_up xx xx xx

The color to display a line after a UP command.

back_cursor xx xx xx

The cursor color.

foreground xx xx xx

The foreground color.

font fnt On UNIX systems, the general font.

dy_font fnt The font to be used by the buttons.

geometry hhxll+xx+yy

On **UNIX** systems, the height (hh) in units of characters, the width (11) in units of characters, and the position (xx, yy) in pixel units of the rxd window starting at the upper-left corner.

On **WINDOWS** systems, these values are memorized when rxd exits, and the memorized values are used next time rxd is started.

button dis cmd

Creates a button labelled dis, which will execute the cmd command.

mbutton dis "dis1:cm1" "dis2:cmd2"

On UNIX systems, creates a menu button labelled dis. When the first mouse button is used upon this button, cmd1 is executed. When the third mouse button is used, a menu with the dis1, dis2, ... labels is displayed, permitting the choice amongst the cmd1, cmd2, ... commands to be executed.

In addition, any command, such as alias, may be used within .rxdinit. An example is provided in the {install-dir}/.rxdinit file.

The following options may be used when starting rxd in explicit mode on UNIX systems:

-Wh or -heightlinesthe number of linesWf or -fontfontnamethe font to be used at initializationdy_fontfontnamethe font to be used by the buttonsdisplaydisplaythe X11 display to be usedWp or -positionx ythe RXD window locationWP or -icon_position x ythe RXD icon location.	-Ww or -width	columns	the number of columns.
-Wf or -fontfontnamethe font to be used at initializationdy_fontfontnamethe font to be used by the buttonsdisplaydisplaythe X11 display to be usedWp or -positionx ythe RXD window locationWP or -icon_position x ythe RXD icon location.	-Wh or -height	lines	the number of lines.
-dy_fontfontnamethe font to be used by the buttonsdisplaydisplaythe X11 display to be usedWp or -positionx ythe RXD window locationWP or -icon_position x ythe RXD icon location.	-Wf or -font	fontname	the font to be used at initialization.
-displaydisplaythe X11 display to be usedWp or -positionx ythe RXD window locationWP or -icon_position x ythe RXD icon location.	-dy_font	fontname	the font to be used by the buttons.
-Wp or -positionx ythe RXD window locationWP or -icon_position x ythe RXD icon location.	-display	display	the X11 display to be used.
-WP or -icon_position x y the RXD icon location.	-Wp or -position	ху	the RXD window location.
	-WP or -icon_position	ху	the RXD icon location.

These options override the settings described in the .rxdinit file.

Using the Function Keys

The default function keys setting is the following:

F3	s_copy copies the selection into the internal buffer named shelf.
F4	s_paste pastes the shelf contents at the cursor location.
F5	cont continues execution.
F10	next continues execution, and pauses at the next statement within the same stack level. This enables subroutines to be skipped over.
F11	step continues execution, and pauses at the next statement.
F12	stepout continues execution, and pauses after exiting the current subroutine.
S-F5	run terminates the current REXX process, and restarts it with the arguments used for the previous run.
S-F11	stepout
L3	eof
L6	s_copy
L8	s_paste
^ _C	break interrupts the REXX process. An empty DO loop or a parse pull statement cannot be interrupted.
^i	upsource -1 shrinks 1 line the source subwindow.
^k	kill terminates the REXX process.
^0	upcmd 1 shrinks 1 line the command line subwindow.
^p	upcmd -1 expands 1 line the command line subwindow.
^u	upsource 1 expands 1 line the source subwindow.
\wedge_{V}	s_paste

The set command can be used to change the functions keys action.

SET

 $\begin{array}{ccc} & Fk & \{\texttt{string}\} \\ \{\texttt{S-}\} & \{\texttt{C-}\} & \{\texttt{M-}\} & \texttt{Rk} \\ \{\texttt{S-}\} & \{\texttt{C-}\} & \{\texttt{M-}\} & \texttt{Lk} \\ & & & & & \\ & & & & & \\ & & & & & \\ & & & & & \\ & & & & & \\ & & & & & \\ & & & & & \\ \end{array}$

affects string to the given function key.

Without arguments, set displays the function keys setting.

CUSTOMIZING

Appendix A: Keyboard Layouts

SUN APL Keyboard Layout

+ +	1		2	-	з	¥	4	2	5	2	6	~	7	×	8	*	9	(0)	-	-	=	+	1	I	×÷
Ē	!		V	2	4	2	4	2	4	þ	ß	ŗ	e	÷	я	×	e	,	2		ę	•	Ë	3	÷		¥
		Q	¢	ж	ε	E	Ĥ	R	0	Т	2	Y	÷	U	¢	I	~	0	0	Ρ	+	Γ	{]	}		
		Ç	<u>)</u>	Ä	¥	Ē		Ē	<u>}</u>	Ī		7	4	Ĺ	ļ]	[Ç	<u>)</u>	Ē	-	Ľ]	4	È		
			А	×	S	Γ	D	L	F	-	G	4	Н	۵	J		к	III	L		;	:	•	+			
			é	7	μų	2	Ē	<u>)</u>	Ē	-	G	ì	F	l]	Ę	2	Ĺ	-	ŧ	L	ŧ				
				z	U	x	U	с	C	v	υ	в	т	N	т	М	2:	,	<		~	/	?				
				Z	7	Σ	<u>(</u>	Q	2	Ā	2	Ē	Į	N	<u>l</u>	Ŋ	1	,		٩	ì	+	l.				

SUN Type 3 Keyboard 3270 Simulation Layout

EOF	

-	Î	
←	INS	
CAPS	Ļ	APL

SUN Type 4 Keyboard 3270 Simulation Layout

EOF	

		$\mathbf{\mathbf{\mathbf{\mathbf{\mathbf{\mathbf{\mathbf{\mathbf{\mathbf{\mathbf{\mathbf{\mathbf{\mathbf{\mathbf{\mathbf{\mathbf{\mathbf{\mathbf{$
	Ţ	
←	APL	
CAPS	Ļ	

SUN Type 5 Keyboard Layout

When using a type 5 Sun keyboard with OpenWindows 3.x, most of the right Ri keys are not available.

To modify the layout for one particular user, the user must have a ~/.xinitrc file. If this file does not exist, issue the following command:

```
% cp $OPENWINHOME/lib/Xinitrc ~/.xinitrc
```

Then, insert the following command in the user's ~/.xinitrc file **before** the last wait statement in this file:

```
xmodmap /home/xed/keyboard/key5.remap
```

When using Solaris 2.4 and OpenWindows 3.4 (and above), use:

xmodmap /home/xed/keyboard/key5-4.remap

This will map the keyboard in the following way for all users:



The numerical keypad will always be active, and the Compose key will be assigned the previous SUN type 4 keyboard LineFeed character, which is used by **SEDIT** as the 3270 Up-Field function.

The AltGraph key will be assigned the 3270 Down-Field function.

Control-AltGraph enters the linefeed command separator.

If you need to use the Compose key for other applications, please edit the key5.remap file, and remove the line related to the Compose key.

SUN Keyboard Mapping

L2	MAtch
L3	Erase end of field (3270 EOF)
Shift-L3	Erase all field (3270 EAF)
L4	UNDO
Shift-L4	REDO
L6	S_COPY
L8	S_PASTE
L9	S_FIND
L10	S_CUT
F1	Quit
Control-F1	FLQuit
F2	C_EXT
F3	Save
Shift-F3	File
Control-F3	FLFile
F4	C_SPLIT
F5	SWitch
Shift-F5	ISWitch
F6	C_ENDLine
Shift-F6	C_ENDCURL
F7	BAckward
META-F7	S_LSHIFT
F8	FORward
META-F8	S_RSHIFT
F9	?
Shift-F9	?I
F10	CURsor Home
F12	=
R1	COMPLete
S-R1	COMPLete Reverse
S-R2 or S-F11	TOP
S-R3 or S-F12	Bot
Control-R5	<pre>filter \$xhome/filters/\$arch/toggle_comment</pre>
C-Left-Arrow	prevword
C-Right-Arrow	nextword
Control-a	C_LINEAdd
Control-c	smart_comp \$name 0
Control-C	smart_comp \$name 1
Control-d	C_LINEDel
Control-f	f
Control-g	smart_compd \$name 0
Control-G	smart_compd \$name 1
Control-h	C_SCRH
Control-l	S_Lower
Control-n	f \$fn *
Control-p	shell lpr -h \$name &
Control-r	Tree
Control-u	S_Upper
Control-U	S_Upper WORD

Control-v	C_SCRV
Control-w	C_SCRJ
Control-x	S_Xed
Control-z	Left O
Control	NEXTerror
Control-=	C_Dup

IBM, Silicon Graphics and PCs Keyboard Mapping

Escape	Erase end of field (3270 EOF)
Control-Escape	Erase all field (3270 EAF)
F1	S_FIND
F2	S_CUT
F3	S_COPY
F4	S_PASTE
F5	SWitch
Shift-F5	ISWitch
F6	C_ENDLine
Shift-F6	C_ENDCURL
F7	BAckward
META-F7	S_LSHIFT
F8	FORward
META-F7	S RSHIFT
F9	?
Shift-F9	?I
F10	CURsor Home
F11	IINDO
Shift-F11	REDO
F12	=
R1	Ouit
Control-R1	FLOuit
R2	COMPLete
S-R2	COMPLete Reverse
P3	Save
Control-R6	filter \$vhome/filters/\$arch/toggle_comment
C-Left-Arrow	preuword
C-Dight-Arrow	prevword
chift_D2	
chift D6	
Shift_D0	Pot
Control_P?	
Control - A	C I INFAG
Control-a	C_LINEADD
Control-C	smart_comp shame 1
Control-C	Smart_comp shame I
Control-a	C_LINEDEI
Control-I	
Control-g	smart_compd sname U
Control-G	smart_compd \$name 1
Control-n	C_SCRH
Control-1	S_Lower
Control-m	MAtch
Control-n	t ștn *
Control-p	shell lpr -h \$name &
Control-r	Tree
Control-s	C_SPLIT
Control-u	S_Upper
Control-U	S Upper WORD
	b_opper word

Control-w	C_SCRJ
Control-x	S_Xed
Control-z	Left 0
Control	NEXTerror
Control-=	C_Dup

DEC/COMPAQ/HP TRUE64 Station Keyboard Mapping

F1	s_find
F2	s_cut
F3	s_copy
F4	s_paste
F5	switch
Fб	c_endline
F7	backward
F8	forward
F9	?
F10	cursor home
F11	undo
F12	=
F13	Erase end of field (3270 EOF)
S-F13	Erase all field (3270 EAF)
F14	filter \$xhome/filters/dec/toggle_comment
F15	help
F16	save
S-F5	iswitch
S-F6	c endcurl
S-F7	pqup
S-F8	pqdown
S-F9	?i
S-F11	redo
S-F15	help task
S-F16	file
C-F7	left40
C-F8	right40
C-F10	delay.home
C-F16	flfile
META-F7	S LSHIFT
META-F8	
R7	backward
R9	forward
S-R7	top
S-R9	bot
C-Left-Arrow	prevword
C-Right-Arrow	nextword
L1	quit
L2	match
C-L1	flquit
L3	COMPLete
S-L3	COMPLete Reverse
^_	nexterror
^=	c dup
^C	smart_comp \$name 1
^G	smart_compd \$name 1
^N	f \$fn * \$fd
^a	c_lineadd
^ _C	smart_comp \$name 0
	-

^d	c_linedel
^e	c_apltrace
^f	flist
^ g	smart_compd \$name 0
^h	c_scrh
^1	s_lower
^ n	f \$fn *
^ p	shell lpr \$name &
^r	tree
^s	c_split
^t	tree
^u	s_upper
^v	c_scrv
^ _W	c_scrj
^x	s_xed
^Z	left0

HP Keyboard Mapping

F1	s_find
F2	s_cut
F3	s_copy
F4	s_paste
F5	switch
F6	c_endline
F7	backward
F8	forward
F9	?
F10	home
F11	undo
F12	=
S-F1	s find
S-F5	iswitch
S-F6	c endcurl
S-F7	
S-F8	paqown
S-F9	?i
S-F10	home
S-F11	redo
S-F12	bot
C-F1	s find
C-F7	l_{eft40}
C-F8	right 40
C-F10	delay home
M-F1	a find
	guit
	quit
	backward
RJ R11	forward
с_р)	file
S 112 S_DQ	top
S-R9 C_D11	bot
	flouit
	flfilo
C = RZ	filter (whome/filters/hp/teggle_germent
C-Loft-Arrow	prouverd
C Dight Arrow	previoud
C-RIGHL-ALLOW	Erage and of field (2270 EOE)
LL Chift Il	Erase ella di itela (3270 EDF)
	ELASE ALL LIELU (5270 EAF)
LO Chift IC	complete Reverse
SIIII (-110	
_ ^_	
	C_dup
A.C.	smart_comp shame i
ANT.	smart_compo sname i
	1 9111 ° 910
A ^2	s_man
d Ar	C_IIIeada
D A	smart_comp sname u
a	c_timedet

^e	c_apltrace
^f	f
^g	smart_compd \$name 0
^h	c_scrh
^l	s_lower
^ m	match
^n	f \$fn *
^p	shell lp \$name &
^r	tree
^s	c_split
^t	tree
^u	s_upper
^ _V	c_scrv
^w	c_scrj
^x	s_xed
^Z	left0
WINDOWS Keyboard Mapping

Facapa	Frage and of field (3270 FOF)
Chift Eggapo	Erage all field (2270 ENE)
SHIIL-ESCape	C FIND
г <i>2</i> г2	CLUNEADD
F S E 4	
Г4 ПС	
F D F C	SWIICH
F 0 E 7	
F / E 0	EODWARD
FO	PORWARD
F 9 E 1 0	: LIOME
	HOME
	UNDO
FIZ	
S-F1	S_FIND
S-F2	
S-F3	
S-F5	ISWITCH
S-F6	C_ENDCURL
S-F7	PGUP
S-F8	PGDOWN
S-F9	?I
S-F11	REDO
C-F1	S_FIND
C-F3	FLFILE
C-F7	LEFT40
C-F8	RIGHT40
C-F10	DELAY.HOME
META-F7	S_LSHIFT
META-F8	S_RSHIFT
R1	AQUIT
R2	COMPLETE
R5	C_STARTLINE
R6	BACKWARD
R7	C_ENDLINE
R9	FORWARD
C-Left-Arrow	PREVWORD
C-Right-Arrow	NEXTWORD
s_R1	FLQUIT
S-R2	COMPLETE REVERSE
S-R6	TOP
S-R9	BOT
C-R1	FLQUIT
C-R6	<pre>FILTER \$xhome\filters\wnt\toggle_comment</pre>
^a	S_SET ALL
^c	S_COPY
^d	C_LINEDEL
^f	FLIST
^h	C_SCRH

^1	S_LOWER
^m	MATCH
^ n	F "\$fn" *
^ p	PRINTFILE
^q	AQUIT
^r	TREE
^s	DY_SAVE
^t	TREE
^u	S_UPPER
^ _V	S_PASTE SHELF
^ _W	C_SCRJ
^x	S_CUT
^ _Z	UNDO
^C	smart_comp \$name 0
^F	FLOW
^ G	smart_compd \$name 0
^ H	S_HELP
^L	LEFTADJUST
^M	MATCH CURSOR
^N	F "\$fn" * "\$fd"
^R	RIGHTADJUST
^ V	S_PASTE SHELF OVERLAY
^ X	S_XED
^_	NEXTERROR
^=	C_DUP

Character Mode Terminals Mapping

Escape	Erase end of field (3270 EOF)
Fl	Quit
F2	NEXTerror
F3	Save
F4	C_SPLIT
F5	SWitch
Fб	C_ENDLine
F7	BAckward
F8	FORward
F9	?
F10	CURsor Home
F11	UNDO
F12	=
Control-a	C_LINEAdd
Control-b	C_STARTS
Control-c	<pre>smart_comp \$name 0</pre>
Control-d	C_LINEDel
Control-e	C_ENDS
Control-f	f
Control-g	smart_compd \$name 0
Control-h	Backspace
Control-i	NEXT-FIELD
Control-j	UP-FIELD
Control-l	command separator
Control-m	Return or Enter
Control-n	C_ENDSR
Control-o	S_COpy
Control-p	shell lpr -h \$name &
Control-r	REFRESH Clear
Control-t	enters the tab character
Control-u	S_Upper
Control-v	C_SCRV
Control-w	C_SCRJ
Control-x	S_Xed
Control-y	S_Paste
Control-z	Left 0

Character Mode

Appendix B: Hardware String

SUN SUNOS	sun4
SUN Solaris (sparc)	sparc
SUN Solaris (PCs)	і8брс
IBM RS/6000	ibm
Hewlett Packard	hp
SiliconGraphics	sgi
SCO PC systems	SCO
Linux PC systems	linux
Unixware PC systems	uxw
DEC/COMPAQ/HP Alpha TRUE64	alpha
systems	
Siemens RM systems	sinix
Windows systems	wnt

Within this manual, arch or \$arch is the following hardware dependent string:

SEDIT Release Notes

This appendix highlights **SEDIT** enhancements since the release of version 3.50

The 3.60 File Editor Enhancements

New Commands

- ARBCHAR
- DOSFILE
- DOSSAVE
- DUPLICAT
- DY_ALL
- DY_EXCLUDE
- DY_FIND
- DY_FONT
- DY_OPEN
- DY_SAVE
- DY_SHOW
- ESCAPEDELAY
- EXCLUDE
- FLATH
- HEX
- ISOCONV
- MBUTTON
- METAKEY
- MODE TOPLINE
- MODE CURSOR
- MODE GET
- PRESERVE
- READSCREEN
- RELOAD
- RESTORE
- SHOW
- SOS INS
- SOS BAKSPACE
- S_HELP
- XTESTCHARS
- WRAP

- \$ command substitution can be escaped with a backslash. See Avoiding Variable Substitution on page 148.
- All directory related commands accept the ~user C-Shell syntax: typing

cd ~john will switch to john's home directory, as described in the /etc/passwd file.

- Error messages are displayed on a specific field.
- New ARBCHAR/ENVIRON/FILE/MATCH/WRAP EXTRACT operands.
- The UNDO command accepts a parameter.
- The Ch command is renamed Change. CHANGE allows the user to insert a string in the first zone column, and supports hexadecimal specification when HEX is ON.
- The SCh command is renamed SChange.
- The TOP OF FILE line is a virtual 0 line, allowing the user to insert data before the first line in the file. Since this is an incompatible change with the previous **SEDIT** release, the MODE command allows the user to set the TOP OF FILE line to 1.
- The AUTOI command is renamed AUTOIndent.
- The MODE Change command is renamed into MODE CHange.
- The SET command allows the user to program the keyboard arrow keys.
- The VERIFY command allows the user to enable the new fullshift mode.
- The GET command allows the user to specify the number of lines to be inserted.
- The GET_PANEL command allows the user to specify a field intensity, a cursor location and a refresh mode.
- The SAVE and FILE commands respect the owner and the group of the saved file.
- The **MOTIF** version returns the focus keyboard to the window that had the focus at **SEDIT** initialization.
- S/REXX MOTIF and OPENLOOK dialog facilities.

The 3.60 Directory Editor Enhancements

- The length of the filename zone is variable, allowing full display of longer file names.
- The file related permissions display may be switched off by typing ^a, or by using the **SEDIT** FLATH command.
- New DIFF built-in command.

The 3.60 Tree Editor Enhancements

- New button SCAN ALL.
- Initial scanning hides subdirectories belonging to different file systems.

The 4.0 File Editor Enhancements

New or Enhanced Commands

- ALL
- AQUIT
- BACKWARD
- BOUNDS
- BUILTIN
- CAPS
- CANCEL
- CHANGE
- CLEARERRORS
- CN
- COLOR * and COLOR CURSOR
- COPY
- COUNT
- CTLCHAR
- CREATE
- DELETE
- DUPLICAT
- EDIT
- END
- EXCLUDE
- FIND
- FINDUP
- FORWARD
- HELP
- HEXTYPE
- HISTORY
- IMPCMSCP
- LASTLORC
- LOCATE
- LOWERCAS
- MACRO
- MODE
- MOVE
- MOUSEMODE
- •NFIND
- NFINDUP
- NUMBER
- POINT
- PQUIT
- PREFIX
- PRESERVE
- PRINTSCREEN
- RESERVE

- PUT
- QUIT
- READ
- READSCREEN
- REPEAT
- RESTORE
- RESERVED
- SET
- SC
- SCN
- SELECT
- SHIFT
- SPAN
- STACK
- STAY
- S_PASTE
- UPPERCAS
- VARBLANK
- VERIFY
- XCSHELL
- XKSHELL

- New /CTLCHAR/IMPCMSCP/MACRO/NUMBER/POINT/PREFIX/RESERVED /SOURCE/SPAN/VARBLANK/STAY/ENTER/LASTLORC/NBSCOPE/MOUSEMO DE/CMDLINE EXTRACT operands.
- EXTRACT/SELECTION/ returns a different set of values.
- EXTRACT VERIFY returns 3 strings instead of 2.
- VERIFY accepts ON and OFF as parameter.
- PRESERVE and RESTORE save and restore new settings.
- A logical operator within an ALL target must be enclosed within delimiters. The previous **SEDIT** release accepted a search string such as "/str|/str2". You must now type "/str/|/str2".
- DISplay is renamed into DISPlay.
- Left is renamed LEft.
- MOde renamed MODe.
- MEnu renamed MENu.
- Put renamed PUT.
- SHell renamed SHEll.
- SETP without parameters frees the last window line.
- General XEDIT targets. * is now a target that cannot be used as a comment within an internal macro: the user will have to edit all its previous internal macros, and replace the * comment sign with the # comment sign.
- The various CHANGE commands are no longer restricted by the VERIFY setting.
- Commands and macros are parsed up to the first non-alphabetic character. "SCREEN1" is treated as "SCREEN 1". In order to call macros ending with a

numerical character, such as set_sun_t5, the new MACRO command must be used. Entering "set_sun_t5" will fail. The user must enter "MACRO set_sun_t5" instead.

- When more than one message is issued from a macro, **SEDIT** creates a new file in the editing ring displaying all the messages.
- The /home/xed/xedit scrip allows the user to start **SEDIT** using the /home/xed/prof_xedit.sedit profile, which initializes **SEDIT** with the same default settings as XEDIT default settings.
- The -p option allows the use of shortened profile names: "sedit -p foo" is the same as "sedit -p foo.sedit".
- The CURLINE command accepts an optional ON keyword.
- The XED command is renamed into XEDit.
- **RXD** graphical debugger support.
- The NEXT and UP commands return 1 when the end or top of a file is reached.
- QUIT is now the same as QQUIT. However, the standard profile file makes QUIT a synonym to the new AQUIT command, which performs in the same way as the QUIT command under **SEDIT** 3.60.
- The SET command permits the user to define the ENTER key, and recognize the XEDIT AFTER/ONLY/IGNORE/BEFORE keywords. Note that SET F1 *string* is now treated as SET F1 BEFORE *string*. The previous **SEDIT** release treated all key definitions as ONLY definitions. **To define the same key action as SEDIT 3.60**, **the user should enter** SET F1 ONLY *string*.
- In earlier versions, QUERY was ignored since every **SEDIT** command without parameters returned its status. In this release, QUERY is defined in the same way as in XEDIT and accepts a limited number of parameters, the same ones as XEDIT QUERY.
- The NEXTERROR command finds the lines in error even when the user adds or deletes lines.
- GET_PANEL saves the mouse position in the MOUSE environment variable, and the cursor position in the CURSOR environment variable.
- PRINTSCREEN allows the user to specify a default printer.
- HELP supports **S/REXX** help files.
- LINUX support.
- The -np option suppresses the profile execution at initialization.
- The -font option accepts a fontname starting with a -.

The 4.0 Directory Editor Enhancements

- The file size field is larger.
- New ^xx commands.

The 4.0 Tree Editor Enhancements

• TREESCANLEVEL command.

The 4.10 File Editor Enhancements

New or Enhanced Commands

- CENTER
- CHANGE
- COLOR
- DY_OPEN
- DY_SAVE
- FOLLOW
- FLOW
- FORMAT
- GET
- LEFTADJUST
- MARGINS
- MATCH
- MODE
- MOUSEMODE
- NUMBER
- NUMBER_SCREEN
- PREFIX
- PREFIX_SCREEN
- PRINTSCREEN
- PUT
- RFLIST
- RIGHTADJUST
- SCALE
- SCALE_SCREEN
- SYNTAX
- TABLINE
- TABLINE_SCREEN
- VERIFY
- VERIFY_SCREEN

- \bullet New /FORMAT/MARGINS/ EXTRACT operands.
- SEDIT supports 62 colors.
- The background and foreground colors are no longer set by modifying the BLACK and WHITE colors. Use COLOR BACKGROUND R G B and COLOR FOREGROUND R G B for that purpose. This is an incompatible change with previous **SEDIT** releases. **The user will have to edit all its previous macros using the** COLOR WHITE **or** COLOR BLACK **commands**.
- Syntax coloring.
- The /NUMBER/PREFIX/SCALE/TABLINE/ZONE/ settings are both file and view dependent.
- Text formatting capabilities.
- When the screen is split with the 'screen N' or 'screen N V' command, this

command will be applied automatically every time the window is resized.

- MOUSEMODE FULLMOTIF assigns the cursor motion function to the first mouse button.
- PENDING prefix commands are displayed in the function keys help field.
- The userid is displayed at the top of the **SEDIT** window.
- MODE EXPAND ON ENV makes **SEDIT** search for **UNIX** environment variables within commands. MODE EXPAND OFF disables completely any variable substitution.
- Used with ARBCHAR and ZONE, the CHANGE command can remove a set of columns.
- The PUT and GET commands can be used with native **UNIX** file names.
- C_ENDLINE extends the line if necessary.
- Directory symbolic link resolving can be disabled with the FOLLOW command.
- SUN's SunView and IBM's WORKBENCH are no longer supported.

The 4.10 Directory Editor Enhancements

- Better pattern matching, with ? meta character support.
- Regular expression pattern matching.

The 4.10 Tree Editor Enhancements

- TREE supports the Home, End, PageUp and PageDown function keys.
- The PRINTSCREEN command changes the default TREE printer and printing daemon.

The 4.20 File Editor Enhancements

New or Enhanced Commands

- ACCESS
- BACKUP
- DRELEASE
- DY_LASTFILES
- FD
- FLDATE
- FLPP
- FN
- FORMAT
- FT
- GLOBALCASE
- LASTFILES
- POWERINPUT
- PRINTFILE
- RELEASE
- SCKEYS changes the confirmation keys used by SCHANGE.
- SHOWPATH
- SHOWCDPATH

- SAVE error messages are displayed in the editing ring.
- When MOUSEMODE is set to **MOTIF** or FULLMOTIF, rectangular selections can be pasted with the second mouse button.
- PRIntscreen renamed into PRINTScreen.
- The backup string (% by default) can be changed with the BACKUP command.
- The SHIFT command, and the <, >, <<, and >> prefix commands affect text from the left zone column.
- When the STRING keyword is not used in a SYNTAX file, the quote and double quotes characters are not treated as the start of a string.
- WINDOWS NT and WINDOWS 95 support.
- The POWERINPUT mode supports characters inserted in the middle of a line.
- The search for a file in the path does not stop when finding a directory with the same name as the requested file.
- C_LINEADD scrolls down one line when the cursor is on the last displayed line.
- S/REXX macros are enabled without an S/REXX license.

The 4.20 Directory Editor Enhancements

- FLIST displays a "..." string. Clicking on it initiates a new FLIST level upon the parent directory.
- Shift-F2 and ^M generate an **SEDIT** file with the full names of the files displayed within **FLIST**.
- FLIST can display dates in US format.

The 4.20 Tree Editor Enhancements

- ^s (and FIND on Sun keyboards) searches for a directory.
- The UP and DOWN arrow keys scroll the view.

The 4.30 File Editor Enhancements

New or Enhanced Commands

- C_ENDSALL
- DY_FILL
- LINECOL
- MBUTTON
- MENU
- MENUBAR
- NEXTWORD
- PREVWORD
- PRINTFILE
- RELOAD
- REPEATDELAY
- SET
- SORT
- SOS
- S_SET
- STAMPDELAY
- VISIBLE

- New /VISIBLE/ EXTRACT operands.
- Alt-cc (or Meta-cc) keys can be programmed.
- The line and column corresponding to the cursor position are displayed, as well as the hexadecimal value of the character on the screen.
- Files describing a menu can reference another file.
- PRINTFILE prints only the visible part of the file defined with the ALL command.
- SORT sorts only the visible part of the file defined with the ALL command.
- Pressing the first button mouse on the field located between the prefix fields and the data fields selects a whole line.
- O and OO prefix commands.

The 4.30 Directory Editor Enhancements

- ? displays the last command.
- The total size of the displayed files is displayed on the first line.

The 4.30 Tree Editor Enhancements

• New **CLONE** menu option.

The 4.40 File Editor Enhancements

New or Enhanced Commands

- AUTOBIN
- BEEP
- BINARY
- CASE
- CHANGE
- CURSOR
- CN
- EXIT
- EXTRACT
- FLOW
- FMACRO
- KEEPBLANKS
- POWERINPUT
- RCHANGE
- SCHANGE
- SCN
- SET
- SHBLANK
- SRCHANGE
- SORT
- SYNONYM (QUERY SYNONYM)
- SYNTAX for COBOL files (SEDIT 4.40B and above)
- VERIFY_KSAVE
- VERIFY_SSAVE
- VERIFY_SAVE
- XBIN
- XKB

- The SORT and the various CHANGE commands case sensitivity is tailored by the CASE command.
- Binary files editing.
- New /BINARY/KEEPBLANKS/RMATCH/SHBLANK/SYNONYM EXTRACT operands.
- An internal or S/REXX macro can use the NULL character.
- The POWERINPUT mode has been enhanced, and is now a file related setting.
- xinfo is a graphical utility, and can be used on remote clients.
- The license server is supported on WINDOWS NT systems.
- The EXTRACT command can be replaced with the extract built-ins, such as the arbchar.0() built-in. See Using EXTRACT on page 142 for more information.
- EXTRACT/CMDLINE/ also returns the command line content.
- EXTRACT/CURSOR/ also returns the line position of the cursor in the file when the cursor is on the corresponding prefix field.

- <u>CURSOR</u> can place the cursor at the start of a prefix field.
- Function keys can be specified with several modifiers held down, and SET uses symbolic names like LeftArrow. See the <u>SET</u> command.
- Bookmarking with the ^nn keys. See the section Using Function Keys for more information.
- KEDIT-like keyboard personality with the kedit command (UNIX) or icon (WINDOWS).
- S/REXX syntax error messages are displayed within the SEDIT window.

The 4.40 Directory Editor Enhancements

- XBIN and XKB commands.
- The file size field is no longer limited to 2 Gb.
- **S/REXX** macros (see page 472).

The 4.50 File Editor Enhancements

New or Enhanced Commands

- DFLIST
- FFLIST
- MESSAGESDIR
- RECYCLE
- SAVECLEARUNDO
- SET ? displays all the editor settings.
- SHOWHISTORY
- SORTRING
- SOS INSERT
- STATUS
- S_COPY
- S_PASTE
- XCSHELL
- XKSHELL
- XSHELL
- XSHELLMAX
- XSHOWHISTORY

Miscellaneous

- -batch option. See Using the BATCH Option on page 144.
- New /INSERT/XSHELL/WIDTH/ EXTRACT operand.
- The command field extends automatically to 2 lines when needed.
- The history commands can search for commands starting with a given letter.

The 4.50 Directory Editor Enhancements

- On **WINDOWS** systems, when RECYCLE is ON, removing files places them in the recycle bin.
- The command fields expand to 2 lines when needed.
- Sorting files is done in reversed order when using the shift key.
- Control-HOME and Control-END scroll to the first and last file.
- On **WINDOWS** systems, the HOME and END keys move the cursor to the start and the end of the typed string. See **FLIST** function keys description page 458 to achieve the same functionality on **UNIX** systems.
- WIPE macro.
- DFLIST only displays directories.
- FFLIST only displays non-directories.

The 4.50 Tree Editor Enhancements

• On **WINDOWS** systems, when RECYCLE is ON, removing files or directories places them in the recycle bin.

The 4.60 File Editor Enhancements

New or Enhanced Commands

- EXTRACT
- FONT

Miscellaneous

- New /FONT/CLIPBOARD/ EXTRACT operand.
- Clicking with the first mouse button on the scale line changes the first <u>VERIFY</u> setting to the corresponding column. This allows to scroll the file display to the right up to this column.
- with non-US keyboards, it is necessary to remove the default right ALT key "down_field" assignment.

This is achieved by adding in the profile the "set down_field" command after the architecture dependent "set_xxx" keyboard setting macro has been called. On IBM stations for example, the keyboard setting macro is "set_ibm".

Using "set down_field" replaces the obsolete

"setenv SEDIT_META_ON_RIGHT" syntax.

• Files with a large number of lines (100,000+) load much faster.

The 4.60 Directory Editor Enhancements

- The CP, MV and DIFF commands used without arguments bring the filename, filetype and the = sign on the corresponding command line, allowing easy editing.
- BOTTOM and TOP commands.

The 4.70 File Editor Enhancements

New or Enhanced Commands

- ALT
- EXTRACT/SELECT/
- COLOR EDITED
- LIMIT
- SELECTALL

Miscellaneous

• A large file is a file larger than 2,147,483,647 bytes. **SEDIT** supports large files on the operating systems displayed when typing HELP LARGEFILES.

The 4.70 Directory Editor Enhancements

• A large file is a file larger than 2,147,483,647 bytes. **SEDIT** supports large files on the operating systems displayed when typing HELP LARGEFILES, and **FLIST** displays correctly large files length.

The 4.70 Tree Editor Enhancements

• WIPE menu option.

SEDIT RELEASE NOTES

S/REXX Release Notes

This appendix highlights **S/REXX** enhancements since the release of version 1.0.

1.10 Enhancements

Enhanced Built-in Functions

- ARG
- CHARIN
- DATE

Miscellaneous

- ISPF-like tables.
- Programming Interface.
- { and } support.

1.20 Enhancements

New or Extended Instructions

- DO
- EXECIO
- OPTION

New Built-in Functions

- DY_BUTTON
- DY_DESTROY
- DY_END
- DY_INPUT
- DY_LABEL
- DY_MAP
- DY_SINPUT
- DY_START
- DY_STG
- DY_TG
- DY_UNMAP
- DY_VINPUT
- DY_VTG
- MKDIR
- RM
- TEE
- SLEEP
- USLEEP

Enhanced Built-in Functions

• STATE

Miscellaneous

- When SIGNAL ON NOVALUE is in effect, and a variable which has not been assigned a value is used, an error 71 occurs when the NOVALUE label is not defined.
- Floating S/REXX licenses.
- VM/CMS EXECIO support.
- Dialog management.
- ccsr allows the user to compile a program.

2.00 Enhancements

New or Extended Instructions

- ADDRESS has been extended to include the C shell or the Korn shell as command destinations.
- OPTION

New Built-in Functions

- CHANGE
- CSH
- DY_CH
- DY_VCH
- KSH
- SH
- TEEC
- TEEK

- Bracket indexing.
- RXD graphical debugger support.
- The dialog boxes can be used in standalone REXX shells.
- CUSERID() accepts a parameter.

2.10 Enhancements

New or Enhanced Built-in Functions

- DY_ASCL
- DY_BEEP
- DY_BUTTON
- DY_BUTTON_COLOR
- DY_CH_COLOR
- DY_DSCL
- DY_FOCUS
- DY_INPUT
- DY_INPUT_COLOR
- DY_LABEL
- DY_LABEL_COLOR
- DY_OPEN
- DY_PSCL
- DY_RSCL
- DY_SCL
- DY_SCL_COLOR
- DY_SSCL
- DY_TG_COLOR
- DY_VSCL
- SORT
- SUBDIRS
- TBOPEN
- TCSH

- Dialog scrolled lists.
- When OPTION NOLOAD is in effect, **S/REXX** searches for external subroutines, and executes them in a different subprocess. See Using OPTION NOLOAD on page 496.
- The .srexxrc and sedit.srexxrc files tailor the default settings. See Setting Default Options for SEDIT REXX Macros on page 497.
- **MOTIF** dialog items can be colored individually.
- The DISKI and DISKD EXECIO options allow the insertion and removal of lines from a file.
- ADDRESS supports the tcsh option.
- The license server is supported on WINDOWS NT systems.

2.20 Enhancements

New or Enhanced Built-in Functions

- CLOSE_CONS
- CONCAT
- CP or COPY
- •DEL or RM
- •DIR or LS
- DY_PRINTER
- DY_SLABEL
- DY_WARP
- FILECONV
- GETPID
- MV or RENAME
- OPEN_CONS
- RMDIR

Miscellaneous

- The PATH environment variable is parsed every time an external routine is called.
- WINDOWS NT and WINDOWS 95 support.
- Specific double click reason code for scrolled lists.

2.30 Enhancements

New or Enhanced Built-in Functions

- ACOS
- ASIN
- ATAB
- COS
- CVTAILS
- DATE
- DESBUF
- DROPBUF
- DY_END
- DY_OPEN
- DY_SCH
- EXECIO
- MAKEBUF
- SENTRIES
- SIN
- STATE
- SCRIPT
- TAN

Miscellaneous

- env_rx2() new programming interface.
- \bullet RENAME() and MV() work across file systems.
- The background color can be specified with DY_END() and DY_OPEN().
- The C API applies to the **MOTIF** msrexx or the **WINDOWS** wsrexx.exe version.

2.40 Enhancements

New or Enhanced Built-in Functions

- ACCEPT
- BIND
- •C20
- CHARIN
- CLEAR
- CLOSESOCKET
- CLS
- CONNECT
- CPUID
- DATE
- FOLLOW
- FORK
- FLFILES
- GETFILE
- GETHOSTBYADDR
- GETHOSTBYNAME
- GETHOSTID
- GETPEERNAME
- GETSOCKNAME
- GETSOCKOPT
- IOCTL
- KILL
- LINEIN
- LISTEN
- •QPID
- RECV
- RECVFROM
- REGISTRY_DEL
- REGISTRY_GET
- REGISTRY_KEYS
- REGISTRY_SET
- REGISTRY_VALUES
- SELECT
- SEND
- SENDTO
- SERVICE_CREATE

- SERVICE_DELETE
- SERVICE_START
- SERVICE_STATUS
- SERVICE_STOP
- SETSOCKOPT
- SHUTDOWN
- SOCKACCEPT
- SOCKBIND
- SOCKCLOSE
- SOCKCONNECT
- SOCKDROPFUNCS
- SOCKET
- SOCKGETHOSTBYADDR
- SOCKGETHOSTBYNAME
- SOCKGETHOSTID
- SOCKGETPEERNAME
- SOCKGETSOCKNAME
- SOCKGETSOCKOPT
- SOCKINIT
- SOCKIOCTL
- SOCKLISTEN
- SOCKLOADFUNCS
- SOCKPSOCK_ERRNO
- SOCKRECV
- SOCKRECVFROM
- SOCKSELECT
- SOCKSEND
- SOCKSENDTO
- SOCKSETSOCKOPT
- SOCKSHUTDOWN
- SOCKSOCKET
- SOCKSOCK_ERRNO
- SOCKSOCLOSE
- SOCKVERSION
- STATE
- STIME
- SYSCLS
- SYSFILEDELETE
- SYSFILESEARCH
- SYSFILETREE
- SYSGETKEY
- SYSMKDIR
- SYSRMDIR
- SYSSEARCHPATH
- SYSSETPRIORITY
- SYSSLEEP

- SYSTEMPFILENAME
- SYSVERSION
- UTIME
- VERSION
- WAITPID

Miscellaneous

- The S/REXX Debugger supports function keys, and various new commands.
- The S/REXX Debugger runs on WINDOWS systems.
- On **WINDOWS** systems, the EXECIO PRINT command and the dialog box management are supported by both srexx.exe and wsrexx.exe.
- An **S/REXX** program can be used as a standard input filter. See the LINEIN() and CHARIN() functions for more information.

2.50 Enhancements

New or Enhanced Built-in Functions

- DY_HEADER
- DY_REFRESH
- DY_OPEN: several filters can be specified by using a ; separator.
- KILL
- RECYCLE
- WIPE

Miscellaneous

- GLOBALV support.
- OPTION GLOBALV NOGLOBALV.
- The WINDOWS environment supports the ASSOC CLS COPY DEL ERASE FTYPE MD MOVE RD REN RENAME START TIME TYPE VER VERIFY VOL DOS commands.
- On **WINDOWS** systems, anysrexx.exe and anywsrexx.exe can be used for automatic execution of an **S/REXX** program.
- srexx fname searches fname in the PATH.

2.60 Enhancements

New or Enhanced Built-in Functions

- EXEC
- GETDISKSPACE
- LSTATE (see the STATE() built-in)

- ADDRESS EXEC
- The WINDOWS environment also supports the DIR DOS commands.
- "123" [4:] returns an empty string instead of reporting an index error.

2.70 Enhancements

Miscellaneous

- When the query to the system succeeds, ${\tt STATE}$ () and ${\tt LSTATE}$ () set the RC REXX variable to 0.

When the query fails, STATE() and LSTATE() return 0, and set RC to a string describing the error.

Index

Symbols

! special meaning in mainframe procedures 492 \$cdpath 2 % backup file ending with 156 .cshrc 2, 456 .exe executing on WINDOWS 462 .srexxrc 497, 500 /etc/group 327 /etc/passwd 327 /home/xed 1, 15, 441 { using 502 } using 502 ~ on Windows 32, 37, 508, 515

Numerics

3270 simulation layout 662, 663

A

adding a directory to the path 149 adding a line 59, 65, 71, 77, 83, 95, 107, 150, 212, 665, 667, 669, 671, 675 address 506, 507, 629 anysrexx.exe 489 anywsrexx.exe 489 APL compressing 195 displaying a nested array 44 displaying a stop 209, 411 displaying a trace 209, 428 editing UNIX files 54 inserting an object 276 keyboard layout 661 keyboard mode 42 passing command to 152 saving in ./APLOBJ 370 setting a stop 209, 411 setting a trace 209, 428 APLOBJ 370 aquit initial synonym value 345, 413 arbitrary character 148, 153, 248

arch 139, 147, 241, 242, 529, 629, 649, 677 arrow keys 385 ASCII terminals 8, 131, 210, 211, 214, 340, 341, 352 ASCII terminals and reverse video characters 287 auto-binary feature 154 auto-binary feature 154 auto-indent feature 155, 389 automounted directories not displaying the real name 272 auto-repeat delay 356 autosave 156

B

background color 2 backquotes 502 backspace setting the key for ASCII terminals 391 backup file 156 backup string 156 batch 46, 49, 144 beep 157, 288 beeping 536 binary files detecting 154 editing 439, 442 setting mode 158 blanks backup string with 156 directories with 149, 164, 215, 256, 454 files with 271, 275, 440 bracket indexing 503 button color 537 buttons 52, 160, 309, 431 Bye macro 134

С

C 192 C++ 192 caps-lock key 42 case 162, 163 global file case handling 281 handling during a search 163 ccsr 491, 696 cdpath 2, 149, 164, 215, 222, 243 centerline 167, 168, 169 change directory 508, 531 changing file directory 256 filename 271 filetype 275 changing a name 375 changing a string 171, 180, 346, 372, 406 changing an hexadecimal target 284 changing default options 497, 500 changing directory 164, 215 changing the backup string 156 changing the time and date 595 choice color 538 clearing the screen 352, 531, 595 closing the WINDOWS console 101, 179 cobol 333, 414, 415 codecenter 483 color disabling/enabling 182 resetcolor macro 188 reverse video 188 setting the background 2 setting the buttons 7 setting the field colors 182 setting the menu 7 setting the popups 7 setting the RGB value 182 setting the scrollbars 7 the directory editor 183 the tree editor 183 using a grey scale monitor 2 command field 52 command line restoring 179, 208, 288, 448, 449 retrieving the location 243 setting the position 179 command line options (UNIX) 46 command line options (WINDOWS) 49 comment 449 commenting C programs 260 compatibility issues 31 compiling 59, 65, 71, 77, 83, 84, 90, 95, 102, 190, 325 compiling an S/REXX program 491, 696 completion 194 concatenate files 532

console 140, 526 closing the WINDOWS console 101, 179 console window 140, 179, 526, 531, 565 control character 205, 358 control-line-feed key 131, 147, 298, 383, 389, 664 copying a line 108, 110, 115, 196 copying files 532 counting string occurrences 198 cpu id 4, 533 ctags 203 current line 52, 207 cursor duplicating cursor line 210 ending a rectangular selection 211 ending a selection 210, 211 ending a selection at the end of the line 211 moving between screens 402 moving in a macro 208 moving to the command line 58, 63, 69, 76, 82, 95, 97, 179, 208, 218, 288, 669, 675 moving to the end of line 57, 63, 69, 75, 81, 95, 665, 667, 675 moving to the next word 325 moving to the previous word 337 starting a selection 214 Customizing 656 customizing rxd 656 SEDIT (UNIX) 39 SEDIT (WINDOWS) 40

D

data field 51 date format within FLIST 267 date, changing 595 debugger 526, 653 delay 218 delete directories 573, 599 delete files 535, 573 deleting a directory 478 deleting a line 59, 65, 71, 77, 84, 95, 107, 116, 212, 665, 670, 671, 675 deleting the selection on WINDOWS 127 desbuf 508 dialog management 46, 536, 538, 541, 553, 555, 556, 609, 613, 658 direct input field 52 directory editor 453 directory listing 535 displaying the line/column indication 297 do 509 dos saving a compatible file 257, 370 DOS commands 507 DOS files 258 dosfile 257 dossave 370 down field 41 Down-Field 41, 95, 97, 131, 389, 664 dropbuf 510 dy_lastfiles 226, 294 dy printer 512, 547 dynamic loading 494, 498

E

editing multiple files 54 END key 459 end key 385 env rx 630 env_rx2 630 environment 630 erase EOF key 42, 56, 62, 70, 75, 80, 87, 94, 97, 669, 671, 675 erasing a file 469 EUROPEAN date format within FLIST 267 ex end 137 ex ini 136 ex sedit.h 136 exec 506. 557 execio 511 executing a WINDOWS .exe command 462 exiting SEDIT 99, 240, 319, 320 external procedures 494, 498 extract 136, 142 extract2 137

F

FD 454 ffile 257 field moving from one to another 41 file case handling 281 file conversion 258, 558 file directory

changing 256 definition 453 getting 558 filename changing 271 definition 453 getting 559 filename completion 194 filetype changing 275 definition 453 getting 561 filling a rectangular area 226 FLIST 103, 218, 267, 268, 361, 453 getting file names 559 FLIST permissions display 266, 457, 462 FN 453 fonts APL font 42 selecting with FONt command 272 setting the dialog 226, 540 using specials 3, 6 formatting text 166, 273, 296, 307, 362 FORTRAN 192 fortran shifting 111 free extract 137 FT 453 fullscreen interface 277, 358 fullshift mode 435, 436 function keys 384 customizing 39, 40 seeing 388

G

global file case handling 281 globalv 517, 522 GRAB dialog box 539, 549 grey scale monitor 2 group 327

H

hardware string 139, 147, 241, 242, 529, 629, 677 help 282, 418 help key 103, 385 heterogeneous network 26 hexadecimal display 285, 435 hexadecimal target 284 history 287, 444, 448, 449 home 3270 simulation 42 command 288 home key 385, 459 HOME on Windows 32, 37, 508, 515 hostid 4, 17 hostname 562

I

indexing 503 input color 541 inserting data from a file 276 install 16 installation directory 1, 12, 15, 19, 608 invsel macro 138 **ISPF** command **BOUNDS 159 BUILTIN 159** CANCEL 160 **CAPS 162** CHANGE 173 **COPY 197** CREATE 201 **DELETE 217 EDIT 235** END 236 **EXCLUDE 237 FIND 262** LOCATE 303 RCHANGE 347 **REPLACE 357 RESET 360 RFIND 361** ISPF compatibility mode 36, 105, 114, 318, 321, 469 ISPF mode starting script 36

K

kedit 44 KEDIT mode 48 kedit mode 87 key5.remap file 664 keyboard DEC 68

disabling the DOWN FIELD function 390 HP 74 **IBM 62** layout 661 mapping a native DEC 6 mapping a Sun type 3 or 4 6 mapping a Sun type 5 664 mapping an HP PC like 6 mapping with the menu buttons 101 modes 42 redefinition 291 setting the mapping 6 Silicon Graphics 62 SUN 56 using a 12 top keys keyboard 291 using ASCII terminals 8 using the right ALT key to enter special characters with a non-US keyboard 390, 693 WINDOWS 80 WINDOWS in KEDIT mode 87 keyboard focus 540 kfile 257 ksave 370

L

label color 542 large files 297, 455 left function keys on a sun keyboard 56, 386 libex.a 136 license server configuring a heterogeneous network 26 installing 21 killing and restarting 28 reserving licenses 26 starting 23 using an alternate 26 limiting file size 297 line-feed key 96, 131, 147, 389, 664 locate a name 448 locate a string 178, 261, 265, 300, 326 locating an hexadecimal target 284 lowercase translation 60, 66, 72, 78, 85, 90, 96, 418 LSTATE 594

M

macro commands external 133 internal 132 loading 281 overriding 189 prefix 119 purging 344 retrieving information from 133, 241 S/REXX 140, 472 variable substitution 132 macros within FLIST 472 make 130 error scanning 325 makebuf 521, 525 makefile 629, 649 man 306, 419 menu buttons 98, 309 menu buttons for FLIST 461 menubar 98 menus 52, 104, 310, 477 merging lines 314 message field 51 meta key 43, 53, 123, 127, 131, 316, 384, 389, 679 mkdir 565 mkesc 8 mkitab 23 mktrans 292 motif mouse mode 126 resources 7 mouse 557 cancelling a selection in Motif mode 126 cancelling a selection in OpenLook mode 123, 127 making a linear selection 123, 127 making a rectangular selection 125, 128 Motif mode 126 scrolling 53 setting the buttons 322 mouse mode 322 extracting 248 FullMotif 322 Motif 126 OpenLook 123, 322 moving a line 112, 116, 323 moving cursor between screens 402

msrexx 606, 609

Ν

next_field 41, 402 NIS 327 -noauto option 49, 240 number 328 number_screen 328

0

octal conversion 534 open a console 565 opening a file 99, 423, 440 opening a file by using a C or fortran name 203 operators 492 option noload 496 options xrm 7, 46 options (UNIX) 46 options (UNIX) 46 options (WINDOWS) 49 overlaying 118 owner of a file 594

Р

pass UNIX command with S/REXX 533, 557, 605 pass WINDOWS command with S/REXX 607 passing a command to UNIX or WINDOWS with FLIST 471 passing multiples commands 147, 298, 383 passwd 327 passwds file 5, 13, 20 password 3, 16, 21, 26 path 149, 353 adding a directory with ACC command 149 scanning with HASH command 281 searching it for a file 45, 291, 310 setting 2 PATH environment variable 2 pause key 385 pdf UNIX command 1 PDF compatibility mode 1 PDF Exactly 47 PDF Mode 47

pdf starting script 36 pdfcancel 160 pdfchange 173 pdfcopy 197 pdfdelete 217 pdfexclude 237 pdffind 262 pdflocate 303 pdfprof.sedit 37, 39, 40 pdfreplace 357 pending commands 114 power input mode 332 prefix 335 Prefix commands " 110 "" or '' 116 >. < 111 >>, << 117 A 107 CC 115 D 107 DD 116 E 111 G 110 L 119 M 112 MM 116 O 118 OO 118 parsing 105 PP 116 PU 109 S 113 **SCALE 113 TABL 113** U 119 X 112 XX 117 prefix field 51 prefix macro arguments 121 creating a synonym 119, 335 getting the source name 121 using an external macro 121 prefix _screen 335 prev_field 41, 390, 401 printing changing the default screen printer 340 changing the default screen printer dae-

mon 340 changing the default TREE printer 340 the current file 338, 339 the screen 43, 340, 341 the tree 478 printscreen key 385 process getting the process ID 562 killing 563 querying 567 spawning 560 waiting to terminate 607 process identifier 562 process number 562 prof pdf.sedit 1, 2, 37, 47 prof_xedit.sedit 1, 2, 32, 47 profile 144 prof pdf.sedit PDF like profile 37 prof_xedit.sedit XEDIT like profile 32, 683 reprofile 133, 140 suppressing with the -np option 46, 49 PROFILE.sedit 1, 2, 292, 385 profile.sedit 1, 2, 6, 31, 38, 46, 47, 48, 49, 68, 74, 98, 119, 126, 132, 133, 134, 140, 155, 182, 192, 241, 250, 260, 287, 292, 293, 316, 319, 391, 393, 445, 461, 475, 484, 683 psedit starting script 36 pxed starting script 36

Q

quit initial synonym value 345, 413 quitting a file 57, 64, 70, 76, 94, 345 quitting all files 160

R

recording an S/REXX session 573 recycle bin 352, 469, 478, 573 redoing 129, 352 refreshing the screen 352 registry deleting key 568 retrieving key 568 setting key 571 regular expressions 151, 191, 228, 232, 346, 361, 363, 366, 406, 453, 598
reload 354, 409 disabling automatic 354 remove directories 573, 599 removing a directory 478 removing the selection on WINDOWS 127 rename file 565 repainting the screen 352 reprofile 34, 38, 133, 140, 334, 451 resources 7 restart.x macro file 134 retrieve selection 420 reverse video 188 reverse video mode 416 REXX macro commands 140 right function keys 11, 56, 62, 68, 74, 80, 94 rxd 526, 653

S

saber 366, 367, 368 saving a file 57, 64, 70, 76, 94, 99, 257, 370, 437 scale 371 scale line 113, 371 scale screen 371 **SCHANGE** changing the confirmation keys 374 scrollbar 380 scrolled list 536, 538, 547, 548, 549, 553, 557 scrolled list color 536, 541, 542, 549, 553 scrolling 53, 58, 63, 69, 70, 75, 81, 95, 156, 274, 324, 335, 428, 432 scrolling vertically 295, 361 scrolllock key 385 sedit 488, 504, 526, 619 UNIX command 44 sedit.lastfiles 294 sedit.srexxrc 497 seditid 4, 17 seditusers file 26 selection 123, 127 cancelling 123, 127 linear 123, 127 moving to an other window 125 moving to XTERM 125 overlaying 124, 128 rectangular 125, 128 removing 127

retrieve 420 setting an APL stop on selected lines 411 setting an APL trace on selected lines 428 whole lines 125, 128 selective change 35, 375 changing the confirmation keys 373, 374, 376, 407 selective editing 112, 113, 117, 151, 182, 219, 237, 377, 381, 382, 394, 397 selective line editing 151 sends 136 set sun t 306 set_unix 50, 127 setting the background color 2 the number of columns 46, 49, 658 the number of lines 46, 49, 658 the RXD icon position 658 the RXD window location 658 the SEDIT icon position 46 the SEDIT window location 46, 49 setup 12, 19 shell command 395 shift-return in directory editor 454 SINIX 6 size limit 297 SLIP connection 236 smart_comp 59, 65, 71, 77, 83, 90, 95, 192, 665, 667, 675 smart_compd 192, 665, 667, 675 sorting 593 sorting a file 399 sorting the ring 399 sounding the alarm 536 spelling 101, 404 splitting a line 57, 66, 72, 78, 85, 95 splitting the screen 60, 66, 72, 78, 85, 96, 378 ssave 370 stack clearing 508 creating 521, 525 getting 635 length 640 query 525 removing 510 setting 637, 638 status field 51 subdirectories 595 switching between file and directory editor 455 switching between files 55, 57, 63, 69, 75, 81, 95, 289 symbolic link preventing following 272 solving 559 symbolic name 113, 177, 331 symbolic name for a Ri function key 385 synonym 189, 413 syntax coloring 414 sysinfo 4, 17

Т

table)ATTR section 620)BODY section 621)BUTTON section 622)MODEL section 621)TRAIL section 622 adding a line 603, 627 closing 603, 624 deleting a line 603, 627 displaying 603, 625 getting a line 604, 626 opening 604, 625 saving 605, 626 updating 604 tabline 113, 425 tabline screen 425 tabulations displaying the tabline 113, 425 entering 41 expanding 43, 424 setting 43, 426 tags 203 text formatting 451 time stamp of a file 594 time, changing 595 time-out for function keys 356 toggle color 556 toolbar 101, 427 trailing blank disabling automatic removal 290 displaying the last one 394 tree 103, 429 commands 475 switching to 429, 460 treescanlevel 429, 475 TRUE64 17, 68, 391, 669, 677

U

U file symbol 259 uname 4, 17 undoing 56, 63, 69, 76, 82, 87, 90, 95, 129, 370, 431 UNIX commands 288, 395, 438, 442, 443 UNIX files 258 UNIX keyboard layout on WINDOWS 50 UNIXWARE 6, 64 Up-Field 41, 96, 97, 131, 389, 664, 675 uppercase first letter only translation 423 uppercase translation 59, 65, 71, 78, 84, 423 US date format within FLIST 267 uumac prefix command macro 119

V

VARBLANK 434 variable getting 633 setting 645 variable substitution 132, 147, 153 verify 301, 365, 435, 447, 448 verify_ksave 437 verify_screen 435 verify_ssave 437

W

W file symbol 259 warning beep 157 window position 46, 49 window size 46, 49 WINDOWS 80, 98, 127, 179, 186, 230, 234, 248, 258 WINDOWS ADDRESS environment 507 WINDOWS file 258 wiping files 469, 478, 608 wordwrap 435 workstation hostname 562 wsrexx 488, 609 wsrexx.exe 609

X

xc 54 XCDPATH 215 XCDPATH environment variable 2

xe 54 xedit UNIX command 1, 32 XEDIT compatibility mode 1, 155, 318, 319, 320 **XEDIT Exactly 47** XEDIT Mode 47 xedit starting script 32 xeditprof.sedit 32, 39, 40 XF 1, 44 xf 54 xh 54 xi 54 xinfo 27, 29 xm 54 xmac macro directory 1, 31, 119, 130, 132, 134, 141, 170, 188, 192, 369, 392 xmodmap 664 xp 54 XPATH environment variable 2 xs 54 xsdown 29 xserv configuring a heterogeneous network 26 installing 21 killing and restarting 28 restarting 28 xsrexx 606, 609 xt 54 **XTERM** moving selections 57, 63, 68, 75, 87, 125 xx 54

Y

yellow pages 327 ypcat 327

Z

zone 172, 181, 301, 347, 365, 373, 376, 407, 446, 447, 448 zone_screen 446

Index